



Deep Security 11.3

On-Premise

Legal Notices

Trend Micro Incorporated reserves the right to make changes to this document and to the products described herein without notice. Before installing and using the software, please review the release notes and the latest version of the applicable user documentation, which are available from the Trend Micro Web site at:

<https://help.deepsecurity.trendmicro.com/software.html>

Trend Micro, and the Trend Micro t-ball logo are trademarks or registered trademarks of Trend Micro Incorporated. All other company or product names may be trademarks or registered trademarks of their owners. Information contained in this document is subject to change without notice.

© 2018 Trend Micro Incorporated. All rights reserved

Protected by U.S. Patent No. 7,630,982 B2.

Privacy Policy

Trend Micro, Inc. is committed to protecting your privacy. Please read the Trend Micro Privacy Policy available at www.trendmicro.com.

Document Number: APEM118542_181107

Publication Date: 8/24/2020 5:04 PM

Contents

Contents	3
Get Started	66
Privacy and personal data collection disclosure	66
Deep Security Software	66
Protection for VMware environments	67
Deep Security Virtual Appliance features	67
Scan caching	67
Scan storm optimization	68
Ease of management	68
VMware deployments with the virtual appliance and NSX 6.3 or higher	68
VMware deployments without the virtual appliance and NSX (agent only)	70
Additional information	71
What's new?	71
Deep Security 11.3	71
Before you install	72
Feature releases	72
Version numbers	73
Feature release life cycle	73
Platform support	74
Support services	74
About the Deep Security components	75
System requirements	76
Deep Security Manager	76
Deep Security Agent	78
Deep Security Virtual Appliance	79
Deep Security Agent platforms	80

Agent platform support table	80
Docker support	83
Deep Security Agent Linux kernel support	83
Supported features by platform	85
Microsoft Windows (11.3 agent)	86
Red Hat Enterprise Linux (11.3 agent)	90
CentOS Linux (11.3 agent)	91
Oracle Linux (11.3 agent)	92
SUSE Linux (11.3 agent)	93
Ubuntu Linux (11.3 agent)	94
Debian Linux (11.3 agent)	95
Cloud Linux (11.3 agent)	96
Amazon Linux (11.3 agent)	96
Deep Security Virtual Appliance (NSX) (with embedded 11.3 agent)	97
Sizing	104
Deep Security Manager sizing	104
Multiple server nodes	105
Database sizing	106
Disk space estimates	107
Database sizing considerations	107
Deep Security Agent and Relay sizing	108
Deep Security Virtual Appliance sizing	109
Port numbers, URLs, and IP addresses	111
Deep Security port numbers	111
Deep Security URLs	115
Prepare a database for Deep Security Manager	122
Hardware considerations	123
Dedicated server	123
Hardware recommendations	124

Microsoft SQL Server	124
General requirements	124
Transport protocol	125
If using multi-tenancy	125
Oracle Database	125
Oracle RAC (Real Application Clusters) support	126
Database maintenance	126
Index maintenance	126
Backups	127
PostgreSQL recommendations	127
General requirements	127
Tuning PostgreSQL settings	128
Logging settings	128
Lock management	129
Maximum connections	129
Shared buffers	129
Work memory and maintenance work memory	130
Effective cache size	130
Checkpoints	130
Write-ahead log (WAL)	130
Autovacuum settings	131
High availability	131
Backup and recovery	131
Linux recommendations	131
Transparent Huge Pages (Linux)	131
Strengthen host-based authentication (Linux)	131
Microsoft SQL Server Express considerations	132
Express edition limitations	132
Limited number of protected computers	132

Security module limitations	132
Minimize the agent size	133
Database pruning	133
Choose agentless vs. combined mode protection	133
Agentless protection	133
Combined mode	134
Conversion of coordinated approach to combined mode	134
Choose and agent or appliance for each protection feature	135
Deep Security Virtual Appliance memory allocation	136
Configure the appliance's memory allocation prior to deployment to the vCenter	137
Configure the memory allocation of an already-deployed appliance	137
Check digital signatures on software packages	138
Check the signature on software ZIP packages	138
Check the signature on installer files (EXE, MSI, RPM or DEB files)	139
Check the signature on an EXE or MSI file	139
Check the signature on an RPM file	140
Check the signature on a DEB file	141
Deploy Deep Security	144
Install or upgrade Deep Security	144
Prepare your environment	145
Hardware requirements	147
Network requirements	148
Network topology	148
Database requirements	149
Migrate to a supported database	150
Change the remote SQL query timeout	151
Choose agent-based vs. agentless protection	151
Install a supported OS	151
Upgrade unsupported Deep Security Managers	152

Upgrade unsupported relays	152
VMware requirements	153
Upgrade virtual appliances	154
Conversion of coordinated approach to combined mode	157
Pin appliances with VMware HA	158
Upgrade unsupported agents	158
Run the installer	159
Multi-node manager	159
Install Deep Security Manager on Linux	161
Install Deep Security Manager on Windows	161
Install a relay on the Deep Security Manager's server	162
Schema updates	164
Force a multi-tenant database upgrade	165
Roll back an unsuccessful upgrade	165
After the installer	166
Self-signed certificate	166
Strengthen encryption	167
Event data migration	167
Upgrade relays on Linux (dpkg)	168
Upgrade relays on Linux (rpm)	168
Upgrade relays on Windows	169
Upgrade agents on Windows	169
Upgrade agents on Linux	170
Upgrade agents on Solaris to version 10.0	171
Download security updates for Deep Security Agent 8.0 and 9.0	171
Choose and agent or appliance for each protection feature	171
Install a new Deep Security Agent or Relay	173
Set up alerts	174
Run a recommendation scan	176

Silent install of Deep Security Manager	177
Run a silent install readiness check	177
Run a silent install on Windows	177
Run a silent install on Linux	177
Parameters	177
Sample properties file	178
Deep Security Manager settings properties file	179
Required Settings	180
LicenseScreen	180
CredentialsScreen	180
Optional Settings	180
LanguageScreen	180
UpgradeVerificationScreen	181
OldDataMigrationScreen	181
DatabaseScreen	181
AddressAndPortsScreen	183
CredentialsScreen	183
MasterKeyConfigurationScreen	184
SecurityUpdateScreen	184
SoftwareUpdateScreen	185
SmartProtectionNetworkScreen	186
Sample properties files	187
Installation Output	188
Successful install	189
Failed install	190
Run Deep Security Manager on multiple nodes	191
Add a node	191
Remove a node	192
Viewing node statuses	192

Network Map with Activity Graph	192
Jobs by Node	193
Jobs by Type	194
Total jobs by node and type	195
Configure Deep Security Manager memory usage	196
Configuring the installer's maximum memory usage	196
Configuring Deep Security Manager's maximum memory usage	197
Deep Security Manager performance features	197
Performance profiles	197
Low disk space alerts	198
Low disk space on the database	198
Low disk space on the manager	198
Update the load balancer's certificate	198
Set up a multi-tenant environment	201
Multi-tenancy requirements	203
Enable multi-tenancy	203
Create a tenant	204
Examples of messages sent to tenants	205
Email Confirmation Link: Account Confirmation Request	205
Email Generated Password	206
Scalability guidelines	206
Multi-tenancy tips	207
Reconnaissance IP list	207
Use multiple database servers	207
Tenant pending deletion state	207
Multi-tenant options under System Settings	208
Managing tenants	208
Tenant Properties	208
General	208

Modules	209
Features	209
Statistics	210
Agent Activation	210
What does the tenant see?	210
Agent-Initiated Activation	212
Tenant diagnostics	212
Usage monitoring	212
Multi-tenant Dashboard	213
Multi-tenant reports	213
Security Module Usage Cumulative Report	214
Security Module Usage Report	214
Tenant Report	215
Configure database user accounts	215
Configuring database user accounts	216
SQL Server	216
Oracle	224
PostgreSQL	226
Configuring multiple database servers	227
Removing or changing secondary databases	227
APIs	228
Upgrade	228
Supporting tenants	229
Load balancers	230
Multi-tenancy with Deep Security Virtual Appliance	232
Multi-tenant settings	232
Database servers	234
New tenant template	234
Protection usage monitoring	236

Configure SMTP settings for email notifications	237
Install the appliances	238
Deploy the Deep Security Virtual Appliance with NSX	238
Before you begin	239
Step 1: Import appliance packages into Deep Security Manager	240
Step 2: Add vCenter to Deep Security Manager	241
Step 3: Prepare ESXi servers	241
Step 4: Install Guest Introspection	242
Step 5: Install the Deep Security Virtual Appliance	248
Step 6: Prepare for activation	253
Method 1: Create a 'Computer Created' event-based task	254
Method 2: Create an 'NSX Security Group Change' event-based task	255
Method 3: Synchronize your Deep Security policies to NSX	258
Step 7: Create NSX security groups and policies	260
Step 8: Trigger an activation and policy assignment	275
Step 9: Check that VMs are activated and assigned a policy	275
Next steps (how to add new VMs)	276
Automated policy management in NSX environments	276
"NSX Security Group Change" event-based task	277
Conditions under which to perform tasks	278
Available actions	279
Event-based tasks created when adding a vCenter to Deep Security Manager	279
Removal of a vCenter from Deep Security Manager	281
Synchronize Deep Security policies with NSX	281
Deploy agentless protection in a vCloud environment	283
Enable agentless protection of vCloud VMs	284
Create a multi-tenant environment	284
Add a vCenter and deploy the Deep Security Virtual Appliance	284
Configure VMware vCloud resources for integration with Deep Security	284

Create a minimum rights role for vCloud account tenant users	284
Configure the vCenter database to assign unique UUIDs to new virtual machines	285
Enable the OVF Environment Transport for VMware Tools on your guest VMs	286
Activate virtual appliance protection on virtual machines	287
Import computers from a VMware vCloud Organization Account	287
Import computers from a VMware vCloud Air Virtual data center	287
Activate virtual appliance protection on virtual machines	288
Integrate with VMware vRealize Operations Manager	288
Requirements	289
Download the management pack	290
Install and configure	290
Create a user account for vRealize Operations Manager	290
Enable SOAP Web Services in Deep Security Manager	292
Export the Deep Security Manager certificate	293
Import the Deep Security Manager certificate into vRealize Operations Manager	293
Install the Deep Security Management Pack in vRealize Operations	295
Configure the Deep Security Management Pack in vRealize Operations	297
Validate Data Collection in vRealize Operations	299
Migrate from a 5.x environment	301
Navigate Deep Security in vROps	301
Dashboards	303
Deep Security Top 10 Analysis	303
Deep Security Troubleshooting	304
Deep Security Total Event Count Heat Map	305
Metrics	306
Alerts, Symptoms, and Recommendations	307
Configure NSX security tags	315
Configure Anti-Malware to apply NSX security tags	315
Configure Intrusion Prevention to apply NSX security tags	317

Install the agents	318
Get Deep Security Agent software	318
Download agent software packages into Deep Security Manager	318
Automatically import software updates	319
Manually import software updates	319
Export the agent installer	319
Delete a software package from the Deep Security database	320
Deleting agent packages in single-tenancy mode	321
Deleting agent packages in multi-tenancy mode	321
Deleting kernel support packages	321
Manually install the Deep Security Agent	322
Install a Windows agent	322
Installation on Amazon WorkSpaces	323
Installation on Windows 2012 Server Core	323
Install a Red Hat, SUSE, Oracle Linux, or Cloud Linux agent	324
Install an Ubuntu or Debian agent	324
Install the agent on a Microsoft Azure VM	325
Generate and run a deployment script	325
Add a custom script extension to an existing virtual machine	325
Install the agent on VMware vCloud	326
Create a minimum rights role for vCloud account tenant users	326
Configure the vCenter database to assign unique UUIDs to new virtual machines	327
Enable the OVF Environment Transport for VMware Tools on your guest VMs	328
Import computers from a VMware vCloud Organization Account	328
Import computers from a VMware vCloud Air Virtual data center	329
Install the agent on Amazon EC2 and WorkSpaces	330
Add your AWS accounts to Deep Security Manager	331
Set the communication direction	331
Configure the activation type	332

Open ports	333
Which ports should be opened?	334
Deploy agents to your Amazon EC2 instances and WorkSpaces	335
Verify that the agent was installed and activated properly	335
Assign a policy	336
Bake the agent into your AMI or WorkSpace bundle	337
Add your AWS account to Deep Security Manager	338
Set the communication direction	338
Configure the activation type	338
Launch a 'master' Amazon EC2 instance or Amazon WorkSpace	338
Deploy an agent on the master	338
Verify that the agent was installed and activated properly	339
(Recommended) Set up policy auto-assignment	339
Create an AMI or custom WorkSpace bundle based on the master	340
Use the AMI	341
Automatically upgrade agents on activation	341
Enable automatic agent upgrade	342
Check that agents were upgraded successfully	342
Configure communication between components	343
Agent-manager communication	344
Configure the heartbeat	344
Configure communication directionality	346
Supported cipher suites for agent-manager communication	348
SSL implementation and credential provisioning	349
Use agent-initiated communication with cloud accounts	350
Enable agent-initiated communication on the policy	350
Assign the policy to a deployment script	351
Connect agents behind a proxy	351
Requirements	351

Register the proxy in Deep Security Manager	351
Connect agents, appliances, and relays to security updates via proxy	352
Connect agents to security services via proxy	352
Connect agents to a relay via proxy	353
Connect agents to a relay's private IP address	353
Remove a proxy setting	354
Windows	354
Linux	354
Subsequent agent deployments	354
Configure agents that have no Internet access	354
Solutions	355
Use a proxy	355
Install a Smart Protection Server locally	356
Install a relay and supporting components in your DMZ or Internet-ready area	356
Disable the features that use Trend Micro security services	359
Proxy protocols supported by Deep Security	361
Proxy settings	362
Proxy server use	362
Proxy servers	364
Manage trusted certificates	364
Import trusted certificates	364
View trusted certificates	365
Remove trusted certificates	366
If I have disabled the connection to the Smart Protection Network, is any other information sent to Trend Micro?	367
Linux Secure Boot support for agents	367
Activate the agent	370
Deactivate the agent	372
Stop or start the agent	372

Stop or start the appliance	372
Diagnose problems with agent deployment (Windows)	373
Configure teamed NICs	373
Agent settings	374
Hostnames	374
Agent-Initiated Activation	374
Agent Upgrade	376
Inactive Agent Cleanup	376
Data Privacy	376
Agentless vCloud Protection	376
Install the Deep Security Notifier	377
Copy the Installation Package	377
Install the Deep Security Notifier for Windows	377
Create an Azure app for Deep Security	378
Record the Azure Active Directory ID	378
Create the Azure app	378
Record the Azure app ID and password	379
Record the Subscription ID	379
Assign the Azure app a reader role and add it to your Azure Subscription	379
Distribute security and software updates with relays	380
How relays work	380
Determine the number of relays to use	381
Geographic region of agents	381
Network configuration	381
Network bandwidth usage	382
Sizing recommendations	382
Configure one or more relays	382
Create one or more relay groups	383
Enable one or more relays	385

Assign agents to a relay group	385
Configure relay settings for security and software updates	386
Security updates	386
Software updates	386
Remove relay functionality from an agent	387
10.2 or later	387
10.1 or earlier	388
DevOps, automation and scaling	389
Command-line basics	390
Deep Security Agent	390
dsa_control	390
Usage	390
Agent-initiated activation ("dsa_control -a")	393
Agent-initiated activation via proxy	394
Agent-initiated heartbeat command ("dsa_control -m")	394
Activate an agent	402
Windows	402
Linux	403
Configure a proxy for anti-malware and rule updates	403
Windows	403
Linux	403
Configure a proxy for connections to the manager	403
Windows	403
Linux	404
Force the agent to contact the manager	404
Windows	404
Linux	404
Initiate a manual anti-malware scan	404
Windows	404

Linux	404
Create a diagnostic package	405
Reset the agent	405
Windows	405
Linux	405
dsa_query	405
Usage	405
Check CPU usage and RAM usage	406
Windows	406
Linux	406
Check that ds_agent processes or services are running	407
Windows	407
Linux	407
Restart an agent on Linux	407
Deep Security Manager	407
Usage	407
Return codes	416
Use the Deep Security API to automate tasks	417
Legacy REST and SOAP APIs	417
Enable the Status Monitoring API (optional)	418
Create a Web Service user account	418
Schedule Deep Security to perform tasks	418
Create scheduled tasks	419
Enable or disable a scheduled task	421
Set up recurring reports	421
Automatically perform tasks when a computer is added or changed	422
Create an event-based task	422
Edit or stop an existing event-based task	422
Events that you can monitor	422

Conditions	423
Actions	426
Order of execution	426
Temporarily disable an event-based task	426
AWS Auto Scaling and Deep Security	427
Pre-install the agent	427
Install the agent with a deployment script	428
Delete instances from Deep Security as a result of Auto Scaling	430
Azure virtual machine scale sets and Deep Security	430
Step 1: (Recommended) Add your Azure account to Deep Security Manager	430
Step 2: Prepare a deployment script	431
Step 3: Add the agent through a custom script extension to your VMSS instances	431
Example 1: Create a new VMSS that includes the agent	432
Example 2: Add the agent to an existing VMSS	434
Use deployment scripts to add and protect computers	437
Enable agent-initiated activation	437
Generate a deployment script	437
Troubleshooting and tips	440
Automatically assign policies by AWS instance tags	441
Integrate Deep Security with AWS Elastic Beanstalk	442
For more information	443
Deep Security Smart Check	443
Protect	443
Intrusion Prevention	444
Anti-Malware	444
Firewall	444
Web Reputation	445
Integrity Monitoring	445
Log Inspection	445

Application Control	445
Manage protected computers	446
Add computers and other resources to Deep Security Manager	446
Add computers to the manager	446
Group computers	447
Export your computers list	448
Delete a computer	448
Add local network computers	448
Agent-initiated activation	448
Manually add a computer	449
Discover computers	450
Add a VMware vCenter	451
Add a vCenter when Deep Security Manager is in FIPS mode	453
Add an ESXi to a protected NSX cluster	455
Add AWS cloud accounts	455
Method: Manager instance role and cross-account role	457
Configure the AWS DSM account	457
Configure AWS Account A	460
Add the AWS accounts to Deep Security Manager	462
Method: IAM user and cross-account role	463
Configure AWS Account X	464
Configure AWS Account Y	466
Add the access keys to Deep Security Manager	468
Add the AWS accounts to Deep Security Manager	468
Method: Manager instance role (single AWS account)	469
Method: AWS access keys	471
Edit a cloud account	473
Remove a cloud account from the manager	473
Add Amazon WorkSpaces	474

Protect Amazon WorkSpaces if you already added your AWS account	474
Protect Amazon WorkSpaces if you have not yet added your AWS account	475
How do I migrate to the new cloud connector functionality?	475
Add a Microsoft Azure account to Deep Security	477
Configure a proxy setting for the Azure account	477
Add virtual machines from a Microsoft Azure account to Deep Security	477
Quick	478
Advanced	478
Manage Azure classic virtual machines with the Azure Resource Manager connector	479
Remove an Azure account	480
Create an Azure app for Deep Security	480
Record the Azure Active Directory ID	481
Create the Azure app	481
Record the Azure app ID and password	481
Record the Subscription ID	481
Assign the Azure app a reader role and add it to your Azure Subscription	482
Why should I upgrade to the new Azure Resource Manager connection functionality?	482
Add virtual machines hosted on VMware vCloud	483
Proxy setting for cloud accounts	483
Create a VMware vCloud Organization account for the manager	483
Import computers from a VMware vCloud Organization Account	484
Import computers from a VMware vCloud Air data center	485
Configure software updates for cloud accounts	486
Remove a cloud account	486
Add computer groups from Microsoft Active Directory	486
Additional Active Directory options	488
Remove Directory	488
Synchronize Now	488
Server certificate usage	488

Filter Active Directory objects	489
Import users and contacts	489
Keep Active Directory objects synchronized	490
Disable Active Directory synchronization	491
Remove computer groups from Active Directory synchronization	491
Delete Active Directory users and contacts	491
Protect Docker containers	492
Deep Security protection for the Docker host	493
Deep Security protection for Docker containers	493
Limitation on Intrusion Prevention recommendation scans	493
Computer and agent statuses	494
Status column - computer states	494
Status column - agent or appliance states	495
Task(s) column	496
Computer errors	499
Protection module status	500
Perform other actions on your computers	501
Computers icons	505
Status information for different types of computers	507
Ordinary computer	507
Relay	508
Deep Security Scanner	508
Docker hosts	509
ESXi server	509
Virtual appliance	510
Virtual machine with agentless protection	510
Using Deep Security with iptables	511
Rules required by Deep Security Manager	511
Rules required by Deep Security Agent	511

Prevent Deep Security from automatically adding iptables rules	512
Enable or disable agent self-protection	512
Via Deep Security Manager	513
Via command line	513
Are "Offline" agents still protected by Deep Security?	514
Deep Security Notifier	514
How the notifier works	515
Create policies to protect your computers and other resources	519
Create a new policy	520
Other ways to create a policy	521
Edit the settings for a policy or individual computer	521
Assign a policy to a computer	522
Disable automatic policy updates	523
Send policy changes manually	523
Export a policy	524
Policies, inheritance, and overrides	524
Inheritance	525
Overrides	526
Override object properties	527
Override rule assignments	528
View the overrides on a computer or policy at a glance	528
Manage and run recommendation scans	529
What gets scanned?	530
Scan limitations	530
Run a recommendation scan	532
Create a scheduled task to regularly run recommendation scans	533
Configure an ongoing scan	533
Manually run a recommendation scan	534
Cancel a recommendation scan	534

Exclude a rule or application type from recommendation scans	534
Automatically implement recommendations	535
Check scan results and manually assign rules	536
Configure recommended rules	537
Implement additional rules for common vulnerabilities	537
Troubleshooting: Recommendation Scan Failure	539
Communication	539
Server resources	539
Timeout values	539
Detect and configure the interfaces available on a computer	540
Configure a policy for multiple interfaces	540
Enforce interface isolation	541
Overview section of the computer editor	541
General tab	542
Computer status	543
Protection module status	543
VMware virtual machine summary	545
Actions tab	545
Activation	545
Policy	546
Agent Software	546
Support	546
TPM tab	547
System Events tab	547
Overview section of the policy editor	547
General tab	548
General	548
Inheritance	548
Modules	548

Computer(s) Using This Policy tab	548
Events tab	548
Network engine settings	549
Define rules, lists, and other common objects used by policies	559
Rules	560
Lists	560
Other	560
Create a firewall rule	561
Add a new rule	561
Select the behavior and protocol of the rule	562
Select a Packet Source and Packet Destination	564
Configure rule events and alerts	565
Alerts	566
Set a schedule for the rule	566
Assign a context to the rule	566
See policies and computers a rule is assigned to	566
Export a rule	566
Delete a rule	566
Configure intrusion prevention rules	567
See the list of intrusion prevention rules	567
See information about an intrusion prevention rule	568
General Information	568
Details	568
See the list of intrusion prevention rules	569
General Information	569
Identification (Trend Micro rules only)	569
See information about the associated vulnerability (Trend Micro rules only)	570
Assign and unassign rules	570
Automatically assign updated required rules	571

Configure event logging for rules	571
Generate alerts	572
Setting configuration options (Trend Micro rules only)	573
Schedule active times	573
Exclude from recommendations	574
Set the context for a rule	574
Override the behavior mode for a rule	575
Override rule and application type configurations	575
Export and import rules	576
Create an integrity monitoring rule	576
Add a new rule	577
Enter Integrity Monitoring rule information	578
Select a rule template and define rule attributes	578
Registry Value template	578
File template	578
Custom (XML) template	579
Configure Trend Micro Integrity Monitoring rules	579
Configure rule events and alerts	580
Real-time event monitoring	580
Alerts	581
See policies and computers a rule is assigned to	581
Export a rule	581
Delete a rule	581
Define a log inspection rule for use in policies	581
Create a new log inspection rule	582
Decoders	584
Subrules	585
Groups	585
Rules, ID, and Level	586

Description	587
Decoded As	588
Match	588
Conditional Statements	589
Hierarchy of Evaluation	590
Restrictions on the Size of the Log Entry	591
Composite Rules	592
Real world examples	593
Log inspection rule severity levels and their recommended use	602
strftime() conversion specifiers	603
Examine a log inspection rule	604
Log inspection rule structure and the event matching process	604
Duplicate Sub-rules	607
Create a list of directories for use in policies	608
Import and export directory lists	611
See which policies use a directory list	611
Create a list of file extensions for use in policies	611
Import and export file extension lists	612
See which malware scan configurations use a file extension list	612
Create a list of files for use in policies	612
Import and export file lists	614
See which policies use a file list	615
Create a list of IP addresses for use in policies	615
Import and export IP lists	615
See which rules use an IP list	616
Create a list of ports for use in policies	616
Import and export port lists	616
See which rules use a port list	617
Create a list of MAC addresses for use in policies	617

Import and export MAC lists	617
See which policies use a MAC list	618
Define contexts for use in policies	618
Configure settings used to determine whether a computer has internet connectivity	618
Define a context	618
Define stateful firewall configurations	619
Add a stateful configuration	620
Enter stateful configuration information	620
Select packet inspection options	620
IP packet inspection	621
TCP packet inspection	621
FTP Options	623
UDP packet inspection	623
ICMP packet inspection	624
Export a stateful configuration	624
Delete a stateful configuration	625
See policies and computers a stateful configuration is assigned to	625
Define a schedule that you can apply to rules	625
Lock down software with application control	625
Key concepts	626
How does application control work?	627
A tour of the application control interface	628
Application Control: Software Changes (Actions)	629
Application Control Rulesets	630
Security Events	631
What does application control detect as a software change?	631
Differences in how Deep Security Agent 10.x and 11.x compare files	632
Set up application control	633
Turn on application control	633

Monitor new and changed software	634
Tips for handling changes	636
Turn on maintenance mode when making planned changes	637
Application control tips and considerations	638
Verify that application control is enabled	639
Monitor application control events	641
Choose which application control events to log	641
View application control event logs	642
Interpret aggregated security events	642
Monitor application control alerts	644
View and change application control rulesets	644
View application control rulesets	645
Security Events	647
Change the action for an application control rule	647
Delete an individual application control rule	649
Delete an application control ruleset	649
Reset application control after too much software change	649
Use the API to create shared and global rulesets	650
Create a shared ruleset	653
Change from shared to computer-specific allow and block rules	654
Deploy application control shared rulesets via relays	655
Single tenant deployments	655
Considerations when using relays with share rulesets	656
Protect against malware	657
Types of malware scans	658
Real-time scan	658
Manual scan	658
Scheduled scan	659
Quick scan	659

Scan objects and sequence	659
Malware scan configurations	660
Malware events	660
SmartScan	661
Predictive Machine Learning	661
Connected Threat Defense	662
Malware types	662
Virus	662
Trojans	663
Packer	663
Spyware/grayware	663
Cookie	665
Other threats	665
Possible malware	665
Enable and configure anti-malware	665
Turn on the anti-malware module	666
Select the types of scans to perform	666
Configure scan exclusions	667
Ensure that Deep Security can keep up to date on the latest threats	667
Configure malware scans	668
Create or edit a malware scan configuration	669
Test malware scans	670
Scan for specific types of malware	671
Scan for spyware and grayware	671
Scan for compressed executable files (real-time scans only)	671
Scan process memory (real-time scans only)	672
Scan compressed files	672
Scan embedded Microsoft Office objects	673
Specify the files to scan	673

Inclusions	673
Exclusions	674
Test file exclusions	675
Syntax for directory lists	675
Syntax of file lists	677
Syntax of file extension lists	679
Syntax of process image file lists (real-time scans only):	679
Scan a network directory (real-time scan only)	679
Specify when real-time scans occur	679
Configure how to handle malware	680
Customize malware remedial actions	680
ActiveAction actions	681
Generate alerts for malware detection	682
Apply NSX security tags	682
Identify malware files by file hash digest	682
Configure notifications on the computer	683
Performance tips for anti-malware	683
Minimize disk usage	683
Optimize CPU usage	684
Optimize RAM usage	686
Disable Windows Defender after installing Deep Security anti-malware on Windows Server 2016	686
Installing the Anti-Malware module when Windows Defender is already disabled	686
Virtual Appliance Scan Caching	687
Scan Cache Configurations	687
Malware Scan Cache Configuration	688
Integrity Monitoring Scan Cache Configuration	689
Scan Cache Settings	689
When to change the default configuration	690
Detect emerging threats using Predictive Machine Learning	690

Ensure Internet connectivity	691
Enable Predictive Machine Learning	691
Detect emerging threats using Connected Threat Defense	692
How does Connected Threat Defense work?	692
Check the Connected Threat Defense prerequisites	693
Set up the connection to Deep Discovery Analyzer	694
Set up the connection to Trend Micro Control Manager	695
Create a malware scan configuration for use with Connected Threat Defense	697
Enable Connected Threat Defense for your computers	698
Manually submit a file to Deep Discovery for analysis	699
Allow a file that has raised a false alarm	699
Configure the scan action for a suspicious file	699
Update the suspicious objects list in Deep Security	700
Configure Connected Threat Defense in a multi-tenant environment	700
Supported file types	701
Enhanced anti-malware and ransomware scanning with behavior monitoring	702
How does enhanced scanning protect you?	702
How to enable enhanced scanning	703
What happens when enhanced scanning finds a problem?	704
What if my agents can't connect to the Internet directly?	709
Smart Protection in Deep Security	709
Anti-malware and Smart Protection	709
Enable Smart Scan	709
Smart Protection Server for File Reputation Service	710
Web Reputation and Smart Protection	711
Smart Feedback	712
Handle malware	712
View and restore identified malware	713
See a list of identified files	713

Working with identified files	714
Search for an identified file	715
Restore quarantined files	717
Create a scan exclusion for the file	717
Restore the file	720
Manually restore quarantined files	720
Create anti-malware exceptions	720
Create an exception from an anti-malware event	721
Manually create an anti-malware exception	722
Exception strategies for spyware and grayware	722
Scan exclusion recommendations	723
Increase debug logging for anti-malware in protected Linux instances	723
Block exploit attempts using intrusion prevention	724
Intrusion prevention rules	724
Application types	725
Rule updates	725
Recommendation scans	726
Use behavior modes to test rules	726
Override the behavior mode for rules	727
Intrusion prevention events	727
Support for secure connections	728
Contexts	728
Interface tagging	728
Set up intrusion prevention	728
Enable intrusion prevention in Detect mode	729
Test intrusion prevention	731
Apply recommended rules	732
Monitor your system	734
Monitor system performance	734

Check intrusion prevention events	734
Enable 'fail open' for packet or system failures	734
Switch to prevent mode	734
Implement best practices for specific rules	735
HTTP Protocol Decoding rule	735
Cross-site scripting and generic SQL injection rules	735
Apply NSX security tags	736
Configure intrusion prevention rules	736
See the list of intrusion prevention rules	737
See information about an intrusion prevention rule	737
General Information	737
Details	738
See the list of intrusion prevention rules	738
General Information	739
Identification (Trend Micro rules only)	739
See information about the associated vulnerability (Trend Micro rules only)	739
Assign and unassign rules	740
Automatically assign updated required rules	741
Configure event logging for rules	741
Generate alerts	742
Setting configuration options (Trend Micro rules only)	742
Schedule active times	743
Exclude from recommendations	744
Set the context for a rule	744
Override the behavior mode for a rule	744
Override rule and application type configurations	745
Export and import rules	746
Configure an SQL injection prevention rule	746
What is an SQL injection attack?	747

What are common characters and strings used in SQL injection attacks?	747
How does the Generic SQL Injection Prevention rule work?	749
Examples of the rule and scoring system in action	751
Example 1: Logged and dropped traffic	751
Example 2: No logged or dropped traffic	752
Configure the Generic SQL Injection Prevention rule	753
Character encoding guidelines	756
Application types	758
See a list of application types	758
General Information	759
Connection	759
Configuration	760
Options	760
Assigned To	760
Inspect SSL or TLS traffic	760
Configure SSL inspection	761
Change port settings	762
Use Intrusion Prevention when traffic is encrypted with Perfect Forward Secrecy (PFS)	762
Special considerations for Diffie-Hellman ciphers	763
Supported ciphers	764
Supported protocols	765
Configure anti-evasion settings	765
Performance tips for intrusion prevention	768
Maximum size for configuration packages	769
Control endpoint traffic using the firewall	770
Firewall rules	770
Set up the Deep Security firewall	771
Test Firewall rules before deploying them	772
Test in Tap mode	773

Test in Inline mode	773
Enable 'fail open' behavior	774
Turn on Firewall	775
Default Firewall rules	776
Default Bypass rule for Deep Security Manager Traffic	777
Restrictive or permissive Firewall design	778
Restrictive Firewall	778
Permissive Firewall	778
Firewall rule actions	778
Firewall rule priorities	779
Allow rules	780
Force Allow rules	780
Bypass rules	780
Recommended Firewall policy rules	780
Test Firewall rules	781
Reconnaissance scans	782
Stateful inspection	783
Example	784
Important things to remember	785
Create a firewall rule	786
Add a new rule	786
Select the behavior and protocol of the rule	787
Select a Packet Source and Packet Destination	789
Configure rule events and alerts	791
Alerts	791
Set a schedule for the rule	791
Assign a context to the rule	791
See policies and computers a rule is assigned to	792
Export a rule	792

Delete a rule	792
Allow trusted traffic to bypass the firewall	792
Create a new IP list of trusted traffic sources	792
Create incoming and outbound firewall rules for trusted traffic using the IP list	793
Assign the firewall rules to a policy used by computers that trusted traffic flows through	793
Firewall rule actions and priorities	794
Firewall rule actions	794
More about Allow rules	794
More about Bypass rules	795
Default Bypass rule for Deep Security Manager traffic	795
More about Force Allow rules	796
Firewall rule sequence	797
A note on logging	798
How firewall rules work together	798
Rule Action	799
Rule priority	800
Putting rule action and priority together	800
Firewall settings	801
General	801
Firewall	801
Firewall Stateful Configurations	802
Port Scan (Computer Editor only)	802
Assigned Firewall Rules	802
Interface Isolation	803
Interface Isolation	803
Interface Patterns	803
Reconnaissance	804
Reconnaissance Scans	804
Advanced	806

Events	806
Events	807
Firewall settings with Oracle RAC	807
Add a rule to allow communication between nodes	807
Add a rule to allow UDP port 42424	808
Allow other RAC-related packets	810
Ensure that the Oracle SQL Server rule is assigned	813
Ensure that anti-evasion settings are set to "Normal"	813
Define stateful firewall configurations	814
Add a stateful configuration	815
Enter stateful configuration information	815
Select packet inspection options	815
IP packet inspection	815
TCP packet inspection	816
FTP Options	817
UDP packet inspection	818
ICMP packet inspection	818
Export a stateful configuration	819
Delete a stateful configuration	819
See policies and computers a stateful configuration is assigned to	819
Scan for open ports	820
Container Firewall rules	821
Kubernetes Firewall rules	821
Swarm Firewall rules	822
Monitor for system changes with integrity monitoring	823
Set up integrity monitoring	824
How to enable Integrity Monitoring	824
Turn on Integrity Monitoring	824
Run a Recommendation scan	825

Apply the Integrity Monitoring rules	826
Build a baseline for the computer	828
Periodically scan for changes	828
Test Integrity Monitoring	828
When Integrity Monitoring scans are performed	829
Integrity Monitoring scan performance settings	830
Limit CPU usage	830
Change the content hash algorithm	831
Enable a VM Scan Cache configuration	831
Integrity Monitoring event tagging	832
Create an integrity monitoring rule	832
Add a new rule	833
Enter Integrity Monitoring rule information	833
Select a rule template and define rule attributes	834
Registry Value template	834
File template	834
Custom (XML) template	835
Configure Trend Micro Integrity Monitoring rules	835
Configure rule events and alerts	836
Real-time event monitoring	836
Alerts	836
See policies and computers a rule is assigned to	836
Export a rule	836
Delete a rule	837
Integrity monitoring rules language	837
Entity Sets	838
Hierarchies and wildcards	839
Syntax and concepts	840
Include tag	841

Exclude tag	842
Case sensitivity	842
Entity features	843
ANDs and ORs	845
Order of evaluation	846
Entity attributes	846
Shorthand attributes	847
onChange attribute	848
Environment variables	848
Environment variable overrides	849
Registry values	849
Use of "."	850
Best practices	850
DirectorySet	851
Tag Attributes	851
Entity Set Attributes	852
Short Hand Attributes	853
Meaning of "Key"	853
Sub Elements	854
FileSet	854
Tag Attributes	854
Entity Set Attributes	855
Short Hand Attributes	856
Drives Mounted as Directories	856
Alternate Data Streams	857
Meaning of "Key"	858
Sub Elements	858
Special attributes of Include and Exclude for FileSets:	858
GroupSet	858

Tag Attributes	859
Entity Set Attributes	859
Short Hand Attributes	859
Meaning of "Key"	859
Include and Exclude	859
InstalledSoftwareSet	860
Tag Attributes	860
Entity Set Attributes	860
Short Hand Attributes	861
Meaning of "Key"	861
Sub Elements	862
Special attributes of Include and Exclude for InstalledSoftwareSets:	862
PortSet	862
Tag Attributes	863
Entity Set Attributes	863
Meaning of "Key"	864
IPV6	864
Matching of the Key	864
Sub Elements	865
Special attributes of Include and Exclude for PortSets:	865
ProcessSet	866
Tag Attributes	866
Entity Set Attributes	866
Short Hand Attributes	867
Meaning of "Key"	867
Sub Elements	867
Special attributes of Include and Exclude for ProcessSets:	868
RegistryKeySet	869
Tag Attributes	869

Entity Set Attributes	870
Short Hand Attributes	870
Meaning of "Key"	870
Sub Elements	870
RegistryValueSet	871
Tag Attributes	871
Entity Set Attributes	871
Short Hand Attributes	872
Meaning of "Key"	872
Default Value	872
Sub Elements	873
ServiceSet	873
Tag Attributes	874
Entity Set Attributes	874
Short Hand Attributes	875
Meaning of "Key"	875
Sub Elements	876
Special attributes of Include and Exclude for ServiceSets:	876
UserSet	876
Tag Attributes	877
Entity Set Attributes	877
Common Attributes	877
Windows-only Attributes	878
Linux-only Attributes	878
Short Hand Attributes	878
Meaning of "Key"	879
Sub Elements	880
Include and Exclude	880
Special attributes of Include and Exclude for UserSets	880

WQLSet	881
Entity Set Attributes	882
Meaning of Key	884
Include Exclude	885
Virtual Appliance Scan Caching	885
Scan Cache Configurations	886
Malware Scan Cache Configuration	887
Integrity Monitoring Scan Cache Configuration	887
Scan Cache Settings	887
When to change the default configuration	888
Analyze logs with log inspection	889
Set up log inspection	890
Turn on the log inspection module	890
Run a recommendation scan	890
Apply the recommended log inspection rules	891
Test Log Inspection	892
Configure log inspection event forwarding and storage	892
Define a log inspection rule for use in policies	893
Create a new log inspection rule	894
Decoders	896
Subrules	897
Groups	898
Rules, ID, and Level	898
Description	900
Decoded As	900
Match	900
Conditional Statements	901
Hierarchy of Evaluation	902
Restrictions on the Size of the Log Entry	903

Composite Rules	904
Real world examples	905
Log inspection rule severity levels and their recommended use	914
strftime() conversion specifiers	915
Examine a log inspection rule	916
Log inspection rule structure and the event matching process	916
Duplicate Sub-rules	919
Block access to malicious URLs with web reputation	920
Turn on the web reputation module	921
Switch between inline and tap mode	921
Enforce the security level	922
To configure the security level:	922
Create exceptions	923
To create URL exceptions:	923
Configure the Smart Protection Server	924
Smart Protection Server Connection Warning	925
Edit advanced settings	925
Blocking Page	925
Alert	926
Ports	926
Test Web Reputation	926
Deep Security Scanner	927
Activate the Deep Security Scanner feature	927
Add the SAP Server	928
Enable the SAP integration feature in a computer or policy	928
Set up SAP integration	928
Deep Security and SAP components	930
Install the agent	931
Add the SAP server to the manager	932

Activate SAP in the manager	932
Add the SAP server	933
Activate the agent	933
Assign a security profile	936
Configure SAP to use the agent	942
Configure the Trend Micro scanner group	943
Configure the Trend Micro virus scan provider	949
Configure the Trend Micro virus scan profile	955
Test the virus scan interface	964
Supported MIME types	970
Deep Security Best Practice Guide	974
Maintain	975
Check your license information	975
Back up and restore your database	976
Back up your database	976
Restore the database only	976
Restore both the Deep Security Manager and the database	977
Export objects in XML or CSV format	977
Import objects	979
Restart the Deep Security Manager	979
Linux	979
Windows	980
Windows desktop	980
Command prompt	980
PowerShell	980
Upgrade Deep Security	981
About upgrades	981
How agents validate the integrity of updates	982
How Deep Security Manager checks for software updates	983

Update the Deep Security Agent	984
Update available notifications	984
Initiate an agent update	985
Select the agent for newly-activated virtual appliances	986
Manually upgrade the agent	986
Windows	987
Linux	987
Upgrade the Deep Security Virtual Appliance	987
Upgrade an existing appliance SVM automatically	988
Step 1: Verify permissions	989
Step 2: Import the new virtual appliance packages into the manager	989
Step 3: Upgrade the appliance SVM in the manager	990
Troubleshooting the 'Appliance (SVM) Upgrade Failed' system event	994
Step 4: Final step	995
Upgrade an existing appliance SVM manually	995
Step 1: Import the new virtual appliance packages into the manager	995
Step 2: Review or restore identified files	996
Step 3: Migrate guest VMs to another ESXi host	996
Step 4: Upgrade your old appliance SVM	998
Step 5: Check that maintenance mode was turned off	1004
Step 6: Check that the new appliance SVM is activated	1004
Step 7: Final step	1007
Upgrade the agent embedded on the appliance SVM and apply OS patches	1007
Compatibility table: appliance, agent, and patch	1009
Determine the installed appliance version	1009
Error: The installer could not establish a secure connection to the database server	1009
Upgrade the NSX license to Advanced or Enterprise	1010
Step 1: Upgrade to NSX Advanced or Enterprise	1011
Step 2: Remove Deep Security from NSX completely	1017

Step 3: Redeploy the Deep Security Virtual Appliance	1017
Get and distribute security updates	1018
Configure a security update source and settings	1021
Configure Anti-Malware Engine Update	1022
Perform security updates	1023
Special case: configure updates on a relay-enabled agent in an air-gapped environment	1023
Check your security update status	1024
See details about pattern updates	1024
See details about rule updates	1025
Use a web server to distribute software updates	1026
Web server requirements	1027
Copy the folder structure	1027
Configure agents to use the new software repository	1029
Disable emails for New Pattern Update alerts	1030
Harden Deep Security	1031
Protect Deep Security Manager with an agent	1031
Protect Deep Security Agent	1033
Bind Deep Security Agent to a specific Deep Security Manager	1033
Replace the Deep Security Manager SSL certificate	1035
See your trusted certificates	1036
Replace the SSL certificate in a Windows environment	1036
Create a new .keystore file and add your certificates to the cacerts file	1036
Create a PKCS12 keychain file and import it into the new .keystore file	1038
Configure Deep Security Manager to use the new .keystore file	1039
Replace the SSL certificate in a Linux environment	1040
Create a new .keystore file and add your certificates to the cacerts file	1040
Create a PKCS12 keychain file and import it into the new .keystore file	1041
Configure the Deep Security Manager to use the new .keystore file	1042
Encrypt communication between the Deep Security Manager and the database	1043

Encrypt communication between the manager and database	1043
Microsoft SQL Server database (Linux)	1043
Microsoft SQL Server (Windows)	1045
Oracle Database	1047
PostgreSQL	1049
Running an agent on the database server	1049
Disable encryption between the manager and database	1049
Microsoft SQL Server database (Linux)	1050
Microsoft SQL Server (Windows)	1050
Oracle Database	1051
PostgreSQL	1051
Change the Deep Security Manager database password	1051
Change your Microsoft SQL Server password	1052
Change your Oracle password	1053
Change your PostgreSQL password	1053
Enable Content Security Policy and HTTP Public Key Pinning	1054
Add a content security policy or public key pin policy	1055
Reset your configuration	1055
Content security policy	1055
Public key pin policy	1055
Enforce user password rules	1056
Specify password requirements	1056
Use another identity provider for sign-on	1057
Add a message to the Deep Security Manager Sign In page	1057
Present users with terms and conditions	1058
Other Security settings	1058
Set up multi-factor authentication	1058
Enable multi-factor authentication	1059
Disable multi-factor authentication	1061

Supported multi-factor authentication (MFA) applications	1062
Troubleshooting MFA	1063
What if my MFA is enabled but not working?	1063
What if my MFA device is lost or stops working?	1063
Manage AWS regions	1064
Add an Amazon Web Services region	1064
Viewing your Amazon Web Services regions	1065
Removing an Amazon Web Services region	1065
Configure alerts	1066
View alerts in Deep Security Manager	1067
Configure alert settings	1068
Set up email notification for alerts	1068
Turn alert emails on or off	1069
Configure an individual user to receive alert emails	1071
Configure recipients for all alert emails	1071
Generate reports about alerts and other activity	1071
Set up a single report	1071
Set up a recurring report	1075
Customize the dashboard	1077
Date and time range	1077
Computers and computer groups	1078
Filter by tags	1079
Select dashboard widgets	1080
Monitoring:	1081
System:	1082
Ransomware:	1082
Anti-Malware:	1082
Web Reputation:	1083
Firewall:	1083

Intrusion Prevention:	1084
Integrity Monitoring:	1085
Log Inspection:	1086
Application Control:	1086
Change the layout	1086
Save and manage dashboard layouts	1087
Events in Deep Security	1088
Where are event logs on the agent?	1088
When are events sent to the manager?	1089
How long are events stored?	1090
System events	1090
Security events	1090
See the events associated with a policy or computer	1091
View details about an event	1091
Filter the list to search for an event	1092
Export events	1093
Improve logging performance	1093
Log and event storage best practices	1094
Troubleshooting	1096
Limit log file sizes	1097
Event logging tips	1098
Apply tags to identify and group events	1099
Manual tagging	1100
Auto-tagging	1100
Set the precedence for an auto-tagging rule	1101
Auto-tagging log inspection events	1102
Trusted source tagging	1103
Local trusted computer	1103

How does Deep Security determine whether an event on a target computer matches an event on a trusted source computer?	1104
Tag events based on a local trusted computer	1104
Tag events based on the Trend Micro Certified Safe Software Service	1105
Tag events based on a trusted common baseline	1105
Delete a tag	1106
Reduce the number of logged events	1107
Rank events to quantify their importance	1109
Web reputation event risk values	1110
Firewall rule severity values	1110
Intrusion prevention rule severity values	1110
Integrity monitoring rule severity values	1111
Log inspection rule severity values	1111
Asset values	1111
Forward Deep Security events to an external syslog or SIEM server	1111
Forward system events to a syslog or SIEM server	1112
Forward security events to a syslog or SIEM server	1113
Forward security events directly from agent computers to a syslog or SIEM server	1113
Forward security events from the agent computers via the Deep Security Manager	1114
Define a syslog configuration	1115
Troubleshooting	1118
"Failed to Send Syslog Message" alert	1118
Can't edit syslog configurations	1118
Can't see the syslog configuration sections of Deep Security Manager	1118
Syslog not transferred due to an expired certificate	1119
Syslog not delivered due to an expired or changed server certificate	1119
Syslog or SIEM servers used for testing	1119
Syslog message formats	1119
CEF syslog message format	1120

LEEF 2.0 syslog message format	1123
Events originating in the Manager	1123
System event log format	1123
Events originating in the agent	1124
Anti-malware event format	1124
Application control event format	1138
Firewall event log format	1143
Integrity monitoring log event format	1146
Intrusion prevention event log format	1148
Log inspection event format	1152
Web reputation event format	1154
Configure Red Hat Enterprise Linux to receive event logs	1156
Set up a Syslog on Red Hat Enterprise Linux 6 or 7	1156
Set up a Syslog on Red Hat Enterprise Linux 5	1157
Access events with Amazon SNS	1158
Create an AWS user	1159
Create an Amazon SNS topic	1160
Enable SNS	1160
Create subscriptions	1161
SNS configuration in JSON format	1161
Version	1161
Statement	1162
Topic	1162
Condition	1162
Bool	1163
Exists	1164
IpAddress	1165
NotIpAddress	1166
NumericEquals	1167

NumericNotEquals	1168
NumericGreaterThan	1169
NumericGreaterThanEquals	1170
NumericLessThan	1171
NumericLessThanEquals	1172
StringEquals	1173
StringNotEquals	1174
StringEqualsIgnoreCase	1175
StringNotEqualsIgnoreCase	1175
StringLike	1175
StringNotLike	1176
Multiple statements vs. multiple conditions	1178
Multiple statements	1178
Multiple conditions	1179
Example SNS configurations	1180
Send all critical intrusion prevention events to an SNS topic	1180
Send different events to different SNS topics	1181
Events in JSON format	1182
Valid event properties	1182
Data types of event properties	1197
Example events in JSON format	1198
System event	1198
Anti-malware events	1200
DevOps, automation and scaling	1203
DevOps, automation and scaling	1203
Forward system events to a remote computer via SNMP	1204
Lists of events and alerts	1204
Predefined alerts	1205
Agent events	1215

System events	1220
Anti-malware events	1251
What information is displayed for anti-malware events?	1251
List of all anti-malware events	1253
Firewall events	1254
What information is displayed for firewall events?	1254
List of all firewall events	1256
Intrusion prevention events	1264
What information is displayed for intrusion prevention events?	1264
List of all intrusion prevention events	1266
Integrity monitoring events	1269
What information is displayed for integrity monitoring events?	1269
List of all integrity monitoring events	1270
Log inspection events	1272
What information is displayed for log inspection events?	1272
List of log inspection security events	1274
Web reputation events	1274
What information is displayed for web reputation events?	1275
Add a URL to the list of allowed URLs	1275
Troubleshoot common events, alerts, and errors	1275
Why am I seeing firewall events when the firewall module is off?	1277
Why am I getting "Unrecognized Client" events?	1277
Troubleshoot "Smart Protection Server disconnected" errors	1278
Check the error details	1278
Is the issue on a Deep Security Virtual Appliance?	1278
Error: Activation Failed	1279
Activation Failed - Protocol Error	1279
Agent-initiated communication	1279
Bidirectional communication	1280

Activation Failed - Unable to resolve hostname	1280
Activation Failed - No agent/appliance	1280
Activation Failed - Blocked port	1280
Error: Agent version not supported	1282
Error: Installation of Feature 'dpi' failed: Not available: Filter	1282
Additional information	1283
Error: Interface out of sync	1283
Check the interfaces on the VM	1284
Check the VM's interface information in vCenter	1284
Check the vmx file and the VM's interface information in Deep Security Manager	1284
Check the VM's interface information in the Deep Security Virtual Appliance	1285
Workaround Options	1286
Option 1	1286
Option 2	1286
Option 3	1286
Further Troubleshooting	1287
Error: Integrity Monitoring Engine Offline and other errors occur after activating a virtual machine	1288
Error: Module installation failed (Linux)	1289
Error: There are one or more application type conflicts on this computer	1290
Resolution	1290
Consolidate ports	1291
Disable the inherit option	1291
Error: Unable to connect to the cloud account	1292
Your AWS account access key ID or secret access key is invalid	1292
The incorrect AWS IAM policy has been applied to the account being used by Deep Security	1292
NAT, proxy, or firewall ports are not open, or settings are incorrect	1293
Error: Unable to resolve instance hostname	1293
Error: Anti-malware engine offline	1294
Agent-based protection	1294

If your agent is Windows:	1295
If your agent is Linux:	1296
Agentless protection	1296
Error: Check Status Failed	1297
Error: Log Inspection Rules Require Log Files	1298
If the file's location is required:	1298
If the files listed do not exist on the protected machine:	1299
Alert: Integrity Monitoring information collection has been delayed	1299
Alert: The memory warning threshold of Manager Node has been exceeded	1300
Increase the allocated memory on a Windows server	1300
Increase the allocated memory on a Linux server	1300
Verify the memory allocation change	1301
Alert: Manager Time Out of Sync	1301
Event: Max TCP connections	1301
Warning: Census, Good File Reputation, and Predictive Machine Learning Service Disconnected	1302
Cause 1: The agent or relay-enabled agent doesn't have Internet access	1303
Cause 2: A proxy was enabled but not configured properly	1303
Warning: Reconnaissance Detected	1304
Types of reconnaissance scans	1304
Suggested actions	1304
Warning: Insufficient disk space	1306
Tips	1306
Create and manage users	1306
Synchronize with an Active Directory	1307
Filtering the Active Directory	1308
Add or edit an individual user	1309
Change a user's password	1312
Lock out a user or reset a lockout	1312
View system events associated with a user	1312

Delete a user	1312
Define roles for users	1313
Add or edit a role	1314
Default settings for full access, auditor, and new roles	1326
Add users who can only receive reports	1335
Add or edit a contact	1336
Delete a contact	1336
Create an API key for a user	1336
Lock out an existing API key	1337
Unlock a locked out user name	1338
Unlock users as an administrator	1338
Unlock administrative users from a command line	1338
Implement SAML single sign-on	1339
What are SAML and single sign-on?	1339
How SAML single sign-on works in Deep Security	1339
Establishing a trust relationship	1339
Creating Deep Security accounts from user identities	1340
Implement SAML single sign-on in Deep Security	1341
Getting started with SAML single sign-on	1341
Configure pre-set up requirements	1342
Configure Deep Security as a SAML service provider	1343
Configure SAML in Deep Security	1345
Import your identity provider's SAML metadata document	1345
Create Deep Security roles for SAML users	1345
Provide information for your identity provider administrator	1346
Download the Deep Security Manager service provider SAML metadata document	1346
Send URNs and the Deep Security SAML metadata document to the identity provider administrator	1346
SAML claims structure	1346
Deep Security user name (required)	1347

Sample SAML data (abbreviated)	1347
Deep Security user role (required)	1347
Sample SAML data (abbreviated)	1348
Maximum session duration (optional)	1348
Sample SAML data (abbreviated)	1348
Preferred language (optional)	1349
Sample SAML data (abbreviated)	1349
Test SAML single sign-on	1350
Review the set-up	1350
Create a Diagnostic Package	1350
Service and identity provider settings	1350
Navigate and customize Deep Security Manager	1351
Group computers dynamically with smart folders	1351
Create a smart folder	1352
Edit a smart folder	1355
Clone a smart folder	1355
Focus your search using sub-folders	1355
Automatically create sub-folders	1356
Searchable Properties	1357
General	1357
AWS	1360
Azure	1363
vCenter	1363
vCloud	1364
Folder	1364
Operators	1365
View active Deep Security Manager nodes	1367
Customize advanced system settings	1369
Primary Tenant Access	1369

Load Balancers	1370
Multi-tenant Mode	1370
Deep Security Manager Plug-ins	1371
SOAP Web Service API	1371
Status Monitoring API	1371
Export	1372
Whois	1372
Licenses	1372
CPU Usage During Recommendation Scans	1373
NSX	1373
Logo	1373
Manager AWS Identity	1374
Application control	1374
Accelerate compliance	1379
Meet PCI DSS requirements with Deep Security	1380
GDPR	1380
FIPS 140-2 support	1381
Differences when operating Deep Security in FIPS mode	1382
System requirements for FIPS mode	1383
Deep Security Manager requirements	1383
Deep Security Agent requirements	1384
Deep Security Virtual Appliance requirements	1384
Enable FIPS mode for your Deep Security Manager	1384
Enable FIPS mode for a Deep Security Manager on Windows	1384
Enable FIPS mode for a Deep Security Manager on Linux	1385
Connect to external services when in FIPS mode	1385
Enable FIPS mode for the operating system of the computers you are protecting	1386
Enable FIPS mode for the Deep Security Agent on the computers you are protecting	1386
Enable FIPS mode for a Windows agent	1386

Enable FIPS mode for an RHEL 7 or CentOS 7 agent	1387
Enable FIPS mode for the Deep Security Virtual Appliance	1387
Using FIPS mode with a PostgreSQL database	1387
Using FIPS mode with a Microsoft SQL Server database	1391
Disable FIPS mode	1393
Bypass vulnerability management scan traffic in Deep Security	1394
Create a new IP list from the vulnerability scan provider IP range or addresses	1394
Create firewall rules for incoming and outbound scan traffic	1395
Assign the new firewall rules to a policy to bypass vulnerability scans	1396
Use TLS 1.2 with Deep Security	1396
Benefits of TLS 1.2	1399
TLS 1.2 architectures	1399
Upgrade components to use TLS 1.2	1404
Verify and upgrade your Deep Security Manager	1404
Verify your Deep Security Manager database	1404
Verify your Deep Security Agents	1405
Verify your Deep Security Relays	1405
Verify your Deep Security Virtual Appliance	1406
Enforce TLS 1.2	1406
Where can TLS 1.2 be enforced?	1407
What happens when TLS 1.2 enforced?	1407
Is TLS 1.2 enforced by default?	1408
Under what circumstances is TLS 1.2 enforcement possible?	1408
Enforce TLS 1.2 on Deep Security Manager	1408
Enforce TLS 1.2 on the Deep Security Relay	1409
Enforce TLS 1.2 on just the manager's GUI port (4119)	1409
Test that TLS 1.2 is enforced	1410
Enable early TLS (1.0)	1412
Enable TLS 1.0 on Deep Security Manager and the Deep Security Relay	1412

Enable TLS 1.0 on the manager's GUI port (4119)	1413
Enable TLS 1.0 in deployment scripts	1413
Determine whether TLS 1.2 is enforced	1414
Guidelines for deploying agents, virtual appliances, and relays after TLS 1.2 is enforced	1415
Guidelines for deploying agents, virtual appliances, and relays when TLS 1.2 is enforced	1415
Guidelines for using deployment scripts when TLS 1.2 is enforced	1415
Upgrade the Deep Security cryptographic algorithm	1416
Upgrade the algorithm on Windows	1416
Upgrade the algorithm on Linux	1417
Upgrade the algorithm in a multi-node environment	1417
Upgrade the algorithm in a multi-tenant environment	1417
Migrate a Microsoft SQL Server Express database to Enterprise	1418
Uninstall Deep Security	1419
Uninstall Deep Security Relay	1420
Uninstall a relay (Windows)	1420
Uninstall a relay (Linux)	1420
Uninstall Deep Security Agent	1421
Uninstall an agent (Windows)	1421
Uninstall an agent (Linux)	1422
Uninstall an agent (Solaris 9 or 10)	1423
Uninstall an agent (Solaris 11)	1423
Uninstall an agent (AIX)	1423
Uninstall an agent (HP-UX)	1423
Uninstall Deep Security Notifier	1424
Uninstall Deep Security Manager	1424
Uninstall the manager (Windows)	1424
Uninstall the manager (Linux)	1425
Uninstall Deep Security from your NSX environment	1425
Uninstall Deep Security from NSX automatically	1426

Uninstall Deep Security from NSX manually	1430
Step 1: Remove the NSX Manager from Deep Security Manager	1430
Step 2: Remove the Trend Micro service on NSX Manager	1431
Automate offline computer removal with inactive agent cleanup	1438
Enable inactive agent cleanup	1439
Ensure computers that are offline for extended periods of time remain protected with Deep Security	1439
Set an override to prevent specific computers from being removed	1440
Check the audit trail for computers removed by an inactive cleanup job	1440
Search system events	1441
System event details	1442
2953 - Inactive Agent Cleanup Completed Successfully	1442
251 - Computer Deleted	1442
716 - Reactivation Attempted by Unknown Agent	1442
FAQs	1443
Deep Security release strategy and life cycle policy	1443
Support milestones for major releases	1444
Major release support services	1444
Agent platform support policy	1445
Agent platform support policy:	1445
Why does my Windows machine lose network connectivity when I turn on protection?	1447
How do I get news about Deep Security?	1447
AWS GovCloud (US) support	1448
Protecting GovCloud instances using a manager in a commercial AWS instance	1449
How can I minimize heartbeat alerts for offline environments in an AWS Elastic Beanstalk environment?	1449
Why can't I add my Azure server using the Azure cloud connector?	1451
Why can't I view all of the VMs in an Azure subscription in Deep Security?	1451
Troubleshooting	1452
"Activation Failed" agent status	1452
"Offline" agent	1452

Causes	1452
Verify that the agent is running	1454
Verify DNS	1454
Allow outbound ports (agent-initiated heartbeat)	1455
Allow inbound ports (manager-initiated heartbeat)	1456
Allow ICMP on Amazon AWS EC2 instances	1457
High CPU usage	1457
"Anti-Malware Driver Offline" status with VMware	1458
Anti-Malware Windows platform update failed	1458
An incompatible Anti-Malware component from another Trend Micro product	1458
An incompatible Anti-Malware component from a third-party product	1459
Other/unknown Error	1459
Performance issues on an agentless virtual machine	1459
Cause: Limited resources	1459
Cause: Anti-malware	1459
Cause: Network traffic	1460
Cause: Policy	1460
Cause: High CPU	1460
Cause: Security Update	1461
Security update connectivity	1461
SQL Server domain authentication problems	1462
Step 1: Verify the host name and domain	1463
Step 2: Verify the servicePrincipalName (SPN)	1464
Step 2a: Identify the account (SID) running the SQL Server service	1465
Step 2b: Find the account in Active Directory	1467
Step 2c: Identify which FQDN to use in the SPN	1468
Step 2d: Identify whether you're using a default instance or named instance	1468
Case 1: Set the SPN under a local virtual account	1469
Case 2: Set the SPN under a domain account	1471

Case 3: Set the SPN under a Managed Service account	1473
Case 4: Set the SPN for a failover cluster	1475
SPN references	1477
SPN debugging tips	1477
Step 3: Verify the krb5.conf file (Linux only)	1478
Step 4: Verify the system clock	1480
Step 5: Verify the firewall	1480
Purple screen of death	1481
Prevent MTU-related agent communication issues across Amazon Virtual Private Clouds (VPC)	1481
Create a diagnostic package and logs	1484
Deep Security Manager diagnostics	1484
Create a diagnostic package for Deep Security Manager	1484
Enable debug logs for Deep Security Manager	1484
Deep Security Agent diagnostics	1485
Create an agent diagnostic package via Deep Security Manager	1486
Create an agent diagnostic package via CLI on a protected computer	1487
Collect debug logs with DebugView	1488
Increase verbose diagnostic package process memory	1489

Get Started

Privacy and personal data collection disclosure

Certain features available in Trend Micro products collect and send feedback regarding product usage and detection information to Trend Micro. Some of this data is considered personal in certain jurisdictions and under certain regulations. If you do not want Trend Micro to collect personal data, you must ensure that you disable the related features.

The following link outlines the types of data that Trend Micro Deep Security collects and provides detailed instructions on how to disable the specific features that feed back the information.

<https://success.trendmicro.com/data-collection-disclosure>

Data collected by Trend Micro is subject to the conditions stated in the Trend Micro Privacy Policy:

https://www.trendmicro.com/en_us/about/legal/privacy-policy-product.html

[Skip To Main Content](#)

Filter:

- All Files

Submit Search

D

Deep Security Software

Long Term Support (LTS)
[Subscribe via RSS](#)

Feature Releases (FR) Earlier Versions

© 2020 Trend Micro
Incorporated. All rights reserved.

Protection for VMware environments

Trend Micro Deep Security has worked closely with VMware to offer agentless security at the hypervisor level. This security is provided by the Deep Security Virtual Appliance. The appliance is deployed at the cluster level through NSX Manager to offer protection to VMs on the same ESXi host.

Topics on this page:

- ["Deep Security Virtual Appliance features" below](#)
- ["VMware deployments with the virtual appliance and NSX 6.3 or higher" on the next page](#)
- ["VMware deployments without the virtual appliance and NSX \(agent only\)" on page 70](#)
- ["Additional information" on page 71](#)

Deep Security Virtual Appliance features

Scan caching

The scan cache allows the results of an anti-malware scan to be used when scanning multiple machines with the same files. When the appliance scans the original guest virtual machine, it keeps track of attributes of the files it is scanning. When other virtual machines are scanned, it can compare these attributes for each file. This means that subsequent files with the same attributes do not need to be scanned fully a second time, which reduces the overall scan time. In situations like virtual desktop infrastructure (VDI) where the images are nearly identical, the performance savings from scan cache are greater.

Scan storm optimization

A 'scan storm' occurs where many scans occur concurrently, causing performance slowdowns. Typically, scan storms occur in large-scale VDI deployments. When performing anti-malware scanning, the appliance can use the [scan cache](#) feature to optimize its resource usage during a scan storm.

Ease of management

Generally, deploying one Deep Security Virtual Appliance to each ESXi host is easier than deploying an agent on multiple VMs. With NSX, this management savings increases because NSX Manager automatically deploys Deep Security the service when you add a new ESXi host to the cluster.

The virtual appliance can also help with network flexibility. Each Deep Security Agent requires network connectivity to resolve the Deep Security Manager and Relay. By using the Deep Security Virtual Appliance, this network connectivity is limited to the virtual appliance and connectivity to each VM is not required.

In some cases, the infrastructure and VMs may be managed by different teams. By using the virtual appliance, the infrastructure team does not require access to the virtual machine to add protection because it can be deployed at the hypervisor level to protect each of the virtual machines.

VMware deployments with the virtual appliance and NSX 6.3 or higher

If you want to use the Deep Security Virtual Appliance to protect your guest VMs, you'll need to use VMware NSX. NSX has several license types. These license types are shown in the table below, along with the Deep Security features supported by each.

Note: For an exhaustive list of supported features and sub-features that are supported by the Deep Security Virtual Appliance, see "[Deep Security Virtual Appliance \(NSX\) \(with embedded 11.3 agent\)](#)" on page 97.

	Deep Security Virtual Appliance deployment (agentless)	
	NSX Advanced OR NSX Enterprise	NSX for vShield Endpoint (free) OR NSX Standard OR NSX Professional
Anti-malware	✓ (Windows guest VMs only)	✓ (Windows guest VMs only)
Integrity monitoring	✓ (Windows guest VMs only)	✓ (Windows guest VMs only)
Firewall	✓	X ¹
Intrusion prevention	✓	X ¹
Web reputation	✓	X ¹
Log inspection	X ¹	X ¹
Application control	X ¹	X ¹

¹ Available if you install an agent on each of your guest VMs ([combined mode](#))

With **NSX Advanced** or **Enterprise**, the Deep Security Virtual Appliance can perform anti-malware (for Windows guest VMs only), integrity monitoring (for Windows guest VMs only), firewall, intrusion prevention, and web reputation for all guest VMs. There is no need to install agents on the VMs. If however, you want log inspection and application control, or you want anti-malware and integrity monitoring for Linux VMs, you'll need to install agents.

With **NSX for vShield Endpoint (free)**, **NSX Standard**, or **NSX Professional**, the Deep Security Virtual Appliance supports anti-malware, and integrity monitoring on Windows VMs. You'll need to install agents if you want the firewall, intrusion prevention, web reputation, log inspection, application control features, or if you want anti-malware and integrity monitoring for Linux VMs.

When you install agents to supplement the virtual appliance's functionality, this is known as [combined mode](#).

Some key points when considering combined mode:

- Management: Deep Security has deployment scripts that can be used to script the deployment of the Deep Security Agent using various orchestration tools (Chef, Puppet, etc). Using the [deployment scripts](#) allows for easier deployment of the agent. These scripts also allow activation and assignment of policy. They help to reduce the manual intervention required and reduce the management cost when deploying the agent in a VMware environment.
- "Scan caching" on page 67 performance improvements and "Scan storm optimization" on page 68: In combined mode, the virtual appliance will do scan caching and scan storm optimization for anti-malware scanning. This allows the agent footprint on each VM to remain small because only a network driver needs to be installed.

For details on how to set up the Deep Security Virtual Appliance environment, see ["Deploy the Deep Security Virtual Appliance with NSX" on page 238](#).

VMware deployments without the virtual appliance and NSX (agent only)

If you want to protect VMware environments without NSX, you can do so by deploying the Deep Security Agent to each of your VMs. In this scenario, you don't need the Deep Security Virtual Appliance, since all protection is provided by the agents. By using the Deep Security Agent, you get all of main features of Deep Security, namely: [anti-malware](#), [integrity monitoring](#), [firewall](#), [intrusion prevention](#), [web reputation](#), [log inspection](#), and [application control](#). In addition, the agent has the following characteristics:

- It is lightweight (a Smart Agent). Only the protection modules that you specify (for example, anti-malware and integrity monitoring) are installed using a policy that you set up on the manager. Further, Deep Security has a feature called 'recommendation scanning', which allows you to only assign rules necessary for the specific workload you are protecting.
- Windows agents include an anti-malware scan cache, containing hashes of previously-scanned files that are frequently accessed, so that they don't need to be rescanned.

To deploy agents, Trend Micro has provided [deployment scripts](#) that can be used with various orchestration tools (Chef, Puppet, etc). You can also [install the agent manually](#).

Additional information

- Trend Micro and VMware Website: <http://www.trendmicro.com/VMware/>

What's new?

Deep Security 11.3

Below are major changes in the **feature release** Deep Security 11.3. For the support life cycle, see "[Feature releases](#)" on the next page. For a detailed change log, see the [Deep Security release notes](#).

- **Deep Security API updates:** The Deep Security API now includes a Python SDK and the API reference includes Python examples. The API also introduces a new `/roles` endpoint. For more information, visit the [Deep Security Automation Center](#).
- **Upgrade on activation:** Deep Security Manager 11.3 provides an option that instructs Deep Security Agents to automatically upgrade to the latest compatible version of the agent software when the agent is activated. For details, see "[Automatically upgrade agents on activation](#)" on page 341.

Note: Upgrade on activation is initially supported for Linux platforms only (Windows and UNIX platforms are skipped when the feature is enabled) and is controlled through a global system setting.

- **Seamless appliance upgrade:** The appliance Service Virtual Machine (SVM) upgrade process has been simplified. You can now automatically upgrade the selected appliance SVMs and agents inside the VMware NSX for vSphere infrastructure. The new upgrade process reduces the complex steps required to upgrade manually. See "[Upgrade the Deep Security Virtual Appliance](#)" on page 987.
- **Logging improvement:** To help with troubleshooting and to allow for the correlation of events between the Deep Security Manager and the Deep Security Agent, you can now

choose to include the time zone in events. See ["Forward Deep Security events to an external syslog or SIEM server" on page 1111](#).

- **New agent platform support:** Deep Security Agent 11.3 adds support for:
 - Windows 10 version 1809 (RS5)
 - Windows Server 2019
 - Windows 10 Embedded (64-bit), Windows 8.1 Embedded (32-bit), and Windows 7 Embedded (32-bit). For important details about Windows Embedded support, see ["Supported features by platform" on page 85](#).

Note: The Deep Security Agent for AIX and Solaris have not been tested for use with this feature release. The AIX and Solaris platforms continue to be fully supported using Deep Security Manager 11.0 and will continue to be supported in the next major release (Deep Security 12.0). If you have AIX and/or Solaris platforms in your deployment, please continue to use Deep Security Manager 11.0.

Before you install

Feature releases

Major releases of Deep Security Manager, such as Deep Security Manager 10.0, are made available on an annual basis, and include new functionality and enhancements for existing functionality. Feature releases are interim versions of Deep Security that provide early access to new functionality and are made available at regular intervals between major releases. This means that with feature releases you can immediately benefit from new functionality without having to wait for the next major release of Deep Security. Feature releases meet the same quality and release criteria as major releases, and are intended for use in production environments.

Feature releases are comprised of new versions of Deep Security Manager and Agent. The new manager is compatible with both the new and older versions of agent. However, new features in a feature release can require that both the new manager and the new agent are used. For information about which new features require an agent update, see "What's New".

While several feature releases may become available between major releases, the functionality of all feature releases is cumulative and is ultimately rolled into the next major release, which continue to be made available on an annual basis. For example, if you are now using the latest major release of Deep Security, you can obtain the Deep Security feature release to immediately take advantage of new functionality that it provides.

Note: If you are constrained to longer adoption cycles, wait for the next major release to benefit from the new functionality.

For more information about major releases and support services, see "[Deep Security release strategy and life cycle policy](#)" on page 1443.

Version numbers

You can easily distinguish major releases and feature releases by the version number:


- Major releases use the x.0.z version pattern, for example the 10.0 GM version number is 10.0.3259, where 10 is the major version, 0 is the minor version, and 3259 is the build number:
 - Maintenance update versions are distinguished on the [Deep Security Software](#) page with a "U" suffix, for example 10.0_U1.
 - Maintenance updates have the build number incremented, for example the first maintenance update of 10.0 is 10.0.3271.
- Feature releases increment the minor version number, for example 10.1.z, or 10.2.z, where z is the build number.

You can obtain feature releases from the feature releases tab on the [Deep Security Software](#) page.

Feature release life cycle

Deep Security feature releases have a shorter life cycle than major releases, and you should upgrade to the next major release when it becomes available. If you do not upgrade, you risk running an unsupported version of Deep Security. To ease the challenges of scheduling the upgrade in your production environment, support for feature releases is provided until 6 months

after the next major release is available. The following diagram illustrates the timing of feature release availability and the support duration with respect to that of the major releases.



Platform support

Feature releases support the same platforms that the next major release supports, but may support more (or fewer) platforms than the current major release. For a list of operating systems that are supported by the Deep Security Agent, see ["Deep Security Agent platforms" on page 80](#) and for the agent platform support policy, see ["Agent platform support policy" on page 1445](#). If you want to know which Deep Security features are supported for each platform, see ["Supported features by platform" on page 85](#).

Support services

Most support items are provided for feature releases.

Support item	Major release	Feature release	Delivery mechanism
Small enhancements (no change to core functionality)	✓		Update
Linux kernel updates	✓	✓	Linux Kernel Package (LKP)
General bug fixes	✓		Update
Critical bug fixes (system crash or hang, or loss of major functionality)	✓	✓	Update or Hot-fix
Critical and high vulnerability fixes	✓	✓	Update or Hot-fix

Trend Micro Deep Security On-Premise 11.3

Support item	Major release	Feature release	Delivery mechanism
Medium and low vulnerability fixes	✓		Update
Anti-Malware pattern updates	✓	✓	iAU (Active Update)
Intrusion prevention system, integrity monitoring, and log inspection rules updates	✓	✓	iAU
Support for Agents and Deep Security Manager on new versions of supported operating systems	✓		Update

Although updates that include small enhancements, general bug fixes, and support for new versions of operating systems are not provided for feature releases, these improvements are included in new feature release versions. For example, if you use 10.1, to benefit from any of these support items you need to obtain 10.2 when it is released. You should use the currently available feature release to benefit from these continual improvements.

About the Deep Security components

Trend Micro Deep Security provides advanced server security for physical, virtual, and cloud servers. It protects enterprise applications and data from breaches and business disruptions without requiring emergency patching. This comprehensive, centrally managed platform helps you simplify security operations while enabling regulatory compliance and accelerating the ROI of virtualization and cloud projects.

For information on the protection modules that are available for Deep Security, see ["Protect" on page 443](#).

Deep Security consists of the following set of components that work together to provide protection:

- **Deep Security Manager**, the centralized web-based management console that administrators use to configure security policy and deploy protection to the enforcement components: the Deep Security Virtual Appliance and the Deep Security Agent.

- **Deep Security Virtual Appliance** is a security virtual machine built for VMware vSphere environments that agentlessly provides anti-malware and integrity monitoring protection modules for virtual machines in a vShield environment. In an NSX environment, the anti-malware, integrity monitoring, firewall, intrusion prevention, and web reputation modules are available agentlessly.
- **Deep Security Agent** is a security agent deployed directly on a computer which provides application control, anti-malware, web reputation service, firewall, intrusion prevention, integrity monitoring, and log inspection protection to computers on which it is installed.
- The Deep Security Agent contains a **Relay** module. A relay-enabled agent distributes software and security updates throughout your network of Deep Security components.
- **Deep Security Notifier** is a Windows System Tray application that communicates information on the local computer about security status and events, and, in the case of relay-enabled agents, also provides information about the security updates being distributed from the local machine.

System requirements

Each part of a Deep Security deployment has its own system requirements.

- ["Deep Security Manager" below](#)
- ["Deep Security Agent" on page 78](#)
- ["Deep Security Virtual Appliance " on page 79](#)

Requirements vary by version. For older versions of Deep Security Manager, agents, relays, or virtual appliances, see their documentation.

Note: If you plan to operate Deep Security in FIPS mode, see ["FIPS 140-2 support" on page 1381](#) for additional requirements.

Deep Security Manager

For a list of agent versions that are compatible with this version of the manager, see ["Deep Security Agent platforms" on page 80](#).

System component	Requirements
Minimum memory (RAM)	<p>Minimum RAM requirements depend on the number of agents that are being managed. See "Deep Security Manager sizing" on page 104.</p> <p>Note:</p> <p>On Linux, reserved system memory is separate from process memory. Therefore, although the installer's estimate might be similar, it will detect less RAM than the computer actually has. To verify the computer's actual total RAM, log in with a superuser account and enter:</p> <pre>grep MemTotal /proc/meminfo</pre>
Minimum disk space	1.5 GB (200 GB recommended)
Operating system	<ul style="list-style-type: none"> • Red Hat Enterprise Linux 7 (64-bit) • Red Hat Enterprise Linux 6 (64-bit) • Windows Server 2016 (64-bit) • Windows Server 2012 or 2012 R2 (64-bit) • Windows Server 2008 or 2008 R2 (64-bit)
Database	<ul style="list-style-type: none"> • Azure SQL Database (SaaS) (multi-tenancy is not supported) • Microsoft SQL Server 2017 • Microsoft SQL Server 2016 • Microsoft SQL Server 2014 • Microsoft SQL Server 2012 • Microsoft SQL Server 2008 R2 • Microsoft SQL Server 2008 (* Express not supported for this version) • Microsoft SQL RDS • Oracle Database 12c • Oracle Database 11g

System component	Requirements
	<ul style="list-style-type: none"> • Oracle RDS • PostgreSQL 10.x (only Core or Amazon RDS distributions) • PostgreSQL 9.6.x (only Core or Amazon RDS distributions) <p>Disk space required varies by the size of the deployment, data retention, and frequency of logging. See "Sizing" on page 104.</p> <p>Minimum free disk space = (2 x database size) + transaction log</p> <p>For example, if your database plus transaction log is 40 GB, you must have 80 GB (40 x 2) of free disk space for database schema upgrades. To free disk space, delete any unnecessary event log data and transaction logs.</p> <p>Note:</p> <ul style="list-style-type: none"> • Microsoft SQL Server Express is only supported in very limited deployments. See "Microsoft SQL Server Express considerations" on page 132. • Microsoft SQL Server service packs for these versions are also supported. • Oracle Database Express (XE) is not supported. • Oracle container database (CDB) configuration is not supported with Deep Security Manager multi-tenancy. • Apache Derby, which provided an embedded database for proof-of-concept and testing in previous versions of Deep Security, is not supported anymore.

Deep Security Agent

Requirements vary by OS version and the features that you enable. See ["Deep Security Agent and Relay sizing" on page 108](#)

For a list of all operating systems and agent versions that are compatible with Deep Security Manager 11.3, see ["Deep Security Agent platforms" on the next page](#).

Note: [Supported Deep Security features vary by platform](#).

Note: On supported versions of Microsoft Windows, Powershell 4.0 or newer is required to run the agent deployment script.

Deep Security Virtual Appliance

Because the appliance uses the same protection modules as agents, if you import an update to the 64-bit agent for Red Hat, it may notify you that new software is available for the appliance, like it does for Red Hat agents.

Note: VMware does not support running nested ESXi servers in production environments. For more information, see the [VMware Knowledge Base article](#).

System component	Requirements
CPU	64-bit, Intel-VT or AMD-V present and enabled in BIOS 2 vCPU
Minimum memory (RAM)	Varies by the number of VMs being protected. See "Deep Security Virtual Appliance sizing" on page 109 .
Minimum disk space	40 GB
VMware	<ul style="list-style-type: none">• VMware vCenter 6.7 with ESXi 6.7 (supported in Deep Security Manager 11.0 Update 1 and later)• VMware vCenter 6.5 with ESXi 6.0 or 6.5• VMware vCenter 6.0 with ESXi 6.0• VMware Tools on each ESXi host (including Guest Introspection)• VMware NSX Manager 6.3 or later

System component	Requirements
	<p>Note: VMware vSphere 6.5a is the minimum supported version with NSX for vSphere 6.3.0.</p> <p>For details, see the VMware compatibility matrix.</p> <p>For more information about VMware product interoperability, see VMware Interoperability Matrices.</p>
vSwitches	vSphere Distributed Switch (vDS)
Guest operating system	<p>For a list of supported platforms and details about the features supported on each platform, see "Supported features by platform" on page 85.</p> <p>For information on vSphere versions that are compatible with the operating systems listed below, see this VMware Compatibility Guide.</p>

Deep Security Agent platforms

Topics on this page:

- ["Agent platform support table" below](#)
- ["Docker support" on page 83](#)

See also ["Agent platform support policy" on page 1445](#).

Agent platform support table

Deep Security Manager 11.3 supports the Deep Security Agents on the operating systems shown in the table below.

Note: The Deep Security Agent for AIX and Solaris have not been tested for use with Deep Security Manager 11.3, which is a feature release. The AIX and Solaris platforms continue to be fully supported using Deep Security Manager 11.0 and will continue to be supported in the

Trend Micro Deep Security On-Premise 11.3

next major release (Deep Security 12.0). If you have AIX and/or Solaris platforms in your deployment, please continue to use Deep Security Manager 11.0. For more information on support for Solaris, see <https://success.trendmicro.com/solution/1120706>.

Note: The Deep Security Agent can be installed and is fully supported on any of the below platforms running in Amazon AWS or Microsoft Azure.

Note: Not all Deep Security features are available on all platforms. See "[Supported features by platform](#)" on page 85.

Deep Security Agent Platform	Deep Security Agent Version					
	11.3	11.2	11.1	11.0	10.0	9.6
Windows 2000, Service Pack 3 or 4 (32-bit)						✓ (1)
Windows XP (32- and 64-bit)					✓	✓
Windows Server 2003 SP1 (32- and 64-bit)					✓	
Windows Server 2003 SP2 (32- and 64-bit)					✓	
Windows Server 2003 R2 SP2 (32- and 64-bit)					✓	✓
Windows 7 (32- and 64-bit)	✓	✓	✓	✓	✓	✓
Windows 7 Embedded (32-bit) (6)	✓					
Windows Server 2008 (Full) (32- and 64-bit)	✓	✓	✓	✓	✓	✓
Windows Server 2008 R2 (Full) (64-bit)	✓	✓	✓	✓	✓	✓
Windows 8 (32- and 64-bit)	✓	✓	✓	✓	✓	✓
Windows 8.1 (32- and 64-bit)	✓	✓	✓	✓	✓	✓
Windows 8.1 Embedded (32-bit) (6)	✓					
Windows 10 (32- and 64-bit) (2)	✓	✓	✓	✓	✓	✓
Windows 10 Embedded (64-bit) (6)	✓					
Windows Server 2012 (Full) (64-bit)	✓	✓	✓	✓	✓	✓
Windows Server 2012 R2 (Full or Core) (64-bit)	✓	✓	✓	✓	✓	✓
Windows Server 2016 LTS (64-bit)	✓	✓	✓	✓	✓	✓
Windows Server 2016 Version 1709 (RS3) (64-bit)	✓	✓	✓	✓		
Windows Server 2016 Version 1803 (RS4) (64-bit)	✓	✓			✓ (7)	
Windows Server 2019 Version 1809 (64-bit)	✓				✓ (7)	
Red Hat Enterprise Linux 5 (32- and 64-bit)					✓	✓
Red Hat Enterprise Linux 6 (32- and 64-bit)	✓	✓	✓	✓	✓	✓
Red Hat Enterprise Linux 7 (64-bit)	✓	✓	✓	✓	✓	✓
Ubuntu 10.04 (64-bit)						✓
Ubuntu 12.04 (64-bit)						✓
Ubuntu 14.04 (64-bit)					✓	✓
Ubuntu 16.04.1 (64-bit)	✓	✓	✓	✓	✓	✓
Ubuntu 18.04 (64-bit)	✓	✓		✓ (5)		
CentOS 5 (32- and 64-bit)					✓	✓

Trend Micro Deep Security On-Premise 11.3

Deep Security Agent Platform	Deep Security Agent Version					
	11.3	11.2	11.1	11.0	10.0	9.6
CentOS 6 (32- and 64-bit)	✓	✓	✓	✓	✓	✓
CentOS 7 (64-bit)	✓	✓	✓	✓	✓	✓
Debian 6 (64-bit)						✓
Debian 7 (64-bit)	✓	✓	✓	✓	✓	✓
Debian 8 (64-bit)	✓	✓	✓	✓	✓ (3)	
Debian 9 (64-bit)	✓	✓	✓			
Amazon Linux (64-bit)	✓	✓	✓	✓	✓	✓
Amazon Linux 2 (64-bit)	✓	✓	✓	✓	✓ (4)	
Oracle Linux 5 (32- and 64-bit)					✓	✓
Oracle Linux 6 (32- and 64-bit)	✓	✓	✓	✓	✓	✓
Oracle Linux 7 (64-bit)	✓	✓	✓	✓	✓	✓
SUSE Linux Enterprise Server 10 SP3, SP4 (32- and 64-bit)						✓
SUSE Linux Enterprise Server 11 SP1, SP2, SP3 (32- and 64-bit)	✓	✓	✓	✓	✓	✓
SUSE Linux Enterprise Server 11 SP4 (64-bit)	✓	✓	✓	✓		
SUSE Linux Enterprise Server 12 SP1, SP2, SP3 (64-bit)	✓	✓	✓	✓	✓	✓
Cloud Linux 5 (32- and 64-bit)						✓
Cloud Linux 6 (32- and 64-bit)					✓	✓
Cloud Linux 7 (64-bit)	✓	✓			✓	✓

(1) Requires Deep Security Agent 9.6 SP1 Patch 1 Update 17

(2) Microsoft releases regular, semi-annual releases for Microsoft Windows 10. For details about which specific releases are supported, see [Deep Security Support for Windows 10](#).

(3) Requires Deep Security Agent 10.0 Update 1

(4) Requires Deep Security Agent 10.0 Update 8

(5) Requires Deep Security Agent 11.0 Update 2

(6) All Trend Micro testing on Windows Embedded platforms is performed in a virtualized environment. Because these operating systems are typically run on custom hardware (for example, on point-of-sale terminals), customers must plan to thoroughly test on their target hardware platform prior to deployment in a production environment. In addition, before raising support cases, customers should attempt to reproduce problems in a virtualized environment because this is the environment the Trend Micro support team has available. If the issue is specific to deployments on custom hardware, Trend Micro may require the customer to provide us with remote access to a suitable environment before we can fully respond to support cases.

(7) Requires Deep Security Agent 10.0 Update 16

Docker support

You can use Deep Security 10.0 or later to protect Docker hosts and containers running on Linux distributions. Windows is not supported.

With each Deep Security release, Deep Security supports the last two stable releases of Docker Community Edition (CE) and Docker Enterprise Edition (EE). (See [Announcing Docker Enterprise Edition](#).) We do not officially support Docker Edge releases, but strive to test against Docker Edge releases to the best of our ability.

Support for new stable Docker releases is introduced with each release of Deep Security. We recommend that you refrain from upgrading to the latest stable release of Docker until Trend Micro documents the support statements for the latest Deep Security release.

Deep Security release	Supported Docker Releases
Deep Security 10.0	Docker v1.12.x, v1.13.x
Deep Security 11.0	Docker 17.03-ee, 17.06-ee, 17.09-ce, 17.12-ce
Deep Security 11.1	Docker 17.12-ce, 18.03-ce, 17.06-ee
Deep Security 11.2	Docker 18.03-ce, 18.06-ce, 17.06-ee, 18.03-ee
Deep Security 11.3	Docker 18.06-ce, 18.09-ce, 17.06-ee, 18.03-ee

Before deploying Deep Security into your target environment, you should ensure that Docker supports your target environment and platform configuration.

Deep Security Agent Linux kernel support

- [Deep Security Agent 11.3 Linux kernel support](#)
- [Deep Security Agent 11.2 Linux kernel support](#)
- [Deep Security Agent 11.1 Linux kernel support](#)
- [Deep Security Agent 11.0 Linux kernel support](#)

- [Deep Security Agent 10.3 Linux kernel support](#)
- [Deep Security Agent 10.2 Linux kernel support](#)
- [Deep Security Agent 10.1 Linux kernel support](#)
- [Deep Security Agent 10.0 Linux kernel support](#)
- [Deep Security Agent 9.6 SP1 Linux kernel support](#)
- [Deep Security Agent 9.5 SP1 Linux kernel support](#)

You can also use a [JSON version](#) of the complete list of the supported Linux kernels for Deep Security Agent 10.0 and higher with scripts and automated workflows.

Supported features by platform

The tables below list the features available for each OS platform of **Deep Security Agent 11.3**:

- ["Microsoft Windows \(11.3 agent\)" on the next page](#)
- ["Red Hat Enterprise Linux \(11.3 agent\)" on page 90](#)
- ["CentOS Linux \(11.3 agent\)" on page 91](#)
- ["Oracle Linux \(11.3 agent\)" on page 92](#)
- ["SUSE Linux \(11.3 agent\)" on page 93](#)
- ["Ubuntu Linux \(11.3 agent\)" on page 94](#)
- ["Debian Linux \(11.3 agent\)" on page 95](#)
- ["Cloud Linux \(11.3 agent\)" on page 96](#)
- ["Amazon Linux \(11.3 agent\)" on page 96](#)
- ["Deep Security Virtual Appliance \(NSX\) \(with embedded 11.3 agent\)" on page 97](#)

Note:

Older agents are compatible with other platforms (although they don't support new features on Deep Security Manager 11.3). See their ["Deep Security Agent platforms" on page 80](#), [Deep Security Agent release notes](#), and supported features lists:

- Deep Security Agent 10.0 (and newer) supported features: In the drop-down menu above, select that version of Deep Security. [Deep Security Agent 10.0 \(and newer\) supported features](#)
- [Deep Security Agent 9.6 Service Pack 1 supported features](#)

Microsoft Windows (11.3 agent)

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring						Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2					Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports				
Windows 7 32	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓		
Windows 7 64	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓	✓	✓
Windows 7 Embedded 32 (3)	✓	✓	✓		✓	✓	✓	✓					✓	✓	✓		✓		
Windows Server 2008 32	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓		
Windows Server 2008 64	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓		✓
Windows	✓	✓	✓		✓	✓	✓	✓	✓ (1)	✓	✓	✓	✓	✓	✓	✓	✓	✓	✓

Trend Micro Deep Security On-Premise 11.3

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring						Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Server 2008 R2 64																			
Windows 8 32	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓			
Windows 8 64	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓	✓		✓
Windows 8.1 32	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓			
Windows 8.1 64	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓	✓		
Windows 8.1 Embedded 32 (3)	✓	✓	✓		✓	✓	✓	✓			✓	✓	✓	✓		✓			
Windows 10 32 (2)	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓			

Trend Micro Deep Security On-Premise 11.3

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring						Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2					File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Windows 10 64 (2)	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓	✓		✓
Windows 10 Embedded 64 (3)	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓	✓		
Windows Server 2012 64	✓	✓	✓		✓	✓	✓	✓	✓	✓	✓	✓	✓	✓		✓	✓		✓
Windows Server 2012 R2 64	✓	✓	✓		✓	✓	✓	✓	✓ (1)	✓	✓	✓	✓	✓	✓	✓	✓	✓	✓
Windows Server Core 2012 64	✓	✓	✓		✓	✓	✓	✓	✓ (1)	✓	✓	✓	✓	✓	✓	✓	✓		✓
Windows Server Core 2012 R2 64	✓	✓	✓		✓	✓	✓	✓	✓ (1)	✓	✓	✓	✓	✓	✓	✓	✓		✓

Trend Micro Deep Security On-Premise 11.3

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring						Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2					Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports				
Windows Server 2016 64	✓	✓	✓		✓	✓	✓	✓	✓ (1)	✓	✓	✓	✓	✓	✓	✓	✓	✓	✓
Windows Server 2016 1709 (RS3) 64	✓	✓	✓		✓	✓	✓	✓	✓ (1)	✓	✓	✓	✓	✓	✓	✓	✓		✓
Windows Server 2016 1803 (RS4) 64	✓	✓	✓		✓	✓	✓	✓	✓ (1)	✓	✓	✓	✓	✓	✓	✓	✓		✓
Windows Server 2019 1809 64	✓	✓	✓		✓	✓	✓	✓	✓ (1)	✓	✓	✓	✓	✓	✓	✓	✓		✓

Red Hat Enterprise Linux (11.3 agent)

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System		Integrity Monitoring					Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Red Hat Enterprise Linux 6 32	✓ (4)		✓			✓	✓	✓		✓	✓		✓	✓		✓			
Red Hat Enterprise Linux 6 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓	✓	
Red Hat Enterprise Linux 7 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓	✓	✓

CentOS Linux (11.3 agent)

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System		Integrity Monitoring					Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
CentOS 6 32	✓ (4)		✓			✓	✓	✓		✓	✓		✓	✓		✓			
CentOS 6 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓		
CentOS 7 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓		✓

Oracle Linux (11.3 agent)

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System		Integrity Monitoring					Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Oracle Linux 6 32			✓			✓	✓	✓		✓	✓		✓	✓		✓			
Oracle Linux 6 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓		
Oracle Linux 7 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓		

SUSE Linux (11.3 agent)

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring					Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand							
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports					
SUSE Linux Enterprise Server 11 32	✓ (4)		✓			✓	✓	✓		✓	✓		✓	✓		✓		
SUSE Linux Enterprise Server 11 64	✓ (4)		✓		✓	✓	✓	✓		✓	✓		✓	✓		✓	✓	
SUSE Linux Enterprise Server 12 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓	

Ubuntu Linux (11.3 agent)

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring						Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Ubuntu 16.04.1 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓		
Ubuntu 18.04 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓		

Debian Linux (11.3 agent)

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System		Integrity Monitoring					Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Debian 7 64			✓		✓	✓	✓	✓			✓		✓	✓		✓	✓		
Debian 8 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓		
Debian 9 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓		

Cloud Linux (11.3 agent)

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System		Integrity Monitoring					Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Cloud Linux 7 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓		

Amazon Linux (11.3 agent)

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System		Integrity Monitoring					Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Amazon Linux 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓	✓		

Trend Micro Deep Security On-Premise 11.3

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring					Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand							
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File and Directory Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports					
Amazon Linux 2 64	✓ (4)		✓		✓	✓	✓	✓	✓ (1)	✓	✓		✓	✓	✓	✓		

Deep Security Virtual Appliance (NSX) (with embedded 11.3 agent)

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring					Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand							
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports					
Windows 7 32	✓		✓		✓	✓	✓				✓				✓			N/A
Windows 7 64	✓		✓		✓	✓	✓				✓				✓			N/A

Trend Micro Deep Security On-Premise 11.3

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring					Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand							
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports					
Windows Server 2008 32	✓		✓		✓	✓	✓				✓					✓		N/A
Windows Server 2008 64	✓		✓		✓	✓	✓				✓					✓		N/A
Windows Server 2008 R2 64	✓		✓		✓	✓	✓				✓					✓		N/A
Windows 8 32	✓		✓		✓	✓	✓				✓					✓		N/A
Windows 8 64	✓		✓		✓	✓	✓				✓					✓		N/A
Windows 8.1 32	✓		✓		✓	✓	✓				✓					✓		N/A
Windows 8.1 64	✓		✓		✓	✓	✓				✓					✓		N/A
Windows Server 2012 64	✓		✓		✓	✓	✓				✓					✓		N/A
Windows Server 2012	✓		✓		✓	✓	✓				✓					✓		N/A

Trend Micro Deep Security On-Premise 11.3

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring						Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
R2 64																			
Windows 10 32 (2)	✓		✓		✓	✓	✓				✓					✓			N/A
Windows 10 64 (2)	✓		✓		✓	✓	✓				✓					✓			N/A
Windows Server 2016 1709 (RS3) 64 (with NSX 6.3.3)	✓		✓		✓	✓	✓				✓					✓			N/A
Windows Server 2016 1803 (RS4) 64	✓		✓		✓	✓	✓				✓					✓			N/A
Windows Server 2019 1809 64	✓		✓		✓	✓	✓				✓					✓			N/A
Red Hat Enterprise Linux 5 32					✓	✓	✓												N/A
Red Hat Enterprise Linux 5 64					✓	✓	✓												N/A

Trend Micro Deep Security On-Premise 11.3

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring						Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Red Hat Enterprise Linux 6 32					✓	✓	✓												N/A
Red Hat Enterprise Linux 6 64					✓	✓	✓												N/A
Red Hat Enterprise Linux 7 64					✓	✓	✓												N/A
CentOS 5 32					✓	✓	✓												N/A
CentOS 5 64					✓	✓	✓												N/A
CentOS 6 32					✓	✓	✓												N/A
CentOS 6 64					✓	✓	✓												N/A
CentOS 7 64					✓	✓	✓												N/A
Oracle Linux 6 32					✓	✓	✓												N/A

Trend Micro Deep Security On-Premise 11.3

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring						Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Oracle Linux 6 64					✓	✓	✓												N/A
Oracle Linux 7 64					✓	✓	✓												N/A
SUSE Linux Enterprise Server 10 SP4 32					✓	✓	✓												N/A
SUSE Linux Enterprise Server 10 SP4 64					✓	✓	✓												N/A
SUSE Linux Enterprise Server 11 SP4 32					✓	✓	✓												N/A
SUSE Linux Enterprise Server 11 SP4 64					✓	✓	✓												N/A
SUSE Linux Enterprise Server 12 SP3 64					✓	✓	✓												N/A
Ubuntu 14.04 LTS 64					✓	✓	✓												N/A

Trend Micro Deep Security On-Premise 11.3

	Anti-Malware				Web Reputation Service	Firewall	Intrusion Prevention System	Integrity Monitoring						Log Inspection	Application Control	Recommendation Scan	Relay	Scanner	FIPS mode
	Real-time		On-demand						Real-time		On-demand								
	Feature set 1	Feature set 2	Feature set 1	Feature set 2			Unencrypted Traffic	SSL Encrypted Traffic	File and Directory Scans	Scans of Running Services, Processes, Listening Ports	File Scans	Registry Scans	Scans of Running Services, Processes, Listening Ports						
Ubuntu 16.04 LTS 64					✓	✓	✓												N/A
Ubuntu 18.04 LTS 64					✓	✓	✓												N/A
Debian 8 64					✓	✓	✓												N/A
Debian 9 64					✓	✓	✓												N/A

Feature set 1 includes signature-based file scanning, spyware scanning, and document exploit protection.

Feature set 2 includes behavior monitoring, process memory scanning, and registry scanning.

- (1) This platform supports enhanced real-time integrity monitoring. It uses the application control driver to provide file monitoring and captures information about *who* made changes to a monitored file.
- (2) Microsoft releases regular, semi-annual releases for Microsoft Windows 10. For details about which specific releases are supported, see [Deep Security Support for Windows 10](#).

Trend Micro Deep Security On-Premise 11.3

(3) All Trend Micro testing on Windows Embedded platforms is performed in a virtualized environment. Because these operating systems are typically run on custom hardware (for example, on point-of-sale terminals), customers must plan to thoroughly test on their target hardware platform prior to deployment in a production environment. In addition, before raising support cases, customers should attempt to reproduce problems in a virtualized environment because this is the environment the Trend Micro support team has available. If the issue is specific to deployments on custom hardware, Trend Micro may require the customer to provide us with remote access to a suitable environment before we can fully respond to support cases.

(4) **Real-time Anti-Malware support on Linux:** Real-time Anti-Malware scanning is highly dependent on the file system hooking implementation, so file system incompatibility can cause issues with this feature. The following table shows which file systems are compatible with the feature:

File system type		Deep Security Agent version								
		11.3	11.2	11.1	11.0	10.3	10.2	10.1	10.0	9.6
Disk file systems	ext2	✓	✓	✓	✓	✓	✓	✓	✓	✓
	ext3	✓	✓	✓	✓	✓	✓	✓	✓	✓
	ext4	✓	✓	✓	✓	✓	✓	✓	✓	✓
	XFS	✓	✓	✓	✓	✓	✓	✓	✓	✓
	Btrfs	✓	✓	✓	✓	✓	✓	✓	✓	✓
	VFAT	✓	✓	✓	✓	✓	✓	✓	✓	✓
Optical discs	ISO 9660	✓	✓	✓	✓	✓	✓	✓	✓	✓

Trend Micro Deep Security On-Premise 11.3

File system type		Deep Security Agent version								
		11.3	11.2	11.1	11.0	10.3	10.2	10.1	10.0	9.6
Special file systems	tmpfs	✓	✓	✓	✓	✓	✓	✓	✓	✓
	aufs	✓	✓	✓	✓	✓	✓	✓	✓	
	OverlayFS	✓	✓	✓	✓	✓	✓	✓	✓	✓
Network file systems (see Note, below)	NFSv3	✓	✓	✓	✓	✓	✓	✓	✓	✓
	NFSv4	✓	✓	✓	✓	✓	✓	✓	✓	✓
	SMB	✓	✓	✓	✓	✓	✓	✓	✓	✓
	CIFS	✓	✓	✓	✓	✓	✓	✓	✓	✓
	FTP	✓	✓	✓	✓	✓	✓	✓	✓	✓

Note: To protect network file systems, you must select **Enable network directory scan** in the malware scan configuration. For information, see ["Scan a network directory \(real-time scan only\)" on page 679](#).

Sizing

Sizing guidelines for Deep Security deployments vary by the scale of your network, hardware, and software.

Deep Security Manager sizing

The sizing recommendations for the Deep Security Manager computer depends on the number of agents that are being managed:

Trend Micro Deep Security On-Premise 11.3

Number of agents	Number of CPUs	RAM	JVM process memory	Number of manager nodes	Recommended disk space
<500	2	8 GB	4 GB	2	200 GB
500-1000	4	8 GB	4 GB	2	200 GB
1000-5000	4	12 GB	8 GB	2	200 GB
5000-10000	8	16 GB	12 GB	2	200 GB
10000-20000	8	24 GB	16 GB	2	200 GB

- Two manager nodes are recommended to provide redundancy and ensure the availability of the manager services.
- To ensure adequate performance during concurrent operations, you should install Deep Security Manager and the database on separate, dedicated servers in the same physical location.
- Java Virtual machine (JVM) memory allocation is important for Deep Security Manager performance. To change the default allocated memory for the Deep Security Manager JVM process, see ["Configure Deep Security Manager memory usage" on page 196](#).
- Recommendation scans are CPU-intensive for the Deep Security Manager. The performance impact to the Deep Security Manager should be taken into consideration when determining how often to run recommendation scans. For more information, see ["Manage and run recommendation scans" on page 529](#).
- Resource spikes may occur if a large number of virtual machines are rebooted simultaneously and agents re-establish their connection with Deep Security Manager at the same time.

Multiple server nodes

For better availability and scalability in larger deployments, use a load balancer, and install the same version of Deep Security Manager on multiple servers ("nodes"). Connect them to the same database storage.

Tip: To avoid high load on database servers, don't connect more than two Deep Security Manager nodes to each database server.

Each manager node is capable of all tasks. No node is more important than any of the others. You can log in to any node, and agents, appliances, and relays can connect with any node. If one node fails, other nodes can still provide service, and no data will be lost.

Database sizing

Several variables affect database disk space requirements:

- Number of computers
- Number of events (logs) recorded per second
- How long events are retained

Event retention settings can be configured in the policy, the individual computer settings, or both. (See ["Policies, inheritance, and overrides" on page 524.](#)) To configure disk space usage, see ["Limit log file sizes" on page 1097](#), including which events are logged for stateful Firewall of TCP, UDP, and ICMP. See also ["Deep Security Manager performance features" on page 197](#).

The database sizes in the following tables are suggestions for use with the default settings for log and event retention. (See ["Log and event storage best practices" on page 1094.](#)) To estimate sizing for your database:

1. Identify the security features you are enabling and the number of agents that you are deploying.
2. Add the individual recommendations for each security feature to estimate the database size.
3. Compare this value with the Full Policy recommendation and provision the lesser of the two.

For example, you could deploy 750 agents with Deep Security Anti-Malware, Intrusion Prevention System and Integrity Monitoring. The total of the individual recommendations is 320 GB (20 + 100 + 200). However, the "Full Policy" recommendation is 300 GB. Therefore, you should provision 300 GB.

Disk space estimates

Number of agents	Anti-Malware	Web Reputation Service	Log Inspection	Firewall	Intrusion Prevention System	Application Control	Integrity Monitoring	Full Policy
1-99	10 GB	15 GB	20 GB	20 GB	40 GB	50 GB	50 GB	100 GB
100-499	10 GB	15 GB	20 GB	20 GB	40 GB	100 GB	100 GB	200 GB
500-999	20 GB	30 GB	50 GB	50 GB	100 GB	200 GB	200 GB	300 GB
1000-9999	50 GB	60 GB	100 GB	100 GB	200 GB	500 GB	400 GB	600 GB
10,000-20,000	100 GB	120 GB	200 GB	200 GB	500 GB	750 GB	750 GB	1 TB

Database sizing considerations

- By default, data pruning is not performed on system events, which have a large impact on the database size. Adjust pruning settings according to your compliance requirements. (See ["Log and event storage best practices" on page 1094](#).)
- If you require long retention requirements for system events, use SIEM or Syslog servers for event forwarding. You can also use SEIM or Syslog servers for Security Control event forwarding. (See ["Forward Deep Security events to an external syslog or SIEM server" on page 1111](#).)

Note: When system events and Security Control events are forwarded to SIEM or Syslog servers, they are not deleted from the database. To delete these events use data pruning.

- To conserve disk space, delete all agent configuration packages for each platform that are not in use. For more information, see ["Delete a software package from the Deep Security database" on page 320](#). If you need to keep the configuration packages, add disk space accordingly. To help with estimating disk space requirements, consider a newly-installed Deep Security Manager with co-located relay that is assigned a policy that protects a Manager computer. When 29 agents (maximum 5 versions per agent platform) are added, the database size grows approximately 5 GB.

Trend Micro Deep Security On-Premise 11.3

- The Rebuild Baseline, Scan for Integrity Changes, and Scan for Inventory Changes operations retain all records in the database and are never pruned or forwarded to external Syslog or SIEM systems. The Application Control and Integrity Monitoring security modules use these operations and therefore require more storage space than other security modules. Other types of operations, such as system or security events, are pruned or forwarded to external Syslog or SIEM systems.
- High-traffic environments that use the Firewall and Intrusion Prevention system modules can cause a large number of related events. Factors that influence the number of events are the number of applied Intrusion Prevention system rules and Firewall rule configuration. Because these events can require significant database storage, you should monitor these security events and use suitable data pruning.
- Intrusion Prevention rules are applied based on vulnerabilities assessed during a recommendation scan. You can reduce the number of rules assigned by regularly patching your system and keeping applications up to date.
- If you anticipate a significant number of Firewall events, consider disabling "Out of allowed policy" events. (See the ["Advanced" on page 806](#) section in ["Firewall settings" on page 801](#).)

Deep Security Agent and Relay sizing

Platform	Features enabled	RAM	Minimum disk space
Windows	All protection	2 GB (4 GB recommended)	1 GB
Windows	Relay only	2 GB (4 GB recommended)	30 GB
Linux	All protection	1 GB (5 GB recommended)	1 GB
Linux	Relay only	2 GB (4 GB recommended)	30 GB

Trend Micro Deep Security On-Premise 11.3

- Requirements vary by OS version, so some may require less RAM. Less RAM is also required if you are not enabling all of the Deep Security features.
- The Deep Security Relay must store packages for each of your agents' platforms. For more information, see ["Get Deep Security Agent software" on page 318](#). If you have many different platforms, more disk space is required. For information on the number of relays you should use, see ["Distribute security and software updates with relays" on page 380](#).
- If V-Motions are expected, another 10 GB of disk space is recommended for a total of 40 GB.

Deep Security Virtual Appliance sizing

By default, the Deep Security Virtual Appliance has only 4 GB of memory. The number of virtual machines that a Deep Security Virtual Appliance is protecting determines the hardware requirements of the appliance. The following table lists the minimum number of vCPUs and amount of memory to allocate based on the number of protected virtual machines. To allocate memory for virtual appliances, see ["Deep Security Virtual Appliance memory allocation" on page 136](#).

Number of protected virtual machines	Number of vCPUs	RAM	Minimum disk space
1-25	2	6 GB	40 GB
26-50	2	8 GB	40 GB
51-100	2	10 GB	40 GB
101-150	4	12 GB	40 GB
151-200	4	16 GB	40 GB
201-250	6	20 GB	40 GB
251-300	6	24 GB	40 GB

Trend Micro Deep Security On-Premise 11.3

The workloads above are supported by Deep Security, with the following stipulations:

- If you want agentless [Integrity Monitoring](#), you'll need a deployment of 0-50 VMs per ESXi server. For larger VDI deployments (approximately 51-300 servers), Integrity Monitoring should be turned off. If you have a VDI deployment and need Integrity Monitoring, we recommend deploying agents on each of your VMs.
- If you want to use agentless [Anti-Malware scanning](#), you'll need VMware's Guest Introspection capability. Guest Introspection may support different workloads from the ones described in the table above. For details, see the [VMware Configuration Maximum tool](#).
- If you want to use agentless [Firewall](#), [Web Reputation](#), or [Intrusion Prevention](#) features, you'll need VMware's Network Introspection capability. Network Introspection may support different workloads from the ones described in the table. For details, see [NSX for vSphere Recommended Configuration Maximum](#).

We recommend that you patch the OS under protection (especially Windows) before turning on Intrusion Prevention. An unpatched OS results in a larger number of Intrusion Prevention rules assigned to the VMs and increases the appliance's memory usage. The memory recommendation for 300 protected VMs is based on approximately 350 to 400 Intrusion Prevention rules being assigned per VM. If a recommendation scan recommends more rules, you should increase the Deep Security Virtual Appliance memory accordingly. For example, here are approximate recommendations for 300 VMs targeting VDI (full, linked or instant clones):

Number of Intrusion Prevention rules	Appliance memory
350-400	24 GB
500-600	30 GB
600-700	40 GB
700+	50 GB

Running recommendation scans on all 300 protected VMs may result in timeouts. If you find that recommendation scans are failing due to timeout errors, follow the instructions in "[Manage and run recommendation scans](#)" on [page 529](#) to increase timeout values.

Port numbers, URLs, and IP addresses

Deep Security default port numbers, URLs, IP addresses, and protocols are listed in the sections below. If a port, URL or IP address is configurable, a link is provided to the relevant configuration page.

- ["Deep Security port numbers" below](#)
- ["Deep Security URLs" on page 115](#)

Note: If your network uses a proxy or loadbalancer, you can configure Deep Security to use it instead of the default ports and URLs listed on this page. For details, see ["Proxy settings" on page 362](#) and ["Load Balancers" on page 1370](#).

Note: In addition to the ports on this page, Deep Security uses [ephemeral ports](#) when opening a socket (source port). Under rare circumstances these may be blocked, causing connectivity issues. For details, see ["Activation Failed - Blocked port" on page 1280](#).

Deep Security port numbers

Port type	Default port number
Manager listen ports	<ul style="list-style-type: none">• 4119/HTTPS (Deep Security Manager GUI and API listen port)• 4120/HTTPS (Deep Security Manager heartbeat port)
Manager destination ports	<ul style="list-style-type: none">• 25/SMTP* (email server port)• 53/DNS (DNS server port)• 80/HTTP, 443/HTTPS* (these ports are used by various Deep Security cloud services, Smart Protection Network services, Control Manager, Deep Discovery Analyzer, VMware components (vCenter, ESXi, NSX), Whois server, AWS, and Azure)

Port type	Default port number
	<ul style="list-style-type: none">• 123/NTP* (NTP server port; the NTP server can be Trend Micro Control Manager)• 162/SNMP* (SNMP manager port)• 389/LDAP, 636/LDAPS* (Active Directory)• 514/Syslog* (SIEM or syslog server port)• 1433/SQL (Microsoft SQL database port)• 1521/SQL (Oracle database port)• 5432/SQL (PostgreSQL database port)• 4118/HTTPS* (Deep Security Agent port)• 4122/HTTPS (Deep Security Relay port)• 11000-11999/SQL, 14000-14999/SQL* (Azure SQL Database port) <p>* Notes:</p> <ul style="list-style-type: none">• Open 25 if you want email notifications. 25 is configurable in the manager.• 80 and 443 are configurable depending on the service being accessed. To configure the Control Manager and Deep Discovery Analyzer ports, click here. For the NSX and vCenter ports, click here. To configure the Whois port, click here.• Open 123 if you want to synchronize the manager with an NTP server.• Open 162 if you want to "Forward system events to a remote computer via SNMP" on page 1204.• Open 389 and 636 if you want to add computers from Active Directory to the manager. 389 and 636 are configurable in the manager if your Active Directory server uses a different port.• Open 514 if you want to forward Deep Security events to an external SIEM or syslog server. 514 is configurable in the

Port type	Default port number
	<p>manager.</p> <ul style="list-style-type: none">• Open 4118 if you are using bidirectional or manager-initiated communication. By default, bidirectional communication is used, so 4118 must be opened. See "Agent-manager communication" on page 344 for details.• Open 11000-11999, 14000-14999 if you are using Azure SQL Database with the manager deployed on Azure, for example, the Deep Security Manager VM for Azure Marketplace. If the manager runs inside the Azure cloud boundary, it uses a direct route to interact with the Azure SQL Database server. For more information, see this Azure document.
Deep Security Agent/appliance listen port	<ul style="list-style-type: none">• 4118/HTTPS (Agent/appliance listen port for heartbeats) <div>Note: 4118 can be closed if you are using agent-initiated communication. By default, bidirectional communication is used, so 4118 must be opened. See "Agent-manager communication" on page 344 for details.</div>
Deep Security Agent/appliance destination ports	<ul style="list-style-type: none">• 53/DNS (DNS server port)• 80/HTTP, 443/HTTPS (Smart Protection Network port)• 123/NTP* (NTP server port)• 514/syslog* (SIEM or syslog server port)• 4119/HTTPS (Deep Security Manager GUI and API port)• 4120/HTTPS* (Deep Security Manager heartbeat port)• 4122/HTTPS (Deep Security Relay port)• 5274/HTTP, 5275/HTTPS* (Smart Protection Server ports)

Port type	Default port number
	<p>* Notes:</p> <ul style="list-style-type: none">• Open 123 if you want to synchronize the agent with an NTP server.• Open 514 if you want the agent to send its security events directly to your SIEM or syslog server. 514 is configurable in the manager.• Open 4120 if you are using bidirectional or agent-initiated communication. By default, bidirectional communication is used, so 4120 must be opened. See "Agent-manager communication" on page 344 for details.• Open 5274 and 5275 if you are hosting a Smart Protection Server in your local network or Virtual Private Network (VPC), instead of having your agents/appliance connect to the cloud-based Smart Protection Network over 80/HTTP and 443/HTTPS. For details, see the Smart Protection Server documentation, or Deploy a Smart Protection Server in AWS.
Deep Security Relay listen ports	<ul style="list-style-type: none">• Open all the agent listen ports, since they apply to the relay as well• 4122/HTTPS (relay port)• 4123 (port for communication between the agent and its own internal relay) <div><p>Note: 4123 should not be listening to connections from other computers, and you don't need to configure it in network firewall policies. But if you have firewall software (such as Windows Firewall or iptables) on the manager's server itself, verify that it does not block this connection to itself. Also verify that other applications do not use the same port (a port conflict).</p></div>
Deep Security Relay destination ports	<ul style="list-style-type: none">• 80/HTTP, 443/HTTPS (Trend Micro Update Server/Active Update and Download Center ports)• 4122 (port of other relays)

Deep Security URLs

If you need to restrict the URLs that are allowed in your environment, read this section.

You'll need to make sure your firewall allows traffic to the following Trend Micro, Deep Security, AWS, and Azure server URLs on port 443 (HTTPS) and port 80 (HTTP).

Source	Destination server or service name	Destination URL
SOAP and REST API clients	Deep Security SOAP and REST APIs	<ul style="list-style-type: none">• <manager FQDN or IP>:4119/webservice/Manager?WSDL• <manager FQDN or IP>:4119/api• <manager FQDN or IP>:4119/rest
REST API clients	Deep Security Status Monitoring API	<ul style="list-style-type: none">• <manager FQDN or IP>:4119/rest/status/manager/ping
The manager, agent/appliance, and relay	Download Center or web server Hosts software.	<ul style="list-style-type: none">• files.trendmicro.com
The manager	Smart Protection Network - Certified Safe Software Service (CSSS) Used for event tagging with Integrity Monitoring .	<ul style="list-style-type: none">• gacl.trendmicro.com• grid-global.trendmicro.com• grid.trendmicro.com
The agent/appliance	Smart Protection Network - Global Census Service	11.0 and higher <ul style="list-style-type: none">• ds1100-en-census.trendmicro.com

Trend Micro Deep Security On-Premise 11.3

Source	Destination server or service name	Destination URL
	Used for behavior monitoring , and predictive machine learning .	<ul style="list-style-type: none">• ds1100-jp-census.trendmicro.com 10.2 and 10.3 <ul style="list-style-type: none">• ds1020-en-census.trendmicro.com• ds1020-jp-census.trendmicro.com• ds1020-sc-census.trendmicro.com 10.1 and 10.0 <ul style="list-style-type: none">• ds1000-en.census.trendmicro.com• ds1000-jp.census.trendmicro.com• ds1000-sc.census.trendmicro.com• ds1000-tc.census.trendmicro.com
The agent/appliance	Smart Protection Network - Good File Reputation Service Used for behavior monitoring , predictive machine learning , and process memory scans .	11.0 and higher <ul style="list-style-type: none">• deepsec11-en.gfrbridge.trendmicro.com• deepsec11-jp.gfrbridge.trendmicro.com 10.2 and 10.3 <ul style="list-style-type: none">• deepsec102-en.gfrbridge.trendmicro.com• deepsec102-jp.gfrbridge.trendmicro.com

Trend Micro Deep Security On-Premise 11.3

Source	Destination server or service name	Destination URL
		10.1 and 10.0 <ul style="list-style-type: none">deepsec10-en.grid-gfr.trendmicro.comdeepsec10-jp.grid-gfr.trendmicro.comdeepsec10-cn.grid-gfr.trendmicro.com
The manager	Smart Protection Network - Smart Feedback	11.0 and higher <ul style="list-style-type: none">deepsecurity1100-en.fbs25.trendmicro.comdeepsecurity1100-jp.fbs25.trendmicro.com 10.0 <ul style="list-style-type: none">deepsecurity1000-en.fbs20.trendmicro.comdeepsecurity1000-jp.fbs20.trendmicro.comdeepsecurity1000-sc.fbs20.trendmicro.com
The agent/appliance	Smart Protection Network - Smart Scan Service	11.0 and higher <ul style="list-style-type: none">ds110.icrc.trendmicro.comds110-jp.icrc.trendmicro.com 10.2 and 10.3

Source	Destination server or service name	Destination URL
		<ul style="list-style-type: none">ds102.icrc.trendmicro.comds102-jp.icrc.trendmicro.comds102-sc.icrc.trendmicro.com.cn <p>10.1 and 10.0</p> <ul style="list-style-type: none">ds10.icrc.trendmicro.comds10.icrc.trendmicro.com/tmcss/ds10-jp.icrc.trendmicro.com/tmcss/ds10-sc.icrc.trendmicro.com/tmcss/ <p>9.6 and 9.5</p> <ul style="list-style-type: none">iaufdbk.trendmicro.comds96.icrc.trendmicro.comds96-jp.icrc.trendmicro.comds96-sc.icrc.trendmicro.com.cnds95.icrc.trendmicro.comds95-jp.icrc.trendmicro.comds95-sc.icrc.trendmicro.com.cn
The agent/appliance	Smart Protection Network -	11.0 and higher

Trend Micro Deep Security On-Premise 11.3

Source	Destination server or service name	Destination URL
	<div>Trend X server</div> <div>Used for predictive machine learning.</div>	<div><ul style="list-style-type: none">ds110-en-b.trx.trendmicro.comds110-jp-b.trx.trendmicro.comds110-en-f.trx.trendmicro.comds110-jp-f.trx.trendmicro.com</div> <div>10.2 and 10.3</div> <div><ul style="list-style-type: none">ds102-en-f.trx.trendmicro.comds102-jp-f.trx.trendmicro.comds102-sc-f.trx.trendmicro.com</div>
The agent/appliance	<div>Smart Protection Network -</div> <div>Web Reputation Service</div>	<div>11.0 and higher</div> <div><ul style="list-style-type: none">ds11-0-en.url.trendmicro.comds11-0-jp.url.trendmicro.com</div> <div>10.2 and 10.3</div> <div><ul style="list-style-type: none">ds10-2-en.url.trendmicro.comds10-2-sc.url.trendmicro.com.cnds10-2-jp.url.trendmicro.com</div> <div>10.1 and 10.0</div>

Trend Micro Deep Security On-Premise 11.3

Source	Destination server or service name	Destination URL
		<ul style="list-style-type: none">ds100-en.url.trendmicro.comds100-sc.url.trendmicro.comds100-jp.url.trendmicro.com <p>9.6 and 9.5</p> <ul style="list-style-type: none">ds96-en.url.trendmicro.comds96-jp.url.trendmicro.comds95-en.url.trendmicro.comds95-jp.url.trendmicro.com
The manager	Help and support	<ul style="list-style-type: none">help.deepsecurity.trendmicro.comsuccess.trendmicro.com/product-support/deep-security
The manager	Licensing and registration servers	<ul style="list-style-type: none">licenseupdate.trendmicro.comclp.trendmicro.comolr.trendmicro.com/redirect/product_view_lic.aspx?lang=E&AC={0}olr.trendmicro.com/registration/us/en-us/product_login.aspxolr.trendmicro.com/registration/us/en-us/login.aspx
The manager	News feed	<ul style="list-style-type: none">news.deepsecurity.trendmicro.com

Trend Micro Deep Security On-Premise 11.3

Source	Destination server or service name	Destination URL
		<ul style="list-style-type: none">news.deepsecurity.trendmicro.com/news.atomnews.deepsecurity.trendmicro.com/news_ja.atom
Browser on agent computers and the computer used to log in to the manager	Site Safety	Optional. There are links to the URLs below within the manager UI and on the agent's 'Your administrator has blocked access to this page for your safety' page. <ul style="list-style-type: none">sitesafety.trendmicro.comjp.sitesafety.trendmicro.com
The manager, agent/appliance, and relay	Update Server (also called Active Update) Hosts security updates.	<ul style="list-style-type: none">iaus.activeupdate.trendmicro.comiaus.trendmicro.comipv6-iaus.trendmicro.comipv6-iaus.activeupdate.trendmicro.comipv6-iaus-preopr.trendmicro.com/iau_server.dll/
The manager	AWS and Azure URLs Used for adding AWS accounts and Azure accounts to Deep Security Manager.	AWS URLs <ul style="list-style-type: none">URLs of AWS EC2 endpoints. For the endpoint URL names, see this AWS page. Azure URLs <ul style="list-style-type: none">login.windows.net (authentication)management.azure.com (Azure API)

Source	Destination server or service name	Destination URL
		<ul style="list-style-type: none">management.core.windows.net (Azure API)azureconnector.deepsecurity.trendmicro.com (Azure connector 'Quick' option) <p>Note: The management.core.windows.net URL is only required if you used the v1 Azure connector available in Deep Security Manager 9.6 to add an Azure account to the manager. With Deep Security Manager 10.0 and later, a v2 connector is used, and does not require access to this URL.</p>

Prepare a database for Deep Security Manager

Before you install Deep Security Manager, you must prepare a database and user account for Deep Security Manager to use. Refer to your database provider's documentation for instructions on database installation and deployment, but also consider the following for integration with Deep Security:

1. Check the ["Hardware considerations" on the next page](#).
2. Choose your database type. For a list of supported databases, see [Database](#).

Depending on which database you choose, see ["Microsoft SQL Server" on page 124](#), ["Oracle Database" on page 125](#), or ["PostgreSQL recommendations" on page 127](#) for database-specific considerations.

Note: Microsoft SQL Server Express is supported only in limited deployments. For details, see ["Microsoft SQL Server Express considerations" on page 132](#).

Trend Micro Deep Security On-Premise 11.3

3. For high availability, the Deep Security database is compatible with database failover protection so long as no alterations are made to the database schema. For example, some database replication technologies add columns to the database tables during replication, which can result in critical failures. For this reason, database mirroring is recommended over database replication.
4. The database time must be synchronized with the time on the Deep Security Manager computer. Ensure that the database and the manager use the same time zone and that they are synchronizing their time to the same time source.
5. Allow communication from the Deep Security Manager computer to the database computer. See ["Port numbers, URLs, and IP addresses" on page 111](#).
6. During the Deep Security Manager installation, you will be asked for database connection details. Enter the database hostname under "Hostname" and the database that you created for Deep Security under "Database Name".

The installation supports both SQL and Windows Authentication. When using Windows Authentication, click the "Advanced" button to display additional options.

7. ["Database maintenance" on page 126](#) is a crucial part of Deep Security operations.

Hardware considerations

Dedicated server

The database should be installed on a dedicated server that is separate from the manager nodes. It is also important that the database and the Deep Security Manager be co-located on the same network with a 1 GB LAN connection to ensure unhindered communication between the two. (WAN connections are not recommended.) The same applies to additional Deep Security Manager nodes. 2 ms latency or less is recommended for the connection from the manager to the database.

To achieve this if you install the manager and database on VMs, make sure they are always run in the same ESXi host.

1. In the vCenter Web Client, go to **Host and Clusters** and select the cluster.
2. Go to the **Manage** tab and click **VM/Host Rules > Add**.
3. Type a name for the rule.
4. Select **Enable rule**.

Trend Micro Deep Security On-Premise 11.3

5. From **Type** select **Keep Virtual Machines Together**.
6. Click **Add** and select the manager and database VMs.

Hardware recommendations

Many Deep Security Manager operations (such as updates and recommendation scans) require high CPU and memory resources. Trend Micro recommends that each manager node has four cores and sufficient RAM in high scale environments.

The database should be installed on hardware that is equal to or better than the specifications of the best Deep Security Manager node. For the best performance, the database should have 8-16 GB of RAM and fast access to the local or network attached storage. Whenever possible, a database administrator should be consulted on the best configuration of the database server and a maintenance plan should be put in effect.

Microsoft SQL Server

General requirements

- You must create an empty database that will be used by Deep Security.
- Enable "Remote TCP Connections"(see [https://msdn.microsoft.com/en-us/library/bb909712\(v=vs.120\).aspx](https://msdn.microsoft.com/en-us/library/bb909712(v=vs.120).aspx)).
- Grant **db_owner** rights to the Deep Security Manager's database user.

Note:

If you use Microsoft SQL Server, Deep Security Manager must connect as either a Microsoft Active Directory domain or SQL user. Windows workgroup authentication is no longer supported.

Transport protocol

- The supported [transport protocol](#) is **TCP** for newly-installed versions of Deep Security 10.2 or later versions.
- If you are upgrading from Deep Security 10.1 or a previous version and you are using a named pipe as the transport protocol, DSM will continue to use a named pipe when you upgrade. Trend Micro recommends that you use TCP and encrypt communications. (See ["Encrypt communication between the Deep Security Manager and the database" on page 1043.](#))

If using multi-tenancy

- Keep the main database name short. It will be easier to read your tenants' database names. (For example, if the main database is "MAINDB", the first tenant's database name will be "MAINDB_1", the second tenant's database name will be "MAINDB_2", and so on.)
- Grant **dbcreator** rights to Deep Security Manager's database user account. For information on multi-tenancy, see ["Set up a multi-tenant environment" on page 201.](#)

Oracle Database

- Start the "Oracle Listener" service. Verify that it accepts TCP connections.
- Don't use special characters in Deep Security Manager's database user name. Although Oracle allows special characters when configuring the database user object if they are surrounded by quotes, Deep Security does not support special characters for the database user.
- Grant the **CONNECT** and **RESOURCE** roles and **UNLIMITED TABLESPACE**, **CREATE SEQUENCE**, **CREATE TABLE** and **CREATE TRIGGER** permissions to the Deep Security Manager's database user.

If using multi-tenancy, also grant **CREATE USER**, **DROP USER**, **ALTER USER**, **GRANT ANY PRIVILEGE** and **GRANT ANY ROLE** to the Deep Security Manager's database user.

Note: Oracle container database (CDB) configuration is **not** supported with Deep Security Manager multi-tenancy.

Oracle RAC (Real Application Clusters) support

Deep Security supports:

- SUSE Linux Enterprise Server 11 SP3 with Oracle RAC 12c Release 1 (v12.1.0.2.0)
- Red Hat Linux Enterprise Server 6.6 with Oracle RAC 12c Release 1 (v12.1.0.2.0)

The default Linux Server Deep Security policy is compatible with the Oracle RAC environment, with the exception of Firewall settings. You can disable Firewall or customize the Firewall settings according to the instructions in ["Firewall settings with Oracle RAC" on page 807](#).

Database maintenance

Database maintenance is necessary to ensure the health of your Deep Security deployment.

Index maintenance

To improve Deep Security Manager performance, we recommend that you perform regular index maintenance on the Deep Security database to keep it from becoming overly fragmented. Follow your organization's best practices for reindexing databases, or refer to your database vendor's documentation for guidance:

- **PostgreSQL:** See <https://www.postgresql.org/docs/10/sql-reindex.html> for details on the PostgreSQL reindex command. Note that this command will block some operations, so it's best to run it offline, during upgrades. When run offline on a previous snapshot, it takes approximately 45 minutes to complete.
- **Microsoft SQL:** Refer to documentation from Microsoft for index maintenance best practices: <https://docs.microsoft.com/en-us/sql/relational-databases/indexes/reorganize-and-rebuild-indexes>.
- **Oracle Database:** Follow Oracle's best practices on managing indexes. For example, see https://docs.oracle.com/cd/B28359_01/server.111/b28310/indexes002.htm#ADMIN11713.

There are also open source websites that provide scripts that can help you with this task.

Backups

It's important to have a backup strategy in place for the Deep Security database in case of failure. Consult your database vendor's documentation for instructions on how to back up your database and see ["Back up and restore your database" on page 976](#) for instructions on how to restore the database, if necessary.

PostgreSQL recommendations

Tuning recommendations that you should consider depend on your organization's needs (see ["Tuning PostgreSQL settings" on the next page](#)).

General requirements

- General database setup recommendations are located in ["Prepare a database for Deep Security Manager" on page 122](#). For information on how to install and configure a PostgreSQL database specifically, refer to the [PostgreSQL documentation](#).

If you need additional help, PostgreSQL offers [professional support](#).
- To prepare a PostgreSQL database for use with Deep Security Manager:

```
CREATE DATABASE "<database>";
```

```
CREATE ROLE "<username>" WITH PASSWORD '<password>';
```

```
GRANT ALL ON DATABASE "<database>" TO "<username>";
```

```
GRANT CONNECT ON DATABASE "<database>" TO "<username>";
```
- Based on your security requirements, consider using TLS to secure traffic between the Deep Security Manager and PostgreSQL. To turn on TLS after Deep Security Manager has been installed, see ["Encrypt communication between the Deep Security Manager and the database" on page 1043](#).

Trend Micro Deep Security On-Premise 11.3

- If using multi-tenancy, users also need the right to create new databases and roles:

```
ALTER ROLE <username> CREATEDB CREATEROLE;
```

Tuning PostgreSQL settings

To change the settings described in this section:

1. Open the `postgresql.conf` file. [File locations depends on your PostgreSQL configuration.](#)
2. Edit the parameters that you want to change.
3. Save and close the file.
4. Restart the PostgreSQL service.

Logging settings

By default, PostgreSQL log files are not rotated, which can lead to the log files using a large amount of disk space. When using PostgreSQL with Deep Security, we recommend that you use these four parameters in the `postgresql.conf` file to configure log rotation:

- `log_filename`
- `log_rotation_age`
- `log_rotation_size`
- `log_truncate_on_rotation`

`log_rotation_age` and `log_rotation_size` control when a new log file is created. For example, setting `log_rotation_age` to 1440 will create a new log file every 1440 minutes (1 day), and setting `log_rotation_size` to 10000 will create a new log file when the previous one reaches 10 000 KB.

`log_filename` controls the name given to every log file. You can use time and date format conversion in the name. For a complete list, see <http://pubs.opengroup.org/onlinepubs/009695399/functions/strftime.html>.

Trend Micro Deep Security On-Premise 11.3

When `log_truncate_on_rotation` is set to "on", it will overwrite any log file that has the same name as a newly created log file.

There are several combinations of parameters that you can use to achieve a log rotation to suit your requirements. Here is one example:

- `log_filename = 'postgresql-%a.log'` (every log file has the first 3 letters of the weekday in its name)
- `log_rotation_age = 1440` (a new log file is created daily)
- `log_rotation_size = 0`. (setting is disabled to prevent the overwriting of the daily log file every time this limit is exceeded)
- `log_truncate_on_rotation = on` (enable log file overwrite)

Lock management

By default, the `deadlock_timeout` setting in the `postgresql.conf` file is configured to 1 second. This means every time a query waits on a lock for more than 1 second, PostgreSQL will launch a check for deadlock condition and will log an error if the logging setting has been configured that way (by default, it is). This can lead to performance degradation on bigger systems, where it can be normal for queries to wait for more than 1 second during load times. On large systems, consider increasing the `deadlock_timeout` setting. The PostgreSQL documentation contains this recommendation: "Ideally the setting should exceed your typical transaction time [...]".

Maximum connections

The `max_connections` setting in the `postgresql.conf` file specifies the maximum number of open connections to the database. The default value is 100. We recommend increasing this value to 500.

Shared buffers

The `shared_buffers` setting in the `postgresql.conf` file specifies how much memory PostgreSQL can use to cache data. A system with 1 GB of RAM must have one quarter of its memory value for shared buffer, which means the shared buffer should be set to 256 MB (the default is 32 MB).

Work memory and maintenance work memory

The `work_mem` setting in the `postgresql.conf` file specifies the amount of memory that can be used by internal sort operations and hash tables before writing to temporary disk files. The default value is 1 MB, but it should be increased when running complex queries. The `maintenance_work_mem` setting determines the maximum amount of memory used for maintenance operations such as ALTER TABLE.

Effective cache size

The `effective_cache_size` setting in the `postgresql.conf` file is used to estimate cache effects by a query. This setting only affects cost estimates during query planning and does not result in higher memory consumption. Consider increasing this setting.

Checkpoints

Checkpoints are usually the main source of writes to data files. To get the smoothest performance, most checkpoints should be "timed" (triggered by `checkpoint_timeout`) and not "requested" (triggered by filling all the available WAL segments or by an explicit CHECKPOINT command). We strongly recommend that you make checkpoints less frequent.

Setting	Default value	Recommended value
<code>checkpoint_timeout</code>	5min	15min
<code>checkpoint_completion_target</code>	0.5	0.9
<code>max_wal_size</code>	1GB	16GB

Write-ahead log (WAL)

The default value for the `wal_level` setting is 'minimal', which is appropriate when replication is not in place. Consider changing it if you plan to set up replicas.

Autovacuum settings

PostgreSQL requires periodic maintenance called "vacuuming". Auto vacuuming is recommended in many cases, so there is no need to change the default setting:

```
autovacuum_max_workers = 3.
```

High availability

High availability (HA) is not set by default and was not enabled in our test environment, but it is highly recommended to ensure business continuity in the case of a database malfunction or server inaccessibility. Refer to your PostgreSQL documentation for information on how to enable and configure HA.

Backup and recovery

Backup and recovery is not set by default, but it's absolutely essential in a production environment.

Note: Basic tools like `pg_dump` or `pg_basebackup` are not suitable for backups in an enterprise environment. Consider using other tools like Barman (<https://www.pgbarman.org/index.html>) for backup and recovery.

Linux recommendations

Transparent Huge Pages (Linux)

Transparent Huge Pages (THP) is a Linux memory management system that reduces the overhead of Translation Lookaside Buffer (TLB) lookups on machines with large amounts of memory by using larger memory pages. THP is enabled by default on Linux, but it is not recommended for computer running a database and should be disabled if PostgreSQL is installed on a Linux computer. Refer to your OS vendor's documentation for details.

Strengthen host-based authentication (Linux)

By default, Linux does not have restricted host-based authentication (HBA) for databases. Strengthening the HBA settings on a database appliance helps to prevent unauthorized access from external hosts. The HBA settings restrict access to an IP address range so that only hosts within that range have access. HBA settings were not

Trend Micro Deep Security On-Premise 11.3

used on our test environment and we do not recommend them.

Microsoft SQL Server Express considerations

Some deployments might be able to use Microsoft SQL Server Express for the Deep Security Manager database. Important limitations are below. If you think your deployment cannot operate within these limitations, use another supported database instead.

Warning: If you exceed the limits, you will experience a service outage and you will need to upgrade to a paid version of Microsoft SQL Server.

Express edition limitations

Microsoft SQL Server Express has a [10 GB maximum database size and other important limits](#). High load scenarios are not supported by Express. Symptoms can include database connection errors.

Express has a "LocalDB" preset. More configuration may be required to [accept remote connections](#).

Limited number of protected computers

Do not use Microsoft SQL Server Express if your deployment has more than 50 protected computers. More computers' events will cause a larger database which Microsoft SQL Server Express cannot handle.

Multi-node Deep Security Manager, required for larger deployments, is not supported by Express.

Security module limitations

Only Deep Security Anti-Malware and Intrusion Prevention modules are supported with a Microsoft SQL Server Express database due to its limitations. If you require any other protection modules, use another supported database instead.

Minimize the agent size

Remove any unneeded agent software packages from the Deep Security Manager to save disk space.

Database pruning

Security updates and events require additional space in the database. Monitor your deployment to ensure that you stay within the Express database size limit. For information on database pruning, see ["Log and event storage best practices" on page 1094](#). You may also choose to use the SQL Server settings described in [Considerations for the "autogrow" and "autoshrink" settings in SQL Server](#).

Choose agentless vs. combined mode protection

If you are protecting virtual machines (VMs) you can install Deep Security Agent, just as you would for other types of computers. But in Deep Security 9.6 or later, there are two other ways to protect VMs:

- Agentlessly (via virtual appliance), or
- Mixture of agent-based and agentless ("combined mode")

Agentless protection

Anti-malware and integrity monitoring protection can be provided *without* installing Deep Security Agent. Instead, the VMware Tools driver installed on the VM can offload security processing to a Deep Security Virtual Appliance.

Note: On Linux VMs, Deep Security Agent provides anti-malware protection, not the Deep Security Virtual Appliance.

Note: In Deep Security 9.5 or earlier, to protect VMs without installing a Deep Security Agent, you would use the Deep Security Virtual Appliance and filter driver. The filter driver was installed on the ESXi server and was used to intercept network traffic at the hypervisor, and send it to the appliance. **VMware does not support vShield (VMsafe-NET API driver) anymore, so the old driver is not supported by Deep Security 11.3, and must be removed.**

Because agentless protection requires fast connectivity between the appliance and the computer you want to protect, don't use agentless if the computer is far from the appliance, on a remote ESXi server or another data center.

See also ["Deploy agentless protection in a vCloud environment" on page 283](#).

Combined mode

If you require other protection features that Deep Security Virtual Appliance doesn't support, you must install the Deep Security Agent on each of your VMs, but you can still use the Deep Security Virtual Appliance to provide some of the protection, which can improve performance. Both the appliance and agent used together is known as "combined mode".

With combined mode, the appliance provides the anti-malware and integrity monitoring. The Deep Security Agent provides other features.

Conversion of coordinated approach to combined mode

- **Coordinated approach** – In Deep Security 9.5, if the agent on a VM was offline, protection features would be provided by the Deep Security Virtual Appliance instead as an alternative. However, it could *not* be configured separately for each feature.
- **Combined mode** – In Deep Security 9.6, each protection feature was configurable to use either the agent or appliance. However, if the preferred protection source was offline, the computer *didn't* use the other alternative.

In the new Deep Security, its "protection source" settings provide *both* behaviors:

Trend Micro Deep Security On-Premise 11.3

- whether each feature is provided by the agent or appliance
- whether to use the agent or appliance alternative if the preferred protection is not available

So if you need behavior like the old coordinated approach, you might want to upgrade *directly* from Deep Security 9.5 to 11.3 – *not* from 9.5 to 9.6 and then 11.3.

Choose an agent or appliance for each protection feature

If a computer could be protected by either an appliance or agent, you can select which will provide each protection feature.

Note: Log inspection and application control do not have this setting. With current VMware integration technologies, Deep Security Virtual Appliance cannot provide those features.

To configure the protection source, import a VMware vCenter into Deep Security Manager, then in the **Computer or Policy editor**¹, go to **Settings > General**.

Protection Source when in Combined Mode

Select which component will provide protection when both the Agent and the Appliance are present.

Anti-Malware:	Inherited (Appliance preferred)
Web Reputation / Firewall / Intrusion Prevention:	Inherited (Agent preferred)
Integrity Monitoring:	Inherited (Appliance preferred)

Protection Modules not shown here do not support Combined Mode configuration.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

For each protection module or group of protection modules, select either:

- **Appliance Only:** Only the Deep Security Virtual Appliance will provide protection, even if there is an agent on the VM and the appliance is deactivated or removed.

Warning: Don't use the appliance if you require the scanner (SAP). It requires Deep Security Agent anti-malware.

Tip: When anti-malware is enabled on the agent, the agent downloads the Anti-malware Solution Platform (AMSP) and starts it as a service. If you do not want this, then from **Anti-Malware**, select **Appliance Only**. That way, even if the appliance is deactivated, the agent won't start the AMSP service.

- **Appliance Preferred:** If there is an activated appliance on the ESXi server, it will provide the protection. But if the appliance is deactivated or removed, then the agent will provide protection instead.
- **Agent Only:** Only the agent will provide protection, even if there is an activated appliance available.
- **Agent Preferred:** If there is an activated agent on the VM, it will provide the protection. But if there is no activated agent, then the appliance will provide protection instead.

Deep Security Virtual Appliance memory allocation

The default configuration of the Deep Security Virtual Appliance is to use 4 GB of RAM. If you expect to need more than the default 4 GB, you will need to modify the appliance's configuration. There are two options:

- Modify the configuration of the appliance prior to being imported to Deep Security Manager and then to the vCenter, thereby setting the default configuration for all subsequent appliance service deployments in that vCenter.
- Modify the memory allocation of the appliance on a case-by-case basis after it has been imported to the vCenter and deployed as a service on a ESXi.

For information about the amount of RAM to allocate for appliances, see ["Deep Security Virtual Appliance sizing" on page 109](#).

Configure the appliance's memory allocation prior to deployment to the vCenter

To change the appliance's default memory allocation, you must edit the allocation settings in the appliance's OVF file before it gets imported to the vCenter.

1. Unzip the appliance zip file you downloaded from the Trend Micro Download Center.
2. Open **dsva.ovf** in a text editor.
3. Edit the default memory allocation (4096 MB) to be appropriate for your environment. See, ["Deep Security Virtual Appliance sizing" on page 109](#) for more information.

```
<Item>
<rasd:AllocationUnits>byte * 2^20</rasd:AllocationUnits>
<rasd:Description>Memory Size</rasd:Description>
<rasd:ElementName xmlns:rasd="http://schemas.dmtf.org/wbem/wscim/1/cim-schema/2/CIM_ResourceAllocationSettingData">4096 MB of
memory</rasd:ElementName>
<rasd:InstanceID xmlns:rasd="http://schemas.dmtf.org/wbem/wscim/1/cim-schema/2/CIM_ResourceAllocationSettingData">2</rasd:InstanceID>
<rasd:Reservation>4096</rasd:Reservation>
<rasd:ResourceType>4</rasd:ResourceType>
<rasd:VirtualQuantity>4096</rasd:VirtualQuantity>
</Item>
```

4. Save the OVF file and return it to the zip package.
5. On Deep Security Manager, go to **Administration > Updates Software > Local** and import the appliance ZIP package.

Configure the memory allocation of an already-deployed appliance

Warning: Changing the appliance's memory allocation settings requires powering off the appliance's virtual machine. Virtual machines normally protected by the appliance will be unprotected until it is powered back on. To mitigate this, temporarily configure agent-based protection where possible.

1. In your VMware vSphere Web Client, right-click on the appliance and select **Power > Shut Down Guest**.
2. Right-click on the appliance again and select **Edit Settings**. The Virtual Machine **Properties** screen displays.

Trend Micro Deep Security On-Premise 11.3

3. On the **Hardware** tab, select **Memory** and change the memory allocation to the desired value.
4. Click **OK**.
5. Right-click the appliance again and select **Power > Power On**.

Check digital signatures on software packages

Before you install Deep Security, you should check the digital signature on the software ZIP packages and installer files to make sure the software hasn't been tampered with.

Topics on this page:

- ["Check the signature on software ZIP packages" below](#)
- ["Check the signature on installer files \(EXE, MSI, RPM or DEB files\)" on the next page](#)

Note: You can also check the signature on the Deep Security modules installed into the agent. See ["Linux Secure Boot support for agents" on page 367](#) for details.

Check the signature on software ZIP packages

The ZIP files for the Deep Security Agents, Deep Security Virtual Appliance, and online help are digitally signed using the jarsigner Java utility. The signatures can be verified with the same utility.

To check the signature on the ZIP files:

1. Make sure you have the latest [Java Development Kit](#) installed on the computer where you intend to check the signature.
2. Download the ZIP to the computer where the JDK is installed.
3. Use the [jarsigner utility](#) within the JDK to check the signature. The command is:

```
jarsigner -verify -verbose -certs <ZIP_file>
```

Trend Micro Deep Security On-Premise 11.3

Example:

```
jarsigner -verify -verbose -certs Agent-RedHat_EL7-11.2.0-124.x86_64.zip
```

4. Read any warnings (or errors, if you also included the `-strict` parameter) as well as the content of the certificate to determine if the signature can be trusted.

Note: In addition to checking the agent ZIP file, you can also [check the agent installer file](#).

Check the signature on installer files (EXE, MSI, RPM or DEB files)

The installers for the Deep Security Agent, Deep Security Manager, and Deep Security Notifier are digitally signed using RSA. The installer is an EXE or MSI file on Windows, an RPM file on Linux-based operating systems (namely, Amazon, CloudLinux, Oracle, RedHat, and SuSe), or a DEB file on Debian and Ubuntu.

Note: The instructions below describe how to check a digital signature manually. If you'd like to automate this check, you can include it in your agent deployment scripts. For more on deployment scripts, see ["Use deployment scripts to add and protect computers" on page 437](#).

Follow the instructions that correspond to the type of installer file you want to check.

- ["Check the signature on an EXE or MSI file" below](#)
- ["Check the signature on an RPM file" on the next page](#)
- ["Check the signature on a DEB file" on page 141](#)

Check the signature on an EXE or MSI file

1. Right-click the MSI file and select **Properties**.
2. Click the **Digital Signatures** tab to check the signature.

Check the signature on an RPM file

1. (Optional) Before you begin, check the digital signature on the agent's ZIP file which contains the RPM and supporting files. See ["Check the signature on software ZIP packages" on page 138](#) for details.
2. Find the `3trend_public.asc` file. It's located in the root folder of the agent's ZIP file. The ASC file contains a standard GPG signing key that you can use to verify the digital signature.
3. (Optional) Verify the SHA-256 hash digest of the ASC file using any hashing utility. The hash is:

```
c59caa810a9dc9f4ecdf5dc44e3d1c8a6342932ca1c9573745ec9f1a82c118d7
```

4. On the computer where you intend to check the signature, import the ASC file. Use this command:

Note: Commands are case-sensitive.

```
gpg --import 3trend_public.asc
```

The following messages appear:

```
gpg: directory `/home/build/.gnupg' created
```

```
gpg: new configuration file `/home/build/.gnupg/gpg.conf' created
```

```
gpg: WARNING: options in `/home/build/.gnupg/gpg.conf' are not yet active during this run
```

```
gpg: keyring `/home/build/.gnupg/secring.gpg' created
```

```
gpg: keyring `/home/build/.gnupg/pubring.gpg' created
```

```
gpg: /home/build/.gnupg/trustdb.gpg: trustdb created
```

```
gpg: key E1051CBD: public key "Trend Micro (trend linux sign) <alloftrendetscodesign@trendmicro.com>" imported
```

```
gpg: Total number processed: 1
```

```
gpg: imported: 1 (RSA: 1)
```


Trend Micro Deep Security On-Premise 11.3

5. Export the public key from the ASC file:

```
gpg --export -a 'Trend Micro' > RPM-GPG-KEY-CodeSign
```

6. Import the public key to the RPM database:

```
sudo rpm --import RPM-GPG-KEY-CodeSign
```

7. Verify that the public key has been imported:

```
rpm -qa gpg-pubkey*
```

8. The fingerprints of imported public keys appear. The Trend Micro one is:

```
gpg-pubkey-e1051cbd-5b59ac99
```

9. Check the signature on the RPM file:

```
rpm -K <agent_rpm_file>
```

Example:

```
rpm -K Agent-Core-RedHat_EL7-11.2.0-124.x86_64.rpm
```

10. If the signature is verified successfully, the following message appears:

```
Agent-Core-RedHat_EL7-11.2.0-124.x86_64.rpm: rsa sha1 (md5) pgp md5 OK
```

Check the signature on a DEB file

1. (Optional) Before you begin, check the digital signature on the agent's ZIP file which contains the DEB file and supporting files. See ["Check the signature on software ZIP packages" on page 138](#) for details.
2. Find the `3trend_public.asc` file. It's located in the root folder of the agent's ZIP file. The ASC file contains a standard GPG signing key that you can use to verify the digital signature.

Trend Micro Deep Security On-Premise 11.3

3. (Optional) Verify the SHA-256 hash digest of the ASC file using any hashing utility. The hash is:

```
c59caa810a9dc9f4ecdf5dc44e3d1c8a6342932ca1c9573745ec9f1a82c118d7
```

4. On the computer where you intend to check the signature, import the ASC file. Use this command:

```
sudo apt-key add < 3trend_public.asc
```

The following message appears:

```
OK
```

5. Display the fingerprint of the Trend Micro key:

```
apt-key fingerprint /etc/apt/trusted.gpg
```

The Trend Micro fingerprint is the 40-character string on the second line. In the example below, the fingerprint begins with `CF5E`:

```
pub rsa2048 2018-07-26 [SC] [expires: 2021-07-25]
CF5E BBC1 7D81 78A7 776C 1D36 5B09 AD42 E105 1CBD
uid [ unknown] Trend Micro (trend linux sign) <alloftrendetscodesign@trendmicro.com>
sub rsa2048 2018-07-26 [E] [expires: 2021-07-25]
```

6. Copy the fingerprint to a file for later use.
7. Create a keyring directory. Include *the last* 16 characters of the Trend Micro fingerprint, without spaces. For example:

```
mkdir /usr/share/debsig/keyrings/5B09AD42E1051CBD/
```

8. Import the public key to the `debsig-verify` GPG keyring:

```
gpg --no-default-keyring \
--keyring /usr/share/debsig/keyrings/5B09AD42E1051CBD/<debsig.gpg> \
```

Trend Micro Deep Security On-Premise 11.3

```
--import my-public-key
```

where `<debsig.gpg>` is replaced with any file name you want. These steps assume you used `debsig.gpg`.

9. Create a directory for a policy document that includes the Trend Micro 16-character fingerprint in the path:

```
mkdir /etc/debsig/policies/5B09AD42E1051CBD/
```

10. Create an XML policy document. For example:

```
<?xml version="1.0"?>

<!DOCTYPE Policy SYSTEM "http://www.debian.org/debsig/1.0/policy.dtd">

<Policy xmlns="http://www.debian.org/debsig/1.0/">

  <Origin Name="DSA" id="5B09AD42E1051CBD" Description="Deep Security Agent Package"/>

  <Selection>

    <Required Type="origin" File="debsig.gpg" id="5B09AD42E1051CBD"/>

  </Selection>

  <Verification MinOptional="0">

    <Required Type="origin" File="debsig.gpg" id="5B09AD42E1051CBD"/>

  </Verification>

</Policy>
```

More policy examples are available in `/usr/share/doc/debsig-verify/examples`. Instructions on how to create policy documents are available in `/usr/share/doc/debsig-verify/policy-syntax.txt`.

Trend Micro Deep Security On-Premise 11.3

11. Save the policy document with a `POL` file extension. Example:

```
debsig-verify.pol
```

12. Verify the signature on the DEB file:

```
debsig-verify <agent_deb_file>
```

Example:

```
debsig-verify Agent-Core-Debian_9-11.2.0-122.x86_64.deb
```

13. If the signature is verified successfully, the following message appears:

```
debsig: Verified package from 'Deep Security Agent Package' (DSA)
```

Deploy Deep Security

Install or upgrade Deep Security

This document guides you through the steps required to install or upgrade to Deep Security 11.3.

Tip: If you are upgrading from a previous version of Deep Security, get a version of this article customized for your environment by running the Deep Security Manager installer. Before it installs anything, the installer checks your environment and also provides a link to the customized upgrade instructions.

Prepare your environment

This document is your checklist. Choose your Deep Security platform, then follow these steps for a basic, functional deployment. Once finished, you'll be ready to make security policies.

1. **Download software:** Get your license activation codes.

- Download any required vCenter, ESXi, VMware Tools, and NSX Manager software from [VMware](#).
- Download the latest patch and Deep Security Manager installer (<https://help.deepsecurity.trendmicro.com/software.html>).
- Agent and relay installers are not required; they can be downloaded via the manager. See "[About upgrades](#)" on page 981 for information on installing or updating agents, relays, and the Deep Security Virtual Appliance.

Warning: All Deep Security Relays must be upgraded before upgrading the Deep Security Agent. Failure to do so may cause the relay upgrade to fail.



2. **Verify that the Deep Security installers are authentic (check hashes):**

To verify software authenticity, check the SHA256 hash (also called a fingerprint). Trend Micro publishes its hashes on the [Deep Security Software](#) page. You must click the plus sign next to the software to see the hash (see the figure below).

Manager

Linux

Show All Versions

Software	Release Type	Build	Release Date	File Size	Download
 Deep Security Manager 11.0.240 for Linux-x64	Update: 11.0_U1	11.0.240	2018-08-02	378 MB	

Filename: Manager-Linux-11.0.240.x64.sh

SHA256: 92c6029b9c2fbd8f3a28a261df1bcac917759a9e930004c48275579e689bbe2d

3. **Check compatibility:** Start the installer. Before it installs anything, it checks your environment to make sure it complies with [system requirements](#). The installer also makes sure that *all* your deployment components are compatible with the new version of Deep Security Manager. The readiness check generates a "to do" list of compatibility issues (if any) for your specific environment.

For example, you may need to free disk space, allocate more vRAM, or upgrade old Deep Security Agents to supported versions. If you're not ready yet, you can cancel the install, and return when ready.

The readiness check also customizes this guide for your environment's needs when you click **View My Upgrade Guide**. *Before you install, all tasks under "Prepare your environment" on the previous page must be complete.*

Note: Supported Deep Security features vary by platform. See ["Supported features by platform" on page 85](#).

4. **Back up your data:** Before you install, make a system restore point or VM snapshot of the server and each protected computer. (Multi-node Deep Security Manager deployments should have a backup for each server node.) Also, if upgrading, stop the service and back up your existing Deep Security Manager database.

Warning: Verify your backups. If you don't have backups, and the installer is interrupted for any reason, you won't be able to [revert your deployment](#). This could require you to re-install your entire deployment.

Trend Micro Deep Security On-Premise 11.3

Note:

If you have an existing multi-tenant deployment, back up *all* databases.

- With Microsoft SQL and PostgreSQL, there's one main database and an additional database for each tenant.
- With Oracle, all tenant information is in one Deep Security Manager database, but an additional user is created for each tenant. Each user has its own tables.

Hardware requirements

Recommended hardware varies by enabled features, size of your deployment, and future growth. See [sizing guidelines](#).

On the Deep Security Manager server where you are running the installer, the installer's readiness check will verify hardware before it installs. If hardware does not meet [minimum system requirements](#), the installer will either warn you about reduced performance, or block the install.

Only the *local* server's hardware and some other deployment information that is stored in the database is tested. You must manually verify other servers' hardware, run the readiness check on any other manager nodes, or both.

Note:

On Linux, reserved system memory is separate from process memory. Therefore, although the installer's estimate might be similar, it will detect less RAM than the computer actually has. To verify the computer's actual total RAM, log in with a superuser account and enter:

```
grep MemTotal /proc/meminfo
```

After you install Deep Security 11.3 , you may be able to optimize performance. See ["Configure Deep Security Manager memory usage" on page 196](#), ["Low disk space alerts" on page 198](#), and ["Performance profiles" on page 197](#).

Network requirements

Before you run the installer, verify that the Deep Security Manager server can use its required network services. This includes NTP for reliable time stamps and DNS for name resolution. For a list of protocols, associated features, expected source or destination, and required open network port numbers, see ["Port numbers, URLs, and IP addresses" on page 111](#).

Note: The system clock of the manager operating system must be synchronized with the clock of the database. Both computers should use the same NTP service.

Once Deep Security Manager is installed, when you deploy new agents, appliances, and relays, the manager automatically applies firewall rules to open their required ports.

Warning: If network connectivity is unreliable on required ports, some features may be unreliable or fail.

For some features, Deep Security must be able to resolve host names into IP addresses. If your DNS server does not already have entries so that the manager can resolve each computer or VM's host name to its IP address, then either use their IP address instead, or perform one of the following actions:


- Add an A record, an AAAA record, or both, on your DNS server so that the manager, agents, appliances, and relays can perform DNS lookup queries.
- Add an entry in the agent or appliance computer's hosts file.

Note: Deep Security Manager's certificate generator for SSL or TLS connections requires that the server have an RFC 1034-compliant FQDN. The server's DNS name cannot start with a number, such as 0000-dsm.example.com. If it does, the install log shows this error message:

```
java.io.IOException: DNSName components must begin with a letter
```

Network topology

If you are deploying multiple server nodes of Deep Security Manager for a large scale deployment, a load balancer can help distribute connections with Deep Security Agents and Virtual Appliances. Load balancers with virtual IPs can also provide a single inbound port number such as TCP 443, instead of the multiple port numbers that Deep Security normally requires.



Database requirements

The Deep Security Manager must be co-located on the same network as its database, with the connection speed of 1 GB LAN or higher. Connections over WAN are discouraged. Deep Security Manager relies on the database to function. Any increase in latency can have a serious negative impact on Deep Security Manager's performance and availability.

Requirements vary by database type. See ["System requirements" on page 76](#) and ["Prepare a database for Deep Security Manager" on page 122](#).

Trend Micro Deep Security On-Premise 11.3

If you are installing Deep Security for the first time, before you run the installer, create and grant permissions to the database where Deep Security Manager will store its data.

Note:

If you use Microsoft SQL Server, Deep Security Manager must connect as either a Microsoft Active Directory domain or SQL user. Windows workgroup authentication is no longer supported.

Warning:

Microsoft SQL Server Express is supported only in certain limited deployments. For details, see "[Microsoft SQL Server Express considerations](#)" on page 132.

Migrate to a supported database

If the database is not compatible, you must migrate to a supported database before you can install Deep Security Manager 11.3.

If you are upgrading Deep Security, to continue to store new data until you are ready to install Deep Security Manager 11.3, migrate to a database that is compatible with *both* current and future software. Check the "[System requirements](#)" on page 76 for this version and for the version you are migrating from ([Deep Security 10.0 system requirements](#) or you can find system requirements for earlier versions in their install guides: <http://docs.trendmicro.com/en-us/enterprise/deep-security.aspx>).

For example, if you were currently using an Oracle 10g database with Deep Security Manager 9.5, you would migrate the database to Oracle 11g or 12c first (since it is supported by both Deep Security Manager 9.5 and 11.0), and then upgrade to Deep Security Manager 11.0.

1. Stop the Deep Security Manager service.

Deep Security Agents will continue with their current protection policies while the manager is stopped.

2. Back up the database(s).
3. Back up the database connection settings file:

Trend Micro Deep Security On-Premise 11.3

```
[Deep Security install directory]/webclient/webapps/ROOT/WEB-INF/dsm.properties
```

4. Migrate to a database type that's supported by both your current Deep Security Manager version and Deep Security 11.3.
5. If the migration did not preserve existing databases, load the database backup(s) into the new database engine.
6. If required, edit `dsm.properties` to use the migrated database.
7. Restart the Deep Security Manager service.

Change the remote SQL query timeout

If you use Microsoft SQL Server databases, go to **SQL management studio > SQL Server properties > Connections > Remote query timeout** and select **0 (No Timeout)**. This setting prevents database connection timeouts that can occur when you upgrade if each database schema migration operation takes a long time to complete.

Choose agent-based vs. agentless protection

If you are installing Deep Security for the first time, and you want to protect VMs, you may be able to provide some protection *without* installing a Deep Security Agent, using a Deep Security Appliance instead, or by using both together ("combined mode"). See ["Choose agentless vs. combined mode protection" on page 133](#) and ["Deploy agentless protection in a vCloud environment" on page 283](#).

Install a supported OS

If your server's operating system (OS) is not supported by Deep Security Manager 11.3, you must [install a supported OS](#) before you can install the manager.

If you are upgrading a multi-node deployment, depending on whether you have a load balancer, you might be able to migrate servers to another OS without downtime.

For example, if you already had Deep Security Manager 9.5 on Windows 2003, to migrate the OS you would:

1. Add another manager node that is running a newer OS supported by both Deep Security Manager 9.5 and 11.3, such as Windows Server 2012 (64-bit).

Tip: For a list of supported operating systems, see the install documentation for your current version of Deep Security Manager (See [Deep Security 10.0 system requirements](#) or you can find system requirements for earlier versions in their install guides: <http://docs.trendmicro.com/en-us/enterprise/deep-security.aspx>).

Trend Micro Deep Security On-Premise 11.3

To add the new node, on the Windows 2012 server, run the Deep Security Manager 9.5 installer. When the installer wizard reaches the Database screen, enter the same database connection settings that you used for your other Deep Security Manager node(s). The next page will allow you to specify that you want to add a new manager node. Alternatively, you can perform a silent install to add a new node. For instructions, see ["Silent install of Deep Security Manager" on page 177](#).

2. Verify that everything is working correctly.
3. In Deep Security Manager, go to **Administration > Manager Nodes**, right-click the old Windows 2003 node and select **Decommission** to remove it.
4. Upgrade the OS of the decommissioned node, then return it to the pool.
5. Repeat these steps with any other nodes that have an unsupported OS.

Upgrade unsupported Deep Security Managers

If your manager is old and the installer does not support upgrading it, the installer will prevent you from continuing. You must upgrade the manager to a supported version first. After that, you can install Deep Security Manager 11.3.

The installer supports upgrade from:

- Deep Security Manager 10.0, 10.1, 10.2, or 10.3
- Deep Security Manager 9.6 Service Pack 1 Patch 1
- Deep Security Manager 9.6 Patch 1

For instructions on how to upgrade from an unsupported version to a supported version, see the installation guide for the unsupported version:

<http://docs.trendmicro.com/en-us/enterprise/deep-security.aspx>

Upgrade unsupported relays

If your relays don't meet [minimum system requirements](#), you must upgrade them to be compatible with the new version of the manager *before* you upgrade the manager itself. Since it would break part of your deployment, the installer will warn you if you have incompatible versions, although it won't stop you if a specific relay isn't compatible. This allows you to continue if a specific relay isn't being used now, or is offline.

Trend Micro Deep Security On-Premise 11.3

Note: Deep Security 11.3 requires 64-bit relays.

For instructions on how to upgrade to a supported version, see those versions' install guides:

<http://docs.trendmicro.com/en-us/enterprise/deep-security.aspx>

After you have upgraded the manager, to use new features, you will upgrade the relays again to Deep Security Relay 11.3.

VMware requirements

If you want to use agentless or combined mode protection, follow the steps below to [install compatible VMware components](#) before you install the new Deep Security.

If you are upgrading, and your existing appliances are not compatible with the new Deep Security, also follow those steps to install compatible versions.

- **vSphere or ESXi** – ESXi 6.0 or later is required.
- **vCNS** – vCloud Networking & Security (vCNS) is not supported. If you have legacy vCNS infrastructure for agentless anti-malware and integrity monitoring with Deep Security Virtual Appliances, VMware has discontinued support, so Deep Security Manager 11.3 cannot support it. You must update vCNS to VMware's equivalent new solution: NSX.

Use either:

- **NSX Advanced or Enterprise license** – Full agentless protection. Requires Deep Security Virtual Appliance 10.0 or later and ESXi 6.0 or later.
- **NSX vShield Endpoint or Standard license** – Only agentless anti-malware and integrity monitoring. (No network protection: firewall, intrusion prevention, web reputation.) Also requires manual sync of Deep Security Manager with NSX Manager or vCenter to determine NSX security group membership. Requires Deep Security Virtual Appliance 10.0 or later and ESXi 6.0 or later.

Alternatively, for full protection including network protection features, combine the virtual appliance with a Deep Security Agent on each guest VM (also known as "combined mode").

Trend Micro Deep Security On-Premise 11.3

During vCNS upgrade, you must also replace the network filter driver with the NetX API on each ESXi server. The VMware Tools driver for EPSec on each guest VM must also be upgraded, and is now called Guest Introspection.

- **NSX** – NSX 6.3 or later is required.
- **Deep Security Virtual Appliances** – Deep Security Virtual Appliances 10.0 or later are required. See the [minimum system requirements](#) and see "Upgrade the Deep Security Virtual Appliance" on page 987.

Upgrade virtual appliances

Since it would break part of your deployment, the installer will warn you if you have incompatible versions of virtual appliances, although the installer will not stop installation if a specific appliance is not compatible. (This allows you to proceed if the virtual appliance isn't used, or is offline.) However, the installer will not allow you to continue if you have incompatible versions of ESXi or vShield Manager / NSX Manager.

VMware dependencies exist. You must select versions that are compatible with each other. To easily choose compatible versions, see Trend Micro Support's VMware compatibility matrix (updated with each release):

<https://success.trendmicro.com/solution/1060499>

Warning: To ensure that you don't lose connectivity by upgrading an infrastructure component to a version that isn't compatible with the others, and to minimize downtime, **update in this order**.

1. [Back up the vCenter database](#). Methods vary by version and storage.
2. [Upgrade vCenter](#).
3. If you are upgrading, on Deep Security Manager, go to **Computers**. Deactivate agentless computers or agents in combined mode.

Deactivate the Deep Security Virtual Appliances.

Trend Micro Deep Security On-Premise 11.3

In NSX Manager, also delete the virtual appliances on each ESXi server.

Tip: Alternatively, to ensure continuous protection during the upgrade of NSX, ESXi, or virtual appliances, configure computers to use agents for protection instead. Otherwise, computer's won't be protected until you install and activate the appliances and agents again.

4. If they exist, on protected guest VMs, uninstall the VMware Tools EPSec driver. On ESXi servers, uninstall the VMsafe-net API (network filter driver).

In Deep Security Manager, disconnect vShield Manager or NSX 6.2.3 or earlier (*not vCenter*).

Then [upgrade vShield Manager or older NSX versions to NSX 6.3.x](#).

If you don't have legacy vShield Manager or its components (such as the filter driver) and you have NSX 6.3.x or later, skip this step.

Warning: You must replace vShield Manager with NSX. Otherwise any configured agentless protection won't work after you upgrade to Deep Security 11.3. This could compromise the security of your protected computers.

5. [Upgrade ESXi](#).

Depending on your architecture, you might also be required to upgrade:

- [dvSwitches](#)
- [vShield App \(to NSX Distributed Firewall\)](#)
- [vShield Edge](#)

6. ["Run the installer" on page 159](#) for Deep Security Manager.

7. If you disconnected NSX Manager in [step 4](#), in Deep Security Manager, go to **Computers > vCenter**. Reconnect NSX Manager. Click **Test Connection** to verify the connection.

This will add "Trend Micro Deep Security service" to NSX Manager.

Trend Micro Deep Security On-Premise 11.3

8. To protect your VMs with Deep Security Virtual Appliance for file-based protection such as anti-malware, [install Guest Introspection](#).

VMware vShield Endpoint Driver in VMware Tools 5.x is renamed Guest Introspection in NSX 6.2.4 and later.

9. On every protected guest VM, to provide file-based protection such as anti-malware, perform a custom install of VMware Tools. Ensure that the NSX File Introspection option is selected. (See [Installing VMware Tools](#) in the vSphere documentation.)

Warning: You must install VMware Tools. If you don't, Deep Security Manager won't be able to get the VM's correct hostname and IP address. If the manager forwards incorrect data to Trend Micro Control Manager, Control Manager won't be able to display that endpoint.

10. On NSX Manager, [deploy new Deep Security Virtual Appliances](#) onto each ESXi. If you are upgrading the appliance, refer to "[Upgrade the agent embedded on the appliance SVM and apply OS patches](#)" on page 1007.

Note: Do not upgrade the virtual appliance's VMware Tools; it is packaged with a compatible version, and upgrading them can break connectivity.

A "VMware Network Fabric" service dependency alert might appear, even if communications succeed. To dismiss the alert, click **Failed**, then click **Resolve**.

11. Verify that ESXi and NSX are integrated and communicating.

12. [Create NSX security groups](#).

If using the vShield Endpoint or Standard license, also manually sync Deep Security Manager with vCenter or vShield Endpoint to [retrieve the NSX security group membership and start protection](#).

13. [Create NSX security policies](#).

If VMs might change security groups, set up [automated NSX security policy management](#) or "[Synchronize Deep Security policies with NSX](#)" on page 281

14. "[Enable agentless protection of vCloud VMs](#)" on page 284.

Trend Micro Deep Security On-Premise 11.3

["Configure VMware vCloud resources for integration with Deep Security" on page 284.](#)

15. [Deploy and activate new Deep Security Virtual Appliances.](#)

(Refer to ["Upgrade the Deep Security Virtual Appliance" on page 987](#) for information on upgrading the Deep Security Virtual Appliance.)

If you are using the VMware Distributed Resource Scheduler (DRS) for high availability (HA), [use affinity rules](#) to "pin" each virtual appliance to its specific ESXi host.

16. [Install and activate new Deep Security Agents.](#)

If NSX has the NSX vShield Endpoint or Standard license, network-based protection features (firewall, intrusion prevention, web reputation) are not supported by the new NSX license. To maintain protection and provide those features, configure agents in combined mode. To verify that security features are working again, you can test each feature's configuration:

<https://success.trendmicro.com/solution/1098449>

Tip: Firewall features can now be provided by the NSX Distributed Firewall. You can disable the firewall in Deep Security 11.3. Alternatively, you can exclude VMs from the NSX Distributed Firewall, and use the Deep Security firewall instead (see [Exclude Virtual Machines from Firewall Protection](#)).

If you are upgrading, after you have installed Deep Security Manager 11.3, if you want to use the new features, you will upgrade your virtual appliances, agents, and relays again, to Deep Security 11.3.

Conversion of coordinated approach to combined mode

- **Coordinated approach** – In Deep Security 9.5, if the agent on a VM was offline, protection features would be provided by the Deep Security Virtual Appliance instead as an alternative. However, it could *not* be configured separately for each feature.
- **Combined mode** – In Deep Security 9.6, each protection feature was configurable to use either the agent or appliance. However, if the preferred protection source was offline, the computer *didn't* use the other alternative.

In the new Deep Security, its "protection source" settings provide *both* behaviors:

Trend Micro Deep Security On-Premise 11.3

- whether each feature is provided by the agent or appliance
- whether to use the agent or appliance alternative if the preferred protection is not available

So if you need behavior like the old coordinated approach, you might want to upgrade *directly* from Deep Security 9.5 to 11.3 – *not* from 9.5 to 9.6 and then 11.3.

Pin appliances with VMware HA

If you will use [agentless](#) protection, and use VMware Distributed Resource Scheduler (DRS) for high availability (HA), configure it before you install Deep Security. Then deploy Deep Security Virtual Appliance on **all** ESXi hypervisors (including backup hypervisors), and use affinity settings "pin" them to each ESXi server. This will ensure that agentless protection is still being applied after HA failover.

Warning: If DRS moves a VM from an ESXi that has an appliance to one that doesn't, the VM will become unprotected. If the VM then returns to the original ESXi, it still won't be protected again *unless* you create an event-based task to re-activate and protect a VM when vMotion moves it to an ESXi with an appliance. For more information, see ["Automatically perform tasks when a computer is added or changed" on page 422](#).

Note: Don't apply vMotion to the appliance. Keep each appliance on its specific ESXi server: in the DRS settings, select **Disabled** (recommended) or **Manual**. (Alternatively, deploy the appliance onto local storage, not shared storage. When the virtual appliance is deployed onto local storage, DRS won't apply vMotion.) For more information, see your VMware documentation.

Upgrade unsupported agents

If your agents don't meet [minimum system requirements](#), you must upgrade them to be compatible with the new version of the manager *before* you upgrade the manager itself. Since it would break part of your deployment, the installer will warn you if you have incompatible versions, although it won't stop you if a specific agent isn't compatible. This allows you to continue if a specific agent isn't being used now, or is offline.

For instructions on how to upgrade to a supported version, see those versions' install guides:

<http://docs.trendmicro.com/en-us/enterprise/deep-security.aspx>

Trend Micro Deep Security On-Premise 11.3

After you have upgraded the manager, to use new features, you will upgrade the agents again to Deep Security Agent 11.3.

Run the installer

Once your environment is ready, install the latest patches (if any), then run the installer as root, superuser, or (on Windows) Administrator. You can use either:

- Graphical, interactive installer (follow the steps in the wizard)
- Silent installer (see ["Silent install of Deep Security Manager" on page 177](#))

If you use Microsoft SQL Server, then Deep Security Manager connection settings vary by authentication type:

- **SQL Server:** Enter the **User name** and **Password**.
- **Active Directory:** Enter the **User name (no domain)** and **Password**, then click **Advanced** and enter the **Domain** separately. Also known as Kerberos or Windows domain authentication.

See also ["SQL Server domain authentication problems" on page 1462](#).

If you are installing Deep Security Manager on Linux with iptables enabled, also configure the iptables to allow agents' heartbeat port numbers and management traffic. See ["Port numbers, URLs, and IP addresses" on page 111](#).

If you are upgrading to the new Deep Security Manager, if you want to use the new features, upgrade your virtual appliances, agents, and relays again to match the new version.

Multi-node manager

For high availability and scalability in larger deployments, [use a load balancer](#), and install **same version** of Deep Security Manager on multiple servers ("nodes") with the **same master key** (if configured). Connect them to the **same database storage**.

Trend Micro Deep Security On-Premise 11.3

All nodes that use the same database must have the same software version. This ensures data compatibility, and that how they handle protected computers is consistent. All nodes must also use the same master key (if configured) and have it always available so that they all can decrypt and read the encrypted configuration properties and personal data when required. For more information, see [masterkey](#).

Warning: Never run the installer on multiple nodes at the same time. Simultaneous upgrades can corrupt the database. If this happens, you must restore the database backup (if upgrading) or recreate the database (if a new install), and then start the installer again.

If you are **upgrading** a multi-node Deep Security Manager:

1. Stop all nodes.
2. Run the installer on one node first.

When upgrade is complete for the first node, its service will start. Until other nodes are also upgraded, it will be the only node whose software is compatible with the database, so initially it will be the only available manager. Because it must perform all jobs, you might notice that performance is reduced during this time. On **Administration > System Information**, Network Map with Activity Graph will indicate that other nodes are offline, and that they require an upgrade.

3. Upgrade other nodes.

As you upgrade them too, other nodes will return online, and begin to share the load again.

4. If you configured a custom master key, run the [masterkey](#) commands to encrypt existing data on only *one* of the nodes.

Warning: Never run the installer on multiple nodes at the same time. Simultaneous upgrades can corrupt the database. If this happens, you must restore the database backup, then start the upgrade again.

Other steps in the install or upgrade process are the same, regardless of whether you have one server or multiple.

Trend Micro Deep Security On-Premise 11.3

Install Deep Security Manager on Linux

You can use the command line to perform a [silent install](#), or, if you have X Windows installed, you can use the graphical installer.

1. Run the install package. Follow the instructions in the setup wizard.
2. The installer will detect existing Deep Security Manager installations on that server. Select either:
 - **Fresh install (can use existing or new database):** Install Deep Security software. Initialize the database.
 - **Upgrade:** Install new Deep Security software, but keep existing computer details, policies, intrusion prevention rules, firewall rules, etc. Migrate data to new formats if required.

Warning: If you select **Fresh install (can use existing or new database)**, the installer will delete all data from any previous installation.

3. If iptables is enabled, configure rules to allow incoming connections from agents' heartbeat and management traffic port numbers. See also "[Port numbers, URLs, and IP addresses](#)" on page 111.

Install Deep Security Manager on Windows

You can use the command line to perform a [silent install](#), or you can use the graphical installer.

1. Run the install package. Follow the instructions in the setup wizard.
2. The installer will detect existing Deep Security Manager installations on that server. Select either:
 - **Fresh install (can use existing or new database):** Install Deep Security software. Initialize the database.
 - **Upgrade:** Install new Deep Security software, but keep existing computer details, policies, intrusion prevention rules, firewall rules, etc. Migrate data to new formats if required.

Warning: If you select **Fresh install (can use existing or new database)**, the installer will delete all data from any previous installation.


Trend Micro Deep Security On-Premise 11.3

Install a relay on the Deep Security Manager's server

Deep Security requires at least one relay. Relays distribute [security updates](#) to protected computers. For more information on relays, see "[Distribute security and software updates with relays](#)" on page 380.

Trend Micro Deep Security On-Premise 11.3

When you run the Deep Security Manager installer, it will search its local directory for a full ZIP package of the agent installer. (Relays are agents whose relay feature is enabled.) If it's not found, then the manager's installer will try to download one from the Trend Micro Download Center on the Internet.



Trend Micro Deep Security On-Premise 11.3

- If an agent installer is found in either location, the manager's installer will offer to install the newest relay.

Tip:

Trend Micro recommends that you install a local relay to:

- Provide a relay that is local to the manager
- Ensure that at least one relay is always available, even when you decommission old computers with relays

Warning: When the manager's installer adds an agent to its server, it **only enables the relay feature**. It does not apply any default security settings. To protect the server, in Deep Security Manager, [apply a security policy](#) to its agent.

- If no agent installer is found, you can download and [install an agent or relay later](#).

Schema updates

Unlike with Deep Security Manager 9.6 and earlier, if you are updating, your database administrator (DBA) doesn't need to update the manually database schema first. The installer will make any required database schema changes. If that is interrupted for any reason, simply restore your database backup, then try again. Many possible causes are temporary, such as unusually high load or network maintenance. If the problem persists, contact your support provider. Errors, if any, are logged in:

```
<install-directory>/DBUpgrade/SchemaUpdate
```

where the default <install-directory> is `/opt/dsm` (Linux) or `C:\Program Files\Trend Micro\Deep Security Manager` (Windows). Two types of files are created:

- `T-00000-Plan.txt` - All data definition language (DDL) SQL statements that the installer will use to update the schema.
- `T-00000-Progress.txt` - Schema update progress logs. When finished, the installer changes the file name to either `T-00000-Done.txt` (successful update) or `T-00000-Failed.txt` (update failure).

If the schema update fails for t0 (the root tenant), the installer will not continue. You must restore the database backup and then try again.

Trend Micro Deep Security On-Premise 11.3

However, if multi-tenancy is enabled, and if the upgrade fails for any *other* tenant(s), the installer *will* continue. For each tenant, the installer will create one of each type of log file, where "00000" is the tenant number, such as "00001" for tenant t1. You can either restore the database backup and try again, or retry the schema update for that specific tenant (see Force a multi-tenant upgrade).

Force a multi-tenant database upgrade

If you have a [multi-tenant environment](#), and are upgrading Deep Security Manager:

1. The installer updates the database schema.
2. The installer migrates data into the new structures for the primary tenant (t0).

If t0 migration fails, the installer can't recover. It will not continue. You must restore the database from backup, and then try again.

3. The installer migrates data for other tenants (five in each batch).

If any non-primary tenant's migration fails, the installer *will* continue, but those tenant's state on **Administration > Tenants** will be **Database Upgrade Required (offline)**. You can either restore from backup and run the installer again, or you can retry migration for that specific tenant.

To retry a tenant's migration, use the tenant's interface. If forcing a retry does not work, please contact your support provider.

Roll back an unsuccessful upgrade

If you are upgrading, and problems occur when you install Deep Security Manager 11.3, you can quickly revert to a functional state if you:

- Backed up the database *before* the upgrade
- Didn't upgrade the agents, relays, or virtual appliances yet (or have VM snapshots or system backups that you made *before* the upgrade)

1. Stop the Deep Security Manager service.
2. Restore the database.
3. Restore all Deep Security Manager server nodes.

Trend Micro Deep Security On-Premise 11.3

4. If you changed the hostname, FQDN, or IP address of the Deep Security Manager during the upgrade, restore them.
5. Restore the agents, relays, and virtual appliances.
6. Start the Deep Security Manager service.
7. Verify connectivity to the Deep Security Manager, including the connection between the manager and agents.

After the installer

The "Trend Micro Deep Security Manager" service starts automatically when you finish its installer. To log into Deep Security Manager's GUI, open a web browser and go to:

```
https://[host_name]:[port]/
```

where `[host_name]` is the IP address or domain name of the server where you installed Deep Security Manager, and `[port]` is the Manager Port you specified during installation.

Complete the deployment by installing the:

1. Relay(s)
2. Virtual appliance(s), if any
3. Agent(s), if any

Note: Upgrade to Deep Security Manager 11.3 *before* you upgrade relays, appliances, and agents to 11.3. They must be of the same version or less than their manager. If they aren't, they may not be able to communicate with the manager until you upgrade it, too.

Self-signed certificate

If you are installing Deep Security for the first time, the installer creates a self-signed server certificate that Deep Security Manager will use to identify itself during secure connections with agents, appliances, relays, and your web browser. It is valid for 10 years. However, because it is not signed by a trusted certificate authority (CA), and

Trend Micro Deep Security On-Premise 11.3

therefore the manager's identity can't be automatically authenticated, your web browser will display warnings. To eliminate the error message and improve security, replace Deep Security's server certificate with one signed by a trusted CA. For information on using a certificate from a CA, see ["Replace the Deep Security Manager SSL certificate" on page 1035](#).

Upgrades keep the manager's server certificate. You won't need to re-install it each time, unless you perform a fresh install.

Strengthen encryption

If you are upgrading, the manager's server certificate is kept. You won't need to re-install it each time, unless you perform a fresh install. Weak cryptography usually violates compliance, however. **Exploits and fast brute force exist for old authentication, encryption methods, and protocols.** This includes SHA-1. So you may need to replace your Deep Security certificates anyway. See ["Upgrade the Deep Security cryptographic algorithm" on page 1416](#) and ["Replace the Deep Security Manager SSL certificate" on page 1035](#).

Event data migration

If you are upgrading, the installer will make any required database schema changes. It then migrates data for protected computers into the new schema.

Part of the database is event data. Event data can be large, depending on how much data you chose to keep during the installer. Event data isn't required for policy and computer management features, however, so the installer *won't* wait until all event data is migrated.

Instead, when you exit it, the installer will restart the Deep Security Manager service. Then Deep Security Manager will continue to migrate older event data into the new schema. Progress is indicated in the status bar at the bottom of the window, in new events, and (if an error occurs) alerts. Total migration time required varies by the amount of data, disk speed, RAM, and processing power.

New event data will still be recorded, and is available as usual during that time.

Note: Alerts, dashboards, event search, and reports all use event data. Until database upgrade migration is complete, results which include *older* event data may be incomplete, and counters may be inaccurate.

Trend Micro Deep Security On-Premise 11.3

Upgrade relays on Linux (dpkg)

For Linux distributions that use the dpkg package manager (Debian and Ubuntu), the command is the same.

1. Go to **Administration > Updates > Software > Download Center**. "[Get Deep Security Agent software](#)" on page 318.
2. Go to **Computers**.
3. Find the computer that you want to upgrade.
4. Right-click the computer and select **Actions > Upgrade Agent software**.

The new agent software will be sent to the computer and the relay will be upgraded.

Alternatively, manually copy the agent installer file to the computer and run it.

- a. Copy the agent installer file to the computer.

Enter the command:

- b. `sudo dpkg -i <installer file>`

Upgrade relays on Linux (rpm)

For Linux distributions that use the rpm package manager (Red Hat, CentOS, Amazon Linux, Cloud Linux, and SUSE), the command is the same.

1. Go to **Administration > Updates > Software > Download Center**. "[Get Deep Security Agent software](#)" on page 318.
2. Go to **Computers**.
3. Find the computer that you want to upgrade.
4. Right-click the computer and select **Actions > Upgrade Agent software**.

The new agent software will be sent to the computer and the relay will be upgraded.

Alternatively, manually copy the agent installer file to the computer and run it.

Trend Micro Deep Security On-Premise 11.3

- a. Copy the agent installer file to the computer.

Enter the command:

- b. `sudo rpm -U <installer rpm>`

(The "-U" argument instructs the installer to perform an upgrade.)

Upgrade relays on Windows

1. On Deep Security Manager, go to **Settings > General > Agent Self Protection**.
2. Disable agent self-protection so that the agent will allow the upgrade.
3. Go to **Computers**.
4. Find the computer that you want to upgrade.
5. Right-click the computer and select **Actions > Upgrade Agent software**.

The new agent software will be sent to the computer and the relay will be upgraded.

Alternatively, manually copy the agent installer file to the computer and run it. Follow the wizard's instructions.

Upgrade agents on Windows

1. On Deep Security Manager, go to **Settings > General > Agent Self Protection**.
2. Disable agent self-protection so that the agent will allow the upgrade.
3. Go to **Computers**.
4. Find the computer that you want to upgrade.
5. Right-click the computer and select **Actions > Upgrade Agent software**.

The new agent software will be sent to the computer and the agent will be upgraded.

Trend Micro Deep Security On-Premise 11.3

Alternatively, manually copy the agent installer file to the computer and run it. Follow the wizard's instructions.

6. If anti-malware is enabled, and you upgraded the agent on Windows Server 2012 or later (or, for personal computers, Windows 8 or later), reboot the computer.

Warning: The upgrade will not be complete (and protection may not be functional) until you reboot.

Upgrade agents on Linux

1. Go to **Administration > Updates > Software > Download Center**. "[Get Deep Security Agent software](#)" on page 318.
2. Go to **Computers**.
3. Find the computer that you want to upgrade.
4. Right-click the computer and select **Actions > Upgrade Agent software**.

The new agent software will be sent to the computer and the relay will be upgraded.

Alternatively, manually copy the agent installer file to the computer and run it.

- a. Copy the agent installer file to the computer.

If the computer uses the rpm package manager (Red Hat, CentOS, Amazon Linux, Cloud Linux, SUSE), enter the command:

- b. `sudo rpm -U <installer file>`

(The "-U" argument instructs the installer to perform an upgrade.)

If the computer uses the dpkg package manager (Debian or Ubuntu), enter the command:

```
sudo dpkg -i <installer file>
```

Trend Micro Deep Security On-Premise 11.3

Upgrade agents on Solaris to version 10.0

Note: The Deep Security Agent for AIX and Solaris have not been tested for use with Deep Security Manager 11.3, which is a feature release. The AIX and Solaris platforms continue to be fully supported using Deep Security Manager 11.0 and will continue to be supported in the next major release (Deep Security 12.0). If you have AIX and/or Solaris platforms in your deployment, please continue to use Deep Security Manager 11.0.

Download security updates for Deep Security Agent 8.0 and 9.0

Deep Security 11.3 is a feature release and has not been tested for use with Deep Security Agent 8.0 or 9.0, including:

- Deep Security Agent 8.0 on Windows 2000
- Deep Security Agent 9.0 on AIX 6.1, 7.1, or 7.2
- Deep Security Agent 9.0 Solaris 10 Updates 4-10

Those platforms continue to be fully supported using Deep Security Manager 11.0 and will continue to be supported in the next major release (Deep Security 12.0). If you have AIX and/or Solaris platforms in your deployment, please continue to use Deep Security Manager 11.0. If you are currently using Deep Security Agent 8.0 on Windows 2000, you can upgrade the agent to version 9.6, which is compatible with Deep Security Manager 11.3.

Choose an agent or appliance for each protection feature

If a computer could be protected by either an appliance or agent, you can select which will provide each protection feature.

Note: Log inspection and application control do not have this setting. With current VMware integration technologies, Deep Security Virtual Appliance cannot provide those features.

To configure the protection source, import a VMware vCenter into Deep Security Manager, then in the **Computer or Policy editor**¹, go to **Settings > General**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Protection Source when in Combined Mode

Select which component will provide protection when both the Agent and the Appliance are present.

Anti-Malware:

Inherited (Appliance preferred)

Web Reputation / Firewall / Intrusion Prevention:

Inherited (Agent preferred)

Integrity Monitoring:

Inherited (Appliance preferred)

Protection Modules not shown here do not support Combined Mode configuration.

For each protection module or group of protection modules, select either:

- **Appliance Only:** Only the Deep Security Virtual Appliance will provide protection, even if there is an agent on the VM and the appliance is deactivated or removed.

Warning: Don't use the appliance if you require the scanner (SAP). It requires Deep Security Agent anti-malware.

Tip: When anti-malware is enabled on the agent, the agent downloads the Anti-malware Solution Platform (AMSP) and starts it as a service. If you do not want this, then from **Anti-Malware**, select **Appliance Only**. That way, even if the appliance is deactivated, the agent won't start the AMSP service.

- **Appliance Preferred:** If there is an activated appliance on the ESXi server, it will provide the protection. But if the appliance is deactivated or removed, then the agent will provide protection instead.
- **Agent Only:** Only the agent will provide protection, even if there is an activated appliance available.
- **Agent Preferred:** If there is an activated agent on the VM, it will provide the protection. But if there is no activated agent, then the appliance will provide protection instead.

Trend Micro Deep Security On-Premise 11.3

Install a new Deep Security Agent or Relay

To use new features, you must install Deep Security Agent or Relay 11.3. If you don't require the newest features, or if you need compatibility with legacy systems, however, you can install any supported version. For supported Deep Security Agent versions on each platform, see ["Deep Security Agent platforms" on page 80](#).

Most steps are the same, whether you want to install a Deep Security Agent or Relay. (A relay is a Deep Security Agent where you have enabled the relay feature.) Relays update your agents more quickly, reduce manager load, and save internet connection or WAN bandwidth. **You must have at least one relay. Relays download software and security updates from Trend Micro and the manager, and redistribute them to your protected computers.**

1. Go to **Administration > Updates > Software > Download Center**. ["Get Deep Security Agent software" on page 318](#).

Warning: Even if you use a third party deployment system, you **must** import all installed Deep Security Agent software into the Deep Security Manager's database. When a Deep Security Agent is first activated, it only installs protection modules that are currently enabled in the security policy. If you enable a new protection module later, Deep Security Agent will try to download its plug-in from Deep Security Manager. If that software is missing, the agent may not be able to install the protection module.

2. Install the agent software on computers. There are multiple methods:
 - **Manual deployment:** Run the install package on the computer, then activate it and assign a policy. For instructions, see ["Manually install the Deep Security Agent" on page 322](#).
 - **Deployment scripts:** Upload and then run the installer using Linux or Unix shell scripts or Microsoft PowerShell. For instructions, see ["Use deployment scripts to add and protect computers" on page 437](#).
 - **Ansible:** For Ansible recipes, see the [Deep Security Ansible playbook](#) on GitHub.
 - **Chef:** For Chef recipes for deployment and management, see the [Deep Security Chef cookbook](#) on GitHub.
 - **Puppet:** For Puppet manifests, see the [Deep Security Puppet manifests repository](#) on GitHub.

- **SCCM:** Microsoft System Center Configuration Manager (SCCM) can install an agent, activate it, and apply a policy. To use SCCM, go to **Administration > System Settings > Agents** and enable agent-initiated activation.
 - **Template or Elastic Beanstalk:** Include the agent in your VM template. See ["Bake the agent into your AMI or WorkSpace bundle" on page 337](#) and [AWS Elastic Beanstalk scripts](#)
3. ["Activate the agent" on page 370.](#)
 4. ["Assign a policy to a computer" on page 522.](#)
 5. If you want to enable the agent to act as a Deep Security Relay, see ["Distribute security and software updates with relays" on page 380](#). (Alternatively, if you already have a web server, you can provide agent software updates via the web server instead of a relay-enabled agent. To do this, you must mirror the software repository of the relay-enabled agent on your web server. For more information on configuring your own software distribution web servers, see ["Use a web server to distribute software updates" on page 1026.](#))

Relays must be able to download components that they will redistribute. To test the relay, go to the **Administration > Updates > Security**. Under both **Pattern Updates** and **Rule Updates**, click **Check For Updates and Download**.

To configure how often your relays check for updates, go to **Administration > Scheduled Tasks**.

Warning: Deployments require at least one relay. Agents cannot download important software and security updates if they cannot connect to a relay. You can add a relay on the same server while installing Deep Security Manager. If you did not do this, then enable the relay feature on at least one 64-bit agent. To verify how many relays you have, go to **Administration > Updates > Relay Management** and examine how many relays are below each group. For details, see ["Distribute security and software updates with relays" on page 380](#).

6. If you require security update packages for older agents, go to **Administration > System Settings > Update** and select **Allow supported 8.0 and 9.0 Agents to be updated**.

Set up alerts

Deep Security Manager can notify you when important system events occur.

Alternatively, if you have an external SIEM, you can forward events to it. Go to **Policies > Common Objects > Other > Syslog Configurations and Administration > System Settings > Event Forwarding** (see ["Forward Deep Security events to an external syslog or SIEM server" on page 1111](#)).

1. Go to **Administration > System Settings > SMTP**. Configure how Deep Security Manager will connect to your email server.
When you test, you should see a **Test connection to SMTP server succeeded** message. If the test fails, verify your [SMTP settings](#), and that your server and the network allows communication on the [required port numbers](#).
2. Go to **Administration > User Management > Users**. Double-click your user account, and select **Receive Alert Emails**.
3. Go to **Alerts and Administration > System Settings > Alerts** (see ["Configure alerts" on page 1066](#)). Double-click each alert, then select which conditions will send an

email.

General

Alert Information

Alert:

Anti-Malware Alert

Description:

A Malware Scan Configuration that is configured for alerting has raised an event on one or more computers.

Dismissible:

Yes

On

When on, the alert will be raised when the conditions are met.

Options

Severity:

Warning

Alert for all rules (Regardless of rule settings)

Send Email to notify when this alert is raised.

Send Email to notify when conditions for this alert change (such as the # of items).

Send Email to notify when this alert no longer exists.

Off

When off, the alert will not be raised. Use this setting if you do not wish this condition to raise an alert.

OK

Cancel

Apply

Run a recommendation scan

If you're not sure how to begin configuring your security policies, Deep Security Manager can scan your protected computers, looking for vulnerable software and settings, and provide recommended security settings. Go to **Computers** and select **Actions > Scan for Recommendations** (see ["Manage and run recommendation scans" on page 529](#)).

176

Silent install of Deep Security Manager

Run a silent install readiness check

You can run the installer in readiness check mode to make sure your environment is ready for the Deep Security installation. Nothing will be installed but the installer will create reports about your installation environment, which you can use to fix any issues before actually installing Deep Security Manager.

To initiate a silent readiness check on Windows, open a command prompt in the same directory as the install package and run:

```
Manager-Windows-<Version>.x64.exe -q -console -Dinstall4j.language=<ISO code>-varfile <PropertiesFile> -t
```

To initiate a silent readiness check on Linux, use the command line to go to the same directory as the install package and run:

```
Manager-Linux-<Version>.x64.sh [-q] [-console] -t [-Dinstall4j.language=<ISO code>] [-varfile <PropertiesFile>]
```

Run a silent install on Windows

To initiate a silent install on Windows, open a command prompt in the same directory as the install package and run:

```
Manager-Windows-<Version>.x64.exe -q -console -Dinstall4j.language=<ISO code> -varfile <PropertiesFile>
```

Run a silent install on Linux

Note: Before executing this command, grant execution permission to the installation package.

To initiate a silent install on Linux, use the command line to go to the same directory as the install package and run:

```
Manager-Linux-<Version>.x64.sh [-q] [-console] [-Dinstall4j.language=<ISO code>] [-varfile <PropertiesFile>]
```

Parameters

`-q` forces the installer to execute in unattended (silent) mode.

Trend Micro Deep Security On-Premise 11.3

`-console` forces messages to appear in the console (stdout).

`-Dinstall4j.language=<ISO code>` lets you override the default installation language (English) if other languages are available. Specify a language using standard ISO language identifiers:

- Japanese: **ja**
- Simplified Chinese: **zh_CN**

`-varfile <PropertiesFile>` , where `<PropertiesFile>` is the full path to standard Java properties file with entries for the various settings you can apply during a Deep Security Manager install. Each property is identified by its equivalent GUI screen and setting in the Windows Deep Security Manager installation. For example, the Deep Security Manager address on the "Address and Ports" screen is specified as:

```
AddressAndPortsScreen.ManagerAddress=
```

Most of the properties in this file have acceptable defaults and may be omitted.

For a complete description of available settings, see ["Deep Security Manager settings properties file" on the next page](#).

`-t` runs an installer readiness check rather than a regular install.

Sample properties file

This is an example of the content of a typical properties file:

```
AddressAndPortsScreen.ManagerAddress=10.xxx.xxx.xxx
AddressAndPortsScreen.NewNode=True
UpgradeVerificationScreen.Overwrite=False
LicenseScreen.License.-1=XY-ABCD-ABCDE-ABCDE-ABCDE-ABCDE-ABCDE
DatabaseScreen.DatabaseType=Microsoft SQL Server
DatabaseScreen.Hostname=10.xxx.xxx.xxx
DatabaseScreen.Transport=TCP
DatabaseScreen.DatabaseName=XE
```

Trend Micro Deep Security On-Premise 11.3

```
DatabaseScreen.Username=DSM
DatabaseScreen.Password=xxxxxxx
AddressAndPortsScreen.ManagerPort=4119
AddressAndPortsScreen.HeartbeatPort=4120
CredentialsScreen.Administrator.Username=masteradmin
CredentialsScreen.Administrator.Password=xxxxxxx
CredentialsScreen.UseStrongPasswords=False
SecurityUpdateScreen.UpdateComponents=True
SecurityUpdateScreen.Proxy=False
SecurityUpdateScreen.ProxyType=""
SecurityUpdateScreen.ProxyAddress=""
SecurityUpdateScreen.ProxyPort=""
SecurityUpdateScreen.ProxyAuthentication="False"
SecurityUpdateScreen.ProxyUsername=""
SecurityUpdateScreen.ProxyPassword=""
SoftwareUpdateScreen.UpdateSoftware=True
SoftwareUpdateScreen.Proxy=False
SoftwareUpdateScreen.ProxyType=""
SoftwareUpdateScreen.ProxyAddress=""
SoftwareUpdateScreen.ProxyPort=""
SoftwareUpdateScreen.ProxyAuthentication="False"
SoftwareUpdateScreen.ProxyUsername=""
SoftwareUpdateScreen.ProxyPassword=""
SoftwareUpdateScreen.ProxyAuthentication="False"
RelayScreen.Install=True
SmartProtectionNetworkScreen.EnableFeedback=False
```

Deep Security Manager settings properties file

The settings properties file can be used in a command-line installation (silent Install) of the Deep Security Manager. (See [Silent Install of Deep Security Manager](#).)

Trend Micro Deep Security On-Premise 11.3

The format of each entry in the settings property file is:

```
<Screen Name>.<Property Name>=<Property Value>
```

The settings properties file has required and optional values.

Note: If you enter an invalid value for optional properties, the installer will use the default value instead.

Required Settings

LicenseScreen

Property	Possible Values	Default Value
LicenseScreen.License.-1	<activation code for all modules>	<none>

OR

Property	Possible Values	Default Value
LicenseScreen.License.0	<activation code for Anti-Malware>	<none>
LicenseScreen.License.1	<activation code for Firewall/DPI>	<none>
LicenseScreen.License.2	<activation code for Integrity Monitoring>	<none>
LicenseScreen.License.3	<activation code for Log Inspection>	<none>

CredentialsScreen

Property	Possible Values	Default Value
CredentialsScreen.Administrator.Username	<username for the master administrator>	<none>
CredentialsScreen.Administrator.Password	<password for the master administrator>	<none>

Optional Settings

LanguageScreen

Property	Possible Values	Default Value	Notes
sys.languageId	en_US	en_US	<ul style="list-style-type: none">"en_US" indicates

Trend Micro Deep Security On-Premise 11.3

Property	Possible Values	Default Value	Notes
	ja		English. <ul style="list-style-type: none">"ja" indicates Japanese.

UpgradeVerificationScreen

Note: This setting is not referenced unless an existing installation is detected.

Property	Possible Values	Default Value
UpgradeVerificationScreen.Overwrite	<ul style="list-style-type: none">TrueFalse	False

Warning: If you set this value to True, it will overwrite any existing data in the database. It will do this without any further prompts.

OldDataMigrationScreen

This screen defines the number of days of data to keep. When this setting is 0, all historical data will be kept, but this may increase the amount of time the upgrade will take. During the data migration, the silent install will show the percentage of records migrated at 10% intervals.

Note: This setting is not referenced unless an existing installation is detected and it requires a data migration to upgrade the database schema.

Property	Possible Values	Default Value
OldDataMigrationScreen.HistoricalDays	<integer>	0

DatabaseScreen

This screen defines the database type and optionally the parameters needed to access certain database types.

Note: In the interactive install, you can click **Advanced** to define the instance name and domain of a Microsoft SQL server. This appears in a dialog. Because the unattended install does not support dialogs, these arguments are included in the DatabaseScreen settings below.

Property	Possible Values	Default Value	Notes
DatabaseScreen.DatabaseType	<ul style="list-style-type: none">Microsoft SQL ServerOraclePostgreSQL	Microsoft SQL Server	None
DatabaseScreen.Hostname	<ul style="list-style-type: none"><database hostname or IP address>Current host name	Current host name	None
DatabaseScreen.DatabaseName	<string>	dsm	
DatabaseScreen.Transport	<ul style="list-style-type: none">Named PipesTCP	Named Pipes	Required for SQL Server only
DatabaseScreen.Username	<database username>	<none>	Username used by the manager to authenticate to the database server. Must match an existing database account. Note that the Deep Security Manager database permissions will correspond to this user's permissions. For example, if you choose a database account with read-only privileges, the Deep Security Manager will not be able to write to the database. Mandatory for Microsoft SQL Server and Oracle.
DatabaseScreen.Password	<database password>	<none>	Password used by the manager to authenticate to the database server. Mandatory for Microsoft SQL Server and Oracle.
DatabaseScreen.SQLServer.Instance	<string>	<none>	Used only with Microsoft SQL Server, which supports multiple instances on a single server or processor. Only one instance

Trend Micro Deep Security On-Premise 11.3

Property	Possible Values	Default Value	Notes
			can be the default instance and any others are named instances. If the Deep Security Manager database instance is not the default, enter the name of the instance here. The value must match an existing instance or be left blank to indicate the default instance.
DatabaseScreen.SQLServer.Domain	<string>	<none>	Used only with Microsoft SQL Server. This is the Windows domain used when authenticating to the SQL Server. The DatabaseScreen.Username and DatabaseScreen.Password described above are only valid within the appropriate domain.
DatabaseScreen.SQLServer.UseDefaultCollation	<ul style="list-style-type: none">TrueFalse	False	Used only with Microsoft SQL Server. Collation determines how strings are sorted and compared. If the value is "False", Deep Security will use Latin1_General_CS_AS for collation on text-type columns. If the value is "True", Deep Security will use the collation method specified by your SQL Server database. For additional information on collation, refer to your SQL Server documentation.

AddressAndPortsScreen

This screen defines the hostname, URL, or IP address of this computer and defines port numbers for the manager. In the interactive installer, this screen also supports connecting a new manager node to an existing database, but this option is not supported in the unattended install.

Property	Possible Values	Default Value	Notes
AddressAndPortsScreen.ManagerAddress	<manager hostname, URL or IP address>	<current host name>	None
AddressAndPortsScreen.ManagerPort	<port number>	4119	See "Port numbers, URLs, and IP addresses" on page 111 .
AddressAndPortsScreen.HeartbeatPort	<port number>	4120	See "Port numbers, URLs, and IP addresses" on page 111 .
AddressAndPortsScreen.NewNode	<ul style="list-style-type: none">TrueFalse	False	<code>True</code> indicates that the current install is a new node. If the installer finds existing data in the database, it will add this installation as a new node. (Multi-node setup is always a silent install.) Note: The "New Node" installation information about the existing database to be provided via the DatabaseScreen properties.

CredentialsScreen

Property	Possible Values	Default Value	Notes
CredentialsScreen.UseStrongPasswords	<ul style="list-style-type: none">TrueFalse	False	<code>True</code> causes Deep Security Manager to enforce strong passwords.

MasterKeyConfigurationScreen

Property	Possible Values	Default Value	Notes
MasterKeyConfigurationScreen.KeyConfigType	<ul style="list-style-type: none">Do not configureLocal KeyKMS	Do not configure	If configured, the installer will use KMS or the local key secret to generate a custom master key. If not configured, a hard-coded seed is used instead. See also masterkey . Instead, you must run masterkey commands after the installer.
MasterKeyConfigurationScreen.ARN	<AWS ARN>	<none>	The Amazon Resource Name (ARN) of the KMS key. Only used if <code>MasterKeyConfigurationScreen.KeyConfigType</code> is KMS.
MasterKeyConfigurationScreen.LocalKey	<string>	<none>	The value that you want to use when the installer configures the local environment variable <code>LOCAL_KEY_SECRET</code> . Only used if <code>MasterKeyConfigurationScreen.KeyConfigType</code> is Local Key.

SecurityUpdateScreen

Property	Possible Values	Default Value	Notes
SecurityUpdateScreen.UpdateComponents	<ul style="list-style-type: none">TrueFalse	True	<code>True</code> will tell the Deep Security Manager to create a scheduled task to automatically check for security updates. The scheduled task will run when installation is complete.
SecurityUpdateScreen.Proxy	<ul style="list-style-type: none">TrueFalse	False	<code>True</code> will cause Deep Security Manager to use a proxy to connect to the Internet to download security updates from Trend Micro.
SecurityUpdateScreen.ProxyType	<ul style="list-style-type: none">HTTPSOCKS4SOCKS5	<none>	The protocol used by the proxy.
SecurityUpdateScreen.ProxyAddress	<valid IPv4 or IPv6 address or hostname>	<none>	None

Trend Micro Deep Security On-Premise 11.3

Property	Possible Values	Default Value	Notes
SecurityUpdateScreen.ProxyPort	<proxy port>	<none>	See "Port numbers, URLs, and IP addresses" on page 111 .
SecurityUpdateScreen.ProxyAuthentication	<ul style="list-style-type: none">• True• False	False	<code>True</code> indicates that the proxy requires authentication credentials.
SecurityUpdateScreen.ProxyUsername	<string>	<none>	None
SecurityUpdateScreen.ProxyPassword	<string>	<none>	None

SoftwareUpdateScreen

Property	Possible Values	Default Value	Notes
SoftwareUpdateScreen.UpdateSoftware	<ul style="list-style-type: none">• True• False	True	<code>True</code> will tell Deep Security Manager to create a scheduled task to automatically check for software updates. The scheduled task will run when installation is complete.
SoftwareUpdateScreen.Proxy	<ul style="list-style-type: none">• True• False	False	<code>True</code> will cause Deep Security Manager to use a proxy to connect to the Internet to download software updates from Trend Micro.
SoftwareUpdateScreen.ProxyType	<ul style="list-style-type: none">• HTTP• SOCKS4• SOCKS5	<none>	The protocol used by the proxy.
SoftwareUpdateScreen.ProxyAddress	<valid IPv4 or IPv6 address or hostname>	<none>	None.
SoftwareUpdateScreen.ProxyPort	<integer>	<none>	See "Port numbers, URLs, and IP addresses" on page 111 .
SoftwareUpdateScreen.ProxyAuthentication	<ul style="list-style-type: none">• True• False	False	<code>True</code> indicates that the proxy requires authentication credentials.
SoftwareUpdateScreen.ProxyUsername	<string>	<none>	None
SoftwareUpdateScreen.ProxyPassword	<string>	<none>	None

Trend Micro Deep Security On-Premise 11.3

SmartProtectionNetworkScreen

This screen defines whether you want to enable Trend Micro Smart Feedback and optionally your industry.

Property	Possible Values	Default Value	Notes
SmartProtectionNetworkScreen.EnableFeedback	<ul style="list-style-type: none">TrueFalse	False	True enables Trend Micro Smart Feedback.
SmartProtectionNetworkScreen.IndustryType	<ul style="list-style-type: none">Not specifiedBankingCommunications and mediaEducationEnergyFast-moving consumer goods (FMCG)FinancialFood and beverageGovernmentHealthcareInsuranceManufacturingMaterialsMedia	<none>	If a value is not entered, it has the same result as Not specified.

Trend Micro Deep Security On-Premise 11.3

Property	Possible Values	Default Value	Notes
	<ul style="list-style-type: none">Oil and gasReal estateRetailTechnologyTelecommunicationsTransportationUtilitiesOther		

Sample properties files

The following is example content of a typical properties file.

```
AddressAndPortsScreen.ManagerAddress=10.xxx.xxx.xxx AddressAndPortsScreen.NewNode=True
UpgradeVerificationScreen.Overwrite=False
LicenseScreen.License.-1=XY-ABCD-ABCDE-ABCDE-ABCDE-ABCDE-ABCDE
OldDataMigrationScreen.HistoricalDays=30
DatabaseScreen.DatabaseType=Microsoft SQL Server
DatabaseScreen.Hostname=10.xxx.xxx.xxx
DatabaseScreen.Transport=TCP
DatabaseScreen.DatabaseName=XE
DatabaseScreen.Username=DSM
DatabaseScreen.Password=xxxxxxx
AddressAndPortsScreen.ManagerPort=4119 AddressAndPortsScreen.HeartbeatPort=4120 CredentialsScreen.Administrator.Username=masteradmin
CredentialsScreen.Administrator.Password=xxxxxxx CredentialsScreen.UseStrongPasswords=False SecurityUpdateScreen.UpdateComponents=True
SecurityUpdateScreen.Proxy=False
SecurityUpdateScreen.ProxyType=""
```

Trend Micro Deep Security On-Premise 11.3

```
SecurityUpdateScreen.ProxyAddress=""
SecurityUpdateScreen.ProxyPort="" SecurityUpdateScreen.ProxyAuthentication="False" SecurityUpdateScreen.ProxyUsername=""
SecurityUpdateScreen.ProxyPassword=""
SoftwareUpdateScreen.UpdateSoftware=True
SoftwareUpdateScreen.Proxy=False
SoftwareUpdateScreen.ProxyType=""
SoftwareUpdateScreen.ProxyAddress=""
SoftwareUpdateScreen.ProxyPort=""
SoftwareUpdateScreen.ProxyAuthentication="False"
SoftwareUpdateScreen.ProxyUsername=""
SoftwareUpdateScreen.ProxyPassword=""
RelayScreen.Install=True
SmartProtectionNetworkScreen.EnableFeedback=False
```

Installation Output

The following is a sample output from a successful install, followed by an example output from a failed install (invalid license). The [Error] tag in the trace indicates a failure.

Trend Micro Deep Security On-Premise 11.3

Successful install

```
Stopping Trend Micro Deep Security Manager Service...
Checking for previous versions of Trend Micro Deep Security Manager...
Upgrade Verification Screen settings accepted...
The installation directory has been set to C:\Program Files\Trend Micro\Deep Security Manager.
Database Screen settings accepted...
License Screen settings accepted...
Address And Ports Screen settings accepted...
Credentials Screen settings accepted...
Security Update Screen settings accepted...
Software Update Screen settings accepted...
Smart Protection Network Screen settings accepted...
All settings accepted, ready to execute...
Extracting files ...
Setting Up...
Connecting to the Database...
Creating the Database Schema...
Creating MasterAdmin Account...
Recording Settings...
Creating Temporary Directory...
Installing Reports...
Installing Modules and Plug-ins...
Creating Help System...
Validating and Applying Activation Codes...
Configure Localizable Settings...
Setting Default Password Policy...
Creating Scheduled Tasks...
Creating Asset Importance Entries...
Creating Auditor Role...
Optimizing...
```

Trend Micro Deep Security On-Premise 11.3

```
Importing Software Packages...
Configuring Relay For Install...
Importing Performance Profiles...
Recording Installation...
Clearing Sessions...
Creating Properties File...
Creating Shortcut...
Configuring SSL...
Configuring Service...
Configuring Java Security...
Configuring Java Logging...
Cleaning Up...
Starting Deep Security Manager...
Finishing installation ...
```

Failed install

This example shows the output generated when the properties file contains an invalid license string:

```
Stopping Trend Micro Deep Security Manager Service...
Detecting previous versions of Trend Micro Deep Security Manager...
Upgrade Verification Screen settings accepted...
Database Screen settings accepted...
Database Options Screen settings accepted...
[ERROR] The license code you have entered is invalid.
[ERROR] License Screen settings rejected...
Rolling back changes...
```

Run Deep Security Manager on multiple nodes

Instead of running Deep Security Manager on *one* server, you can install Deep Security Manager on *multiple* servers ("nodes") and connect them to one shared database. This provides better:

- Reliability
- Availability
- Scalability
- Performance

You can log in to any node. Each node can do all types of tasks. No node is more important than any of the others. A node failure does not cause service downtime, and does not result in data loss. Deep Security Manager processes many concurrent activities in a distributed pool that all online nodes execute. All activity that does not happen due to user input is packaged as a job, and runs on any available manager (with some exceptions for "local" jobs that are executed on each node, like cache clearing).

Each node must run the same Deep Security Manager software version. When you upgrade, the first manager you upgrade will temporarily take over all duties and shut down the other nodes. On **Administration > System Information**, in the **Network Map with Activity Graph** of the **System Activity** area, other nodes' status will be "Offline" with an indication that an upgrade is required. Once upgraded, nodes will automatically return online and begin processing again.

Add a node

After you have installed Deep Security Manager on one server node, run the installer again on another server. When prompted, connect it to the same database as the first node.

Warning: Never run more than one instance of the installer at the same time. Doing so can lead to unpredictable results including corruption of the database.

Note: Set the system clock of each manager node to use the same time zone. The database must also use the same time zone. If the time zone is different, this causes Manager Time Out of Sync errors.

Remove a node

Before you remove or replace a server, you should remove it from the pool of Deep Security Manager nodes.

1. Halt the service or uninstall Deep Security Manager on the node that you want to remove.

Its status must change to "Offline".

2. Log into Deep Security Manager on another node.
3. Go to **Administration > Manager Nodes**.

4. Double-click the node that you want to remove.

The node's Properties window should appear.

5. In the **Options** area, click **Decommission**.

Viewing node statuses


To display all Deep Security Manager nodes along with their status, combined activity, and jobs being processed, go to **Administration > System Information**. From the drop-down menu, select which graph you want to view.

Network Map with Activity Graph

The **Network Map with Activity Graph** in the **System Activity** area displays a map of all installed manager nodes and their current status as well their relative activity over the last hour. The nodes can be in the following states:

Trend Micro Deep Security On-Premise 11.3

- Online
- Offline
- Offline (Upgrade Required)




Note: All Deep Security Manager nodes periodically check the health of all other nodes. If any manager node loses network connectivity for more than 3 minutes, it is considered offline. The remaining nodes assume its tasks.

Jobs by Node

This chart displays the number of jobs carried out over the last hour by each node.


Trend Micro Deep Security On-Premise 11.3



Jobs by Type

This chart displays the jobs carried out over the last hour by type.

Trend Micro Deep Security On-Premise 11.3




Total jobs by node and type

This chart displays the number of job types for each node over the last hour.

Trend Micro Deep Security On-Premise 11.3

System Activity (Over The Last Hour)



Configure Deep Security Manager memory usage

Configuring the installer's maximum memory usage

The installer is configured to use 1GB of contiguous memory by default. If the installer fails to run you can try configuring the installer to use less memory.

1. Go to the directory where the installer is located.
2. Create a new text file called "Manager-Windows-xx.x.xxxx.x64.vmoptions" or "Manager-Linux-xx.x.xxxx.x64.vmoptions", depending on your installation platform (where "xx.x.xxxx" is the build number of the installer).
3. Edit the file by adding the line: "-Xmx800m" (in this example, 800MB of memory will be made available to the installer.)
4. Save the file and launch the installer.

Configuring Deep Security Manager's maximum memory usage

The Deep Security Manager default setting for memory allocated to the Manager JVM process is 4GB. It is possible to change this setting.

1. Go to the Deep Security Manager install directory (the same directory as Deep Security Manager executable).
2. Create a new file. Depending on the platform, give it the following name:
 - **Windows:** "Deep Security Manager.vmoptions".
 - **Linux:** "dsm_s.vmoptions".
3. Edit the file by adding the line: " `-Xmx10g` " (in this example, "10g" will make 10GB memory available to the Deep Security Manager.)
4. Save the file and restart the Deep Security Manager.
5. You can verify the new setting by going to **Administration > System Information** and in the System Details area, expand **Manager Node > Memory**. The Maximum Memory value should now indicate the new configuration setting.

Deep Security Manager performance features

Performance profiles

Deep Security Manager uses an optimized concurrent job scheduler that considers the impacts of each job on CPU, database and agents or appliances. By default, new installations use the "Aggressive" performance profile which is optimized for a dedicated manager. If the Deep Security Manager is installed on a system with other resource-intensive software it may be preferable to use the "Standard" performance profile. The performance profile can be changed by navigating to **Administration > Manager Nodes**. From this screen select a manager node and open the **Properties** window. From here the performance profile can be changed via the menu.

The performance profile also controls the number of agent- or appliance-initiated connections that the manager will accept. The default of each of the performance profiles effectively balances the amount of accepted, delayed and rejected heartbeats.

Low disk space alerts

Low disk space on the database

If the Deep Security Manager receives a "disk full" error message from the database, it will start to write events to its own hard drive and will send an email message to all users informing them of the situation. This behavior is not configurable.

If you are running multiple manager nodes, the events will be written to the disk of whichever node is handling the event. (For more information on running multiple nodes, see ["Run Deep Security Manager on multiple nodes" on page 191.](#))

Once the disk space issue on the database has been resolved, the manager will write the locally stored data to the database.

Low disk space on the manager

If the available disk space on the computer where Deep Security Manager is installed falls below 10%, the manager generates a "Low Disk Space" alert. This alert is part of the normal alert system and is configurable like any other. (For more information, see ["Configure alerts" on page 1066.](#))

If you are running multiple manager nodes, the node will be identified in the alert.

When the manager's available disk space falls below 5 MB, the manager will send an email message to all users and the manager will shut down. The manager cannot be restarted until the available disk space is greater than 5 MB.

You must restart the manager manually.

If you are running multiple nodes, only the node that has run out of disk space will shut down. The other manager nodes will continue operating.


Update the load balancer's certificate

Usually, your browser should warn you with a certificate validation error whenever you try to connect to a server with a self-signed certificate. This is because with any *self*-signed certificate, the browser cannot automatically validate the certificate's signature with a trusted *third party* certificate authority (CA), and therefore the browser doesn't

Trend Micro Deep Security On-Premise 11.3

know if the certificate was sent by an attacker or not. When installed, Deep Security Manager is initially configured to use a self-signed certificate for HTTPS connections (SSL or TLS), so you must manually verify that the server certificate fingerprint used to secure the connection belongs to your Deep Security server. This is normal until you replace the self-signed certificate with a CA-signed certificate.

The same error will occur if you have an AWS Elastic Load Balancer (ELB) or other load balancer, and it presents a self-signed certificate to the browser.



Your connection is not private

Attackers might be trying to steal your information from **deepsecurity.example.com** (for example, passwords, messages, or credit cards). NET::ERR_CERT_AUTHORITY_INVALID

☐ [Automatically report](#) details of possible security incidents to Google. [Privacy policy](#)

HIDE ADVANCED

Back to safety

This server could not prove that it is **deepsecurity.example.com** ; its security certificate is not trusted by your computer's operating system. This may be caused by a misconfiguration or an attacker intercepting your connection. [Learn more.](#)

Proceed to deepsecurity.example.com (unsafe)

Trend Micro Deep Security On-Premise 11.3

You can still access Deep Security Manager if you ignore the warning and proceed (method varies by browser). However, this error will occur again each time you connect, unless you either:

- add the certificate to your computer's store of trusted certificates (not recommended) or
 - replace the load balancer's certificate with one signed by a trusted CA (strongly recommended)
1. With a CA that is trusted by all HTTPS clients, register the fully qualified domain name (*not IP address*) that administrators, relays, and agents will use to connect to Deep Security Manager.

Specify the sub-domain (for example, deepsecurity.example.com) that will uniquely identify Deep Security Manager. For nodes behind an SSL terminator load balancer, this certificate will be presented to browsers and other HTTPS clients by the load balancer, not by each Deep Security Manager node.

When the CA signs the certificate, download both the certificate (with public key) and the private key.

Warning: Store and transmit the private key securely. If file permissions or unencrypted connections allow a third party to access your private key, then all connections secured by that certificate and key are compromised. You must revoke that certificate, remove the key, and get a new certificate and key.

2. [Add the certificate to your certificate store](#) (optional if your computer trusts the CA that signed the certificate).
3. [Update the DNS settings of the load balancer to use the new domain name](#).
4. [Replace the SSL certificate of the load balancer](#).

Set up a multi-tenant environment

The multi-tenancy feature in Deep Security lets you create separate management environments within a single Deep Security Manager. It allows tenants to each have their own settings and policies and to monitor their own events. This can be useful if you want to create separate staging and production environments or if you need to create separate environments for different business units in your organization. You can also use multi-tenancy to provision Deep Security to customers in a service model.

Trend Micro Deep Security On-Premise 11.3

Once you enable multi-tenancy, you (as the "primary tenant") retain all of the capabilities of a regular installation of Deep Security Manager. However, the tenants you subsequently create can have their access to Deep Security functionality restricted to varying degrees, based on how you configure the system for them.

Note: FIPS mode is not supported in a multi-tenant environment, See ["FIPS 140-2 support" on page 1381](#).

In this topic:

- ["Multi-tenancy requirements" on the next page](#)
- ["Enable multi-tenancy" on the next page](#)
- ["Create a tenant" on page 204](#)
- ["Scalability guidelines" on page 206](#)
- ["Multi-tenancy tips" on page 207](#)
- ["Managing tenants" on page 208](#)
- ["Set up a multi-tenant environment" on the previous page](#)
- ["Usage monitoring" on page 212](#)
- ["Configure database user accounts" on page 215](#)
- ["APIs" on page 228](#)
- ["Upgrade" on page 228](#)
- ["Supporting tenants" on page 229](#)
- ["Load balancers" on page 230](#)
- ["Multi-tenancy with Deep Security Virtual Appliance" on page 232](#)

Multi-tenancy requirements

You cannot set up multi-tenancy with:

- Any other license options for Deep Security from AWS Marketplace
- Deep Security Manager VM for Azure Marketplace
- Deep Security as a Service

Multi-tenancy requires an activation code. Multi-tenancy also has additional database requirements. For details, see ["Prepare a database for Deep Security Manager" on page 122](#) and ["Configure database user accounts" on page 215](#).

To maximize scalability, we recommend that you use a multi-node Deep Security Manager (see ["Run Deep Security Manager on multiple nodes" on page 191](#)). All manager nodes process GUI, heartbeat, or job requests for any tenant. For background processing, each tenant is assigned a manager node that takes care of job queuing, maintenance, and other background tasks. Tasks are rebalanced across remaining nodes when manager nodes are added or taken offline.

When you enable multi-tenancy, your current installation of Deep Security Manager becomes the primary tenant (t0) and has special privileges, including the ability to create other tenants. Other tenants are restricted from using certain features and don't have permissions to see the UI for those features in Deep Security Manager. For example, non-primary tenants cannot create other tenants. For details, see ["Set up a multi-tenant environment" on page 201](#)

Enable multi-tenancy

Note: Once you enable multi-tenancy, you cannot disable it or remove the primary tenant.

1. In the Deep Security Manager, go to **Administration > System Settings > Advanced**. In the Multi-Tenant Options area, click **Enable Multi-Tenancy**.
2. The Multi-Tenant Configuration wizard appears. Enter your multi-tenancy activation code and click **Next**.
3. Choose the license mode that you want to use:

- **Inherit Licensing from Primary Tenant:** This option gives all tenants the same licenses that you (the primary tenant) have. This option is recommended if you are using multi-tenancy in a staging environment, or if you intend to set up tenancies for separate departments within your organization.
- **Per Tenant Licensing:** This option is recommended if you are offering Deep Security as a service. With this configuration, you can use the Deep Security API to provide a license when you create a tenant, or the tenant can enter a license when they sign in to the Deep Security Manager for the first time.

4. Click **Next**.

When the wizard closes, you'll be able to see **Administration > System Settings > Tenants**, where you can configure multi-tenancy options. For information about the options on that page, click **Help** in the upper-right corner of Deep Security Manager.

Create a tenant

Tip: You can automate tenant creation and configuration using the Deep Security API. For examples, see the [Create and Manage Tenants](#) guide in the Deep Security Automation Center.

Once multi-tenant mode is enabled, tenants can be managed from **Administration > Tenants**.

For information about the database user account permissions that are required for adding tenants, see "[Configure database user accounts](#)" on page 215.

1. In the Deep Security Manager, go to **Administration > Tenants** and click **New**.
2. The New Tenant wizard appears. Enter a **Tenant Account Name**. The account name can be anything except "Primary", which is reserved for the primary tenant.
3. Enter the email address that is used to contact the tenant.
4. Select the **Locale**. The locale determines the language of the Deep Security Manager user interface for the tenant.
5. Select a **Time Zone**. Times for events are shown relative to this time zone, not the time zone on the system where the event happened.
6. If your Deep Security installation uses more than one database, select whether to let Deep Security automatically select a database server on which to store the new tenant account ("Automatic -- No Preference") or to use a particular server.

Trend Micro Deep Security On-Premise 11.3

Database servers that are not accepting new tenants do not appear in the list.

- 7. Enter a user name for the first user of the new tenant account.
- 8. Select one of the three password options:
 - **No Email:** The tenant’s first user’s user name and password are defined here and no emails are sent.
 - **Email Confirmation Link:** You set the tenant’s first user’s password. However, the account is not active until the user clicks a link in the confirmation email.
 - **Email Generated Password:** This allows you to generate a tenant without specifying the password.

Tip:
All three options are available via the REST API. The confirmation option provides a suitable method for developing public registration. A CAPTCHA is recommended to ensure that the tenant creator is a human not an automated bot.

The email confirmation ensures that the email provided belongs to the user before they can access the account.

- 9. Click **Next** to finish with the wizard and create the tenant.

Tenant creation can take up to four minutes due to the creation of the schema and the population of the initial data. This ensures each new tenant has the most up-to-date configuration and removes the burden of managing database templates, especially between multiple database servers.

Each tenant database has an overhead of around 100 MB of disk space (due to the initial rules, policies and events that populate the system).

Examples of messages sent to tenants

Email Confirmation Link: Account Confirmation Request

Welcome to Deep Security! To begin using your account, click the following confirmation URL. You can then access the console using your chosen password.

Account Name: ExampleCorp

User name: admin

Trend Micro Deep Security On-Premise 11.3

```
Click the following URL to activate your account:  
  
https://managerIP:portnumber/SignIn.screen?confirmation=1A16EC7A-D84F-D451-05F6-706095B6F646&tenantAccount=ExampleCorp&username=admin
```

Email Generated Password

First email : Account and Username Notification

```
Welcome to Deep Security! A new account has been created for you. Your password will be generated and provided in a separate email.  
  
Account Name: ExampleCorp  
  
Username: admin  
  
You can access Deep Security using the following URL:  
  
https://managerIP:portnumber/SignIn.screen?tenantAccount=ExampleCorp&username=admin
```

Second email: Password Notification

```
This is the automatically generated password for your Deep Security account. Your Account Name, Username, and a link to access Deep Security will follow in a separate email.  
  
Password: z3IgRUQ0jaFi
```

Scalability guidelines

Deployments of 50-100 tenants or more should follow these guidelines to avoid scalability issues:

- Create a maximum of 2000 tenants for a set of Deep Security Manager nodes
- Create a maximum of 300 tenants on a single database server
- Use a separate database server for the primary tenant, with no other tenants

Trend Micro Deep Security On-Premise 11.3

- Limit the number of agents per tenant to 3000
- Limit the number of total agents to 20000
- Use a maximum of 2 Deep Security Manager nodes
- Do not use any co-located relays

Multi-tenancy relies on using multiple databases (if you are using Microsoft SQL) or multiple users (if you are using Oracle). To scale further, you can connect Deep Security Manager to multiple database servers and automatically distribute the new tenants across the available set of database servers. See ["Configure database user accounts" on page 215](#).

Multi-tenancy tips

Reconnaissance IP list

In a multi-tenant environment, tenants may need to add the Deep Security Manager IP address to the "Ignore Reconnaissance IP" list found in **Policies > Common Objects > Lists > IP Lists**. This is to avoid getting a "Reconnaissance Detected: Network or Port Scan" warning.

Use multiple database servers

Multi-tenancy relies on using multiple databases (if you are using Microsoft SQL) or multiple users (if you are using Oracle). To scale further, you can connect Deep Security Manager to multiple database servers and automatically distribute the new tenants across the available set of database servers. See ["Configure database user accounts" on page 215](#).

Tenant pending deletion state

Tenants can be deleted, but the process is not immediate. Before it deletes records, Deep Security requires that all its tenant-related jobs are finished. The least frequent job runs every week, so tenants may remain in the "pending deletion" state for up to approximately 7 days.

Multi-tenant options under System Settings

Consider these options on **Administration > System Settings > Tenants**:

Allow Tenants to use the Relays in my "Default Relay Group" (for unassigned Relays): Gives tenants automatic access to relay-enabled agents set up in the primary tenant. This saves tenants the effort of setting up dedicated relay-enabled agents for security updates.

Allow Tenants to use the "Run Script" Scheduled task: Scripts present a potentially dangerous level of access to the system; however, the risk can be mitigated because scripts have to be installed on the Deep Security Manager using file-system access.

Managing tenants

Administration > Tenants displays the list of all tenants. A tenant can be in any of these **States**:

- **Created:** Created, but activation email has not been sent to the tenant user.
- **Confirmation Required:** Created, but the activation link in the confirmation email sent to the tenant user has not been clicked. (You can manually override this state.)
- **Active:** Fully online and managed.
- **Suspended:** No longer accepting sign-ins.
- **Pending Deletion:** Tenants can be deleted, but it is not immediate. The tenant may be in the "pending deletion" state for up to 7 days, until pending jobs finish.
- **Database Upgrade Failed:** For tenants that failed the upgrade path. The Database Upgrade button can be used to resolve this situation.

Tenant Properties

Double-click on a tenant to view the tenant's **Properties** window.

General

You can change the locale, time zone and state. Changes do not affect existing tenant users (only new ones, and parts of the UI that are not user-specific).

Trend Micro Deep Security On-Premise 11.3

The **Database Name** indicates the name of the database used by this tenancy. You can access the tenant database's properties via the hyperlink.

Modules

The **Modules** tab provides options for protection module visibility. The selected visibility can be used to tune which modules are visible for which tenants. By default all unlicensed modules are hidden. You can change this by deselecting **Always Hide Unlicensed Modules**. Alternatively, selected modules can be shown on a per-tenant basis.

By default, if you use "per tenant" licensing, each tenant only sees their licensed modules.

If you select **Inherit License from Primary Tenant**, then all tenants can see all features that you (the primary tenant) are licensed for.

Note: If you select this option, then all of the primary tenant's unlicensed modules are hidden for other tenants, *even if you deselect their option **Always Hide Unlicensed Modules***.

If you are evaluating Deep Security in a test environment and want to see what a full multi-tenancy installation looks like, you can enable "Multi-Tenancy Demo Mode". When in Demo Mode, the manager populates its database with simulated tenants, computers, events, alerts, and other data. Initially, 7 days' worth of data is generated but new data is generated on an ongoing basis to keep the manager's dashboard, reports and events pages populated with data.

Warning: Do **not** use Demo Mode in a production environment. Demonstration data will be mixed with real data, which can make it difficult to determine if there are real attacks or malware.

Features

As an Administrator, you can enable or disable certain features for specific tenants. These available features may change over time.

If you enable **Extended Descriptions for Event Forwarding**, Deep Security includes the full description of events that are forwarded to Amazon SNS or a SIEM. Otherwise, descriptions are omitted. **SAML Identity Provider Integration**, **Amazon WorkSpaces Integration**, and **Application** (Application Control) are enabled by default.

Statistics

The Statistics tab shows information for the current tenant including database size, jobs processed, logins, security events and system events. The spark line show the last 24 hours at a glance.

Agent Activation

The Agent Activation tab displays a command that you can run to activate the agent on the computer. The command is relative to the agent install directory of this tenant's computers. Activation is required so that Deep Security Manager can securely connect with it, and the tenant can assign policies and perform other configuration procedures from the Deep Security Manager.

What does the tenant see?

When multi-tenancy is enabled, the sign-in page has an additional **Account Name** text field.

Tenants are required to enter their account name in addition to their user name and password. The account name allows tenants to have overlapping user names. For example, if multiple tenants synchronize with the same Active Directory server.

Note: When you (as the primary tenant) log in, leave the account name blank or use "Primary".

Some features in the Deep Security Manager UI are not available to tenant users. These areas are hidden for tenants:

- Manager Nodes Widget
- Multi-Tenant Widgets
- Administration > System Information
- Administration > Licenses (If Inherit option selected)
- Administration > Manager Nodes

Trend Micro Deep Security On-Premise 11.3

- Administration > Tenants
- Administration > System Settings:
 - Tenant Tab
 - Security Tab > Sign In Message
 - Updates Tab > Setting for Allowing Tenants to use Relays from the Primary Tenant
 - Advanced Tab > Load Balancers
 - Advanced Tab > Pluggable Section
- Some of the help content not applicable to tenants
- Some reports not applicable to tenants
- Other features based on the multi-tenant options
- Some alert types are also be hidden from tenants:
 - Heartbeat Server Failed
 - Low Disk Space
 - Manager Offline
 - Manager Time Out Of Sync
 - Newer Version of Deep Security Manager available
 - Number of Computers Exceeds Database Limit
 - And when inherited licensing is enabled any of the license-related alerts

Trend Micro Deep Security On-Premise 11.3

It is also important to note that tenants cannot see any of the multi-tenant features of the primary tenant or any data from any other tenant. In addition, certain APIs are restricted since they are only usable with primary tenant rights (such as creating other tenants).

For more information on what is and is not available to tenant users, see ["Multi-tenant settings" on page 232](#).

All tenants have the ability to use role-based access control (RBAC) with multiple user accounts to further sub-divide access. Additionally, they can use Active Directory integration for users to delegate the authentication to the domain. The Tenant Account Name is still required for any tenant authentications.

Agent-Initiated Activation

Agent-initiated activation is enabled by default for all tenants.

Note: Unlike agent-initiated activation for the primary tenant, a password and tenant ID are required to invoke the activation for other tenant users.

Tenants can see the arguments required for agent-initiated activation by going to **Administration > Updates > Software > Local**, selecting the agent software, and then clicking **Generate Deployment Scripts**. For example, the script for Agent-Initiated Activation on a Windows machine might look like this:

```
dsa_control -a dsm://<host or IP>:4120/ "tenantID:XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX" "token:XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX"
```

Tenant diagnostics

Tenants are not able to access manager diagnostic packages due to the sensitivity of the data contained within the packages. Tenants can still generate agent diagnostics by opening the computer editor, going to **Actions > Overview**, and then selecting **Agent Diagnostics**.

Usage monitoring

Deep Security Manager records data about tenant usage. To view it, go to the dashboard's **Tenant Protection Activity** widget, the Tenant **Properties** window's **Statistics** tab, and reports. This information can also be accessed through the REST API's status monitoring, which can be enabled or disabled by going to **Administration > System Settings > Advanced > Status Monitoring API**.

Trend Micro Deep Security On-Premise 11.3

Use the REST API's status monitoring to customize the type of tenant information that you would like to see, depending on your environment. For enterprises, this can be useful to determine the usage by each business unit. You can also use the information to monitor the usage of the overall Deep Security system and look for indicators of abnormal activity. For example, if a single tenant experiences a spike in security event activity, it might be under attack.

Multi-tenant Dashboard

When multi-tenancy is enabled, primary tenant users have access to the following additional Dashboard widgets for monitoring tenant activity:

- Tenant Database Usage
- Tenant Job Activity
- Tenant Protection Activity
- Tenant Security Event Activity
- Tenant Sign-In Activity
- Tenant System Event Activity
- Tenants

The same information is available on **Administration > Tenants** (some in optional columns) and on the **Statistics** tab of a tenant's **Properties** window.

This information provides the ability to monitor the usage of the overall system and look for indicators of abnormal activity. For example, if a single tenant experiences a spike in security event activity, they might be under attack.

Multi-tenant reports

To generate reports that contain the information you require, go to **Event & Reports > Generate Reports** and choose the report you'd like to generate from the drop-down menu. The following are reports for multi-tenant environments, and the information they include:

Trend Micro Deep Security On-Premise 11.3

Security Module Usage Cumulative Report

Tenant	Hostname	ID	Anti-Malware hours	Network hours	System hours	SAP hours	Enterprise hours

Security Module Usage Report

Tenant	ID	Hostname	Display name	Computer group	Instance type	Start date	Start time	Stop time	Duration (seconds)

Trend Micro Deep Security On-Premise 11.3

- Anti-malware
- Web Reputation
- Firewall
- Intrusion prevention
- Integrity monitoring
- Log Inspection
- Application Control
- SAP

Tenant Report

- Tenant name
- Database size
- Peak host count
- Protection hours
- Percentage of protected hours

Configure database user accounts

The majority of each tenant's data is stored in a separate database. This database can co-exist on the same database server as other tenants, or it can be isolated onto its own database server. In all cases, some data only exists in the primary database (the one installed with Deep Security Manager). When multiple database servers are available, tenants are created on the database with the least amount of load.

The segmentation of each tenant's data into a database provides additional benefits:

Trend Micro Deep Security On-Premise 11.3

- **Data destruction:** Deleting a tenant removes all traces of that tenant's data (supported in the product).
- **Backup:** Each tenant's data can be subject to different backup policies. This can be useful for something like tenancy being used for staging and production where the staging environment requires less stringent backups (backups are the responsibility of the administrator setting up Deep Security Manager).
- **Balancing:** The potential for future re-balancing to maintain an even load on all database servers.

Configuring database user accounts

Note:

Microsoft SQL Server, Oracle, and PostgreSQL use different terms for database concepts described below.


Concept	SQL Server term	Oracle term	PostgreSQL term
Process where multiple tenants execute	Database Server	Database	Database Server
One tenant's set of data	Database	Tablespace/User	Database

The following section uses the Microsoft SQL Server terms for both SQL Server and Oracle.

See also ["Configure database user accounts" on the previous page](#).


SQL Server

Multi-tenancy requires that Deep Security can create databases when you create new tenants, so its SQL Server database user requires the "dbcreator" role.




Trend Micro Deep Security On-Premise 11.3

For the user role of the primary tenant, assign DB owner to the main database.




Trend Micro Deep Security On-Premise 11.3

You can restrict the rights to include only the ability to modify the schema and access the data.



Trend Micro Deep Security On-Premise 11.3

With the "dbcreator" role, databases that the account creates are automatically owned by the same user. For example, here are the user's properties after the first tenant has been created:



Trend Micro Deep Security On-Premise 11.3

To create the first account on a secondary database server, only the "dbcreator" server role is required. No user mapping is required.

Oracle

Multi-tenancy in Oracle is similar to Microsoft SQL Server, but with a few important differences. Where SQL Server has a single user account per database server, Oracle uses one user account per tenant. The user that Deep Security was installed with maps to the primary tenant. That user can be granted permission to allocate additional users and tablespaces.

Note: Although Oracle allows special characters in database object names if they are surrounded by quotes, *Deep Security does not support special characters in database object names*. This page on Oracle's web site describes the allowed characters in non-quoted names: https://docs.oracle.com/cd/B28359_01/server.111/b28286/sql_elements008.htm#SQLRF00223#SQLRF00223

Tip: Use a short name for the main database name to make it easier to read your tenants' database names. Deep Security derives tenants' database names from the main (primary tenant)'s Oracle database name. For example, if the main database is named "MAINDB", then the first tenant's database is "MAINDB_1", the second tenant's database name is "MAINDB_2", and so on.

If multi-tenancy is enabled, you must assign these Oracle permissions:

Roles

Role	Admin Option	Default
CONNECT	N	Y
RESOURCE	N	Y

System Privileges

System Privilege	Admin Option
ALTER USER	N
CREATE SEQUENCE	N
CREATE TABLE	N
CREATE TRIGGER	N
CREATE USER	N
DROP USER	N
GRANT ANY PRIVILEGE	N
GRANT ANY ROLE	N
UNLIMITED TABLESPACE	N

Object Privileges

Object Privilege	Schema	Object	Grant Option
No items found			

Tenants are created as users with long random passwords and given these permissions:

Roles

Role	Admin Option	Default
CONNECT	N	Y
RESOURCE	N	Y

System Privileges

System Privilege	Admin Option
CREATE SEQUENCE	N
CREATE TABLE	N
CREATE TRIGGER	N
UNLIMITED TABLESPACE	N

Object Privileges

Object Privilege	Schema	Object	Grant Option
No items found			

For secondary Oracle servers, you must create the first user account (a bootstrap user account). This user has a mostly tablespace. The configuration is identical to the primary user account.

PostgreSQL

The user must have permissions to create new databases and roles:

Trend Micro Deep Security On-Premise 11.3

```
ALTER ROLE [username] CREATEDB CREATEROLE;
```

On a secondary database server, the hostname, username, and password are required. The username must have privileges to create additional users (roles) and databases.

Configuring multiple database servers

By default, all tenants are created on the same database server that Deep Security Manager was installed with. In order to provide additional scalability, Deep Security Manager supports adding additional database servers (sometimes referred to as a secondary database). When you add a tenant, you have the option to let Deep Security automatically select a database server on which to store the new tenant account or you can specify a particular server.

To configure more databases, go to **Administration > System Settings > Tenants**. In the Database Servers section, click **View Database Servers**, and then click **New** .

For Microsoft SQL Server, the secondary database server requires a hostname, user name, and password (named instance and domain). The Deep Security Manager's database user must have these permissions:

- Create databases
- Delete databases
- Define schema

This account is used not only to create the database but to authenticate to the databases that are created.

For Oracle, multi-tenant deployments use a different model. The new database definition defines a user that is bound to a tablespace. That user is used to "bootstrap" the creation of additional users on Oracle.

Removing or changing secondary databases

You can delete database servers (other than the primary database) if there are no tenants on the server.

Trend Micro Deep Security On-Premise 11.3

If the hostname, user name, password or any details change for a secondary server, you can change these values in the Deep Security Manager console. To change values for the primary database, you must shut down all nodes of the Deep Security Manager and edit the `dsm.properties` file with the new details.

APIs

Deep Security Manager includes a number of REST APIs for:

1. Enabling Multi-Tenancy
2. Managing Tenants
3. Accessing Monitoring Data
4. Accessing Chargeback (Protection Activity) Data
5. Managing Secondary Database Servers

In addition, the legacy SOAP API includes a new authenticate method that accepts the Tenant Account Name as a third parameter.

For more information on the REST APIs please see ["Use the Deep Security API to automate tasks" on page 417](#).

Upgrade

When you run the Deep Security Manager installer, it should detect any existing installation. You can choose to either make a new installation, or upgrade the existing one. If you upgrade, the installer first tries to shut down other nodes, and then starts to upgrade.

The installer upgrades the primary tenant first, followed by the other tenants in parallel (five at a time). Once the installer finishes, run the same installer on the other manager nodes.

If a problem occurs during the tenant's database upgrade, then on **Administration > Tenants**, the tenant's **State** is **Database Upgrade Failed (offline)**. The tenant's interface can be used to force the upgrade process. If forcing the upgrade does not work, please contact support.

Supporting tenants

Especially if you are an MSSP that is the first tier support provider to your tenants, sometimes a primary tenant might need to log in to another tenant's user interface.

To do this, go to **Administration > Tenants**. Right-click the tenant's name, and then select **Authenticate As**. (The option may not be available if the tenant has disabled access.) This creates a temporary user account with the "Full Access" role inside that tenant, and immediately logs you into that account. Temporary account names are "support_" followed by their username inside the primary tenant.

For example, if your primary tenant username is "jdoe", and you create a temporary account inside tenant "T1", then you would be immediately logged into "T1" as "support_jdoe".

Temporary support accounts are deleted when either they log out or their session times out. Tenants can see system events about the temporary support account's creation, log in, log out, and deletion.

Users in the primary tenant can access more diagnostic tools and information:

1. **Administration > System Information** has more information about tenant memory usage and the state of threads.
2. `server#.log` log files (such as `server0.log`) on each manager node's disks have the name of the tenant, and the user if applicable, associated with each event.

In some cases, you may need to perform an action or change a tenant's setting that is not available in the GUI. This usually comes at the request of Trend Micro support. In the [command line](#), add the argument:

```
-tenantname <tenant-name>
```

to apply setting changes or actions to that tenant. If the argument is omitted, the command applies to the primary tenant.


Load balancers

By default, a multi-node manager gives the address of all nodes to all agents and virtual appliances. The agents and virtual appliances randomly select a node from the list when they try to connect. If they cannot, then they try another node on the list, continuing this process until either a connection succeeds, or no nodes can be reached. If they can't reach any node, then they wait until the next heartbeat to try again.

This works well in environments with a fixed number of manager nodes if you don't want to configure a load balancer for availability and scalability.

In multi-tenant environments, however, you may want to add and remove manager nodes on demand (perhaps using auto-scaling features of cloud environments). Each time one node is added or removed, this causes an updated list to be sent to all agents and virtual appliances. Until then, connections to old nodes may fail, and the new node will be unused. This causes slow communications and increased network traffic. To avoid this, instead [configure agents and virtual appliances to connect via the load balancer's address](#).

Load balancers can be configured to either use different port numbers for each different type of traffic, or (if the load balancer supports port re-direction) expose all of the required protocols over port 443 using three load balancers.



Trend Micro Deep Security On-Premise 11.3

Balance load based upon TCP connections; do not use SSL termination. This ensures that an entire connection occurs with the same manager node. The next connection may be distributed to a different node.

Multi-tenancy with Deep Security Virtual Appliance

If Deep Security is being deployed in a VMware environment, you can configure the vCenter and its connector in the primary tenant and the vCloud connector in tenants. If this is configured properly, the primary tenant sees the ESXi servers, Deep Security Virtual Appliances, and other infrastructure while tenants only see the agentlessly protected VMs that belong to them in the vCloud environment.

To enable this type of environment, go to **Administration > System Settings > Agents** and select **Allow Appliance protection of vCloud VMs**.

For more information on vCloud integration, see ["Install the agent on VMware vCloud" on page 326](#).

Multi-tenant settings

The **Tenants** tab appears only if you have enabled multi-tenant mode.

- **Multi-Tenant License Mode:** The multi-tenant license mode can be changed after multi-tenant is setup, however it is important to note that switching from inherited to per-tenant will cause existing tenants to no longer have any licensed module.
- **Allow Tenants to use the "Run Script" Scheduled Task:** Scripts present a potentially dangerous level of access to the system, however the risk can be mitigated because scripts have to be installed on the Manager using file-system access.
- **Allow Tenants to run "Computer Discovery" (directly and as a Scheduled Task):** Determines if discovery is allowed. This may not be desirable in service provider environments where network discovery has been prohibited.
- **Allow Tenants to run "Port Scan" (directly and as a Scheduled Task):** Determines if port scans can be executed. This may not be desirable in service provider environments where network scan has been prohibited.

- **Allow Tenants to add VMware vCenters:** Determines for each tenant if vCenter connectivity should be allowed. If the deployment occurs via an unsecured or public network such as the Internet, usually this option should be disabled.
- **Allow Tenants to add with Cloud Accounts:** Determines if tenants can setup cloud sync. This is generally applicable to any deployment.
- **Allow Tenants to synchronize with LDAP Directories:** Determines if tenants can setup both User and Computer sync with Directories (LDAP or Active Directory for Computers, Active Directory only for users). If deployment occurs via an unsecured or public network such as the Internet, usually this option should be disabled.
- **Allow Tenants to configure SIEM settings (If not checked, all Tenants use the settings located on the SIEM tab for ALL event types and syslog is relayed via the Manager):** Displays the SIEM settings on the Event Forwarding tab.
- **Allow Tenants to configure SNS settings:** Displays the SNS settings on the Event Forwarding tab.
- **Allow Tenants to configure SNMP settings:** Allow tenants to forward System Events to a remote computer (via SNMP). If this option is not selected, all tenants use the settings located on the Event Forwarding tab for all event types and syslogs are relayed via the Deep Security Manager.
- **Show the "Forgot Password?" option:** Displays a link on the sign in screen which Users can access to reset their password. SMTP settings must be properly configured on the **Administration > System Settings > SMTP** tab for this option to work.
- **Show the "Remember Account Name and Username" option:** Deep Security will remember the User's Account Name and Username and populate these fields when the sign in screen loads.
- **Allow Tenants to control access from the Primary Tenant:** By default, the primary tenant can sign in to a tenant's account by using the **Sign In As Tenant** option on the **Administration > Tenants** page. When the **Allow Tenants to control access from Primary Tenant** option is selected, tenants are given the option (under **Administration > System Settings > Advanced** in their) to allow or prevent access by primary tenant to their Deep Security environment. (When this option is enabled, the default setting in the tenant's environment is to prevent access by the primary tenant.)

Note: Whenever the primary tenant accesses a tenant's account, the access is recorded in the tenant's System Events.

- **Allow Tenants to use Primary Tenant's Trend Micro Control Manager and Deep Discovery Analyzer Server settings:** Enables the primary tenant to share their Connected Threat Defense settings with tenants. For details, see "[Detect emerging threats using Connected Threat Defense](#)" on page 692.

- **Allow Tenants to use the Relays in my "Default Relay Group":** gives tenants automatic access to relays setup in the primary tenant. This saves tenants from having to setup dedicated Relays for Security Updates.

Note: Tenants can reject the usage of "shared" relays by going to the **Updates** tab on the **Administration > System Settings** page and deselecting the **Use the Primary Tenant Relay Group as my Default Relay Group (for unassigned Relays)** option. If tenants deselect this setting they must set up dedicated Relays for themselves.

Note: When relays are shared, it is the responsibility of the primary tenant to keep the relays up to date. This usually involves creating **Download Security Update Scheduled Tasks** for all relays at a regular intervals.

- **Enable the automatic download of Security Updates on new Tenants:** As soon as you create a new tenant account, it will check for and download the latest available security updates.
- **Lock and hide the following options (all Tenants will use the Primary Tenant's configurations):**
 - **Data Privacy options on the "Agents" Tab:** Allows the primary tenant to configure data privacy settings. (This setting only applies to "Allow Packet Data Capture on Encrypted Traffic (SSL)" in on the **Administration > System Settings > Agents** tab.)
 - **All options on the "SMTP" Tab:** Locks all settings on the **SMTP** tab.
 - **All options on the "Storage" Tab:** Locks all settings on the **Storage** tab.

Database servers

By default, all tenants will be created on the same database server that Deep Security Manager was installed with. In order to provide additional scalability, Deep Security Manager supports adding additional database servers. For details, see ["Set up a multi-tenant environment" on page 201](#).

New tenant template

The tenant template feature provides a convenient way of creating a customized "out-of-the-box" experience for new tenants.

Trend Micro Deep Security On-Premise 11.3

The process is as follows:

1. Create a new tenant.
2. Log in as that tenant.
3. Customize the example policies (adding, removing, or modifying) and the security update version (applying newer versions).
4. Return to the primary tenant and run the tenant template wizard.
5. Select the tenant to snapshot.

The following items are INCLUDED in the new template:

- Latest Security Update rules (Updates that have been applied to the template when created. This includes intrusion prevention rules provided by Trend Micro, change monitoring rules, security log monitoring rules)
- Policy Firewall rules
- IP list
- MAC list
- Directory listing
- File list
- File extension list
- Port list
- Contexts
- Schedule
- Firewall Stateful Configuration
- Malware scan settings

The following items are EXCLUDED from the new template:

Trend Micro Deep Security On-Premise 11.3

- Custom Intrusion Prevention rules
- Custom Application Types
- Custom Integrity Monitoring rules
- Custom Log Inspection rules
- Custom Log Inspection Decoders
- Dashboard
- Alert settings
- System settings
- Scheduled tasks
- Event-based tasks
- Users
- Roles
- Contact information

This feature may be useful in service provider environments where some of the examples are not applicable, or special examples need to be created.

As always the examples are meant to be a starting point. Tenants are encouraged to create policies based on their unique needs.

Note: Creating a new template will not affect existing tenants.

Protection usage monitoring

Deep Security collects information about protected computers. This information is visible on the dashboard in the tenants widget and the Tenant Protection Activity widget. The information is also provide in the Tenant report and is available via the REST API.

Note: In the most basic case, the monitoring can help determine the percentage usage of Deep Security Manager by hours of protection through the report or the API. Commonly called viewback or chargeback this information can be used in a variety of ways. In more advanced cases, this can be used for custom billing based on characteristics like tenant computer operating systems.

Use these options determine which additional tenant computer details are recorded.

Configure SMTP settings for email notifications

Deep Security Manager can send emails to users when selected alerts are triggered (see "[Configure alerts](#)" on page 1066). Before setting up the email notifications, you will need to give Deep Security Manager access to an SMTP mail server.

1. Go to **Administration > System Settings > SMTP**.
2. Type the IP address or hostname of your SMTP email server. Include the port number if it's not the [default port number](#).

Tip:

AWS throttles (rate limits) e-mail on SMTP's IANA standard port number, port 25. If you use AWS Marketplace, you may have faster alerts if you use SMTP over STARTTLS (secure SMTP) instead. For more information, see:

<https://docs.aws.amazon.com/ses/latest/DeveloperGuide/smtp-connect.html>

3. Enter a "From" email address from which the emails should be sent.

Note:

If you are using Amazon SES, the sender email address must be verified. To learn how to verify your email address in Amazon SES and view a list of addresses you've already verified, see:

<https://docs.aws.amazon.com/ses/latest/DeveloperGuide/verify-email-addresses.html>

4. Optionally, type a "bounce" address to which delivery failure notifications (DSN) should be sent if the alert emails can't be delivered to one or more users.
5. If your SMTP mail server requires outgoing authentication, type the user name and password credentials.
6. Select **STARTTLS** if your SMTP server supports the protocol. (STARTTLS is not supported in FIPS mode. See ["FIPS 140-2 support" on page 1381.](#))
7. After you've entered the necessary information, click **Test SMTP Settings** to test the connection.

Install the appliances

Deploy the Deep Security Virtual Appliance with NSX

If you want agentless protection for your VMware images when you deploy deep security, you must deploy the Deep Security Virtual Appliance. You can also ["Upgrade the Deep Security Virtual Appliance" on page 987](#) to protect against new OS vulnerabilities.

To deploy the appliance, follow the steps below, in order.

- ["Before you begin" on the next page](#)
- ["Step 1: Import appliance packages into Deep Security Manager" on page 240](#)
- ["Step 2: Add vCenter to Deep Security Manager" on page 241](#)
- ["Step 3: Prepare ESXi servers" on page 241](#)
- ["Step 4: Install Guest Introspection" on page 242](#)
- ["Step 5: Install the Deep Security Virtual Appliance" on page 248](#)
- ["Step 6: Prepare for activation" on page 253](#)
- ["Step 7: Create NSX security groups and policies" on page 260](#)

Trend Micro Deep Security On-Premise 11.3

- ["Step 8: Trigger an activation and policy assignment" on page 275](#)
- ["Step 9: Check that VMs are activated and assigned a policy" on page 275](#)
- ["Next steps \(how to add new VMs\)" on page 276](#)

Before you begin

Before you begin, be aware that:

1. The following Deep Security features are *not* supported by the Deep Security Virtual Appliance:
 - [application control](#)
 - [log inspection](#)
2. The following features are *not* supported if you are using NSX for vShield Endpoint (free), NSX Standard, or NSX Professional:
 - [firewall](#)
 - [intrusion prevention](#)
 - [web reputation](#)

Note: For an exhaustive list of supported features and sub-features that are supported by the Deep Security Virtual Appliance, see ["Supported features by platform" on page 85](#)

If you want these features, follow this guidance:

1. If you need application control or log inspection, deploy a Deep Security Agent on each guest VM. The agent provides the application control and log inspection features, while the virtual appliance provides the remaining features (limited by what your NSX license supports). The mix of agent-based protection and agentless protection is called ['combined mode'](#).

Trend Micro Deep Security On-Premise 11.3

2. If you need the firewall, intrusion prevention, or web reputation, do one of the following:

- upgrade your NSX license to NSX Enterprise or Advanced. See "[Upgrade the NSX license to Advanced or Enterprise](#)" on page 1010. After the upgrade, the following features are supported by the virtual appliance: firewall, intrusion prevention, web reputation, anti-malware, and integrity monitoring. You'll still need to deploy an agent if you want application control or log inspection.

OR

- install Deep Security Agent on each guest VM. The agent provides firewall, intrusion prevention, web reputation, application control, and log inspection functionality, while the Deep Security Virtual Appliance provides anti-malware and integrity monitoring functionality. The mix of agent-based protection and agentless protection is called '[combined mode](#)'.

Note: If you configured guest VMs to have direct access to a network card, install agents on those VMs. In this case there is no opportunity to intercept packets and an in-guest agent is preferable. See "[Choose agentless vs. combined mode protection](#)" on page 133 for details.

Step 1: Import appliance packages into Deep Security Manager

Follow the instructions below to download the Deep Security Virtual Appliance and import it into Deep Security Manager.

1. On your Deep Security Manager computer, go to the software page at <https://help.deepsecurity.trendmicro.com/software.html>.
2. Download the latest Deep Security Virtual Appliance package to your computer.
3. On Deep Security Manager, go to **Administration > Updates > Software > Local**.
4. Click **Import** and upload the package to Deep Security Manager.

When you import the appliance package, Deep Security Manager automatically downloads Deep Security Agent software that is compatible with the operating system of the appliance's virtual machine. This agent software appears under **Administration > Updates > Software > Local**. When you deploy the appliance, the embedded agent software will be auto-upgraded to the latest compatible version in **Local Software** by default. You can change the auto-upgrade version by clicking **Administration > System Settings > Updates tab > Virtual Appliance Deployment**.

Trend Micro Deep Security On-Premise 11.3

Note: It is acceptable to have multiple versions of the Deep Security Virtual Appliance package appear under **Local Software**. The newest version is always selected when you deploy a new Deep Security Virtual Appliance.

5. Optionally, for guest VMs that run Microsoft Windows, you can also download the Deep Security Notifier. The notifier is a component that displays messages for Deep Security system events in the system tray. For details, see ["Install the Deep Security Notifier" on page 377](#).

Step 2: Add vCenter to Deep Security Manager

Add vCenter to Deep Security Manager following the instructions in ["Add a VMware vCenter" on page 451](#).

After you have finished:


- your guest VMs are displayed in Deep Security Manager.
- the Trend Micro Deep Security service is registered with NSX.

Step 3: Prepare ESXi servers

If you are using NSX Advanced Edition or NSX Enterprise Edition, you must prepare your ESXi servers by installing the drivers necessary for network traffic inspection. This operation is performed on the cluster.

If you are using another NSX edition, skip this step and proceed to the next section.

- 1. In your vSphere Web Client, go to Home > Networking & Security > Installation > Host Preparation:




ESXi host preparation is now complete. For more complete instructions on host preparation, see VMware documentation.

Step 4: Install Guest Introspection


If you want file-based protection such as anti-malware or intrusion prevention for your VMs, you must install the Guest Introspection service on your ESXi servers.

Warning: If you do not install Guest Introspection, the anti-malware and intrusion prevention features will not work.


1. In vSphere Web Client, go to **Home > Networking & Security > Installation**, then click the **Service Deployments** tab.




1. Click the green plus icon (+).
The **Deploy Network & Security Services** window should appear.
2. Select **Guest Introspection**, then click **Next**.




3. Select the cluster that contains the ESXi servers and VMs that you want to protect, then click **Next**.



4. Select the datastore, the distributed port group used by your NSX cluster, and IP assignment method, then click **Next**.



5. Review your settings, then click **Finish**.



vSphere may take a few minutes to install the guest introspection service on your ESXi servers. When it is finished, **Installation Status** will display "Succeeded". To update the status, you may need to refresh the vSphere Web Client.



Step 5: Install the Deep Security Virtual Appliance

Trend Micro Deep Security On-Premise 11.3

1. In the vSphere Web Client, go to **Home > Networking and Security > Installation > Service Deployments**.


2. Click the green plus sign (+).

The screenshot shows the VMware vSphere Web Client interface. The left sidebar contains a navigation menu with categories like 'Networking & Security' and 'Installation'. The main content area is titled 'Installation' and has tabs for 'Management', 'Host Preparation', 'Logical Network Preparation', and 'Service Deployments'. The 'Service Deployments' tab is active, showing a table of 'Network & Security Service Deployments'. A callout box labeled 'New service deployment' points to a green plus icon located above the table. The table has columns for Service, Version, Installation Status, Service Status, Cluster, Datastore, Port Group, and IP Address Range. One row is visible for 'Guest Introspection' with a status of 'Succeeded' and 'Up'. The right sidebar shows 'Recent Tasks' and 'Alarms' sections.

Service	Version	Installation Status	Service Status	Cluster	Datastore	Port Group	IP Address Range
Guest Introspection	6.1.0	✓ Succeeded	✓ Up	Cluster A	Datastor...	dvPortGr...	DHCP


Trend Micro Deep Security On-Premise 11.3

3. In the new window that appears, select the **Trend Micro Deep Security** service and then click **Next**. If you do not see this service, it might be because you have not yet added your vCenter to Deep Security Manager. For details, see ["Step 2: Add vCenter to Deep Security Manager" on page 241](#)



4. Click Finish.

When deployment is complete, the Trend Micro Deep Security service appears in the list of network and security service deployments in the cluster.



Step 6: Prepare for activation

In an upcoming step, you will be activating your VMs in Deep Security, and assigning them a Deep Security policy. For this activation and policy assignment to work properly, you'll need to do some preparation work. This work involves either a) creating event-based tasks in Deep Security Manager that activate and assign policies, or b) synchronizing your Deep Security policies with NSX. Follow this guidance to choose the method that is best for you:

- ["Method 1: Create a 'Computer Created' event-based task" on the next page](#). Use this method if you have:
 - NSX for vShield Endpoint, or
 - NSX Standard Edition, or
 - NSX Professional, or
 - NSX Advanced or Enterprise and don't want to use VMware's Network Introspection Service

With this method, any VMs that you *create* in your system are automatically activated and assigned a policy. This method, and method 2, require the least amount of setup work. Note also that this method does not rely on the Network Introspection Service, unlike methods 2 and 3.

- ["Method 2: Create an 'NSX Security Group Change' event-based task" on page 255](#). Use this method if you have NSX Advanced or NSX Enterprise and you find it acceptable to use VMware's Network Introspection Service. With this method, new and existing VMs are automatically activated and assigned a policy when they are *moved into a designated NSX security group*. (Conversely, when they are moved out of the NSX security group, they are deactivated.) This method, and method 1, require the least amount of setup work.
- ["Method 3: Synchronize your Deep Security policies to NSX" on page 258](#). Use this method if you have NSX Advanced or NSX Enterprise and you find it acceptable to use VMware's Network Introspection Service. With this method, new and existing VMs are activated and assigned a policy with they are moved into a designated NSX security group. This is similar to method 2. However, unlike method 2, Deep Security policies are assigned *through the VMware UI* instead of through a Deep Security event-based task. If you have a lot of Deep Security policies you want to assign, this method can be time-consuming to set up, as it requires you to create individual NSX security policies and NSX security groups for each Deep Security policy. However, if you are more comfortable working in the VMware environment, this might be a good option for you.

Method 1: Create a 'Computer Created' event-based task

Note: The instructions below are task-based. For more explanatory information on event-based tasks, see ["Automated policy management in NSX environments" on page 276](#).

Create a 'Computer Created' event-based task that will activate and assign policies to any future VMs that you add to your system:

1. In Deep Security Manager, click **Administration** at the top.
2. On the left, click **Event-Based Tasks**.
3. In the main pane, click **New**.
4. From the **Event** drop-down list, select **Computer Created (by System)**. The **Computer Created (by System)** event type is triggered when a new VM is created.

Click **Next**.

5. Select **Activate Computer** and set it to 5 minutes.
6. Select **Assign Policy** and select a policy from the drop-down list, for example, **Windows Server 2016**. You can click the arrows to view child policies.

Click **Next**.

7. Specify the conditions that restrict when the event-based task is triggered. Add this condition:
 - **vCenter Name** matches `<your_vCenter_name>`

This configuration says, *'Only perform the actions in this event-based task if the VM's vCenter matches the one specified here'*

8. Add more conditions to further restrict when the event-based task is triggered. For example, if you have a naming convention for your VMs that includes a 'Windows' prefix on all Windows VMs, you would set:
 - **Computer Name** matches `Windows*`.

This configuration says, *'Only perform the actions in this event-based task if the VM name starts with Windows.'*

Trend Micro Deep Security On-Premise 11.3

Click **Next**.

9. In the **Name** field, enter a name for the task that reflects the policy you assigned, for example, `Activate Windows Server 2016`.
10. Select **Task Enabled** and then click **Finish**.
11. Create additional event-based tasks, one per Deep Security policy you plan on assigning. The event-based task must have an event type of **Computer Created (by System)** and must be configured to activate the computer and assign a policy.

You have now set up your event-based tasks to activate and assign policies to newly-created VMs. As soon as a VM is created, all the **Computer Created (by System)** event-based tasks are reviewed. If the conditions in a task are met, the task is triggered, and the VM is activated and assigned the associated policy.

Note: The **Computer Created (by System)** event-based task is only triggered for newly-created VMs. For your existing VMs, you will add them to a designated NSX group to trigger the activation and policy assignment. Details are provided in an upcoming step on this page.

Method 2: Create an 'NSX Security Group Change' event-based task

Note: The instructions below are task-based. For more explanatory information on event-based tasks, see ["Automated policy management in NSX environments" on page 276](#).

Note: This method relies on the Network Introspection Service, which is only available in NSX Advanced and Enterprise.

First, determine whether **NSX Security Group Change** event-based tasks were already created for you (they should be present if you enabled **Create an Event Based task to automatically activate VMs added to protected NSX Security Groups** when you added vCenter to Deep Security Manager):

1. In Deep Security Manager, click **Administration** at the top.
2. On the left, click **Event-Based Tasks**.
3. In the main pane, look for event-based tasks called **Activate <your_vCenter_name>** and **Deactivate <your_vCenter_name>**. Both have a **TYPE** of **NSX Security Group Change**. They may or may not exist.

If these event-based tasks exist, modify them as follows, otherwise, skip to the next procedure to create them.

Trend Micro Deep Security On-Premise 11.3

1. Double-click the **Activate** *<your_vCenter_name>* event-based task.
2. Click the **Actions** tab.
3. Select **Assign Policy** and then select a policy from the drop-down list, for example, **Windows Server 2016**. You can click the arrows to view child policies.
4. Select the **Conditions** tab and specify the conditions that restrict when the event-based task is triggered. Leave the ones that are there and add ones to further restrict when the event-based task is triggered. For example, if you have a naming convention for your VMs that adds a 'Windows' prefix to all Windows VMs, you would set **Computer Name** matches `Windows*`. This configuration says, *'Only perform the actions in this event-based task if the VM name starts with Windows.'*
5. Optionally, under the **General** tab, change the name of the task to reflect the policy you assigned, for example, `Activate Windows Server 2016`.
6. Select **Task Enabled**.
7. Create additional event-based tasks, one per Deep Security policy you plan on assigning. The event-based task must have an event type of **NSX Security Group Change** and must be configured to activate the computer and assign a policy.
8. Do not modify the **Deactivate** *<your_vCenter_name>* event-based task. This task says *'Only perform the actions in this event-based task if the VM is removed from an NSX security group'*.

Create event-based tasks that activate VMs and assign policies:

1. Click **Administration** at the top.
2. On the left, click **Event-Based Tasks**.
3. In the main pane, click **New**.
4. From the **Event** drop-down list, select **NSX Security Group Change**. The **NSX Security Group Change** event type is triggered when a VM is added to (or removed from) an NSX security group that is associated with this event-based task.

Click **Next**.

5. Select **Activate Computer** and set it to `5` minutes.
6. Select **Assign Policy** and select a policy from the drop-down list, for example, **Windows Server 2016**. You can click the arrows to view child policies.

Click **Next**.

Trend Micro Deep Security On-Premise 11.3

7. Specify the conditions that restrict when the event-based task is triggered. Add these conditions:
 - **Appliance Protection Activated** matches **False**.
 - **Appliance Protection Available** matches **True**.
 - **NSX Security Group Name** matches `.+` (which means *any*)
 - **vCenter Name** matches `<your_vCenter_name>`
8. Add more conditions to further restrict when the event-based task is triggered. For example, if you have a naming convention for your VMs that includes a 'Windows' prefix on all Windows VMs, you would set:
 - **Computer Name** matches `Windows*`.

This configuration says, '*Only perform the actions in this event-based task if the VM name starts with Windows*'

Click **Next**.

9. In the **Name** field, enter a name for the task that reflects the policy you assigned, for example, `Activate Windows Server 2016`.
10. Select **Task Enabled** and then click **Finish**.
11. Create additional event-based tasks, one per Deep Security policy you plan on assigning. The event-based task must have an event type of **NSX Security Group Change** and must be configured to activate the computer and assign a policy.

Create an event-based task that deactivates VMs, if it does not already exist:

1. Click **Administration** at the top.
2. On the left, click **Event-Based Tasks**.
3. In the main pane, click **New**.
4. From the **Event** drop-down list, select **NSX Security Group Change**.

Click **Next**.

Trend Micro Deep Security On-Premise 11.3

5. Select **Deactivate Computer**.

Click **Next**.

6. Specify the conditions that restrict when the event-based task is triggered. Add these conditions:

- **Appliance Protection Activated** matches **True**.
- **NSX Security Group Name** matches `^$` (which means *none*)
- **vCenter Name** matches `<your_vCenter_name>`

7. Click **Next**.

8. In the **Name** field, enter a name for the task that reflects the action and vCenter name, for example, `Deactivate computer - My vCenter`.

9. Select **Task Enabled** and then click **Finish**.

You have now set up your event-based tasks to activate and assign policies to VMs that you add to NSX security groups. As soon as a VM is added to a designated NSX group, all the **NSX Security Group Name** event-based tasks are reviewed. If the conditions in a task are met, the task is triggered, and the VM is activated and the associated policy assigned.

Note: For the **NSX Security Group Name** event-based task to work properly, additional configurations are required. Specifically, you'll need to create an NSX security group and NSX security policy. Instructions are provided in an upcoming step.

Method 3: Synchronize your Deep Security policies to NSX


Note: The instructions below are task-based. For more explanatory information on synchronizing policies, see ["Synchronize Deep Security policies with NSX" on page 281](#).

Note: This method relies on the Network Introspection Service, which is only available in NSX Advanced and Enterprise.

1. Log in to Deep Security Manager.
2. Make sure that all of the policies in Deep Security Manager have a unique name before they are synchronized with NSX. All the default ones have unique names.

Trend Micro Deep Security On-Premise 11.3

3. At the top, click **Computers**.
4. On the left, right-click the vCenter where you want to enable synchronization and select **Properties**.
5. On the **NSX Configuration** tab, select **Synchronize Deep Security Policies with NSX Service Profiles**. Click **OK**.
6. Check that your policies are loading into vSphere:
 - a. In the vSphere Web Client Home page, click the **Networking & Security** button. **NSX Home** appears.
 - b. On the left, click **Service Definitions**.
 - c. In the main pane, under the **Services** tab, right-click **Trend Micro Deep Security** and select **Edit settings**.
 - d. In the main pane, select the **Manage** tab, and under that, select **Profile Configurations**.
 - e. Make sure the Deep Security policies are loading. They appear as individual NSX profile configurations of the same name. Each profile configuration has an ID that starts with a 'P', for example, P1, P2, P3, and so on. The 'P' indicates they are based on Deep Security policies.



You have now added your Deep Security policies as profile configurations in NSX.

Note: For the NSX profile configurations to work properly, additional configurations are required. Specifically, you'll need to create an NSX security group and NSX security policy. Instructions are provided in an upcoming step.

Step 7: Create NSX security groups and policies


You need to configure NSX security groups and policies, and associate them with Deep Security.


After completing the tasks in this section, any VMs that are added to these NSX security groups will be activated in Deep Security Manager, and assigned a Deep Security policy. This activation and policy assignment will:

Trend Micro Deep Security On-Premise 11.3


- require a manual synchronization, if you chose "[Method 1: Create a 'Computer Created' event-based task](#)" on page 254.
- be automatic, if you chose "[Method 2: Create an 'NSX Security Group Change' event-based task](#)" on page 255 or "[Method 3: Synchronize your Deep Security policies to NSX](#)" on page 258.

First, create NSX security group(s):

1. In vSphere Web Client, go to **Home > Networking & Security > Service Composer > Security Groups**.
2. Click **New Security Group** ():




3. **Define Dynamic Membership:** If you want to restrict membership in this group based on filtering criteria, enter those criteria here.



4. Select the objects that will be included. Follow this guidance:


Trend Micro Deep Security On-Premise 11.3

- If you decided to use event-based tasks, you can add all your VMs to the security group if you want.
- If you decided to use policy synchronization, only add those VMs that correspond to the Deep Security policy you want to assign. For example, if you want to assign the Windows Server 2016 policy, only include Windows Server 2016 VMs.
- There are many ways to include or exclude objects in a NSX security group. For this example, we will include the NSX cluster that contains the ESXi hosts and VMs that we want to protect. In the **Select objects to include** options, select **Cluster** from the **Object Type** menu, and move the NSX cluster that contains the VMs to protect to the **Selected Objects** column.



Note: If a VM is included in more than one security group, then when you go to **Computers** in Deep Security Manager and search for the VM's name, it will appear more than once in search results. For more information, please see [Duplicate host records appear in Computer page when the host is located in more than one NSX security group](#).


5. Click **Finish** to create the new security group and return to the **Security Groups** tab to see the newly listed security group.



Next, create an NSX security policy:

Trend Micro Deep Security On-Premise 11.3

- 1. In vSphere Web Client, go to **Home > Networking and Security > Service Composer > Security Policies**.
- 2. Click **New Security Policy**.




- 3. **Guest Introspection Services:** Configure Guest Introspection Services if you are using the anti-malware or intrusion prevention modules.

Warning: If you do not install Guest Introspection, the anti-malware and intrusion prevention features will not work.

Click the green plus sign (**+**) to add an **Endpoint Service**. Provide a name for the Endpoint Service and select the following settings:

- **Action:** Apply
- **Service Name:** Trend Micro Deep Security
- **Service Profile:** Select one of the following:
 - If you decided to use event-based tasks, select **Default (EBT)**. This is a profile configuration that is configured to trigger event-based task(s) in Deep Security Manager.
 - If you decided to use policy synchronization, select the profile configuration that matches the Deep Security policy that you want to apply.
- **State:** Enabled
- **Enforce:** Yes




Click **OK**, then click **Next**.

4. **Firewall Rules:** do not make any changes. Click **Next**.
5. **Network Introspection Services:** Network Introspection Services are only available with NSX Advanced and Enterprise, and only need to be configured if you are using the web reputation, firewall, or intrusion prevention modules. You will be adding *two* Network Introspection Services to the NSX Security Policy: a first one for *outbound* traffic, and a second one for *inbound* traffic.

Trend Micro Deep Security On-Premise 11.3

- a. For the first, *outbound*, service, in the **Network Introspection Services** options, click the green plus sign to create a new service. In the **Add Network Introspection Service** window, provide a name for the service (preferably one that includes the word "Outbound") and select the following settings:
 - **Action:** Redirect to service
 - **Service Name:** Trend Micro Deep Security
 - **Service Profile:** Select the same NSX profile configuration as you did in step 4.
 - **Source:** Policy's Security Groups
 - **Destination:** Any
 - **Service:** Any
 - **State:** Enabled
 - **Log:** Do not log




- b. For the second, *inbound*, service, in the **Network Introspection Services** options, click the green plus sign to create a new service. In the **Add Network Introspection Service** window, provide a name for the service (preferably one that includes the word "Inbound") and select the following settings:

Trend Micro Deep Security On-Premise 11.3

- (NSX 6.3) **Action:** Redirect to service

OR

- (NSX 6.4.1 or higher) **Redirect to service:** Yes
- **Service Name:** Trend Micro Deep Security
- **Service Profile:** Select the same NSX profile configuration as you did in step 4.
- **Source:** Any
- **Destination:** Policy's Security Groups
- **Service:** Any
- **State:** Enabled
- **Log:** Do not log




c. Click **OK** in the **Add Network Inspection Service** window, and then click **Finish** to complete and close the **New Security Policy** window.

You have now created an NSX security policy for Deep Security.

Next, associate the NSX security policy you just created with the NSX security group you also just created:

Trend Micro Deep Security On-Premise 11.3

- 1. Stay on the **Security Policies** tab of the **Home > Networking & Security > Service Composer** page in your vSphere Web Client.
- 2. With the new security policy selected, click the **Apply Security Policy** icon (🔧📁).
- 3. In the **Apply Policy to Security Groups** window, select the security group that contains the VMs you want to protect and click **OK**.



The NSX security policy is now applied to the VMs in the NSX security group.

As a final step, if you decided to use policy synchronization, create additional NSX security policies and groups:

Note: This step is not required if you decided to use event-based tasks.

- 1. For each Deep Security policy that you want to assign, create:
 - a. an NSX security *group* with a name that reflects the Deep Security policy you plan to assign. For example, `Linux Server Security Group`.
 - b. an NSX security *policy* (for example, `Linux Server Security Policy`) that has its **Service Profile** set to the Deep Security policy you want to assign.

You should now have multiple NSX security policies and groups. For example:

```
Linux Server Security Group
Linux Server Security Policy
```

Trend Micro Deep Security On-Premise 11.3

```
Windows 10 Desktop Security Group
Windows 10 Desktop Security Policy
```

...and so on.

2. Associate each policy with the corresponding security group. For example, associate the `Linux Server Security Policy` with the `Linux Server Security Group`.

Step 8: Trigger an activation and policy assignment

Your VMs are now ready to be activated and assigned a policy.

If you chose "[Method 1: Create a 'Computer Created' event-based task](#)" on page 254, you'll need to manually synchronize the vCenter. Go to Deep Security Manager, right-click the vCenter on the left, and select **Synchronize Now**.

If you chose "[Method 2: Create an 'NSX Security Group Change' event-based task](#)" on page 255, all VMs should be activated and assigned policy automatically now. To check, see the next step.

If you chose "[Method 3: Synchronize your Deep Security policies to NSX](#)" on page 258, all VMs should be activated and assigned policy automatically now. To check, see the next step.

Step 9: Check that VMs are activated and assigned a policy

Make sure your VMs in Deep Security Manager become activated, and are assigned a policy.

1. In Deep Security Manager, click **Computers** at the top.
2. On the left, expand **Computers > <your_vCenter> > Virtual Machines**.
3. Check the **TASK(S)** and **STATUS** and column. The **TASK(S)** column should indicate **Activating**, and your VMs should move from the **Unmanaged (Unknown)** status, to the **Unmanaged (No Agent)** status, to the **Managed (Online)** status. You may see the VMs move into the **VMware Tools Not Installed** status, but this is temporary.
4. Check the **POLICY** column to make sure the correct Deep Security policy was assigned.

You have now deployed Deep Security Virtual Appliance and protected your VMs with it.

Trend Micro Deep Security On-Premise 11.3

Next steps (how to add new VMs)

Follow the instructions below to learn how to add new VMs to your system and protect them with Deep Security.

To add a new VM if you chose ["Method 1: Create a 'Computer Created' event-based task" on page 254](#):

- Create a new VM in vCenter. This triggers the **Computer Created (by System)** event-based task, which activates and assigns policy to the new VM.

To add a new VM if you chose ["Method 2: Create an 'NSX Security Group Change' event-based task" on page 255](#)

- Create or move the VM into one of the NSX security groups. This triggers the **NSX Security Group Change** event-based task, which activates and assigns policy to the new VM.

To add a new VM if you chose ["Method 3: Synchronize your Deep Security policies to NSX" on page 258](#):


- Create or move the VM into one of the NSX security groups. This activates and assigns policy to the new VM.

Automated policy management in NSX environments

Note: If you have enabled synchronization of Deep Security policies to NSX, you will not need to use the **NSX Security Group Change** EBT. For information on policy synchronization, see ["Synchronize Deep Security policies with NSX" on page 281](#).

The security configuration of a VM in an NSX environment can be be automatically modified based changes to the VM's NSX Security Group. The automation of security configuration is done using the **NSX Security Group Change** Event-Based Task.

VMs are associated with NSX Security Groups, NSX Security Groups are associated with NSX Security Policies, and NSX Security Policies are associated with NSX Service Profiles.



"NSX Security Group Change" event-based task

Deep Security has event-based tasks (EBTs) that can be configured to perform actions when specific events with specific conditions are detected. The **NSX Security Group Change** EBT exists to let you modify the protection settings of a VM if changes to the NSX Security Group that a VM belongs to are detected.

Note: The **NSX Security Group Change** EBT only detects changes to NSX Security Groups that are associated with the **Default (EBT)** NSX Service Profile. Similarly, a VM may be associated with many Groups and Policies, but Deep Security will only monitor and report changes that involve Groups and Policies associated with the **Default (EBT)** NSX Service Profile.

To modify that task, in Deep Security Manager, go to **Administration > Event-Based Tasks**.

The **NSX Security Group Change** EBT is triggered when any of the following events occur:

- A VM is added to an NSX Group that is (indirectly) associated with the **Default (EBT)** NSX Service Profile.
- A VM is removed from an NSX Group that is associated with the **Default (EBT)** NSX Service Profile.
- An NSX Policy associated with the **Default (EBT)** NSX Service Profile is applied to an NSX Group.

Trend Micro Deep Security On-Premise 11.3

- An NSX Policy associated with the **Default (EBT)** NSX Service Profile is removed from an NSX Group.
- An NSX Policy is associated with the **Default (EBT)** NSX Service Profile.
- An NSX Policy is removed from the **Default (EBT)** NSX Service Profile.
- An NSX Group that is associated with an **Default (EBT)** NSX Service Profile changes name.

An event is triggered for each individual VM affected by a change.

Conditions under which to perform tasks

The following conditions are applicable to the **NSX Security Group Change** event-based task and can be tested against before performing an action:

- **Computer Name:** The hostname of the guest VM.
- **ESXi Name:** The hostname of the ESXi where the guest VM runs.
- **Folder Name:** The name of the guest VM's folder in the ESXi folder structure.
- **NSX Security Group Name:** The name of the NSX Security Group that was changed.
- **Platform:** The operating system of the guest VM.
- **vCenter name;** The name of the vCenter that the guest VM belongs to.
- **Appliance Protection Available:** A Deep Security Virtual Appliance is available to protect VMs on the ESXi on which the VM is hosted. The VM may or may not be in a "Activated" state.
- **Appliance Protection Activated:** A Deep Security Virtual Appliance is available to protect VMs on the ESXi on which the VM is hosted and the VM is "Activated".
- **Last Used IP Address:** The current or last known IP address of the VM computer.

For information on these conditions and event-based tasks in general, see ["Automatically perform tasks when a computer is added or changed" on page 422](#).

The **NSX Security Group Name** condition is explicitly for changes to the **NSX Security Group Change** event-based task.

Trend Micro Deep Security On-Premise 11.3

It accepts a java regular expression match to the NSX Security Group the VM belongs to whose properties have changed. Two special cases are considered:

- A match for membership in any group. In this case the recommended regular expression is ".".
- A match for membership in no groups. In this case the recommended regular expression is "^\$".

Other regular expressions can include a specific group name or partial name (to match more than one group) as desired.

Note: The list of potential groups in this condition refers only to groups associated with policies associated with the **Default (EBT)** NSX Service Profile.

Available actions

The following actions can be performed on a VM when Deep Security detects a change to the NSX Security Group the VM belongs to:

- **Activate Computer:** Activate Deep Security protection by the Deep Security Virtual Appliance. Use this when a VM is moved into a Deep Security-protected NSX Security Group.
- **Deactivate Computer:** Deactivate Deep Security protection by the Deep Security Virtual Appliance. Use this when moving a VM out of a Deep Security-protected NSX Security Group. An Alert will be raised if this action is not performed when a VM is moved out a NSX Security Group protected by Deep Security because the VM can no longer be protected.
- **Assign Policy:** Assign a Deep Security Policy to a VM.
- **Assign Relay Group:** Assign a Relay Group to a VM.

Event-based tasks created when adding a vCenter to Deep Security Manager

Two event-based tasks can be created when adding an NSX vCenter to DSM. The last page of the **Add vCenter** wizard displays a checkbox. If selected, this option creates two event-based tasks. One to activate VMs when protection is added and the other to deactivate VMs when protection is removed.

The first event-based task is configured as follows:

Trend Micro Deep Security On-Premise 11.3

- **Name:** Activate <vCenter Name>, where <vCenter Name> is the value seen in the Name field on the vCenter properties.
- **Event:** NSX Security Group Changed
- **Task Enabled:** True
- **Action:** Activate Computer after a delay of five minutes
- **Conditions:**
 - **vCenterName:** <vCenter Name> Must match because the EBT is vCenter-specific.
 - **Appliance Protection Available:** True. Must have an activated Deep Security Virtual Appliance on the same ESXi.
 - **Appliance Protection Activated:** False. This only applies to unactivated VMs.
 - **NSX Security Group:** ".+". Must be a member of one or more Deep Security Groups.

You can modify the actions associated with this event-based task, for example by applying a Deep Security protection policy or assigning a different relay group. The actions (and other properties) of any existing event-based tasks can be edited on the **Administration > Event-Based Tasks** page in the Deep Security Manager.

The second event-based task is configured as follows:

- **Name:** Deactivate <vCenter Name>, where <vCenter Name> is the value seen in the Name field on the vCenter properties.
- **Event:** NSX Security Group Changed
- **Task Enabled:** False
- **Action:** Deactivate Computer
- **Conditions:**
 - **vCenterName:** <vCenter Name>. Must match because the event-based task is vCenter-specific.
 - **Appliance Protection Activated:** True. This only applies to activated VMs.

Trend Micro Deep Security On-Premise 11.3

- **NSX Security Group:** "^\$". Must not be a member of any Deep Security Group.

Note: This event-based task is disabled by default. You can enable it and customize it as desired after the vCenter installation is complete.

Note: If multiple event-based tasks are triggered by the same condition, the tasks are executed in alphabetical order by task name.

Removal of a vCenter from Deep Security Manager

Whenever a vCenter is removed from Deep Security Manager disables all event-based tasks that meet the following criteria:

1. The **vCenter Name** condition matches the name of the vCenter being removed.

Note: This must be an exact match. Event-based tasks which match multiple vCenter names will not be disabled.

2. The event-based task **Event Type** is "NSX Security Group Changed". Event-based tasks with other event types are not disabled.

To remove a vCenter from Deep Security Manager, you'll first need to remove Deep Security artifacts from NSX. For instructions on removing Deep Security from NSX and vCenter from Deep Security Manager, see ["Uninstall Deep Security from your NSX environment" on page 1425](#).

Synchronize Deep Security policies with NSX

There are two ways to protect your VMs with Deep Security:

- Use event-based tasks to activate and deactivate VMs in Deep Security and apply or remove a default policy. For more information, see "Event-Based Tasks Created When Adding a vCenter to Deep Security Manager" in ["Automated policy management in NSX environments" on page 276](#).
- Synchronize your Deep Security policies with NSX. This method is described below.

Each VM that you want to protect must belong to an NSX Security Group that has an NSX Security Policy assigned to it. When you set up an NSX Security Policy, one of the options that you select is the NSX Service Profile. With Deep Security 9.6 or earlier, there was only one NSX Service Profile for use with Deep Security. In Deep

Trend Micro Deep Security On-Premise 11.3

Security 9.6 SP1 or later, you can choose to synchronize all of your Deep Security policies with NSX. This creates a matching NSX Service Profile (which we call a "Mapped Service Profile" in Deep Security) for each of your Deep Security policies.

Enable policy synchronization:

Note: All of the policies in Deep Security Manager must have a unique name before they are synchronized with NSX.

1. In the Deep Security Manager, go to the **Computers** page and right-click the vCenter where you want to enable synchronization.
2. Click **Properties**.
3. On the **NSX Configuration** tab, select **Synchronize Deep Security Policies with NSX Service Profiles**. Click **OK**.

Next steps:

1. There are several steps required to protect your VMs with Deep Security Virtual Appliance, and they must be completed in a specific order. For a complete list of steps, see ["Deploy the Deep Security Virtual Appliance with NSX" on page 238](#).

Change or remove the policy assigned to a VM

When a VM is protected by a Mapped Service Profile, the policy assignment cannot be changed from within Deep Security Manager. To change the profile used to protect a VM, you must change the NSX Security Policy or NSX Security Group from your vSphere Web Client.

If you unassign an NSX Security Policy from a group, any VMs in that group will be deactivated in Deep Security Manager.

Change the name of a policy

If you rename a policy in Deep Security Manager, the NSX Service Profile Name will also be changed.

Delete a policy

Trend Micro Deep Security On-Premise 11.3

If you delete a policy in Deep Security Manager and the corresponding NSX Service Profile is not in use, it will be deleted. If the corresponding NSX Service Profile is in use, the NSX Service Profile will be no longer be synchronized with Deep Security Manager and its name will be changed to indicate that it is no longer valid. If the NSX Service Profile becomes unused later, it will be deleted.

VMware vRealize

If you are configuring a blueprint with VMware vRealize, you can assign either a NSX Security Group or an NSX Security Policy to the blueprint. The Security Group or Security Policy can both use Mapped Service Profiles.

Deploy agentless protection in a vCloud environment

VMware vCloud integration enables the primary tenant in a multi-tenant installation to add a vCenter to their Deep Security Manager, configure a connector, and to deploy and manage the Deep Security Virtual Appliance. The tenants can import vCloud Organizations as cloud accounts and apply agentless Deep Security protection to them.

When applying agentless protection to vCloud Organizations, only the anti-malware and integrity monitoring modules are supported and the vCloud Organizations must only be added to tenants (not the primary tenant). If you want to enable other protection modules, you will need to use agent-based protection instead (see ["Install the agent on VMware vCloud" on page 326](#)).

In this article:

- ["Enable agentless protection of vCloud VMs" on the next page](#)
- ["Create a multi-tenant environment" on the next page](#)
- ["Add a vCenter and deploy the Deep Security Virtual Appliance" on the next page](#)
- ["Configure VMware vCloud resources for integration with Deep Security" on the next page](#)
- ["Activate virtual appliance protection on virtual machines" on page 287](#)

Enable agentless protection of vCloud VMs

1. In the Deep Security Manager console, go to **Administration > System Settings > Agents**.
2. Select the **Allow Appliance protection of vCloud VMs** checkbox.
3. Click **Save**.

Create a multi-tenant environment

There are two main task required to create a multi-tenancy environment: you must enable multi-tenancy and then create tenants. For step-by-step instructions on how to perform these tasks, as well as requirements and recommendations for a multi-tenant environment, see ["Set up a multi-tenant environment" on page 201](#).

Add a vCenter and deploy the Deep Security Virtual Appliance

The primary tenant must add a vCenter and deploy the Deep Security Virtual Appliance. For instructions, see ["Deploy the Deep Security Virtual Appliance with NSX" on page 238](#).

Configure VMware vCloud resources for integration with Deep Security

To enable vCloud integration, you must assign a minimum set of rights to the user accounts tenants will use to import their vCloud "Cloud Accounts" and you must configure the vCenter database to assign unique UUIDs to new virtual machines.

Create a minimum rights role for vCloud account tenant users

The user accounts you create in vCloud director that the Deep Security tenants will use to add their cloud accounts to their Deep Security Manager require only the **All Rights > General > Administrator View** right.

1. Log in to vCloud Director.
2. In the **System** tab, click on **Administration**.
3. In the navigation panel on the left, click on **Roles**.
4. Click the "plus" sign to create a new Role (for example, "DS_User").

Trend Micro Deep Security On-Premise 11.3

5. Select the **Administrator View** right in the **All Rights > General** folder.
6. Click **OK**.

You can now assign this role to the user accounts you will give to Deep Security rsers to import their vCloud resources into the Deep Security Manager.

Note: When providing a Deep Security user with their credentials, you must include the IP address of the vCloud Organization and instruct them that when importing the vCloud resources into their Deep Security Manager, their username must include "@orgName". For example if the vCloud account's username is **kevin** and the vCloud Organization you've given the account access to is called **CloudOrgOne**, then the Deep Security user must enter **kevin@CloudOrgOne** as their username when importing the vCloud resources. (For a vCloud administrator view, use **@system**.)

Note: You can configure Deep Security Manager to use a proxy server specifically for connecting to instances being protected in Cloud Accounts. The proxy setting can be found in **Administration > System Settings > Proxies > Proxy Server Use > Deep Security Manager (Cloud Accounts)**.

Configure the vCenter database to assign unique UUIDs to new virtual machines

Deep Security requires that all protected virtual machines have unique UUIDs. Virtual machines created from a vApp template can be assigned duplicate UUIDs which can cause problems. However, you can configure your database to assign unique UUIDs to these VMs created from a template.

Note: The following information is taken from a VMware Knowledge Base article, "[BIOS UUIDs in vCloud Director are not unique when virtual machines are deployed from catalog templates \(2002506\)](#)".

To configure the database to assign unique UUIDs to new virtual machines that are created from a template, you must set the **CONFIG** table of the database, with the parameter **backend.cloneBiosUuidOnVmCopy**, to **0**.

To set this parameter in Oracle Database, launch Oracle Database Enterprise Manager and run the following commands:

Note: In this example, "VCLLOUD" is the name of the data base you created for vCloud.

```
set feedback on echo on
```

Trend Micro Deep Security On-Premise 11.3

```
set linesize 120

update "VCLLOUD"."CONFIG" set VALUE = '0' where NAME='backend.cloneBiosUuidOnVmCopy';

commit;

select * from "VCLLOUD"."CONFIG" where VALUE = '0' and NAME='backend.cloneBiosUuidOnVmCopy';
```

To set this parameter in Microsoft SQL Server, launch SQL Server Management Studio and run the following commands:

```
USE VCLLOUD

GO

update config set value = '0' where name='backend.cloneBiosUuidOnVmCopy'

select * from dbo.config where value = 0 and name='backend.cloneBiosUuidOnVmCopy';
```

When the parameter has been set, restart all cells in vCloud Director.

Note: This change does not affect previously existing virtual machines.

Enable the OVF Environment Transport for VMware Tools on your guest VMs

Enabling the OVF Environment Transport for VMware Tools on your guest VMs will expose the **guestInfo.ovfEnv** environment variable making it easier for Agents to uniquely identify their VMs to the Deep Security Manager. This will reduce the risk of VM misidentification.

1. In vCloud Director, open the VM's **Properties** screen, go the **Guest OS Customization** tab and select the **Enable guest customization** checkbox. Click **OK**.
2. In vCenter, select the same VM, open its **Properties** screen, go to the **Options** tab.
3. Click **vApp Options** and select the **Enabled** radio button. **OVF Settings** will now be exposed.
4. In **OVF Settings**, select the **VMware Tools** checkbox in the **OVF Environment Transport** area. Click **OK**.

If your VM is running, it must be restarted for the changes to take effect.

Trend Micro Deep Security On-Premise 11.3

The data used by Deep Security are taken from the following properties: `vmware.guestinfo.ovfenv.vcenterid` and `vmware.guestinfo.ovfenv.vcloud.computername`.

Activate virtual appliance protection on virtual machines

The tenants can import vCloud Organizations as cloud accounts and apply agentless Deep Security protection to them.

Import computers from a VMware vCloud Organization Account

1. In the Deep Security Manager, go to the **Computers** section, right-click **Computers** in the navigation panel and select **Add vCloud Account** to display the **Add vCloud Account** wizard.
2. In **Name** and **Description**, enter a display name and any additional notes.
3. In **Address**, enter the vCloud Director's hostname.
4. Enter your **User name** and **Password**.

Note: Your **User name** must be in the form `username@vcloudorganization`.

5. Click **Next**.
6. Deep Security Manager will verify the connection to the cloud resources and display a summary of the import action. Click **Finish**.

The VMware vCloud resources now appear in the Deep Security Manager under their own branch under **Computers** in the navigation panel.

Import computers from a VMware vCloud Air Virtual data center

1. In the Deep Security Manager, go to the **Computers** section, right-click **Computers** in the navigation panel and select **Add vCloud Account** to display the **Add vCloud Account** wizard.
2. Enter a **Name** and **Description** of the VMware vCloud Air virtual data center you are adding. (These are only used for display purposes in the Deep Security Manager.)
3. Enter the **Address** of the VMware vCloud Air virtual data center.

To determine the address of the VMware vCloud Air virtual data center:

- a. Log in to your VMware vCloud Air portal.
 - b. On the **Dashboard** tab, click on the data center you want to import into Deep Security. This will display the **Virtual Data Center Details** information page.
 - c. In the Related Links section of the **Virtual Data Center Details** page, click on **vCloud Director API URL**. This will display the full URL of the vCloud Director API.
 - d. Use the hostname only (not the full URL) as the Address of the VMware vCloud Air virtual data center that you are importing into Deep Security.
4. Enter your **User name** and **Password**.

Note: Your **User name** must be in the form `username@virtualdatacenterid`.

5. Click **Next**.
6. Deep Security Manager will verify the connection to the virtual data center and display a summary of the import action. Click **Finish**.

The VMware vCloud Air data center now appears in the Deep Security Manager under its own branch under **Computers** in the navigation panel.

Activate virtual appliance protection on virtual machines

To activate virtual appliance protection, right-click on a virtual machine in the **Computers** list and click **Actions > Activate**.

Integrate with VMware vRealize Operations Manager

Note: Deep Security support for the vRealize Operations adapter will end Dec 31, 2018. There will be no further updates to this adapter.

The Deep Security Management Pack for vRealize Operations (vROps) displays security events that occur on your protected virtual machines in the vROps console. Security and operational data appear simultaneously so that you can correlate security status with the overall health of your virtual data center.

Note: The Deep Security Management Pack for vRealize Operations does not support application control.

Trend Micro Deep Security On-Premise 11.3

During each data collection cycle, the management pack connects to Deep Security Manager and queries it for specific metrics. The management pack collects performance data, relationships, and events for Trend Micro Deep Security resources.

- ["Requirements" below](#)
- ["Download the management pack" on the next page](#)
- ["Install and configure" on the next page](#)
- ["Migrate from a 5.x environment" on page 301](#)
- ["Navigate Deep Security in vROps" on page 301](#)
- ["Dashboards" on page 303](#)
- ["Metrics" on page 306](#)
- ["Alerts, Symptoms, and Recommendations" on page 307](#)

Requirements

Before you install the management pack, ensure that your system meets the following requirements.

Deep Security:

- Deep Security 11.3 is installed. Note that versions 9.5 and 9.6 are also supported.
- Access to the Deep Security Manager web console via a web browser
- Deep Security Manager user name and password
- The Deep Security Manager server has network access to the vCenter on which VMware vRealize Operations Manager is installed
- The management pack package is stored in a local directory that is available to the VMware vRealize Operations Manager web console
- The management pack certificate import script (import-cert)

VMware vRealize Operations Management:

Trend Micro Deep Security On-Premise 11.3

- VMware vCenter is installed
- VMware vRealize Operations Manager v6.0.x (Advanced Edition) is installed (requires custom dashboard functionality)
 - vRealize User Name and Password
 - SSH access to vRealize Operations Manager vApp
- Client Integration Plug-in 6.0.0 Build 4275819

Download the management pack

The Deep Security Management Pack for vROps is available to download from the [Deep Security Software page](#). Click the tab for the current version of Deep Security, and click the link in the Support Files area.

Install and configure

To install and configure the management pack, complete the following tasks:

1. ["Create a user account for vRealize Operations Manager" below](#)
2. [" Enable SOAP Web Services in Deep Security Manager" on page 292](#)
3. ["Export the Deep Security Manager certificate" on page 293](#)
4. ["Import the Deep Security Manager certificate into vRealize Operations Manager" on page 293](#)
5. ["Install the Deep Security Management Pack in vRealize Operations" on page 295](#)
6. ["Configure the Deep Security Management Pack in vRealize Operations" on page 297](#)
7. ["Validate Data Collection in vRealize Operations " on page 299](#)

Create a user account for vRealize Operations Manager

Create a read-only Auditor account that the management pack uses to access Deep Security Manager.

Trend Micro Deep Security On-Premise 11.3

- 1. In the Deep Security Manager console, click **Administration > User Management > Users**.
- 2. Click **New** and create a new User account with the role of **Auditor**.

VROPS Properties - Google Chrome

Not secure | https://10.203.251.64:4119/AdministratorProperties.screen?administratorID=2

General

Contact Information

Settings

General Information

Username

VROPS

Name:

DS Adapter

Description:

Role:

Auditor

Edit

Language:

English (US)

Time zone:

(UTC-5.00) Eastern Standard Time (US/Eastern)

Time format:

☐ 12 Hour

☒ 24 Hour

Sign-In Credentials

Set Password...

Last changed: March 24, 2017

☐ Password never expires

☐ Locked Out (Denied permission to sign in)

Multi-Factor Authentication (MFA)

MFA Enabled: No

Enable MFA...

Save


Close

Note: Take note of the Username and Password for the user account. You will need these credentials when installing the management pack in VMware vRealize Operations Manager.

Trend Micro Deep Security On-Premise 11.3

Enable SOAP Web Services in Deep Security Manager

- 1. In the Deep Security Manager console, click **Administration > System Settings > Advanced**.
- 2. In the **SOAP Web Service API** section, select **Enabled**.



Trend Micro Deep Security On-Premise 11.3

Export the Deep Security Manager certificate

Note: The procedures for exporting a security certificate vary across browsers and browser versions. The following steps apply to Mozilla Firefox 33. If you are not using Firefox 33, see your browser's documentation for instructions.

1. Sign in to Deep Security Manager.
2. Click **Menu > Options**.
3. On the **Advanced** panel, click the **Certificates** tab and then click **View Certificates** to open the Certificates Manager window.
4. In the Certificate Manager window, click the **Servers** tab and select the Deep Security Manager server name.
5. Click **Export** and select "X.509 Certificate (DER)" as the format.
6. Save the certificate.

Import the Deep Security Manager certificate into vRealize Operations Manager

Note: In cluster-based environments, you must import the certificate on each collector node.

1. On the vROps computer, as the root user copy the import-cert script and Deep Security Manager certificate to the /root directory. (You downloaded the script with the management pack. See ["Download the management pack" on page 290.](#))
2. In a terminal, enter the following command to change directories:

```
cd $VCOPS_DATA_VCOPS/user/conf/ssl
```

3. Enter the following command to view the storePass.properties file:

```
cat storePass.properties
```

The output should look appear similar to the following example:

```
sslkeystorePassword=xxxxxxxxxxxxxx
```

```
ssltruststorePassword=xxxxxxxxxxxxxx
```

4. Copy the **ssl truststore** password.
5. Enter the following command to edit the **import-cert** file:

```
vi import-cert
```

Trend Micro Deep Security On-Premise 11.3

6. Modify the file with your environment-specific information:

```
CERT="/root/xxxxxxx.der"  
PASS="xxxxxxxxxxx"
```

where /root/xxxxxxx.der is the certificate that you copied to the /root directory, and PASS is the ssl truststore password that you obtained in a previous step.

7. Save the import-cert file.
8. Enter the following command to add the execute permission to the import-cert script:

```
chmod +x import-cert
```

9. Run the import-cert script:

```
./import-cert
```

The script output is similar to the following example. The keytool error is expected:

```
/root/xxxxxxx.der will be imported into the vC Ops trust store.  
Do you wish to import a different certificate ? (y/n) n  
Deleting Deep Security Manager certificate (ignore errors) ...  
keytool error: java.lang.Exception: Alias <Deep_Security_Manager> does not exist  
Importing Deep Security Manager certificate /root/xxxxxxx.der ...  
Certificate was added to keystore
```

10. Run the script again to ensure that the keytool error does not occur:

```
./import-cert>
```

The output is similar to the following example:

```
/root/xxxxxxx.der will be imported into the vC Ops trust store.  
Do you wish to import a different certificate ? (y/n) n  
Deleting Deep Security Manager certificate (ignore errors) ...  
Importing Deep Security Manager certificate /root/xxxxxxx.der ...  
Certificate was added to keystore
```

Trend Micro Deep Security On-Premise 11.3

11. Reboot all vRealize Operations nodes to ensure the certificate is recognized as trusted.


Install the Deep Security Management Pack in vRealize Operations

Install the pak file that you downloaded from the Deep Security Software page (see ["Download the management pack" on page 290](#)).

Note: The Deep Security Management Pack for vRealize Operations is distributed as a .pak file. Before installing the .pak file in vROps, read the included release notes and back up any customized dashboards because they are overwritten during the installation.

1. Save the .pak file in a temporary folder.
2. Log in to vROps as an admin user.
3. Click the **Home** icon, then click the **Administration** icon in the left pane.









4. To upload the .pak file to the vROps server, on the **Solutions** tab of the right-side pane, click the Add icon.



Trend Micro Deep Security On-Premise 11.3

Solutions

Show: All Solutions

Name	Description	Version	Provided by
 VMware vSphere	Manages vSphere objects such as Clusters, H...	6.0.4635876	VMware Inc.
 VMware vRealize Log Insight	Management Pack for VMware vRealize Log I...	6.0.4527690	VMware Inc.
 Trend Micro DSM Adapter	The Trend Micro vRealize Management Pack f...	6.0.3	Trend Micro
 Operating Systems / Remote Service Monitori	The End Point Operations Management Soluti...	1.0.4506154	VMware Inc.

5. In the dialog box that appears, browse to the location of the saved .pak file, then click **Upload**.

Note: The .pak file can require several minutes to upload. Status information appears in the Installation Details text box throughout the installation process.

6. Click **Next** when the upload is complete. Read the End User License Agreement (EULA), select the **I accept the terms of this agreement** checkbox to accept the terms, then click **Next**.
7. Click **Finish** when the installation process is complete.

Configure the Deep Security Management Pack in vRealize Operations

Add an instance of the Deep Security Management adapter instance and enter its Deep Security Manager user name and password to connect to Deep Security Manager. The adapter instance defines the adapter type and from where the management pack retrieves data.

1. In vROps, click the **Administration** icon.



2. In the Solutions list, select **Trend Micro DSM Adapter**.

Trend Micro Deep Security On-Premise 11.3

3. Click the **Configure** icon to open the Manage Solution dialog.



Manage Solution - Trend Micro DSM Adapter?

Adapter Type	Description	Instances	Version	Provided by	Reset Default Content
Deep Security Adapter		1	6.0.3	Trend Micro	

Instance Name ▲

<Adapter Instance name>

Instance Settings

Display Name

<Adapter Instance name>

Description

Basic Settings

Deep Security Manager Host

<Server name or IP Address>

Version

10

Port

4119

Auto Discovery

true

Credential

--Select--

Test Connection

Advanced Settings

Collectors/Groups

Default collector group

Page 1 of 1

Save Settings

Close


4. In the Manage Solution window, enter the following property values:

Trend Micro Deep Security On-Premise 11.3

- **Display Name:** A name to identify this instance of the Deep Security adapter
- **Description:** (Optional) A useful description of the adapter
- **Auto Discovery:** true
- **Deep Security Manager Host:** The server name or IP address of Deep Security Manager
- **Port:** 4119
- **Version:** The version number of Deep Security Manager (for example, 11.3)
- **Credential:** Click the Add icon.



Enter the credentials for the Deep Security User Account that you created in the ["Create a user account for vRealize Operations Manager"](#) on page 290 section:




- 5. Click the **Test Connection** button to ensure that vROps and the Deep Security Management Pack can connect to the Deep Security Manager account.
- 6. Click **Save Settings** to save the credentials.

Validate Data Collection in vRealize Operations

After adding a Deep Security adapter instance, you can validate the data that it collects within vROps.

Trend Micro Deep Security On-Premise 11.3

- 1. Select the **Environment** shortcut.
- 2. Under **Inventory Trees**, select **All Objects**, then expand the Deep Security Adapter objects list.
- 3. Select a resource from the list, then click the **Troubleshooting** tab and **All Metrics** to validate values against the data source.







Migrate from a 5.x environment

Migration is not recommended due to significant changes that were made to object definitions. However, if you must migrate from a 5.x environment, perform the following procedure:


- 1. Ensure that **Auto Discovery** is set to **False** before migrating from the 5.x version of the Deep Security Management Pack.
- 2. Remove the 5.x versions of the Deep Security dashboards after migrating.
- 3. For each Deep Security Computer and Deep Security ESXi Host, fill in the **Parent Deep Security Adapter Instance** identifier with the name of the adapter instance.
- 4. Start collection for all Deep Security resources.

Navigate Deep Security in vROps

Use the vROps Inventory Tree (TraversalSpec) to navigate your Deep Security environment. The adapter recognizes the following resource kinds:

Resource Kind	Description	Icon	Identifiers
Deep Security Adapter Instance	Your configured adapter instance for the Management Pack		Deep Security Manager Host Version Port Auto Discovery
Deep Security ESXi Host	ESXi Host monitored by Deep Security		Deep Security ID Virtual Machine Uuid Virtual Machine Moid
Deep Security Computer	Server monitored by Deep Security		Deep Security ID Virtual Machine Uuid Virtual Machine Moid
DSM - Tags	Used for creating tags related to Trend Micro Deep Security Manager systems		N/A

The hierarchical structure shows relationships among resource kinds and enables you to drill down to root-cause issues.



Dashboards


Dashboards are the primary user interface for monitoring and troubleshooting Deep Security issues in vROps. The following custom dashboards are available in the management pack:

- ["Deep Security Top 10 Analysis" below](#)
- ["Deep Security Troubleshooting" on the next page](#)
- ["Deep Security Total Event Count Heat Map" on page 305](#)

To see the Deep Security dashboards in vROps, go to **Dashboard List > Trend Micro**.


Deep Security Top 10 Analysis

This dashboard displays the top 10 resources by total event count for key performance metrics (KPIs).




Deep Security Troubleshooting

This dashboard displays health information regarding Deep Security resources in a relationships view as well as KPIs for the selected Deep Security resource.



Deep Security Total Event Count Heat Map

This dashboard displays at-a-glance data regarding all Deep Security Manager events, using heat maps and event breakdown charts.



Metrics

The Management Pack collects data for the following metrics for Deep Security resource kinds.

Trend Micro Deep Security On-Premise 11.3

Metric Name	Type	Description
Intrusion Prevention Event Count	integer	Number of Intrusion Prevention Events recorded
Firewall Event Count	integer	Number of Firewall Events recorded
Integrity Monitoring Event Count	integer	Number of Integrity Events recorded
Log Inspection Event Count	integer	Number of Log Inspection Events recorded
Total Event Count	integer	Number of Total Events recorded
Anti-Malware Event Count	integer	Number of Anti-Malware Events recorded
Web Reputation Event Count	integer	Number of Web Reputation Events recorded

Alerts, Symptoms, and Recommendations

The Management Pack creates alerts and provides recommended actions based on various symptoms that it detects in the environment. The table below provides details about each alert.

Name	Description or Symptom	Recommendation
alert_Abnormal_Restart_Detected	Abnormal Restart Detected	An abnormal restart was detected on the computer. This event can have many causes. If you suspect that the agent or appliance is the root cause, invoke the diagnostics package (located in the Support section of the Computer Details dialog).
alert_Activation_Failed	Activation Failed	The agent or appliance could not be activated. Check the affected computers.
alert_A_Deep_Security_Relay_cannot_download_security_components	A Deep Security Relay cannot download security components	A Deep Security Relay can't successfully download security components. This might be due to network connectivity issues or misconfigurations in Deep Security Manager under Administration > System Settings > Updates . Check your network configurations (for example, the proxy settings of the relay group) and System Settings , and then manually initiate an update on the relay using the Download Security Update option on the Administration > Updates > Software page.
alert_Agent_configuration_package_too_large	Agent configuration package too large	This alert is usually caused by too many firewall and intrusion prevention rules being assigned. Run a recommendation scan on the computer to determine whether any rules can be safely unassigned.
alert_Agent_Installation_Failed	Agent Installation Failed	The agent failed to install successfully on one or more computers. The computers are currently unprotected. Reboot the computers to automatically install the agent.
alert_Agent_Upgrade_Recommended_Incompatible_with_Appliance	Agent Upgrade Recommended (Incompatible with Appliance)	A computer is running a version of the agent that is not compatible with the appliance. In this situation, the appliance filters network traffic, resulting in redundant protection.
alert_Agent_Appliance_Upgrade_Recommended	Agent or Appliance Upgrade Recommended	A computer is running an older version of the agent or appliance that does not support all available features. An upgrade of the agent or appliance software is recommended.

Trend Micro Deep Security On-Premise 11.3

Name	Description or Symptom	Recommendation
alert_Agent_Appliance_Upgrade_Recommended_Incompatible_Security_Updates	Agent or Appliance Upgrade Recommended (Incompatible Security Update(s))	A computer is running a version of the agent or appliance that is not compatible with one or more security updates assigned to it. An upgrade of the agent or appliance software is recommended.
alert_Agent_Appliance_Upgrade_Recommended_New_Version_Available	Agent or Appliance Upgrade Recommended (New Version Available)	One or more computers is running a version of the agent or appliance that is older than the latest version imported into the manager. An upgrade of the agent or appliance software is recommended.
alert_Agent_Appliance_Upgrade_Required	Agent or Appliance Upgrade Required	A computer is running a version of the agent or appliance that is not compatible with this version of the manager. Upgrade of the agent or appliance software.
alert_An_update_to_the_Rules_is_available	An update to the Rules is available	A rules update is available. Go to Administration > Updates > Security > Rules and reapply the most recently applied rule update. If you do not reapply the rule update now, the new features in the update will be applied with the application of the next rule update.
alert_Anti-Malware_Alert	Anti-Malware Alert	A malware scan configuration has raised an alert on one or more computers.
alert_Anti-Malware_Component_Failure	Anti-Malware Component Failure	An anti-malware component failed on one or more computers. See the event descriptions on the individual computers for specific details.
alert_Anti-Malware_Component_Update_Failed	Anti-Malware Component Update Failed	One or more agents or relays failed to update its anti-malware components. See the affected computers for more information.
alert_Anti-Malware_Engine_Offline	Anti-Malware Engine Offline	The agent or appliance has reported that the anti-malware engine is not responding. Check the system events for the computer to determine the cause of the failure.
alert_Anti-Malware_protection_is_absent_or_out_of_date	Anti-Malware protection is absent or out of date	The agent on this computer has not received its initial anti-malware protection package, or its anti-malware protection is out of date. Make sure a relay is available and that the agent is configured to communicate with it. To configure relays and other update options go to Administration > System Settings > Updates .
alert_Anti-Malware_Quarantine_Alert_for_Storage_Limit	Anti-Malware Quarantine Alert for Storage Limit	Anti-malware failed to quarantine a file because the storage limit has been reached.
alert_Application_Type_Misconfiguration	Application Type Misconfiguration	Misconfiguration of application types can prevent proper security coverage. Review the system events for details.
alert_Application_Type_Recommendation	Application Type Recommendation	A computer on the network should be assigned an application type due to one of the following scenarios:

Trend Micro Deep Security On-Premise 11.3

Name	Description or Symptom	Recommendation
		<ul style="list-style-type: none">• An agent was installed on a new computer and vulnerable applications were detected.• A new vulnerability was discovered in an installed application that was previously thought to be safe. <p>To assign the application type to the computer, open the Computer Details dialog box, click Intrusion Prevention Rules and assign the Application Type.</p>
alert_Certified_Safe_Software_Service_Offline	Certified Safe Software Service Offline	A Deep Security Manager node cannot connect to the Trend Micro Certified Safe Software Service to perform file signature comparisons for the integrity monitoring module. A locally-cached database will be used until connectivity is restored. Make sure the manager node has Internet connectivity and that proxy settings (if used) are correct.
alert_Clock_Change_Detected	Clock Change Detected	A clock change has been detected. Unexpected clock changes may indicate a problem on the computer and should be investigated before the alert is dismissed.
alert_Communications_Problem_Detected	Communications Problem Detected	A communications problem has been detected. Communications problems indicate that the computer cannot initiate communication with the Deep Security Manager(s) due to network configuration or load issues. Check the system events and verify that communications can be established to the Deep Security Manager(s). The cause of the problem should be investigated before the alert is dismissed.
alert_Computer_Not_Receiving_Updates	Computer Not Receiving Updates	One or more computers have stopped receiving updates. Manual intervention may be required.
alert_Computer_Reboot_Required	Computer Reboot Required	An agent software upgrade was successful but the computer must be rebooted to complete the install. Reboot the computer before you dismiss the alert.
alert_Computer_Reboot_Required_for_Anti-Malware_Protection	Computer Reboot Required for Anti-Malware Protection	The anti-malware protection on the agent indicates that the computer needs to be rebooted. Please check the system events for the computer to determine the reason for the reboot.
alert_Configuration_Required	Configuration Required	One or more computers are using a policy that defines multiple interface types and not all interfaces have been mapped.
alert_Connection_to_Filter_Driver_Failure	Connection to Filter Driver Failure	An appliance failed to connect to the filter driver. This may indicate a configuration issue with the filter driver running on the ESXi or with the appliance. The appliance must connect to the filter driver to protect guests. Investigate and resolve the cause of the issue.
alert_CPU_Critical_Threshold_Exceeded	CPU Critical Threshold Exceeded	The CPU critical threshold has been exceeded.
alert_CPU_Warning_Threshold_Exceeded	CPU Warning Threshold Exceeded	The CPU warning threshold has been exceeded.
alert_Duplicate_Computer_Detected	Duplicate Computer Detected	A duplicate computer has been activated or imported. Remove the duplicate computer and, if necessary, reactivate the original computer.
alert_Duplicate_	Duplicate Unique Identifiers	Consult "Configure the vCenter database to assign unique UUIDs to new virtual machines" on page 327 and VM BIOS UUIDs are not unique when virtual

Trend Micro Deep Security On-Premise 11.3

Name	Description or Symptom	Recommendation
Unique_Identifiers_Detected	Detected	machines are deployed from vApp templates for information about troubleshooting duplicate UUIDs.
alert_Empty_Relay_Group_Assigned	Empty Relay Group Assigned	These computers have been assigned an empty relay group. Assign a different relay group or add relays to the empty relay group.
alert_Events_Suppressed	Events Suppressed	The agent or appliance encountered a high volume of events. As a result, one or more events were suppressed (not recorded) to prevent a potential denial of service. Check the firewall events to determine the cause of the suppression.
alert_Events_Truncated	Events Truncated	Some events were lost because the data file grew too large for the agent or appliance to store. The cause can be an unexpected increase in the number of events or the inability of the agent or appliance to send the data to Deep Security Manager. For more information see the properties of the events truncated system event on the computer.
alert_Firewall_Engine_Offline	Firewall Engine Offline	The firewall engine is offline. Check the status of the engine on the agent or appliance.
alert_Firewall_Rule_Alert	Firewall Rule Alert	A firewall rule raised an alert on one or more computers.
alert_Firewall_Rule_Recommendation	Firewall Rule Recommendation	A computer on your network should be assigned a firewall rule. Either an agent was installed on a new computer and vulnerable applications were detected, or a new vulnerability was discovered in an installed application that was previously thought to be safe. To assign the firewall rule to the computer, open the Computer Details dialog box, click the Firewall Rules node and assign the firewall rule.
alert_Heartbeat_Server_Failed	Heartbeat Server Failed	The heartbeat server failed to start properly. A port conflict can cause this problem. Agents or appliances will not be able to contact the Manager until this problem is resolved. Ensure that another service is not using the port reserved for use by the heartbeat server and restart the Deep Security Manager service. If you do not want to use the heartbeat, turn this alert off in the Alert Configuration section.
alert_Incompatible_Agent_Appliance_Version	Incompatible Agent or Appliance Version	The version of the agent or appliance on the computer is more recent than the version of the manager and is not compatible. Upgrade the manager software.
alert_Insufficient_Disk_Space	Insufficient Disk Space	The agent or appliance was forced to delete an old log file to free up disk space for a new log file. Immediately free up disk space to prevent loss of intrusion prevention, firewall, and agent or appliance events.
alert_Integrity_Monitoring_Engine_Offline	Integrity Monitoring Engine Offline	The agent or appliance has reported that the integrity monitoring engine is not responding. Check the system events for the computer to determine the cause of the problem.
alert_Integrity_Monitoring_information_collection_has_been_delayed	Integrity Monitoring information collection has been delayed	The collection of integrity monitoring information is delayed due to an increase of integrity monitoring data. During this time, the baseline and Integrity Event views may not be current for some computers. This alert will be dismissed automatically when integrity monitoring data collection is no longer delayed.
alert_Integrity_Monitoring_Rule_Alert	Integrity Monitoring Rule Alert	An integrity monitoring rule produced an alert on one or more computers.
alert_Integrity_	Integrity Monitoring Rule	An error was encountered when compiling an integrity monitoring rule on a computer. The rule might not operate as expected.

Trend Micro Deep Security On-Premise 11.3

Name	Description or Symptom	Recommendation
Monitoring_Rule_Compilation_Error	Compilation Error	
alert_Integrity_Monitoring_Rule_Recommendation	Integrity Monitoring Rule Recommendation	A computer on your network should be assigned an integrity monitoring rule. To assign the integrity monitoring rule to the computer, open the Computer Details dialog box, click the Integrity Monitoring > Integrity Monitoring Rules node and assign the integrity monitoring rule.
alert_Integrity_Monitoring_Rule_Requires_Configuration	Integrity Monitoring Rule Requires Configuration	An integrity monitoring rule that requires configuration before use has been assigned to one or more computers. This rule will not be sent to the computer(s). Open the integrity monitoring rule properties and select the Configuration tab for more information.
alert_Integrity_Monitoring_Trusted_Platform_Module_Not_Enabled	Integrity Monitoring Trusted Platform Module Not Enabled	Ensure that the hardware is installed and the BIOS setting is correct.
alert_Integrity_Monitoring_Trusted_Platform_Module_Register_Value_Changed	Integrity Monitoring Trusted Platform Module Register Value Changed	If you did not modify the ESXi hypervisor configuration, this alert can indicate an attack.
alert_Intrusion_Prevention_Engine_Offline	Intrusion Prevention Engine Offline	The intrusion prevention engine is offline. Check the status of the engine on the agent or appliance.
alert_Intrusion_Prevention_Rule_Alert	Intrusion Prevention Rule Alert	An intrusion prevention rule raised an alert on one or more computers.
alert_Intrusion_Prevention_Rule_Recommendation	Intrusion Prevention Rule Recommendation	A computer on your network should be assigned a intrusion prevention rule. Either an agent was installed on a new computer and vulnerable applications were detected, or a new vulnerability was discovered in an installed application that was previously thought to be safe. To assign the intrusion prevention rule to the computer, open the Computer Details dialog box, click Intrusion Prevention Rules and assign the rule.
alert_Intrusion_Prevention_Rule_Removal_Recommendation	Intrusion Prevention Rule Removal Recommendation	A computer on your network has an intrusion prevention rule assigned to it that is not required. Either a vulnerable application was uninstalled, an existing vulnerability was patched, or the rule was assigned unnecessarily. To unassign the intrusion prevention rule from the computer, open the Computer Details dialog box click Intrusion Prevention > Intrusion Prevention Rules .
alert_Intrusion_Prevention_Rule_Requires_Configuration	Intrusion Prevention Rule Requires Configuration	An intrusion prevention rule that requires configuration before use has been assigned to one or more computers. This rule will not be sent to the computer (s). Open the intrusion prevention rule properties and select the Configuration tab for more information.
alert_Log_Inspection_Engine_Offline	Log Inspection Engine Offline	The log inspection engine has failed to initialize. Check the system events for the computer to determine the cause of the failure.

Trend Micro Deep Security On-Premise 11.3

Name	Description or Symptom	Recommendation
alert_Log_Inspection_Rule_Alert	Log Inspection Rule Alert	A log inspection rule that is configured to produce alerts has been encountered on one or more computers.
alert_Log_Inspection_Rule_Recommendation	Log Inspection Rule Recommendation	A computer on your network should be assigned a log inspection rule. To assign the log inspection rule to the computer, open the Computer Details dialog box, click the Log Inspection > Log Inspection Rules node, and assign the log inspection rule.
alert_Log_Inspection_Rule_Requires_Configuration	Log Inspection Rule Requires Configuration	A log inspection rule that requires configuration before use has been assigned to one or more computers. This rule will not be sent to the computer(s). Open the log inspection rule properties and select the Configuration tab for more information.
alert_Low_Disk_Space	Low Disk Space	A Deep Security Manager node has less than 10% remaining disk space. Delete old or unnecessary files or add more storage capacity.
alert_Manager_Offline	Manager Offline	A Deep Security Manager node is offline. Either the computer has experienced a hardware or software problem, or it lost network connectivity. Check the status of the manager computer.
alert_Manager_Time_Out_of_Sync	Manager Time Out of Sync	The clock on each manager computer must be synchronized with the clock on the database. If the clocks are more than 30 seconds out of sync the manager does not function correctly. Synchronize the clock on the manager with the clock on the database.
alert_Memory_Critical_Threshold_Exceeded	Memory Critical Threshold Exceeded	The memory critical threshold has been exceeded.
alert_Memory_Warning_Threshold_Exceeded	Memory Warning Threshold Exceeded	The memory warning threshold has been exceeded.
alert_Multiple_Activated_Appliances_Detected	Multiple Activated Appliances Detected	Multiple connections have been made to the filter driver on the same ESXi. There may be multiple activated appliances running on the same ESXi, which is not supported. Investigate the cause of the problem before you dismiss the alert.
alert_Network_Engine_Mode_Incompatibility	Network Engine Mode Incompatibility	Setting Network Engine Mode to Tap is only available on agent versions 5.2 or higher. Review and update the agent's configuration or upgrade the agent.
alert_New_Pattern_Update_is_Downloaded_and_Available	New Pattern Update is Downloaded and Available	New patterns are available as part of a security update. The patterns have been downloaded to Deep Security Manager but have not yet applied to your computers. To apply the update to your computers go to the Administration > Updates > Security page.
alert_New_Rule_Update_is_Downloaded_and_Available	New Rule Update is Downloaded and Available	New rules are available as part of a security update. The rules have been downloaded to Deep Security Manager but have not yet been applied to policies and sent to your computers. To apply the update and send the updated policies to your computers go to the Administration > Updates > Security page.
alert_Newer_Version_of_Deep_Security_Manager_is_Available	Newer Version of Deep Security Manager is Available	A new version of Deep Security Manager is available. Download the latest version from the Trend Micro Download Center at http://downloadcenter.trendmicro.com .
alert_Newer_Versions_	Newer Versions of Software	New software is available. Software can be downloaded from the Download Center.

Trend Micro Deep Security On-Premise 11.3

Name	Description or Symptom	Recommendation
of_Software_Available	Available	
alert_Number_of_Computers_exceeds_database_limit	Number of Computers exceeds database limit	The number of activated computers has exceeded the recommended limit for an embedded database. Performance will degrade rapidly if more computers are added. Consider another database option (Oracle or SQL Server). Contact Trend Micro for more information about upgrading your database.
alert_Protection_Module_Licensing_Expired	Protection Module Licensing Expired	The protection module license has expired.
alert_Protection_Module_Licensing_Expires_Soon	Protection Module Licensing Expires Soon	The protection module licensing will expire soon. Change your license on the Administration > Licenses page.
alert_Recommendation	Recommendation	The security configuration of one of your computers should be updated. To see what changes are recommended, open the computer's editor window and look through the module pages for warnings of unresolved recommendations. In the Assigned Rules area click Assign/Unassign... to display the list of available rules. Filter the rules using the Show Recommended for Assignment filter .
alert_Reconnaissance_Detected_Computer_OS_Fingerprint_Probe	Reconnaissance Detected: Computer OS Fingerprint Probe	An attempt to identify the computer operating system via a fingerprint probe was detected. Such activity is often a precursor to an attack that targets specific vulnerabilities. Check the computer's events to see the details of the probe.
alert_Reconnaissance_Detected_Network_or_Port_Scan	Reconnaissance Detected: Network or Port Scan	The agent or appliance detected network activity typical of a network or port scan. Such activity is often a precursor to an attack that targets specific vulnerabilities. Check the computer's events to see the details of the scan.
alert_Reconnaissance_Detected_TCP_Null_Scan	Reconnaissance Detected: TCP Null Scan	The agent or appliance detected a TCP Null scan. Such activity is often a precursor to an attack that targets specific vulnerabilities. Check the computer's events to see the details of the scan.
alert_Reconnaissance_Detected_TCP_SYNFIN_Scan	Reconnaissance Detected: TCP SYNFIN Scan	The agent or appliance detected a TCP SYNFIN scan. Such activity is often a precursor to an attack that targets specific vulnerabilities. Check the computer's events to see the details of the scan.
alert_Reconnaissance_Detected_TCP_Xmas_Scan	Reconnaissance Detected: TCP Xmas Scan	The agent or appliance detected a TCP Xmas scan. Such activity is often a precursor to an attack that targets specific vulnerabilities. Check the computer's events to see the details of the scan.
alert_Scheduled_Malware_Scan_Missed	Scheduled Malware Scan Missed	Scheduled malware scan tasks were initiated on computers that already have pending scan tasks. The scanning frequency might be too high. Either lower the scanning frequency or scan fewer computers during each scheduled scan job.
alert_Send_Policy_Failed	Send Policy Failed	Inability to send a policy may indicate a problem with the agent or appliance. Please check the affected computers.
alert_Smart_Protection_Server_Connection_Failed	Smart Protection Server Connection Failed	Failed to connect to a smart protection server. This could be due to a configuration issue or due to network connectivity.

Trend Micro Deep Security On-Premise 11.3

Name	Description or Symptom	Recommendation
Connection_Failed		
alert_Software_Package_Not_Found	Software Package Not Found	An agent software package is required for the proper operation of one or more virtual appliances. Import a Red Hat Enterprise 6 (64 bit) agent Software Package with the correct version for each appliance. If the required version is not available, import the latest package and upgrade the appliance accordingly.
alert_Software_Updates_Available_for_Import	Software Updates Available for Import	New software is available. To import new software, go to Administration > Updates > Software > Download Center .
alert_Unable_to_communicate	Unable to communicate	Deep Security Manager has been unable to query the agent or appliance for its status within the configured period. Please check your network configuration and the affected computer's connectivity.
alert_Unable_to_Upgrade_the_Agent_Software	Unable to Upgrade the Agent Software	Deep Security Manager was unable to upgrade the agent software on the computer.
alert_Upgrade_of_the_Deep_Security_Manager_Software_Recommended_Incompatible_Security_Updates	Upgrade of the Deep Security Manager Software Recommended (Incompatible Security Update(s))	Deep Security Manager has detected a computer that is using security updates that are not compatible with the current version of Deep Security Manager. An upgrade of Deep Security Manager software is recommended.
alert_Upgrade_of_the_Filter_Driver_Recommended_New_Version_Available	Upgrade of the Filter Driver Recommended (New Version Available)	The filter driver that one or more ESXi servers uses is not the latest available version. An upgrade of the Filter Driver is recommended.
alert_User_Locked_Out	User Locked Out	Users can be manually locked out either from repeated sign-in attempts, their password expires, or they have been imported but not yet unlocked.
alert_User_Password_Expires_Soon	User Password Expires Soon	The password expiry setting is enabled and one or more users have passwords that will expire within the next 7 days.
alert_Virtual_Appliance_is_Incompatible_With_Filter_Driver	Virtual Appliance is Incompatible With Filter Driver	The appliance is incompatible with the filter driver. Ensure both are upgraded to their latest versions.
alert_Virtual_Machine_Interfaces_Out_of_Sync	Virtual Machine Interfaces Out of Sync	The interfaces of one or more of the virtual machines that are monitored by a Deep Security virtual appliance are out of sync with the filter driver. The appliance may not be properly monitoring the virtual machine's interfaces. The virtual machine may require manual intervention, such as a configuration change or a restart, to correct the issue.
alert_Virtual_Machine_Moved_to	Virtual Machine Moved to Unprotected ESXi Server	A virtual machine was moved to an ESXi server that does not have an activated Deep Security virtual appliance.

Name	Description or Symptom	Recommendation
Unprotected_ESXi_Server		
alert_Virtual_Machine_Unprotected_after_move_to_another_ESXi	Virtual Machine Unprotected after move to another ESXi	A virtual machine that was protected by an appliance has been unprotected while or after it was moved to another ESXi. This may be due to an appliance reboot or power off during the move or it may indicate a configuration issue. The cause of the issue should be investigated before the alert is dismissed.
alert_VMware_Tools_Not_Installed	VMware Tools Not Installed	A protected virtual machine in an NSX environment does not have VMware Tools installed. VMware Tools is required to protect virtual machines in an NSX environment.
alert_Web_Reputation_Event_Alert	Web Reputation Event Alert	A web reputation event has occurred on one or more computers.

Configure NSX security tags

If you are using agentless protection, you can configure Deep Security Virtual Appliance to apply NSX security tags to protected VMs when the Anti-Malware and Intrusion Prevention (IPS) modules detect a threat. NSX security tags can be used with NSX Service Composer to automate certain tasks, such as quarantining infected VMs. For more information on NSX tagging and dynamic NSX security group assignment, see the documentation from VMware.

Note: VMware NSX security tags are *not* the same thing as Deep Security event tags. NSX tagging occurs in the VMware vSphere environment; Deep Security event tags are in the Deep Security database.

Topics on this page:

- ["Configure Anti-Malware to apply NSX security tags" below](#)
- ["Configure Intrusion Prevention to apply NSX security tags" on page 317](#)

Configure Anti-Malware to apply NSX security tags

To configure the Anti-Malware module to apply NSX security tags when malware is found:

Trend Micro Deep Security On-Premise 11.3

1. Go to **Computer or Policy editor**¹ > Anti-Malware > Advanced > NSX Security Tagging.
2. Select **On** to enable the feature.
3. From the **NSX Security Tag** drop-down list, select the name of the NSX security tag that assigned in NSX when malware is found. Options are:
 - ANTI_VIRUS.VirusFound.threat=low
 - ANTI_VIRUS.VirusFound.threat=medium
 - ANTI_VIRUS.VirusFound.threat=high

For example, if you choose **ANTI_VIRUS.VirusFound.threat=low**, then an NSX security tag called `ANTI_VIRUS.VirusFound.threat=low` is assigned to the VM if malware is found on the VM. The tag name is not related to the threat level of the malware, so the 'low' tag is applied even if the malware poses a high threat (and vice versa).

4. Optionally, select **Apply NSX Security Tag only if remediation action fails** if you only want to apply the NSX security tag if the remediation action attempted by the Anti-Malware module fails. (The remediation action is determined by the malware scan configuration that is in effect. To see which malware scan configuration is in effect, go to the **Computer or Policy editor**² > Anti-Malware > **General** tab and check the **Real-Time Scan**, **Manual Scan**, and **Scheduled Scan** areas.)
5. Optionally, select **Remove previously applied NSX Security Tags if subsequent Malware Scans complete without any malware detection events**. Choose this option if you want to have the security tag removed if a subsequent malware scan does not detect any malware. You should only use this setting if all malware scans are of the same kind.
6. Click **Save**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Configure Intrusion Prevention to apply NSX security tags

To configure the Intrusion Prevention module to apply NSX security tags, go to **Computer or Policy editor**¹ > Intrusion Prevention > Advanced > NSX Security Tagging.

Intrusion Prevention events have a severity level that is determined by the severity level of the Intrusion Prevention rule that triggered the event. To configure the severity level of an Intrusion Prevention rule, go to **Computer or Policy editor**² > Intrusion Prevention > General > Assigned Intrusion Prevention Rules and double-click a rule. Change the **Severity** field as required.

Intrusion Prevention rule severity levels map to NSX tags as follows:

IPS Rule Severity	NSX Security Tag
Critical	IDS_IPS.threat=high
High	IDS_IPS.threat=high
Medium	IDS_IPS.threat=medium
Low	IDS_IPS.threat=low

You can configure the sensitivity of the tagging mechanism by specifying the minimum Intrusion Prevention severity level that can cause an NSX security tag to be applied to a VM.

The options for the **Minimum rule severity to trigger application of an NSX Security Tag** setting are:

- **Default (No Tagging):** No NSX tag is applied.
- **Critical:** An NSX tag is applied to the VM if an Intrusion Prevention rule with a severity level of **Critical** is triggered.
- **High:** An NSX tag is applied to the VM if an Intrusion Prevention rule with a severity level of **High** or **Critical** is triggered.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

- **Medium:** An NSX tag is applied to the VM if an Intrusion Prevention rule with a severity level of **Medium**, **High**, or **Critical** is triggered.
- **Low:** An NSX tag is applied to the VM if an Intrusion Prevention rule with a severity level of **Low**, **Medium**, **High**, or **Critical** is triggered.

Separate settings exist for rules in prevent mode vs. detect-only mode. For information about behavior modes, see ["Use behavior modes to test rules" on page 726](#).

Install the agents

Get Deep Security Agent software

To install Deep Security Agent, you must download the agent installer and load packages for the agent's protection modules into Deep Security Manager. To view a list of software that has been imported into Deep Security Manager, go to **Administration > Updates > Software > Local**.

Deep Security is modular. Initially, Deep Security Agent only has core functionality. When you enable a protection module, then the agent downloads that plug-in and installs it. So before you activate any agents, first download the agent software packages into Deep Security Manager's database("import" them) so that they will be available to the agents and relays.

Warning: Even if you use a third party deployment system, you **must** import all installed Deep Security Agent software into the Deep Security Manager's database. When a Deep Security Agent is first activated, it only installs protection modules that are currently enabled in the security policy. If you enable a new protection module later, Deep Security Agent will try to download its plug-in from Deep Security Manager. If that software is missing, the agent may not be able to install the protection module.

Once you import the agent installer package, depending on your preferred deployment method, you can then export and load the installers into a third party deployment system such as Ansible, Chef, or Puppet which will install it on your computers.

Download agent software packages into Deep Security Manager

Even if you don't use Deep Security Manager to deploy agent updates, you should still import the software into the Deep Security Manager's database. You can do this manually or automatically.

Trend Micro Deep Security On-Premise 11.3

Automatically import software updates

You can configure Deep Security Manager to automatically download any updates to software that you've already imported into Deep Security. To enable this feature, go to **Administration > System Settings > Updates** and select **Automatically download updates to imported software**.

Note: This setting will download the software to the Deep Security but will *not* automatically update your agent or appliance software. Continue with ["Update the Deep Security Agent" on page 984](#).

Manually import software updates

You can manually import software updates as they become available on the Download Center.

1. In Deep Security Manager, go to **Administration > Updates > Software > Download Center**.

The Trend Micro Download Center displays the latest versions of agent software.

2. To download your agent software package to the manager's local storage, select the installer from the list, and then click **Import**.

Deep Security Manager connects to the internet to download the software from Trend Micro. When the manager has finished, a green check mark will appear in the **Imported** column for that agent. Software packages will appear on **Administration > Updates > Software > Local**.

If a package cannot be imported directly, a popup note will indicate that. For these packages, download them from the Trend Micro Download Center website to a local folder, then go to **Administration > Updates > Software > Local** and manually import them.

Tip: Alternatively, if your Deep Security Manager is "air-gapped" (not connected to the Internet) and cannot connect *directly* to the Download Center web site, you can load them *indirectly*. Download the ZIP packages to your management computer first, and then log into the Deep Security Manager and upload them.

Export the agent installer

You can download the agent installer from Deep Security Manager.

Trend Micro Deep Security On-Premise 11.3

1. In Deep Security Manager, go to **Administration > Updates > Software > Local**.
2. Select your agent from the list.
3. Click **Export > Export Installer**.

If you have older versions, the latest version of the software will have a green check mark in the **Is Latest** column.

4. Save the agent installer. If you will install the agent manually, save it on the computer where you want to install Deep Security Agent. Otherwise, if you use a third party deployment system (such as Ansible, Chef, Puppet, PowerShell, or others), load the agent installer into that system.

Tip: To install Deep Security Agent, only use the exported agent installer (the .msi or the .rpm file) - *not* the full agent ZIP package. If you run the agent installer from the same folder that holds the other zipped agent components, all protection modules will be installed, even if you haven't enabled them on the computer. This consumes extra disk space. (For comparison, if you use the .msi or .rpm file, the agent will download and install protection modules *only if your configuration requires them*.)

Tip: Installing an agent, activating it, and applying protection with a security policy can be done using a command line script. For more information, see ["Use deployment scripts to add and protect computers" on page 437](#).

Delete a software package from the Deep Security database

To save disk space, Deep Security Manager will periodically remove unused packages from the Deep Security database. To configure the maximum number of old packages kept, go to **System Settings > Storage**.

Note: Deep Security Virtual Appliance uses protection module plug-ins in the 64-bit Red Hat Enterprise Linux Agent software package. Therefore if you have an activated Deep Security Virtual Appliance, and try to delete the 64-bit Red Hat Enterprise Linux Agent software package from the database, an error message will tell you that the software is in use.

There are two types of packages that can be deleted:

Trend Micro Deep Security On-Premise 11.3

- agent
- kernel support

Deleting agent packages in single-tenancy mode

In single tenancy mode, Deep Security automatically deletes agent packages (*Agent-platform-version.zip*) that are not currently being used by agents. Alternatively, you can manually delete unused agent packages. Only unused software packages can be deleted.

Note: For the Windows and Linux agent packages, only the currently used package (whose version is the same as the agent installer) cannot be deleted.

Deleting agent packages in multi-tenancy mode

In multi-tenancy mode, unused agent packages (*Agent-platform-version.zip*) are **not** deleted automatically. For privacy reasons, Deep Security cannot determine whether software is currently in use by your tenants, even though you and your tenants share the same software repository in the Deep Security database. As the primary tenant, Deep Security does not prevent you from deleting software that is not currently running on any of your own account's computers, but before deleting a software package, be very sure that no other tenants are using it.

Deleting kernel support packages

In both single and multi-tenancy mode, Deep Security automatically deletes unused kernel support packages (*KernelSupport-platform-version.zip*). A kernel support package can be deleted if both of these conditions are true:

- No agent package has the same group identifier.
- Another kernel support package has the same group identifier and a later build number.

You can also manually delete unused kernel support packages. For Linux kernel support packages, only the latest one cannot be deleted.

Manually install the Deep Security Agent

Tip: For easier agent installation and activation, use a deployment script instead. For more information, see ["Use deployment scripts to add and protect computers" on page 437](#).

Before installing the Deep Security Agent, you must import the software into Deep Security Manager and export the installer. See ["Get Deep Security Agent software" on page 318](#).

After installation, the agent must be activated before it can protect its computer or be converted into a relay. See ["Activate the agent" on page 370](#).

In this topic:

- ["Install a Windows agent" below](#)
- ["Install a Red Hat, SUSE, Oracle Linux, or Cloud Linux agent" on page 324](#)
- ["Install an Ubuntu or Debian agent" on page 324](#)
- ["Install the agent on a Microsoft Azure VM" on page 325](#)

Install a Windows agent

1. Copy the installer file to the computer.
2. Double-click the installation file (.MSI file) to run the installer package.

Note: On Windows Server 2012 R2 Server Core, launch the installer using this command instead: `msiexec /i Agent-Core-Windows-11.3.x-xxxx.x86_64.msi`

3. At the Welcome screen, click **Next** to begin the installation.
4. **End-User License Agreement:** If you agree to the terms of the license agreement, select **I accept the terms of the license agreement** and click **Next**.
5. **Destination Folder:** Select the location where you would like Deep Security Agent to be installed and click **Next**.

Trend Micro Deep Security On-Premise 11.3

6. **Ready to install Trend Micro Deep Security Agent:** Click **Install** to proceed with the installation.
7. **Completed:** when the installation has completed successfully, click **Finish**.

The Deep Security Agent is now installed and running on this computer, and will start every time the machine boots.

Note: When installing the agent on Windows 2012 Server Core, the notifier will not be included.

Note: During an install, network interfaces will be suspended for a few seconds before being restored. If you are using DHCP, a new request will be generated, potentially resulting in a new IP address for the restored connection.

Installation on Amazon WorkSpaces

- If you are unable to install Deep Security Agent .msi file due to error code '2503' then you must do one of the following:
 - Edit your C:\Windows\Temp folder and allow the write permission for your userOR
- Open the command prompt as an administrator and run the .msi file

Note: Amazon has fixed this issue for newly-deployed Amazon WorkSpaces.

Installation on Windows 2012 Server Core

- Deep Security does not support switching the Windows 2012 server mode between Server Core and Full (GUI) modes after the Deep Security Agent is installed.
- If you are using Server Core mode in a Hyper-V environment, you will need to use Hyper-V Manager to remotely manage the Server Core computer from another computer. When the Server Core computer has the Deep Security Agent installed and Firewall enabled, the Firewall will block the remote management connection. To manage the Server Core computer remotely, turn off the Firewall module.
- Hyper-V provides a migration function used to move a guest VM from one Hyper-V server to another. The Deep Security Firewall module will block the connection between Hyper-V servers, so you will need to turn off the Firewall module to use the migration function.

Trend Micro Deep Security On-Premise 11.3

Install a Red Hat, SUSE, Oracle Linux, or Cloud Linux agent

1. Copy the installer file to the computer.
2. Install the agent.

```
# sudo rpm -i <package name>

Preparing... ##### [100%]

1:ds_agent ##### [100%]

Loading ds_filter_im module version ELx.x [ OK ]

Starting ds_agent: [ OK ]
```

To upgrade from a previous install, use "rpm -U" instead. This will preserve your profile settings.

The Deep Security Agent will start automatically upon installation.

Install an Ubuntu or Debian agent

1. Go to **Administration > Updates > Software > Download Center**.
2. Import the agent package into Deep Security Manager.
3. , and then export the installer (.deb file).
4. Copy the installer file to the computer.
5. Install the agent.

```
sudo dpkg -i <installer file>
```

To start, stop, or reset the agent:

Trend Micro Deep Security On-Premise 11.3

- **Start:** `/etc/init.d/ds_agent start`
- **Stop:** `/etc/init.d/ds_agent stop`
- **Reset:** `/etc/init.d/ds_agent reset`
- **Restart:** `/etc/init.d/ds_agent restart`
- **Display status:** `svcs -a | grep ds_agent`

Install the agent on a Microsoft Azure VM

To install the agent on VM instances running in the Microsoft Azure cloud, you need to deploy Deep Security Agents to them. You can do this in multiple ways:

- ["Generate and run a deployment script" below](#)
- ["Add a custom script extension to an existing virtual machine" below](#)

Generate and run a deployment script

You can generate Deep Security deployment scripts for automatically deploying agents using deployment tools such as RightScale, Chef, Puppet, and SSH.


For more information on how to do so, see ["Use deployment scripts to add and protect computers" on page 437](#).

Add a custom script extension to an existing virtual machine

You can also add a custom script extension to an existing virtual machine to deploy and activate the Deep Security Agent. To do this, navigate to your existing virtual machine in the Azure management portal and follow the steps below to upload and execute the deployment script on your Azure VM.

1. Log in to the Azure portal.
2. Switch to the preview portal, and then click the virtual machine that you want to add the custom script to.
3. In the **Settings** blade, click **Extensions**, in the **Extensions** blade, click **Add extension**, in the **New Resource** blade, select **Custom Script**, and then click **Create**.
4. In the **Add Extension** blade under **Script File (required)**, click **upload**, select the saved .ps1 deployment script, and then click **OK**.

Trend Micro Deep Security On-Premise 11.3



Install the agent on VMware vCloud

To enable vCloud integration, you must assign a minimum set of rights to the user accounts tenants will use to import their vCloud "Cloud Accounts" and you must configure the vCenter database to assign unique UUIDs to new virtual machines.

Create a minimum rights role for vCloud account tenant users

The user accounts you create in vCloud director that the Deep Security tenants will use to add their cloud accounts to their Deep Security Manager require only the **All Rights > General > Administrator View** right.

1. Log in to vCloud Director.
2. In the **System** tab, click on **Administration**.
3. In the navigation panel on the left, click on **Roles**.
4. Click the "plus" sign to create a new Role (for example, "DS_User").
5. Select the **Administrator View** right in the **All Rights > General** folder.
6. Click **OK**.

You can now assign this role to the user accounts you will give to Deep Security users to import their vCloud resources into the Deep Security Manager.

Note: When providing a Deep Security user with their credentials, you must include the IP address of the vCloud Organization and instruct them that when importing the vCloud resources into their Deep Security Manager, their username must include "@orgName". For example if the vCloud account's username is **kevin** and the vCloud

Trend Micro Deep Security On-Premise 11.3

Organization you've given the account access to is called **CloudOrgOne**, then the Deep Security user must enter **kevin@CloudOrgOne** as their username when importing the vCloud resources. (For a vCloud administrator view, use **@system**.)

Note: You can configure Deep Security Manager to use a proxy server specifically for connecting to instances being protected in Cloud Accounts. The proxy setting can be found in **Administration > System Settings > Proxies > Proxy Server Use > Deep Security Manager (Cloud Accounts)**.

Configure the vCenter database to assign unique UUIDs to new virtual machines

Deep Security requires that all protected virtual machines have unique UUIDs. Virtual machines created from a vApp template can be assigned duplicate UUIDs which can cause problems. However, you can configure your database to assign unique UUIDs to these VMs created from a template.

Note: The following information is taken from a VMware Knowledge Base article, "[BIOS UUIDs in vCloud Director are not unique when virtual machines are deployed from catalog templates \(2002506\)](#)".

To configure the database to assign unique UUIDs to new virtual machines that are created from a template, you must set the **CONFIG** table of the database, with the parameter **backend.cloneBiosUuidOnVmCopy**, to **0**.

To set this parameter in Oracle Database, launch Oracle Database Enterprise Manager and run the following commands:

Note: In this example, "VCLLOUD" is the name of the data base you created for vCloud.

```
set feedback on echo on

set linesize 120

update "VCLLOUD"."CONFIG" set VALUE = '0' where NAME='backend.cloneBiosUuidOnVmCopy';

commit;

select * from "VCLLOUD"."CONFIG" where VALUE = '0' and NAME='backend.cloneBiosUuidOnVmCopy';
```

To set this parameter in Microsoft SQL Server, launch SQL Server Management Studio and run the following commands:

Trend Micro Deep Security On-Premise 11.3

```
USE VCLLOUD
```

```
GO
```

```
update config set value = '0' where name='backend.cloneBiosUuidOnVmCopy'
```

```
select * from dbo.config where value = 0 and name='backend.cloneBiosUuidOnVmCopy';
```

When the parameter has been set, restart all cells in vCloud Director.

Note: This change does not affect previously existing virtual machines.

Enable the OVF Environment Transport for VMware Tools on your guest VMs

Enabling the OVF Environment Transport for VMware Tools on your guest VMs will expose the **guestInfo.ovfEnv** environment variable making it easier for Agents to uniquely identify their VMs to the Deep Security Manager. This will reduce the risk of VM misidentification.

1. In vCloud Director, open the VM's **Properties** screen, go the **Guest OS Customization** tab and select the **Enable guest customization** checkbox. Click **OK**.
2. In vCenter, select the same VM, open its **Properties** screen, go to the **Options** tab.
3. Click **vApp Options** and select the **Enabled** radio button. **OVF Settings** will now be exposed.
4. In **OVF Settings**, select the **VMware Tools** checkbox in the **OVF Environment Transport** area. Click **OK**.

If your VM is running, it must be restarted for the changes to take effect.

The data used by Deep Security are taken from the following properties: **vmware.guestinfo.ovfenv.vcenterid** and **vmware.guestinfo.ovfenv.vcloud.computername**.

Import computers from a VMware vCloud Organization Account

1. In the Deep Security Manager, go to the **Computers** section, right-click **Computers** in the navigation panel and select **Add vCloud Account** to display the **Add vCloud Account** wizard.
2. Enter a **Name** and **Description** of the resources you are adding. (These are only used for display purposes in the Deep Security Manager.)

Trend Micro Deep Security On-Premise 11.3

3. Enter the vCloud **Address**. (The hostname of the vCloud Director host machine.)
4. Enter your **User name** and **Password**.

Note: Your **User name** must be in the form `username@vcloudorganization`.

5. Click **Next**.
6. Deep Security Manager will verify the connection to the cloud resources and display a summary of the import action. Click **Finish**.

The VMware vCloud resources now appear in the Deep Security Manager under their own branch under **Computers** in the navigation panel.

After adding the Cloud Provider resources, you must install an agent, activate the agent, and assign a policy to the computer (see ["Manually install the Deep Security Agent" on page 322](#) or ["Use deployment scripts to add and protect computers" on page 437](#), and ["Activate the agent" on page 370](#).)

Import computers from a VMware vCloud Air Virtual data center

1. In the Deep Security Manager, go to the **Computers** section, right-click **Computers** in the navigation panel and select **Add vCloud Account** to display the **Add vCloud Account** wizard.
2. Enter a **Name** and **Description** of the VMware vCloud Air virtual data center you are adding. (These are only used for display purposes in the Deep Security Manager.)
3. Enter the **Address** of the VMware vCloud Air virtual data center.

Note: To determine the address of the VMware vCloud Air virtual data center:

- a. Log in to your VMware vCloud Air portal.
- b. On the **Dashboard** tab, click on the data center you want to import into Deep Security. This will display the **Virtual Data Center Details** information page.
- c. In the Related Links section of the **Virtual Data Center Details** page, click on **vCloud Director API URL**. This will display the full URL of the vCloud Director API.
- d. Use the hostname only (not the full URL) as the Address of the VMware vCloud Air virtual data center that you are importing into Deep Security.

Trend Micro Deep Security On-Premise 11.3

4. Enter your **User name** and **Password**.

Note: Your **User name** must be in the form `username@virtualdatacenterid`.

5. Click **Next**.
6. Deep Security Manager will verify the connection to the virtual data center and display a summary of the import action. Click **Finish**.

The VMware vCloud Air data center now appears in the Deep Security Manager under its own branch under **Computers** in the navigation panel.

After adding the Cloud Provider resources, you must install an agent, activate the agent, and assign a policy to the computer (see ["Manually install the Deep Security Agent" on page 322](#) or ["Use deployment scripts to add and protect computers" on page 437](#) and ["Activate the agent" on page 370](#).)

Install the agent on Amazon EC2 and WorkSpaces

Note: The Deep Security Agent only supports Amazon WorkSpaces Windows desktops—it does not support Linux desktops.

Read this page if you want to protect *existing* Amazon EC2 instances and Amazon WorkSpaces with Deep Security.

If instead you want to:

- launch *new* Amazon EC2 instances and Amazon WorkSpaces with the agent 'baked in', see ["Bake the agent into your AMI or Workspace bundle" on page 337](#).
- protect Amazon WorkSpaces after already protecting your Amazon EC2 instances, see instead ["Protect Amazon WorkSpaces if you already added your AWS account" on page 474](#).

To protect your existing Amazon EC2 instances and Amazon WorkSpaces with Deep Security, follow these steps:

1. ["Add your AWS accounts to Deep Security Manager" on the next page](#)
2. ["Set the communication direction" on the next page](#)
3. ["Configure the activation type" on page 332](#)

Trend Micro Deep Security On-Premise 11.3

4. ["Open ports" on page 333](#)
5. ["Deploy agents to your Amazon EC2 instances and WorkSpaces" on page 335](#)
6. ["Verify that the agent was installed and activated properly" on page 335](#)
7. ["Assign a policy" on page 336](#)

Add your AWS accounts to Deep Security Manager

You'll need to add your AWS account or accounts to Deep Security Manager. These AWS accounts contain the Amazon EC2 instances and Amazon WorkSpaces that you want to protect with Deep Security.

Follow the instructions in ["Add AWS cloud accounts" on page 455](#) to add your AWS accounts.

After adding your AWS accounts:

- your existing Amazon EC2 instances and Amazon WorkSpaces appear in Deep Security Manager. If no agent is installed on them, they appear with a **Status of Unmanaged (Unknown)** and a grey dot next to them. If an agent was already installed, they appear with a **Status of Managed (Online)** and green dot next to them.
- any new Amazon EC2 instances or Amazon WorkSpaces that you launch through AWS under this AWS account are auto-detected by Deep Security Manager and displayed in the list of computers.

Set the communication direction

You'll need to set the communication direction: either agent-initiated, manager-initiated, or bi-directional.

1. Log in to Deep Security Manager.
2. Set the communication direction following the instructions in ["Configure communication directionality" on page 346](#). Follow these guidelines:
 - **Agent/Appliance Initiated** does not require you to open inbound ports on the Amazon EC2 instance or Amazon WorkSpace, while **Bidirectional** and **Manager-Initiated** do.
 - **Agent/Appliance Initiated** is the safest option since no inbound ports need to be opened on the Amazon EC2 instance or Amazon WorkSpace.

3. If you're using Amazon WorkSpaces, and you chose to set the communication direction to **Bidirectional** or **Manager-Initiated**, [manually assign an elastic IP address to each WorkSpace](#) before proceeding with further steps on this page. This gives the WorkSpace a public IP that can be contacted by the Deep Security Manager. This is not required for EC2 instances because they already use public IP addresses. WorkSpaces use private IP addresses.


Configure the activation type

'Activation' is the process of registering an agent with a manager. You'll need to indicate whether you'll allow agent-initiated activation. If not, only manager-initiated activation is allowed.

1. Log in to Deep Security Manager.
2. Click **Administration** at the top.
3. On the left, click **System Settings**.
4. In the main pane, make sure the **Agents** tab is selected.
5. Select or deselect **Allow Agent-Initiated Activation**, noting that:
 - Agent-initiated activation does not require you to open up inbound ports to your Amazon EC2 instances or Amazon WorkSpaces, while manager-initiated activation does.
 - If agent-initiated activation is enabled, manager-initiated activation continues to work.
 - Agent-initiated activation works even if you set the communication direction to **Manager-Initiated**.
6. If you selected **Allow Agent-Initiated Activation**, also select **Reactivate cloned Agents**, and **Enable Reactivate unknown Agents**. See ["Agent settings" on page 374](#) for more information.
7. Click **Save**.
8. If you're using Amazon WorkSpaces, and you *didn't* allow agent-initiated activation, [manually assign an elastic IP address to each WorkSpace now](#), before proceeding with further steps on this page. This gives each Amazon WorkSpace a public IP that can be contacted by other computers. This is not required for EC2

Trend Micro Deep Security On-Premise 11.3

instances because they already use public IP addresses.



Open ports

You'll need to make sure that the necessary ports are open to your Amazon EC2 instances or Amazon WorkSpaces.

To open ports:

Trend Micro Deep Security On-Premise 11.3

1. Open ports to your Amazon EC2 instances, as follows:
 - a. Log in to your [Amazon Web Services Console](#).
 - b. Go to **EC2 > Network & Security > Security Groups**.
 - c. Select the security group that is associated with your EC2 instances, then select **Actions > Edit outbound rules**.
 - d. Open the necessary ports. See "[Which ports should be opened?](#)" below below.
2. Open ports to your Amazon WorkSpaces, as follows:
 - a. Go to the firewall software that is protecting your Amazon WorkSpaces, and open the ports listed above.

You have now opened the necessary ports so that Deep Security Agent and Deep Security Manager can communicate.

Which ports should be opened?

Generally-speaking:

- agent-to-manager communication requires you to open the outbound TCP port (443 or 80, by default), while
- manager-to-agent communication requires you to open an inbound TCP port (4118).

More specifically:

- If you set the communication direction to **Agent/Appliance-Initiated**, you'll need to open the *outbound* TCP port (443 or 80, by default).
- If you set the communication direction to **Manager-Initiated**, you'll need to open the *inbound* TCP port of 4118.
- If you set the communication direction to **Bidirectional**, you'll need to open both the *outbound* TCP port (443 or 80, by default) AND the *inbound* TCP port of 4118.
- If you enabled **Allow Agent-Initiated Activation**, you'll need to open the *outbound* TCP port (443 or 80, by default) regardless of how you set the communication direction.
- If you disabled **Allow Agent-Initiated Activation**, you'll need to open the *inbound* TCP port of 4118 regardless of how you set the communication direction.

Deploy agents to your Amazon EC2 instances and WorkSpaces

You'll need to deploy agents onto your Amazon EC2 instances and Amazon WorkSpaces. Below are a couple of options.

- **Option 1: Use a deployment script to install, activate, and assign a policy**

Use Option 1 if you need to deploy agents to many Amazon EC2 instances and Amazon WorkSpaces.

With this option, you must run a deployment script on the Amazon EC2 instances or Amazon WorkSpaces. The script installs and activates the agent and then assigns a policy. See ["Use deployment scripts to add and protect computers" on page 437](#) for details.

OR

- **Option 2: Manually install and activate**

Use Option 2 if you only need to deploy agents to a few EC2 instances and Amazon WorkSpaces.

- a. Get the Deep Security Agent software, copy it to the Amazon EC2 instance or Amazon Workspace, and then install it. For details, see ["Get Deep Security Agent software" on page 318](#), and ["Manually install the Deep Security Agent" on page 322](#).
- b. Activate the agent. You can do so on the agent (if agent-initiated activation was enabled) or on the Deep Security Manager. For details, see ["Activate the agent" on page 370](#)

You have now installed and activated Deep Security Agent on an Amazon EC2 instance or Amazon Workspace. A policy may or may not have been assigned, depending on the option you chose. If you chose Option 1 (you used a deployment script), a policy was assigned to the agent during activation. If you chose Option 2 (you manually installed and activated the agent), then no policy has been assigned, and you will need to assign one following the instructions further down on this page.

Verify that the agent was installed and activated properly

You should verify that your agent was installed and activated properly.

Trend Micro Deep Security On-Premise 11.3

1. Log in to Deep Security Manager.
2. Click **Computers** at the top.
3. On the navigation pane on the left, make sure your Amazon EC2 instance or Amazon WorkSpace appears under **Computers** > *your_AWS_account* > *your_region* .
(Look for WorkSpaces in a **WorkSpaces** sub-node.)
4. In the main pane, make sure your Amazon EC2 instances or Amazon WorkSpaces appear with a **Status of Managed (Online)** and a green dot next to them.

Assign a policy

Skip this step if you ran a deployment script to install and activate the agent. The script already assigned a policy so no further action is required.

If you installed and activated the agent manually, you must assign a policy to the agent. Assigning the policy sends the necessary protection modules to the agent so that your computer is protected.

To assign a policy, see ["Assign a policy to a computer" on page 522](#).

After assigning a policy, your Amazon EC2 instance or Amazon WorkSpace is now protected.

Bake the agent into your AMI or WorkSpace bundle

Read this page if you want to launch *new* Amazon EC2 instances and Amazon WorkSpaces with the agent 'baked in'.

If instead you want to:

- protect *existing* Amazon EC2 instances and Amazon WorkSpaces with Deep Security, see ["Install the agent on Amazon EC2 and WorkSpaces" on page 330](#).
- protect Amazon WorkSpaces after already protecting your Amazon EC2 instances, see instead ["Protect Amazon WorkSpaces if you already added your AWS account" on page 474](#).

'Baking the agent' is the process of launching an EC2 instance based on a public AMI, installing the agent on it, and then saving this custom EC2 image as an AMI. This AMI (with the agent 'baked in') can then be selected when launching new Amazon EC2 instances.

Similarly, if you want to deploy the Deep Security Agent on multiple Amazon WorkSpaces, you can create a custom 'WorkSpace bundle' that includes the agent. The custom bundle can then be selected when launching new Amazon WorkSpaces.

To bake an AMI and create a custom WorkSpace bundle with a pre-installed and pre-activated agent, follow these steps:

1. ["Add your AWS account to Deep Security Manager" on the next page](#)
2. ["Set the communication direction" on the next page](#)
3. ["Configure the activation type" on the next page](#)
4. ["Launch a 'master' Amazon EC2 instance or Amazon WorkSpace" on the next page](#)
5. ["Deploy an agent on the master" on the next page](#)
6. ["Verify that the agent was installed and activated properly" on page 339](#)
7. ["\(Recommended\) Set up policy auto-assignment" on page 339](#)
8. ["Create an AMI or custom WorkSpace bundle based on the master" on page 340](#)
9. ["Use the AMI" on page 341](#)

Add your AWS account to Deep Security Manager

You'll need to add your AWS accounts to Deep Security Manager. These are the AWS accounts that will contain the Amazon EC2 instances and Amazon WorkSpaces that you want to protect.

See ["Add AWS cloud accounts" on page 455](#) for instructions.

Set the communication direction

You'll need to set the communication direction: either agent-initiated, manager-initiated, or bidirectional.

See ["Install the agent on Amazon EC2 and WorkSpaces" on page 330](#) > ["Set the communication direction" on page 331](#) for instructions.

Configure the activation type

You'll need to indicate whether you'll allow agent-initiated activation.

See ["Install the agent on Amazon EC2 and WorkSpaces" on page 330](#) > ["Configure the activation type" on page 332](#) for instructions.

Launch a 'master' Amazon EC2 instance or Amazon WorkSpace

You'll need to launch a 'master' Amazon EC2 instance or Amazon WorkSpace. The master instance is the basis for the EC2 AMI or WorkSpace bundle that you will create later.

1. In AWS, launch an Amazon EC2 instance or Amazon WorkSpace. See the [Amazon EC2 documentation](#) and [Amazon WorkSpaces documentation](#) for details.
2. Call the instance 'master'.

Deploy an agent on the master

You'll need to install and activate the agent on the master. During this process, you can optionally install a policy.

See ["Install the agent on Amazon EC2 and WorkSpaces" on page 330](#) > ["Deploy agents to your Amazon EC2 instances and WorkSpaces" on page 335](#) for instructions.

Tip: Ideally, if you bake the agent into your AMI or workspace bundle and then want to use a newer agent later on, you should update the bundle to include the new agent. However, if that's not possible, you can use the **Automatically upgrade agents on activation** setting so when the agent in the AMI or bundle activates itself, Deep Security Manager can automatically upgrade the agent to the latest version. For details, see ["Automatically upgrade agents on activation" on page 341](#).

Verify that the agent was installed and activated properly

You should verify that the agent was installed and activated properly on the master before proceeding.

See ["Install the agent on Amazon EC2 and WorkSpaces" on page 330](#) > ["Verify that the agent was installed and activated properly" on page 335](#) for instructions.

(Recommended) Set up policy auto-assignment

You may need to set up policy auto-assignment depending on how you deployed the agent on the master:

- If you used a deployment script, then a policy has already been assigned, and no further action is required.
- If you manually installed and activated the agent, no policy was assigned to the agent, and one should be assigned now so that the master is protected. The Amazon EC2 instances and Amazon WorkSpaces that are launched based on the master will also be protected.

If you want to assign a policy to the master, as well as auto-assign a policy to future EC2 instances and WorkSpaces that are launched using the master, follow these instructions:

1. In Deep Security Manager, create an event-based task with these parameters:
 - Set the **Event** to **Agent-Initiated Activation**.
 - Set **Assign Policy** to the policy you want to assign.
 - (Optional) Set a condition to **Cloud Instance Metadata**, with
 - a **tagKey** of **EC2** and a **tagValue.*** of **True** (for an EC2 instance)
OR
 - a **tagKey** of **WorkSpaces** and a **tagValue.*** of **True** (for WorkSpaces)

The above event-based task says:

When an agent is activated, assign the specified policy, on condition that `EC2=true` or `WorkSpaces=true` exists in the Amazon EC2 instance or Workspace.

If that key/value pair does not exist in the EC2 instance or Workspace, then the policy is not assigned (but the agent is still activated). If you do not specify a condition, then the policy is assigned on activation unconditionally.

For details on creating event-based tasks, see ["Automatically assign policies by AWS instance tags" on page 441](#).

2. If you added a key/value pair in Deep Security Manager in the previous step, do the following:

- a. Go to AWS.
- b. Find your master EC2 instance or Workspace.
- c. Add tags to the master with a **Key** of **EC2** or **WorkSpaces** and a **Value** of **True**.

For details, see this [Amazon EC2 documentation on tagging](#), and this [Amazon Workspace documentation on tagging](#).

You have now set up policy auto-assignment. New Amazon EC2 instances and Amazon WorkSpaces that are launched using the master are activated automatically (since the agent is pre-activated on the master), and then auto-assigned a policy through the event-based task.

3. On the master EC2 instance or Workspace, reactivate the agent by re-running the activation command on the agent, or by clicking the **Reactivate** button in Deep Security Manager. For details, see ["Activate the agent" on page 370](#)

The re-activation causes the event-based task to assign the policy to the master. The master is now protected.

You are now ready to bake your AMI or create a custom Workspace bundle.

Create an AMI or custom Workspace bundle based on the master

- To create an AMI on Linux, see [this Amazon documentation](#).
- To create an AMI on Windows, see [this Amazon documentation](#).
- To create a custom Workspace bundle, see [this Amazon documentation](#).

You now have an AMI or WorkSpace bundle that includes a pre-installed and pre-activated agent.

Use the AMI

Now that you have a custom AMI or WorkSpace bundle, you can use it as the basis for future Amazon EC2 instances and Amazon WorkSpaces. With the custom AMI or bundle, Deep Security Agent starts up automatically, activates itself, and applies the protection policy assigned to it. It appears in Deep Security Manager with a **Status of Managed** and a green dot next to it.

Automatically upgrade agents on activation

If your environment includes Deep Security Agents installed on Linux computers, you can choose to automatically upgrade those agents to the latest software version that's available from **Administration > Updates > Software > Local** when the agent is activated or reactivated.

Note: This feature is currently available only on Linux computers. Support for Windows and Unix is planned for a future release.

Ideally, if you ["Bake the agent into your AMI or WorkSpace bundle" on page 337](#) and then want to use a newer agent, you should update the bundle to include the new agent. However, if that's not possible, you can use the **Automatically upgrade agents on activation** setting so when the agent in the AMI or bundle activates itself, Deep Security Manager can automatically upgrade the agent to the latest version.

Note: Any AWS instances that were added to Deep Security without using a cloud connector will be "rehomed" into a cloud connector after the upgrade. This means they will appear under the appropriate AWS account name on the Computers page, organized in a hierarchy that includes the AWS Region, VPC, and subnet.

This feature works with these operating systems:

- Red Hat Enterprise Linux
- Ubuntu
- CentOS

- Debian
- Amazon Linux
- Oracle Linux
- SUSE Linux Enterprise Server
- Cloud Linux

Note: This feature is currently not supported on computers where Deep Security Virtual Appliance is installed.

Enable automatic agent upgrade

1. Make sure the latest agent software and kernel support packages are available in Deep Security Manager. You can configure Deep Security Manager to automatically download software updates, or import them manually. For details, see ["Get Deep Security Agent software" on page 318](#).
2. Go to **Administration > System Settings > Agents**.
3. Under **Agent Upgrade**, select **Automatically upgrade agents on activation**.
4. Click **Save**.

Check that agents were upgraded successfully

The **Version** column on the **Computers** page displays the installed Deep Security Agent version for each computer.

In addition, when an automatic agent upgrade is triggered, ["System events" on page 1220](#) are generated that you can use to track the status of the upgrade. You can check for these system events:

ID	Event	Description
264	Agent software Upgrade Requested	An agent software upgrade has been triggered, either manually or by an automatic agent upgrade.
277	Auto Agent Software	The agent was eligible for an automatic upgrade, but the upgrade did not occur.

ID	Event	Description
	Upgrade Skipped	<p>The event details list the existing agent version and the attempted upgrade version, along with the reason the upgrade failed. The reasons can be:</p> <ul style="list-style-type: none"> • The agent was not upgraded automatically because the upgrade requires an agent reboot. You can manually upgrade the agent and reboot the system. See "Manually install the Deep Security Agent" on page 322. • The agent was not upgraded automatically because a required Linux kernel support file was not found. Deep Security Manager usually downloads required Linux kernel support packages automatically, but you can also download and import packages to Deep Security Manager manually and then upgrade the agent. See "Get Deep Security Agent software" on page 318. • The agent was not upgraded automatically because the auto-upgrade feature does not support the currently installed OS. You may be able to upgrade the agent manually. See "Manually install the Deep Security Agent" on page 322.
706	Software Update: Agent Software Upgraded	The upgrade was successful.
707	Software Update: Agent Software Upgrade Failed	The upgrade was not successful. Refer to the event details for more information about why it was not successful.

Configure communication between components

Generally, communication-related settings only need to be configured once and then rarely changed.

- ["Agent-manager communication" below](#)
- ["Use agent-initiated communication with cloud accounts" on page 350](#)
- ["Connect agents behind a proxy" on page 351](#)
- ["Proxy protocols supported by Deep Security" on page 361](#)
- ["Proxy settings" on page 362](#)
- ["Configure SMTP settings for email notifications" on page 237](#)
- ["Deep Security URLs" on page 115](#)
- ["Manage trusted certificates" on page 364](#)

Agent-manager communication

Deep Security Manager and the agent or appliance communicate using the latest mutually-supported version of TLS.

Topics in this article:

- ["Configure the heartbeat" below](#)
- ["Configure communication directionality" on page 346](#)
- ["Supported cipher suites for agent-manager communication" on page 348](#)

Configure the heartbeat

A 'heartbeat' is a periodic communication between the Deep Security Manager and agent(or appliance). During a heartbeat, the manager collects this information:

- the status of the drivers (on- or off-line)
- the status of the agent or appliance (including clock time)
- agent or appliance logs since the last heartbeat
- data to update counters
- a fingerprint of the agent or appliance security configuration (used to determine if it is up to date)

The heartbeat can be configured on a base or parent policy, on a sub-policy, or on an individual computer.

You can configure the following properties of the heartbeat:

- **Heartbeat Interval:** How much time passes between heartbeats.
- **Number of Heartbeats that can be missed before an alert is raised:** The number of consecutively missed heartbeats that triggers an alert. For example, a value of three causes the manager to trigger an alert on the fourth missed heartbeat.)

Note: If the computer is a server, too many missed heartbeats in a row may indicate a problem with the agent/appliance or the computer itself. However if the computer is a laptop or any other system that is likely to experience a sustained loss of connectivity, this setting should be set to "unlimited".

- **Maximum change (in minutes) of the local system time on the computer between heartbeats before an alert is raised:** For agents that are capable of detecting changes to the system clock (Windows agents only) these events are reported to the manager as agent event 5004. If the change exceeds the clock change listed here then an alert is triggered. For agents that do not support this capability, the manager monitors the system time reported by the agent at each heartbeat operation and triggers an alert if it detects a change greater than the permissible change specified in this setting.

Note: Once a **Computer-Clock-Changed** alert is triggered, it must be dismissed manually.

- **Raise Offline Errors For Inactive Virtual Machines:** Sets whether an offline error is raised if the virtual machine is stopped.
1. Open the **Policy editor**¹ or the **Computer editor**² for the policy or computer to configure.
 2. Go to **Settings > General > Heartbeat**.
 3. Change the properties as required.
 4. Click **Save**.

¹To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

²To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Configure communication directionality

Configure whether the agent or appliance or the manager initiates communication.

'Communication' includes the heartbeat and all other communications. The following options are available:

Bidirectional: By default, communications are bidirectional. The agent or appliance normally initiates the heartbeat and also listens on the agent's listening port number for connections from the Deep Security Manager. (See ["Deep Security port numbers" on page 111](#).) The manager can contact the agent or appliance to perform required operations. The manager can apply changes to the security configuration of the agent or appliance.

Note: The Deep Security Virtual Appliance can only operate in bidirectional mode. Changing this setting to any other mode for a virtual appliance will disrupt functionality.

- **Manager Initiated:** The manager initiates all communication with the agent or appliance. These communications include security configuration updates, heartbeat operations, and requests for event logs. If you choose this option, we strongly recommend that you ["Protect Deep Security Agent" on page 1033](#) so that it only accepts connections from known Deep Security Managers.
- **Agent/Appliance Initiated:** The agent or appliance does not listen for connections from the manager. Instead they contact the manager on the port number where the Manager listens for agent heartbeats. (See ["Deep Security port numbers" on page 111](#).) Once the agent or appliance has established a TCP connection with the manager, all normal communication takes place: the manager first asks the agent or appliance for its status and for any events. (This is the heartbeat operation.) If there are outstanding operations that need to be performed on the computer (for example, the policy needs to be updated), these operations are performed before the connection is closed. Communications between the manager and the agent or appliance only occur on every heartbeat. If an agent or appliance's security configuration has changed, it is not updated until the next heartbeat.

Note: Before configuring an agent or appliance to initiate communication, ensure that it can reach the manager URL and heartbeat port. If the agent or appliance cannot resolve the manager URL or cannot reach the IP and port, agent- or appliance-initiated

communications will fail. The Manager URL and the heartbeat port are listed in the **System Details** area in **Administration > System Information**.

Note: To enable communications between the Manager and the agents and appliances, the manager automatically implements a (hidden) firewall rule (priority four, Bypass) that opens the listening port number for heartbeats on the agents and appliances to incoming TCP/IP traffic. By default, it will accept connection attempts from any IP address and any MAC address. You can restrict incoming traffic on this port by creating a new priority 4, Force Allow or Bypass firewall rule that only allows incoming TCP/IP traffic from specific IP or MAC addresses, or both. This new firewall rule would replace the hidden firewall rule if the settings match these settings:

action: force allow or bypass

priority: 4 - highest

packet's direction: incoming

frame type: IP

protocol: TCP

packet's destination port: agent's listening port number for heartbeat connections from the manager, or a list that includes the port number. (See [agent listening port number](#).)

While these settings are in effect, the new rule will replace the hidden rule. You can then type packet source information for IP or MAC addresses, or both, to restrict traffic to the computer.

1. Open the **Policy editor**¹ or the **Computer editor**² for the policy or computer to configure.
2. Go to **Settings > General > Communication Direction**.
3. In the **Direction of Deep Security Manager to Agent/Appliance communication** menu, select one of the three options ("Manager Initiated", "agent/appliance Initiated", or "Bidirectional"), or choose "Inherited". If you select "Inherited", the policy or computer

¹To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

²To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

inherits the setting from its parent policy. Selecting one of the other options overrides the inherited setting.

4. Click **Save** to apply the changes.

Note: Agents and appliances look for the Deep Security Manager on the network by the Manager's hostname. Therefore the Manager's hostname **must** be in your local DNS for agent- or appliance-initiated or bidirectional communication to work.

Supported cipher suites for agent-manager communication

Deep Security Manager and the agent or appliance communicate using the latest mutually-supported version of TLS.

The Deep Security Agent supports the following ciphers for communication with the manager. If you need to know the ciphers supported by the Deep Security Manager, contact Trend Micro. If you need to know the ciphers supported by the Deep Security Virtual Appliance, figure out the version of the agent that's embedded on the appliance, and then look up that agent in the list below.

The ciphers consist of a key exchange asymmetric algorithm, a symmetric data encryption algorithm and a hash function.

Deep Security Agent 9.5 supports these TLSv1.0 ciphers:

- TLS_RSA_WITH_AES_256_CBC_SHA
- TLS_RSA_WITH_AES_128_CBC_SHA

Deep Security Agent 9.6 supports these TLSv1.0 ciphers:

- TLS_RSA_WITH_AES_256_CBC_SHA
- TLS_RSA_WITH_AES_128_CBC_SHA

Deep Security Agent 10.0 supports these TLSv1.2 ciphers:

- TLS_RSA_WITH_AES_256_CBC_SHA256
- TLS_RSA_WITH_AES_128_CBC_SHA256

Deep Security Agent 10.3 supports these TLSv1.2 ciphers:

- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256
- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA384
- TLS_RSA_WITH_AES_256_CBC_SHA256
- TLS_RSA_WITH_AES_128_CBC_SHA256

Deep Security Agent 11.0 supports these TLSv1.2 ciphers:

- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256
- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA384
- TLS_RSA_WITH_AES_128_CBC_SHA256
- TLS_RSA_WITH_AES_256_CBC_SHA256

SSL implementation and credential provisioning

The Deep Security Agent may initiate communication to Deep Security Manager or it may be contacted by the manager if the computer object is set to operate in bi-directional mode. Deep Security Manager treats all connections to agents and appliances in a similar way. If the agent has not been activated, a limited set of interactions are possible. If the agent has been activated (either by an administrator or via the agent-initiated activation feature), the full set of interactions are enabled. The Deep Security Manager acts as an HTTP client in all cases, regardless of whether it was the client when forming the TCP connection. Agents and appliances cannot ask for data or initiate operations themselves. The manager requests information such as events and status, invokes operations, or pushes configuration to the agent. This security domain is highly controlled to ensure that agents and appliances have no access to Deep Security Manager or the computer that it is running on.

Both agent and manager use two different security contexts to establish the secure channel for HTTP requests:

1. Before activation, the agent accepts the bootstrap certificate to form the SSL or TLS channel.
2. After authentication, mutual authentication is required to initiate the connection. For mutual authentication, the manager's certificate is sent to the agent and the agent's certificate is sent to the manager. The agent validates that the certificates come from the same

certificate authority (which is the Deep Security Manager) before privileged access is granted.

Once the secure channel is established, the agent acts as the server for the HTTP communication. It has limited access to the manager and can only respond to requests. The secure channel provides authentication, confidentiality through encryption, and integrity. The use of mutual authentication protects against man-in-the-middle (MiTM) attacks where the SSL communication channel is proxied through a malicious third party. Within the stream, the inner content uses GZIP and the configuration is further encrypted using PKCS #7.

Use agent-initiated communication with cloud accounts

If any of the computers you are protecting with Deep Security are in cloud accounts, we recommend that you use agent-initiated communication to prevent communication issues between the Deep Security Manager and agents.

If you are using Deep Security as a Service, agent-initiated communication is enabled by default. The full list of Deep Security default communication direction settings is as follows:

Deep Security	bidirectional
Deep Security AMI from AWS Marketplace	bidirectional
Deep Security as a Service	Agent-initiated

To use agent-initiated communication, you must first enable it on a policy, and then assign that policy to a deployment script.

Enable agent-initiated communication on the policy

You can enable agent-initiated communication by either modifying an existing policy or by creating a new one.

Tip: You can quickly create a new policy from an existing policy by right-clicking it and selecting **Duplicate**.

1. On the **Policies** page, double-click the policy.
2. Go to **Settings > General**.
3. Under Communication Direction, select **Agent/Appliance Initiated**.
4. Click **Save**.

Assign the policy to a deployment script

1. In the upper-right corner, click **Support > Deployment Script**.
2. Select your platform from the list.
3. Select **Activate Agent automatically after installation**, and then select your policy from the list.
4. Click **Close**.

To learn how to use deployment scripts to apply protection to your computers, see ["Use deployment scripts to add and protect computers" on page 437](#).

Connect agents behind a proxy

To protect computers that require a proxy to access the Internet, Deep Security Manager, or relays, you need to configure Deep Security Manager with the proxy's address. It will give this information to agents. (Alternatively, you can [use the CLI to configure proxy settings locally on the agent](#).)

In this topic:

- ["Requirements" below](#)
- ["Register the proxy in Deep Security Manager" below](#)
- ["Connect agents, appliances, and relays to security updates via proxy" on the next page](#)
- ["Connect agents to security services via proxy" on the next page](#)
- ["Connect agents to a relay via proxy" on page 353](#)
- ["Remove a proxy setting" on page 354](#)
- ["Subsequent agent deployments" on page 354](#)

Requirements

Deep Security Agent 10.0 or later (not GA) is required if connecting agents to a relay or manager via proxy (especially for application control rulesets).

Register the proxy in Deep Security Manager

1. In Deep Security Manager, go to **Administration > System Settings > Proxies**.
2. In the **Proxy Servers** area, create a new HTTP proxy by clicking **New** in the menu bar.

3. Enter the protocol, IP Address, port number, user name and password.

Connect agents, appliances, and relays to security updates via proxy

Alternatively, you can [use the command line to configure proxy use](#) instead.

1. Still on the **Proxies** tab, in the **Proxy Server Use** area, change the **Primary Security Update Proxy used by Agents, Appliances, and Relays** setting to point to the new proxy.
2. Click **Save**.

Connect agents to security services via proxy

1. On Deep Security Manager, click **Policies** at the top.
2. On the left, click **Policies**.
3. In the main pane, double-click the policy that you use to protect computers that are behind the proxy.
4. Set up a proxy to the Global Census, Good File Reputation, and Predictive Machine Learning Services as follows:
 - a. Click **Settings** on the left.
 - b. In the main pane, click the **General** tab.
 - c. In the main pane, look for the **Network Setting for Census and Good File Reputation Service, and Predictive Machine Learning** section.
 - d. If the **Inherited** check box is selected, the proxy settings are inherited from the parent policy. To change the settings for this policy or computer, clear the check box.
 - e. Select **When accessing Global Server, use proxy** and in the list, select your proxy, or select **New** to specify another proxy.
 - f. Save your settings.
5. Set up a proxy to the Smart Protection Network for use with anti-malware:
 - a. Click **Anti-Malware** on the left.
 - b. In the main pane, click the **Smart Protection** tab.
 - c. Under **Smart Protection Server for File Reputation Service**, if the **Inherited** check box is selected, the proxy settings are inherited from the parent policy. To change the settings for this policy or computer, clear the check box.
 - d. Select **Connect directly to Global Smart Protection Service**.
 - e. Select **When accessing Global Smart Protection Service, use proxy** and in the list, select your proxy or select **New** to specify another proxy.

- f. Specify your proxy settings and click **OK**.
 - g. Save your settings.
6. Set up a proxy to the Smart Protection Network for use with web reputation:
 - a. Click **Web Reputation** on the left.
 - b. In the main pane, click the **Smart Protection** tab.
 - c. Under **Smart Protection Server for Web Reputation Service**, set up your proxy, the same way you did under **Anti-Malware** in a previous step.
 - d. With **Web Reputation** still selected on the left, click the **Advanced** tab.
 - e. In the **Ports** section, select a group of port numbers that includes your proxy's listening port number, and then click **Save**. For example, if you're using a Squid proxy server, you would select the **Port List Squid Web Server**. If you don't see an appropriate group of port numbers, go to **Policies > Common Objects > Lists > Port Lists** and then click **New** to set up your ports.
 - f. Save your settings.

Your agents can now connect to Trend Micro security services over the Internet through a proxy.

Connect agents to a relay via proxy

1. In the top right-hand corner of Deep Security Manager, click **Support > Deployment Scripts**.
2. From **Proxy to contact Relay(s)**, select a proxy.
3. Copy the script or save it.
4. Run the script on the computer. You can either do this manually or with a third party deployment system such as Ansible, Chef, Powershell, or others.

Connect agents to a relay's private IP address

If your relay has an elastic IP address, agents within an AWS VPC may not be able to reach the relay via that IP address. Instead, they must use the private IP address of the relay group.

1. Go to **Administration > System Settings**.
2. In the **System Settings** area, click the **Updates** tab.
3. Under **Software Updates**, in the window **Alternate software update distribution server(s) to replace Deep Security Relays**, type:

```
https://<IP>:<port>/
```

where `<IP>` is the private network IP address of the relay, and `<port>` is the [relay port number](#)

4. Click **Add**.
5. Click **Save**.

Note: If your relay group's private IP changes, you must manually update this setting. It will not be updated automatically.

Remove a proxy setting

If you've installed an agent with a deployment script that adds proxy settings that you no longer require, you can remove the setting by entering the following commands in a command line:

Windows

```
>C:\Program Files\Trend Micro\Deep Security\dsa_control -x ""
```

```
C:\Program Files\Trend Micro\Deep Security\dsa_control -y ""
```

Linux

```
/opt/ds_agent/dsa_control -x ""
```

```
/opt/ds_agent/dsa_control -y ""
```

Subsequent agent deployments

After your initial deployment, if you add more agents, modify their deployment scripts to use the proxy in the **Deployment Scripts Generator**.

Configure agents that have no Internet access

If your agents or relays don't have access to the Internet (also called "air-gapped agents"), then they won't be able to access several of the security services provided by the Trend Micro Smart Protection Network. These security services are necessary for the full and successful operation of the Deep Security anti-malware and web reputation features.

These Trend Micro security services are:

Trend Micro Deep Security On-Premise 11.3

Service name	Required for these features
Smart Scan Service	Smart Scan
Web Reputation Service	web reputation
Global Census Service	behavior monitoring , predictive machine learning
Good File Reputation Service	behavior monitoring , predictive machine learning , process memory scans
Predictive Machine Learning Service (Trend X)	predictive machine learning

If the above services can't be reached by the agent or relay-enabled agent, you have several solutions, described below.

Solutions

- Solution 1: ["Use a proxy" below](#)
- Solution 2: ["Install a Smart Protection Server locally " on the next page](#)
- Solution 3: ["Install a relay and supporting components in your DMZ or Internet-ready area" on the next page](#)
- Solution 4: ["Disable the features that use Trend Micro security services" on page 359](#)

Use a proxy

If your agents or relay-enabled agents can't connect to the Internet, you can install a proxy that can. Your Deep Security Agents and relays connect to the proxy, and the proxy then connects outbound to the Trend Micro security services in the Smart Protection Network.

Note: With a proxy, each Smart Scan or web reputation request goes out over the Internet to the Smart Protection Network. Consider instead [using a Smart Protection Server inside your LAN](#) to keep these requests within your network and reduce extranet bandwidth usage.

To use a proxy, see ["Connect agents behind a proxy" on page 351](#)

Install a Smart Protection Server locally

If your agents and relay-enabled agents can't connect to the Internet, you can install a Smart Protection Server in your local area network (LAN) to which they *can* connect. The local Smart Protection Server periodically connects outbound over the Internet to the Smart Protection Network to retrieve the latest Smart Scan anti-malware patterns and web reputation information. This information is cached on the Smart Protection Server and disseminated to your agents and relay-enabled agents.

If you decide to use this solution, remember that:

- Only the [Smart Scan](#) and [web reputation](#) features are supported with a local Smart Protection Server.
- Use the proxy solution if you need the [behavior monitoring](#), [predictive machine learning](#), and [process memory scanning](#) features. See "Use a proxy" on the previous page above for details. If you decide not to use these features, you must disable them to prevent a query failure and to improve performance. For instructions on disabling these features, see ["Disable the features that use Trend Micro security services" on page 359](#)

To deploy a Smart Protection Server:

- install it manually. See the [Smart Protection Server documentation](#) for details.

OR

- if your agents or relay-enabled agents are inside AWS, install it using an AWS CloudFormation template created by Trend Micro. See [Deploy a Smart Protection Server in AWS](#) for details.

Install a relay and supporting components in your DMZ or Internet-ready area

If your agents or relay-enabled agents can't connect to the Internet, you can install a relay-enabled Deep Security Agent, Deep Security Manager, and Deep Security Manager's database in your [demilitarized zone \(DMZ\)](#) or another area of your network where Internet access is available. These Deep Security components must be installed *in addition* to your existing air-gapped components.

Once all the components are installed, the relay-enabled agent automatically obtains the latest malware scan updates from the Update Server in the Smart Protection Network. These updates must be extracted to a .zip file, and then manually copied to your air-gapped relay or directly to your air-gapped agents, if you do not have an air-gapped relay. (Detailed instructions follow.)

If you decide to use this solution, remember that:

- The .zip file contains traditional (large) malware patterns, which give you basic anti-malware capabilities.
- The following advanced anti-malware features are *not* available: [Smart Scan](#), [behavior monitoring](#), [predictive machine learning](#), [process memory scans](#), and [web reputation](#). These features all require access to Trend Micro security services.
- You should [disable the advanced anti-malware features](#) (Solution 4) since they cannot be used.
- You should have a plan in place to periodically update the .zip file on your air-gapped relay to ensure you always have the latest malware patterns.

To deploy this solution, follow these steps:

1. Install a Deep Security Manager and its associated database in your DMZ. We'll call these Internet-facing components the 'DMZ manager' and 'DMZ database'.
2. Install a Deep Security Agent in your DMZ and configure it as a relay. We'll call this agent the 'DMZ relay'. For information on setting up relays, see "[Distribute security and software updates with relays](#)" on page 380.

The following items are now installed:

- a DMZ manager
- a DMZ database
- a DMZ relay
- an air-gapped manager
- an air-gapped database
- an air-gapped relay
- multiple air-gapped agents

3. On the DMZ relay, create a .zip file containing the latest malware patterns by running this command:

```
dsa_control -b
```

The command line output shows the name and location of the .zip file that was generated.

4. Copy the .zip file to the air-gapped relay, or, if you are not using an air-gapped relay, copy the .zip directly to each of your air-gapped agents. Place the file in the relay or agent's installation directory.
 - On Windows the default directory is `C:\Program Files\Trend Micro\Deep Security Agent`.
 - On Linux the default directory is `/opt/ds_agent`.

Note: Do not rename the .zip file.

5. On the air-gapped manager, initiate a security update download:
 - a. Click **Computers** at the top.
 - b. In the list of computers, find your air-gapped relay or agent where you copied the .zip file, right-click it and select **Download Security Update**.

The air-gapped relay or agent checks its configured update source (typically the Update Server in the Trend Micro Smart Protection Network on the Internet). Since it can't connect to this server, it checks the .zip file in its installation directory. When it finds the .zip file, it extracts it and imports the updates. If an air-gapped relay is used, the updates are then disseminated to the air-gapped agents that are configured to connect to the relay.

- c. Delete the .zip file after the updates are imported to the air-gapped agent or relay.
6. Configure the air-gapped relay to connect to itself instead of the Trend Micro Update Server (to prevent connection error alerts):
 - a. Log in to the air-gapped manager.
 - b. Click **Administration** on the top.
 - c. On the left, click **System Settings**.
 - d. In the main pane, click the **Updates** tab.

- e. Under **Primary Security Update Source**, select **Other update source** and enter `https://localhost:[port]` where `[port]` is the [configured port number for security updates](#), by default 4122.
- f. Click **OK**.

The air-gapped relay no longer tries to connect to the Update Server in the Trend Micro Smart Protection Network.
7. (Optional but recommended.) To improve performance, "[Disable the features that use Trend Micro security services](#)" below.
8. On a periodic basis, download the latest updates to your DMZ relay, zip them up, copy them to your air-gapped relay or agents, and initiate a security update download on the relay (if you're using one).

You have now deployed a Deep Security Manager, associated database and relay in your DMZ from which to obtain malware scan updates.

Disable the features that use Trend Micro security services

You can disable the features that use Trend Micro security services. Doing so improves performance because the air-gapped agent no longer tries (and fails) to query the services.

Note: Without Trend Micro security services, your malware detection is downgraded significantly, ransomware is not detected at all, and process memory scans are also affected. It is therefore strongly recommended that you use one of the other solutions to allow access to Trend Micro security services. If this is impossible, only then should you disable features to realize performance gains.

- To disable Smart Scans:
 - a. Open the **Computer or Policy editor**¹.
 - b. On the left, click **Anti-Malware**.
 - c. In the main pane, click **Smart Protection**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

- d. Under **Smart Scan**, deselect **Inherited** (if it is selected) and then select **Off**.
 - e. Click **Save**.
- To disable web reputation:
 - a. Open the **Computer or Policy editor**¹.
 - b. On the left, click **Web Reputation**.
 - c. In the main pane, make sure the **General** tab is selected.
 - d. From the **Configuration** drop-down list, select **Off**.
 - e. Click **Save**.
- To disable Smart Feedback:
 - a. In Deep Security Manager, click **Administration** at the top.
 - b. Click **System Settings** on the left.
 - c. In the main pane, click the **Smart Feedback** tab.
 - d. Deselect **Enable Trend Micro Smart Feedback (recommended)**.
 - e. Click **Save**.
- To disable process memory scans:
 - a. In Deep Security Manager, click **Policies** at the top.
 - b. On the left, expand **Common Objects > Other** and then click **Malware Scan Configurations**.
 - c. Double-click a malware scan configuration with a **SCAN TYPE** of **Real-Time**.
 - d. On the **General** tab, under **Process Memory Scan**, deselect **Scan process memory for malware**.
 - e. Click **OK**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

- To disable predictive machine learning:
 - a. Make sure you still have a real-time malware scan configuration open.
 - b. On the **General** tab, under **Predictive Machine Learning**, deselect **Enable Predictive Machine Learning**.
 - c. Click **OK**.
- To disable behavior monitoring:
 - a. Make sure you still have a real-time malware scan configuration open.
 - b. On the **General** tab, under **Behavior Monitoring**, deselect both options, namely, **Detect suspicious activity and unauthorized changes (incl. ransomware)** and **Back up and restore ransomware-encrypted files**.
 - c. Click **OK**.

Also disable the census and grid queries if you want performance gains. If you leave them enabled, a lot of unnecessary background processing takes place. To disable these queries:

1. Disable the census query:

```
dsm_c -action changesetting -name settings.configuration.enableCensusQuery -value false
```

2. Disable the grid query:

```
dsm_c -action changesetting -name settings.configuration.enableGridQuery -value false
```

Proxy protocols supported by Deep Security

You can view and edit the list of proxy servers available to you on the Proxies tab on **Administration > System Settings**.

This table lists the proxy [protocols supported](#) by Deep Security.

Traffic Originating From	To Service	HTTP Support	SOCKS4 Support	SOCKS5 Support
Manager	Software Updates, CSS, News Updates, Product Registration and Licensing	Yes	No	No

Traffic Originating From	To Service	HTTP Support	SOCKS4 Support	SOCKS5 Support
Manager	Smart Feedback	Yes	No	Yes
Manager	Cloud Accounts	Yes	No	No
Manager	Control Manager	Yes	No	No
Manager	Deep Discovery Analyzer	Yes	No	No
Agents or relays	Manager (activation and heartbeats)	Yes	No	No
Agents or relays	Relays (software and security updates)	Yes	Yes	Yes
Agents	Network Setting for Census, Good File Reputation, and Predictive Machine Learning	Yes	No	No
Agents	Global Smart Protection Server	Yes	No	No

Proxy settings

If your network uses a proxy, you can configure Deep Security to use it instead of the [default port numbers](#). Proxy settings are in a few locations.

Proxy server use

To view and edit the list of available proxies, go to **Administration > System Settings > Proxies**.

- **Primary Security Update Proxy used by Agents, Appliances, and Relays:** Select a proxy server that the Deep Security Relays will use to connect to the **Update Source** specified in the **Relays** area on the **Updates** tab (either a **Trend Micro Update Server** or **Other Update Source**).

Note: By default, **agents and appliances**¹ download Anti-Malware components of their security updates from Deep Security Relays. However, if agents or appliances cannot connect to their assigned Relays, and the **Allow Agents/Appliances to download Security Updates from this source if Deep Security Relays are not available** option is selected, agents and appliances will also use this proxy.

Warning: Before Deep Security Agent 10.0, agents didn't have support for connections through a proxy to relays. If a [ruleset download fails](#) due to a proxy, and if your agents [require a proxy to access the relay or manager \(including Deep Security as a Service\)](#), then you must either:

- update agents' software (see "Get Deep Security Agent software" on page 318), then [configure the proxy](#)
- bypass the proxy
- [change the application control rulesets relay setting](#) as a workaround

- **Deep Security Manager (Software Updates, CSSS, Product Registration and Licensing):** Select a proxy that the Deep Security Manager will use to connect to Trend Micro to validate your Deep Security licenses, to connect to the Certified Safe Software Service (a feature of the Integrity Monitoring module), and for connecting to Amazon Web Services (AWS) and VMware vCloud Cloud Accounts.

Note: Changes to the proxy settings for CSSS will not take effect until the Deep Security Manager and all Manager nodes are restarted. (You must restart the services manually.)

- **Deep Security Manager (Cloud Accounts - HTTP Protocol Only):** Select a proxy for the Deep Security Manager to use when connecting to cloud-based instances that have been added to the Deep Security Manager using the "Add Cloud Account" procedure.

Note: After you select a proxy, restart the agents that use it.

¹The Deep Security Agent and Deep Security Virtual Appliance are the components that enforce the Deep Security policies that you have defined. Agents are deployed directly on a computer. Appliances are used in VMware vSphere environments to provide agentless protection. They are not available with Deep Security as a Service.

Trend Micro Deep Security On-Premise 11.3

Proxy servers

Define the proxy servers that will be available for use by various Deep Security clients and services (for example, the proxy servers for Smart Protection on **Computer or Policy editor**¹ > **Anti-Malware** > **Smart Protection**).

The table lists the proxy protocols supported by the Deep Security services and clients:

Service	Origin	HTTP Support	SOCKS4 Support	SOCKS5 Support
Software Updates, Certified Safe Software Service, News Updates, Product Registration and Licensing	Manager	Yes	No	No
Smart Feedback	Manager	Yes	No	Yes
Cloud Accounts (AWS, VMware vCloud, Microsoft Azure)	Manager	Yes	No	No
Control Manager	Manager	Yes	No	No
Deep Discovery Analyzer	Manager	Yes	No	No
Manager (activation and heartbeats)	Agents/Relays	Yes	No	No
Relays (software and security updates)	Agents/Relays	Yes	Yes	Yes
Network Setting for Census, Good File Reputation, and Predictive Machine Learning	Agents	Yes	No	No
Global Smart Protection Server	Agents	Yes	No	No

Manage trusted certificates

Trusted certificates are used for code signing and SSL connections to external services such as a Microsoft Active Directory or VMware vCenter.

Import trusted certificates

Note: If you are importing a trusted certificate to establish trust with an Amazon Web Services region, you must use the `dsm_c` command-line tool.

To import trusted certificates using the Deep Security Manager:

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

1. In the Deep Security Manager, go to **Administration > System Settings > Security**.
2. Under **Trusted Certificates**, click **View Certificate List** to view a list of all security certificates accepted by Deep Security Manager.
3. Click **Import From File** to start the Import Certificate wizard.

To import a trusted certificate using dsm_c:

1. On the Deep Security Manager server, run the following command:

```
dsm_c -action addcert -purpose PURPOSE -cert CERTFILE
```

where the parameters are:

Parameter	Description	Sample value
PURPOSE	What type of connections the certificate will be used for. This value must be selected from one of the sample values listed on the right.	AWS - Amazon Web Services
		DSA - code signing
		SSL - SSL connections
CERTFILE	The (user-defined) name of the file containing the certificate you want to import.	/path/to/cacert.pem

Note: If you are running the Deep Security Manager in a Linux environment, you will need to run the `dsm_c` command as the root user.

View trusted certificates

Note: To view trusted certificates for Amazon Web Services connections, you must use the `dsm_c` command-line tool.

To view trusted certificates using the Deep Security Manager:

1. In the Deep Security Manager, go to **Administration > System Settings > Security**.
2. Under **Trusted Certificates**, click **View Certificate List**.

To view trusted certificates using dsm_c:

1. On the Deep Security Manager server, run the following command:

```
dsm_c -action listcerts [-purpose PURPOSE]
```

The `-purpose PURPOSE` parameter is optional and can be omitted to see a list of all certificates. If you specify a value for `PURPOSE`, then only the certificates used for that purpose will be shown.

Parameter	Description	Sample value
PURPOSE	What type of connections the certificate will be used for.	AWS - Amazon Web Services
		DSA - code signing
		SSL - SSL connections

Note: If you are running the Deep Security Manager in a Linux environment, you will need to run the `dsm_c` command as the root user.

Remove trusted certificates

Note: To remove trusted certificates for Amazon Web Services connections, you must use the `dsm_c` command-line tool.

To remove a trusted certificate using the Deep Security Manager:

1. In the Deep Security Manager, go to **Administration > System Settings > Security**.
2. Under **Trusted Certificates**, click **View Certificate List**.
3. Select the certificate you want to remove and click **Delete**.

To remove a trusted certificate using `dsm_c`:

1. Log in to Deep Security Manager .
2. Run the following command:

```
dsm_c -action listcerts [-purpose PURPOSE]
```

The `-purpose PURPOSE` parameter is optional and can be omitted to see a list of all certificates. If you specify a value for `PURPOSE`, then only the certificates used for that purpose will be shown.

Parameter	Description	Sample value
PURPOSE	What type of connections the certificate will be used for.	AWS - Amazon Web Services
		DSA - code signing
		SSL - SSL connections

3. Find the `ID` value for the certificate you want to remove in the list.

4. Run the following command:

```
dsm_c -action removecert -id ID
```

The `ID` parameter value is required.

Parameter	Description	Sample value
ID	The ID value assigned by Deep Security Manager for the certificate you want to delete.	3

Note: If you are running the Deep Security Manager in a Linux environment, you will need to run the `dsm_c` commands as the root user.

If I have disabled the connection to the Smart Protection Network, is any other information sent to Trend Micro?

When Smart Protection Network is disabled, the Deep Security Agents will not send any threat intelligence information to Trend Micro.

Linux Secure Boot support for agents

When Linux Secure Boot is enabled on a Deep Security Agent computer, the Linux kernel performs a signature check on kernel modules before they are installed. These Deep Security features install kernel modules:

- anti-malware
- web reputation
- firewall

Trend Micro Deep Security On-Premise 11.3

- intrusion prevention
- application control

Note: The Deep Security Agent is only compatible with Secure Boot on RHEL 7.

If you intend to use any of those modules on a Linux computer where Secure Boot is enabled, you must enroll the Trend Micro public key for RHEL 7 (provided during install as DS11.der) into the Linux computer's firmware so that it recognizes the Trend Micro kernel module's signature. Otherwise, the kernel module can't be installed.

Note: Deep Security refreshes the kernel module signing key in every major release (for example, 10.0 and 11.0). To keep security features functioning when you upgrade a Deep Security Agent to a new major release, you must enroll the new public key into any Linux computers that have Secure Boot enabled. You may see "Engine Offline" error message in the Deep Security Manager console because the operating system will not load the upgraded kernel module until the new public key is enrolled.

Use the Unified Extensible Firmware Interface (UEFI) Secure Boot feature to enroll the public key. If you are protecting VMware virtual machines, the Secure Boot feature is available for VMware vSphere 6.5 or newer. For instructions on how to enable it, see [Enable or Disable UEFI Secure Boot for a Virtual Machine](#) on the VMware Docs site.

Note: The Secure Boot feature is not available for AWS instances and Azure VMs.

To enroll the Trend Micro public key:

1. On the RHEL 7 computer that you want to protect, install the Deep Security Agent, if it isn't installed already.

After installation, the Trend Micro public key is in `/opt/ds_agent/DS10.der`.

2. Install the Machine Owner Key (MOK) facility, if it isn't already installed

```
yum install mokutil
```

3. Add the public key, `DS10.der`, to the MOK list:

```
mokutil --import DS10.der
```

Note: For details about manually adding the public key to the MOK list, see the [Red Hat documentation](#).

4. When prompted, enter a password that you will use later in this procedure.
5. Reboot the system.
6. After the computer restarts, the Shim UEFI key management console opens:



7. Press any key to get started.
8. On the **Perform MOK management** screen, select **Enroll MOK**.
9. On the **Enroll MOK** screen, select **View key 0**.
10. On the **Enroll the key(s)?** screen, select **Yes** and then enter the password you set in step 4, above.
11. On the **The system must now be rebooted** screen, select **OK** to confirm your changes and reboot.
12. Next, use the `keyctl` utility to check that key is on the system key ring. If the `keyctl` utility is not already installed, use this command to install it:

```
yum install keyutils
```

13. To list the keys that are on the system key ring:

```
keyctl list %:.system_keyring
```

You should see the Trend Micro signing key listed.

Activate the agent

Tip: If you haven't already installed the agent, see ["Use deployment scripts to add and protect computers" on page 437](#) or ["Manually install the Deep Security Agent" on page 322](#) for instructions.

Before the installed agent can protect its computer or be converted to a relay, you must activate the agent with Deep Security Manager. Activation registers the agent with the manager during an initial communication.

To do this, you can either:

- Activate the agent from the manager. Go to **Computers**, right-click the computer whose agent or appliance you want to activate or reactivate and select **Actions** > **Activate/Reactivate**. (Alternatively, click **Activate** or **Reactivate** in the computer's **Details** window.)
- Activate the agent through a deployment script. See ["Use deployment scripts to add and protect computers" on page 437](#) for details.
- Activate the agent from the computer where the agent is installed. Run this command:

```
dsa_control -a dsm://<dsm_host_or_IP>:<port>/
```

where:

`<dsm_host_or_IP>` is replaced with the Deep Security Manager hostname or IP address, and

`<port>` is replaced with the Deep Security Manager heartbeat port, which is 4120, by default.

For details on this command, including additional parameters, see ["Command-line basics" on page 390](#).
- Activate the agent through an event-based task ("Computer Created (by System)" event) to automatically activate computers when they connect to the manager or when the manager

syncs with an LDAP directory, cloud account, or vCenter. For more information, see ["Automatically perform tasks when a computer is added or changed" on page 422](#).

Before activation, the agent or appliance will have one of these [statuses](#):

- **No Agent/Appliance:** Indicates one of the following situations:
 - No agent or appliance is running or listening on the default port.
 - An agent or appliance is installed and running but is working with another manager and communications are configured as agent/appliance-initiated. In this case, the agent or appliance is not listening for this manager. To correct this situation, deactivate the agent from the computer.
- **Activation Required:** The agent or appliance is installed and listening, and is ready to be activated by the manager.
- **Reactivation Required:** The agent or appliance is installed and listening and is waiting to be reactivated by the manager.
- **Deactivation Required:** The agent or appliance is installed and listening, but has already been activated by another manager.
- **Unknown:** The computer has been imported (as part of an imported Computers list) without state information, or has been added by way of an LDAP directory discovery process.

After a successful activation, the agent or appliance state is Online. If the activation failed, the computer status is Activation Failed with the reason for the failure in brackets. Click this link to display the system event for more details on the reason for the activation failure.

Note: Although IPv6 traffic is supported by Deep Security 8.0 and earlier agents and appliances, it is blocked by default. To allow IPv6 traffic on Deep Security 8.0 Agents and Appliances, open a **Computer or Policy editor**¹ and go to **Settings > Advanced > Advanced Network Engine Settings**. Set the **Block IPv6 for 8.0 and Above Agents and Appliances** option to **No**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Deactivate the agent

If you want to transfer control of a computer from one Deep Security Manager installation to another, you must deactivate the agent or appliance with its current manager, and then re-activate it with the new manager.

You can normally deactivate the agent or appliance from the Deep Security Manager that is currently managing the agent or appliance. If the Deep Security Manager cannot communicate with the agent or appliance, you may have to perform the deactivation manually. To run the commands below, you must have administrator privileges on the local machine.

To deactivate the agent on Windows:

1. From a command line, change to the agent directory (Default is C:\Program Files\Trend Micro\Deep Security Agent)
2. Run the following: **dsa_control -r**

To deactivate the agent on Linux:

1. Run the following: **/opt/ds_agent/dsa_control -r**

Stop or start the agent

To start or stop the agent on Windows:

- Stop: from the command line, run the following: **sc stop ds_agent**
- Start: from the command line, run the following: **sc start ds_agent**

To start or stop the agent on Linux:

- Stop: run the following: **/etc/init.d/ds_agent stop**
- Start: run the following: **/etc/init.d/ds_agent start**

Stop or start the appliance

Stopping or starting the appliance can only be done locally on the host computer.

To start or stop the appliance on Linux:

- Stop: run the following: `/etc/init.d/ds_agent stop`
- Start: run the following: `/etc/init.d/ds_agent start`

Diagnose problems with agent deployment (Windows)

If a Deep Security Agent on Windows fails to install or activate, look in the deployment logs to find the cause and troubleshoot it.

1. Log in to the computer where you were trying to install the agent.
2. Go to `%appdata%\Trend Micro\Deep Security Agent\installer`.
3. Examine:
 - **dsa_deploy.txt** - Log from the PowerShell script. Contains agent activation issues.
 - **dsa_install.txt** - Log from the MSI installer. Contains agent installation issues.

Configure teamed NICs

"Teamed NICs" or "link aggregation" describes forming a network link on a computer by using multiple network interface cards (NICs) together. This is useful to increase the total network bandwidth, or to provide link redundancy.

You can configure teamed NICs on Windows so that they are compatible with Deep Security Agent.

On Windows, when you team NICs, it creates a new master virtual interface. This virtual interface adopts the MAC address of its first teamed physical interface.

By default, during installation or upgrade, the Windows Agent will bind to *all* virtual and physical interfaces. This includes the virtual interface created by NIC teaming. However, Deep Security Agent doesn't function properly if multiple interfaces have the same MAC address, which happens with NIC teaming on Windows

To avoid that, bind the agent *only* to the teamed virtual interface - *not* the physical interfaces.

Note: NIC teaming with Deep Security Agent requires Windows 2003 requires SP 2 or later.

Warning: Don't add or remove network interfaces from a teamed NIC *except* immediately before running the installer. Otherwise network connectivity may fail or the computer may not be correctly detected with Deep Security Manager. The agent's network driver is bound to network interfaces when you install or upgrade; the agent does not continuously monitor for changes after.

Agent settings

Agent settings are located on **Administration > System Settings > Agents**.

Tip: You can automate Agent-related system setting changes using the Deep Security API. For examples, see the [Configure Policy, Computer, and System Settings](#) guide in the Deep Security Automation Center.

Hostnames

Update the "Hostname" entry if an IP is used as a hostname and a change in IP is detected on the computer after **Agent/Appliance-initiated communication or discovery**: Updates the IP address displayed in the computer's "Hostname" property field if an IP change is detected.

Note: The Deep Security Manager always identifies computers by using a unique fingerprint, not their IP addresses or hostnames.

Agent-Initiated Activation

Note: For more information on Agent-Initiated Activation, see Command-Line Utilities and ["Use deployment scripts to add and protect computers" on page 437](#).

Allow Agent-Initiated Activation

- **For Any Computers:** Any computers, whether they are already listed on the Deep Security Manager's **Computers** page or not.
- **For Existing Computers:** Only computers already listed on the **Computers** page.
- **For Computers on the following IP List:** Only computers whose IP address has a match on the specified IP List.

Policy to assign (if Policy not assigned by activation script): The security policy to assign to the computer if no policy has been specified in the activation script.

Note: If an event-based task exists which assigns policies to computers where activation is agent-initiated, the policy specified in the event-based task will override the policy assigned here or in the activation script.

Allow Agent to specify hostname: Select this option to allow the agent to specify the hostname by providing it to the Deep Security Manager during the agent activation process.

If a computer with the same name already exists: If a computer, VMware virtual machine, AWS instance, or Azure VM with the same Agent GUID or certificate is already listed on the **Computers** page, you can configure the Deep Security Manager to take the following actions:

- **Do not allow activation:** The computer object will not be activated.
- **Activate a new Computer with the same name:** The Deep Security Manager will create a new computer object with a new name.
- **Re-activate the existing Computer:** The existing computer object will be re-activated.

Reactivate cloned Agents: When a new computer (computer, VMware virtual machine, AWS instance, or Azure VM) that is running an already activated Deep Security Agent sends a heartbeat to the Deep Security Manager, the Deep Security Manager will recognize it as a clone. It will be reactivated as a new computer without the policies or rules of the original computer .

Reactivate unknown Agents: Select this setting to allow activated computers that were deleted from Deep Security Manager to reactivate if they reconnect.

This setting is often enabled together with [Inactive Agent Cleanup](#) to ensure that certain computers can still reconnect if they are deleted. To learn more, see "[Automate offline computer removal with inactive agent cleanup](#)" on page 1438.

Note: When a removed computer reconnects, it will not have a policy, and will be added as a new computer. Any direct links to the computer will be removed from the Deep Security Manager event data.

Agent activation token: When a value is specified here, the same value must be provided when

agents activate themselves in the Deep Security Manager. You can provide this agent activation secret in the **token** parameter in the agent activation script. For example, the script for agent-initiated activation on a Linux machine might look like this:

```
/opt/ds_agent/dsa_control -a dsm://172.31.2.247:4120/ "token:secret"
```

Note: In a multi-tenant environment, the **Agent activation token** setting applies only to the primary tenant.

Agent Upgrade

If your environment includes Deep Security Agent installed on Linux computers, you can select **Automatically upgrade agents on activation**. When this option is selected and the agent is activated (or reactivated) on a Linux computer, the agent will be upgraded to the latest software version that's compatible with your Deep Security Manager.

For more information, see ["Automatically upgrade agents on activation" on page 341](#).

Inactive Agent Cleanup

If your Deep Security deployment has a large number of offline computers not communicating with the Deep Security Manager that no longer need to be managed, you can automatically remove them with inactive agent cleanup.

Delete Agents that have been inactive for: The period that a computer must be inactive for before being removed.

For more information on configuring inactive agent cleanup, see ["Automate offline computer removal with inactive agent cleanup" on page 1438](#).

Data Privacy

Allow packet data capture on encrypted traffic (SSL): The Intrusion Prevention module allows you to record the packet data that triggers Intrusion Prevention Rules. This setting lets you turn on data capture when Intrusion Prevention rules are being applied to encrypted traffic.

Agentless vCloud Protection

Allow Appliance protection of vCloud VMs: Allow virtual machines in a vCloud environment to be protected by a Deep Security Virtual Appliance and let the security of those virtual machines

be managed by tenants in a multi-tenancy Deep Security environment.

Install the Deep Security Notifier

The Deep Security Notifier is a utility for physical or virtual Windows machines which provides local notification when malware is detected or malicious URLs are blocked. The Deep Security Notifier is automatically installed as part of the Deep Security Agent on Windows machines. The stand-alone installation described here is intended for use on agentless Windows VMs being protected by the Deep Security Virtual Appliance. For more information, see ["Deep Security Notifier" on page 514](#).

Copy the Installation Package

Copy the installation file to the computer.

Install the Deep Security Notifier for Windows

Note: Remember that you must have administrator privileges to install and run the Deep Security Notifier on Windows machines.

1. Double-click the installation file to run the installer package. Click **Next** to begin the installation.
2. Read the license agreement and click **Next**.
3. Click **Install** to proceed with the installation.
4. Click **Finish** to complete the installation.

The Deep Security Notifier is now installed and running on this computer, and the Notifier icon appears in the Windows System Tray. When malware is detected or a URL has been blocked, the Notifier will display pop-up notifications. You can manually disable them by double-clicking the tray icon to open the Notifier status and configuration window.

Note: On VMs protected by a virtual appliance, the anti-malware module must be licensed and enabled on the VM for the Deep Security Notifier to display information.

Create an Azure app for Deep Security

In your operating environment, it may not be desirable to allow the Deep Security Manager to access Azure resources with an account that has both the Global Administrator role for the Azure Active Directory and the Subscription Owner role for the Azure subscription. As an alternative, you can create an Azure app for the Deep Security Manager that provides read-only access to Azure resources.

Note: To create an Azure app, your account must have been assigned the User Administrator role for the Azure Active Directory and the User Access Administrator role for the Azure subscription.

To do this you will need to:

1. ["Record the Azure Active Directory ID" below.](#)
2. ["Create the Azure app" below.](#)
3. ["Record the Azure app ID and password" on the next page.](#)
4. ["Record the Subscription ID" on the next page.](#)
5. ["Assign the Azure app a reader role and add it to your Azure Subscription" on the next page.](#)

Record the Azure Active Directory ID

1. On the Hub menu, click **Azure Active Directory** and select your Azure Active Directory.
2. In the **Azure Active Directory** blade, click **Properties**.
3. Record the **Directory ID**.

Create the Azure app

1. In the **Azure Active Directory** blade, click **App registrations**.
2. Click **Add**.
3. Enter a **Name** (for example, Deep Security Azure Connector).
4. For the **Application Type**, select **Web app/API**.

5. Enter a **Sign-on URL**. The URL can be any value, but it must begin with the `http` prefix.

Note: You must enter a URL in the **Sign-on URL** field, even though it is not used by Deep Security Azure integration. The value does not need to resolve to a valid address.

6. Click **Create**. The **Deep Security Azure Connector** app will appear in the **App registrations** list.

Record the Azure app ID and password

1. In the **App registrations** list, click on the **Deep Security Azure Connector**.
2. Record the **Application ID**.
3. Click on **All settings**.
4. On the **Settings** blade, click **Keys**.
5. Enter a **Description** for the key.
6. Select an appropriate **Duration**.
7. Click **Save**.

The key **Value** will appear.

8. Record the key **Value**. This will be used as the Application Password when registering the Azure app with Deep Security.

Record the Subscription ID

1. On the Hub menu, go to **All Services** and click **Subscriptions**, then select the subscription you added the Deep Security Azure Connector app to.
2. Record the **Subscription ID**.

Assign the Azure app a reader role and add it to your Azure Subscription

1. In the **Subscriptions** blade, click on **Access Control (IAM)**.
2. Click **Add**.
3. Click on the **Reader** role.
4. Select the **Deep Security Azure Connector** app. If it is not already in the list, enter it in the search field and select it when it appears.
5. Click **OK**.

You can now continue configuring Deep Security to add Azure virtual machines by following the remaining steps of the Advanced procedure in ["Add a Microsoft Azure account to Deep Security" on page 477](#).

Distribute security and software updates with relays

To ensure maximum protection for your Deep Security deployment, there are two components that you must periodically update. **Software updates** add new features and improvements to the Deep Security Agent, while **security updates** provide immediate protection against emerging threats.

Deep Security **relays** help to optimize the distribution of these updates. A relay is an agent that is capable of distributing the software and security updates to other agents and virtual appliances. Relays can:

- Reduce WAN bandwidth costs by shaping update traffic.
- Provide redundancy to update distribution.

Note: Relays are a mandatory part of a Deep Security deployment. Your deployment must include at least 1 relay.

First learn about ["How relays work" below](#), then how to ["Determine the number of relays to use" on the next page](#), and finally how to ["Configure one or more relays" on page 382](#).

You can also ["Remove relay functionality from an agent" on page 387](#) if needed.

How relays work

Relays download security updates from the Trend Micro Active Update servers directly through your WAN connection, and software updates from the Deep Security Manager. When you use relays, security and software updates only need to be downloaded once through your WAN connection. Relays then function as update distribution centers and the security and software updates are downloaded by other agents when they are directed to do so by the Deep Security Manager.

Note: If a relay cannot connect to a Deep Security Manager to download updates, it will download them directly from the Deep Security Download Center.

For more detailed information on security updates and how relays distribute them, see ["Get and distribute security updates" on page 1018](#).

Relays are organized into **relay groups**. Organizing relays into groups ensures that the update load is distributed across multiple relays, and also adds redundancy to your Deep Security deployment.

Relay groups can also be part of a distribution hierarchy. By creating distribution hierarchies for your relay groups, you can further improve performance and bandwidth usage by specifying:

- Which relay groups an agent should download security and software updates from.
- The order that relay groups should download security and software updates from each other.

Determine the number of relays to use

Although a Deep Security deployment requires a minimum of 1 relay, as a baseline Trend Micro recommends using at least 2 relays for your deployment. However, you may need to use additional relays depending on:

- ["Geographic region of agents " below](#).
- ["Network configuration " below](#).
- ["Network bandwidth usage " on the next page](#).

Geographic region of agents

Trend Micro recommends that agents download updates from a relay group in the same geographic region. If you have agents in multiple regions, each region should have its own relay group with at least one relay.

Network configuration

Your network configuration may include a low bandwidth WAN connection, routers, firewalls, or proxies between the network segments of agents and a remote Deep Security Manager or Trend

Micro Active Update server. These configurations may cause bottlenecks that slow down the distribution of software and security updates. To reduce the impact of these configurations, you should place a relay inside each network segment.

Network bandwidth usage

The download of security and software updates to the agents can be network intensive. You can use relays to shape how your network bandwidth is used to distribute updates. By placing a relay inside a network segment, it becomes the single download source for security and software updates for that segment. Agents will then update from the local relay, reducing the overall bandwidth required to download updates from the WAN connection to the local internal connection.

Sizing recommendations

Note: Before you enable more relays, check that the computers that you want to enable as relays meet the requirements in ["Deep Security Agent and Relay sizing" on page 108](#). Also check that the agent you are using supported the relay feature (see ["Supported features by platform" on page 85](#)).

In most deployments, Trend Micro recommends deploying a minimum of 2 relays for redundancy, which can be co-located with a Deep Security Manager. However, as noted above, you should also consider factors such as geographical location, network configuration and network bandwidth when determining how many relays to deploy. If your deployment has a large number of agents (more than 10,000), relays should be deployed on a dedicated system.

You might also want to add more relays if:

- The network configuration of your environment has changed.
- You want to provide additional redundancy to update distribution.

Warning: You should **only use as many relays as is necessary**, because deploying unneeded relays on your network will actually decrease performance. A relay requires more system resources than an ordinary agent.

Configure one or more relays

To configure a relay, you need to:

1. ["Create one or more relay groups" below.](#)
2. ["Enable one or more relays" on page 385.](#)
3. ["Assign agents to a relay group" on page 385.](#)
4. ["Configure relay settings for security and software updates" on page 386.](#)

Create one or more relay groups

Every relay must belong to a relay group. If you installed the Deep Security Relay during the Deep Security Manager installation, a default relay group will have been automatically created. You can also create additional relay groups.

Note: Each agent will try to download updates from a randomly arranged list of the relays in the group it is assigned to. If there's no response from a particular relay, the agent will try another from the list until it can successfully download the update. The list is random for each agent so that the update load is shared evenly across relays in a group.

1. Go to **Administration > Updates > Relay Management**.
2. On the Relay Management window, click **New Relay Group**. In the Relay Group Properties pane that appears, configure the settings for the relay group:
 - Enter a **Name** for the relay group.
 - Select an **Update Source**. The update source determines where the relay group will download and distribute security updates from. The update source can be either:
 - The Primary Security Update Source
By default, the Primary Security Update Source is the Trend Micro Active Update servers, but you can configure it to be a local mirror instead. A default relay group will always use the Primary Security Update Source. For more information, see ["Configure a security update source and settings" on page 1021](#).
 - A parent relay group
If you have already created other relay groups, you can configure a relay group to use one of them as the update source.

Tip: When selecting an update download source for a relay group, you should select the source that best matches your cost and speed requirements. Even if a relay group is part of a distribution hierarchy, it does not necessarily need to download updates from a relay in a parent group if downloading updates from the Primary Security Update Source would be cheaper or faster.

Tip: To improve performance in very large deployments, create multiple relay groups and arrange relays in a hierarchy: one or more first-level relay groups download updates directly from the Trend Micro Active Update servers, and then second-level relay groups download updates from the first-level group, and so on. However, each group level adds latency, and if there are too many levels of relay groups, the total latency can be greater than the bandwidth optimization provided by relays, resulting in decreased performance.

- Select the **Update Source Proxy** (if any) that relays must use to access the primary security update source.

Every relay group can be configured to download security updates through a proxy server, except the Default Relay Group. The Default Relay Group uses the same proxy as Deep Security Manager. See ["Connect agents behind a proxy" on page 351](#) and ["Configure a proxy for anti-malware and rule updates" on page 403 \(CLI\)](#).

If the relay group is configured to use the Primary Security Update Source, relays will use this proxy. Otherwise, if this relay group is configured to download security updates from another relay group, relays won't use the proxy unless they can't connect to the parent relay group, and therefore are trying to connect to the Primary Security Update Source.

Warning: Deep Security Agents version 10.0 and earlier do not have support for connections through a proxy to relays. If an application control [ruleset download fails](#) due to a proxy, and if your agents require a proxy to access the relay or manager (this includes Deep Security as a Service), then you must either:

- update agents' software (See ["Get Deep Security Agent software" on page 318](#)) and then [configure the proxy](#)

- bypass the proxy
- [change the application control rulesets relay setting](#) as a workaround

3. Repeat the above steps if you need to create more relay groups.

Enable one or more relays

1. Go to **Administration > Updates > Relay Management**.
2. Click on a relay group to select it.
3. Click **Add Relay**.
4. Select a computer from the Available Agents list and click **Enable Relay and Add to Group**. You can use the search field to filter the list of computers.

The computer is added to the relay group, and displays a relay icon ().

5. If Windows Firewall or iptables is enabled on the computer, add a firewall rule that allows incoming connections to the [relay's listening port number](#).
6. If relays must connect through a proxy, see "[Connect agents, appliances, and relays to security updates via proxy](#)" on page 352.

Note: Newly activated relays will be automatically notified by the Manager to update their security update content.

Assign agents to a relay group

You can either assign an agent to a relay group manually, or you can set up an [event-based task](#) to assign agents automatically.

1. In Deep Security Manager, go to **Computers**.
2. Right click the computer and select **Actions > Assign Relay Group**.

To assign multiple computers, Shift-click or Ctrl-click computers in the list, and then select **Actions > Assign Relay Group**.

3. Select the relay group to use from the list, or from the Computer Details window, use **Download Updates From** to select the relay group.

Configure relay settings for security and software updates

Deep Security Manager provides additional settings on the **Administration > System Settings > Updates** page that affect how relays are used to perform security and software updates.

Security updates

- **Allow supported 8.0 and 9.0 Agents to be updated:** Select this option if you require support for agents on Windows 2000, AIX, or Solaris. By default, Deep Security Manager does not download updates for Deep Security Agent 9.0 and earlier because they are not supported with this version of Deep Security Manager.
- **Download Patterns for all Regions:** If you are operating in multi-tenancy mode and any of your tenants are in other regions, select this option. If this option is deselected, a relay will only download and distribute patterns for the region (locale) that Deep Security Manager was installed in.
- **Use the Primary Tenant Relay Group as my Default Relay Group (for unassigned Relays):** Use the Primary Tenant Relay group. By default, the primary tenant gives other tenants access to its relays. This way, tenants don't need to set up their own relays. If you don't want other tenants to share the primary tenant's relays, deselect this option and create separate relays for other tenants.

Note: If this option is deselected, when you click **Administration > Updates > Relay Groups**, the relay group name will be "Default Relay Group" rather than "Primary Tenant Relay Group".

Note: This setting appears only if you have enabled multi-tenant mode.

For information about other security update settings, see ["Get and distribute security updates" on page 1018](#).

Software updates

- The **Allow Relays to download software updates from Trend Micro Download Center when Deep Security Manager is not accessible** option is useful when your Deep Security Manager is in an enterprise environment and you are managing computers in a cloud environment. If you enable this option and configure a relay in the cloud, the relay will be able to get software updates directly from the Download Center, removing the need for manual software upgrades or opening [port numbers](#) into your enterprise environment from the cloud.

For information about other software update settings, see ["About upgrades" on page 981](#).

Remove relay functionality from an agent

You might want to remove the relay functionality from a relay-enabled agent if:

- You are noticing communication delays because there are too many relay-enabled agents in your environment.
- The computer where the agent is installed does not meet the minimum system requirements for relay functionality.

Note: Deep Security uses relays to store data when a virtual machine protected by a Deep Security Virtual Appliance is being migrated by vMotion. If your deployment uses vMotion to migrate virtual machines, removing the relay functionality from a given agent may result in a loss of protection to the migrated virtual machine as well as loss of the security events of the virtual appliance .

The procedure for removing relay functionality differs depending on if the agent version is ["10.2 or later" below](#) or ["10.1 or earlier" on the next page](#).

10.2 or later

1. Go to **Administration > Updates > Relay Management**.
2. Click the arrow next to the relay group with the computer you want to remove relay functionality from.

3. Click on the computer, and then click **Remove Relay**.

The agent status will change to "Disabling" and the relay functionality will be removed from the agent.

Note: It may take up to 15 minutes for the relay functionality to be removed from the agent. If the agent is in the "disabling" state for significantly longer than this, deactivate and reactivate the agent to finish removing relay functionality from the agent.

10.1 or earlier

Note: If you use multi-factor authentication with Deep Security Manager, you will need to temporarily disable it before proceeding. For information on how to do this, see "[Set up multi-factor authentication](#)" on page 1058.

1. Go to **Administration > System Settings > Advanced** in the Deep Security Manager, click **Enabled - Access the WSDL at:** in the SOAP Web Service API section, and click **Save**.
2. Download the Disable Relay Tool: <https://s3.amazonaws.com/customerscripts/Deep-Security-Disable-Relays.exe>.
3. Run the tool on any Windows computer that can communicate with the computer where the Deep Security Manager is installed.
4. Enter the IP address and port of the Deep Security Manager and your administrator user name and password when prompted.
5. If you are using Deep Security as a Service or a multi-tenant Deep Security Manager, you also have to enter the tenant name.
6. Click **OK** when you have finished entering the information required for the tool to communicate with the Deep Security Manager.
7. Select all of the servers with relays that you want to downgrade from the list retrieved by the Disable Relay Tool and click **Disable Relay On Select Hosts** in the lower left corner.
8. Leave the tool open and click **Refresh Relay List** to monitor the progress of the downgrade. It can take up to 15 minutes to downgrade the agents on the servers you selected.
9. After a relay-enabled agent has been downgraded to a normal agent and no longer appears in the list of servers in the Disable Relay Tool, you should remove the relay files in the following locations for that agent:

- Windows: `C:\ProgramData\Trend Micro\Deep Security Agent\relay`
- Linux: `/var/opt/ds_agent/relay`

DevOps, automation and scaling

To support DevOps workflows, Deep Security offers APIs to automate, monitor, and manage security throughout the release lifecycle. (See ["Use the Deep Security API to automate tasks" on page 417.](#))

To accelerate integration with popular DevOps tools, we've provided the following resources in Github for Chef, Puppet, and Ansible:

- <https://github.com/deep-security/puppet>
- <https://github.com/deep-security/chef>
- <https://github.com/deep-security/ansible>

These resources provide a starting point to integrate Deep Security with your specific deployment, including agent deployment and configuration and support for elastic workloads.

Deep Security also offers many other ways to speed up the protection of your computers and other resources:

- ["Schedule Deep Security to perform tasks" on page 418](#)
- ["Automatically perform tasks when a computer is added or changed" on page 422](#)
- ["AWS Auto Scaling and Deep Security" on page 427](#)
- ["Use deployment scripts to add and protect computers" on page 437](#)
- ["Automatically assign policies by AWS instance tags" on page 441](#)
- ["Command-line basics" on the next page](#)

In addition, Deep Security provides the ability to forward events to SIEMs such as Splunk, QRadar, ArcSight, as well as Amazon SNS. For details, see:

- ["Forward Deep Security events to an external syslog or SIEM server" on page 1111](#)
- ["Access events with Amazon SNS" on page 1158](#)

Command-line basics

You can use the local command-line interface (CLI) to command both Deep Security Agents and the Deep Security Manager to perform many actions. The CLI can also configure some settings, and to display system resource usage.

Tip: You can also automate many of the CLI commands below using the Deep Security API. To get started with the API, see the [First Steps Toward Deep Security Automation](#) guide in the Deep Security Automation Center.

Below are command syntax and examples.

Deep Security Agent

Note: On Windows, when self-protection is enabled (`-s <num>`, `--selfprotect=<num>` where 1 is enable, and 0 is disable), local users cannot uninstall, update, stop, or otherwise control the agent. Your CLI commands must include the authentication password.

dsa_control

You can use `dsa_control` to configure some agent settings, and to manually trigger it to perform some actions such as activation, an anti-malware scan, or baseline rebuild.

In Windows:

- Open a Command Prompt as Administrator
- `cd C:\Program Files\Trend Micro\Deep Security Agent\`
- `dsa_control -m "AntiMalwareManualScan:true"`

In Linux:

- `sudo /opt/ds_agent/dsa_control -m "AntiMalwareManualScan:true"`

Usage

```
dsa_control [-a <str>] [-b] [-c <str>] [-d] [-g <str>] [-s <num>] [-m] [-p <str>] [-r] [-R <str>] [-t <num>] [-u <str>:<str>] [-w <str>:<str>] [-x dsm_proxy://<str>] [-y
```

```
relay_proxy://<str>] [--buildBaseline] [--scanForChanges] [Additional keyword:value  
data to send to manager during activation or heartbeat...]
```

Parameter	Description
<pre>-a <str>, -- activate=<str></pre>	<p>Activate agent with manager at the specified URL in this format:</p> <pre>dsm://<host>:<port>/</pre> <p>where:</p> <ul style="list-style-type: none"> • <code><host></code> could be either the manager's fully qualified domain name (FQDN), IPv4 address, or IPv6 address • <code><port></code> is the manager's listening port number <p>Optionally, after the argument, you can also specify some settings such as the description to send during activation. See "Agent-initiated heartbeat command ("dsa_control -m")" on page 394. They must be entered as key:value pairs (with a colon as a separator). There is no limit to the number of key:value pairs that you can enter, but the key:value pairs must be separated from each other by a space. Quotation marks around the key:value pair are required if it includes spaces or special characters.</p>
<pre>-b, --bundle</pre>	Create an update bundle.
<pre>-c <str>, -- cert=<str></pre>	Identify the certificate file.
<pre>-d, --diag</pre>	Generate an agent package. For more detailed instructions, see " Create an agent diagnostic package via CLI on a protected computer " on page 1487.
<pre>-g <str>, -- agent=<str></pre>	<p>Agent URL. Defaults to:</p> <pre>https://localhost:<port>/</pre> <p>where <code><port></code> is the manager's listening port number.</p>
<pre>-m, --heartbeat</pre>	Force the agent to contact the manager now.

Parameter	Description
<code>-p <str>, --passwd=<str></code>	Authentication password. If you type the password directly into the command line, it will be displayed on screen. To hide the password with asterisks (*) while you type, enter the interactive form of the command, which will prompt you for the password: <code>dsa_control -p *</code>
<code>-r, --reset</code>	Reset the agent's configuration. This will remove the activation information from the agent and deactivate it.
<code>-R <str>, --restore=<str></code>	Restore a quarantined file.
<code>-s <num>, --selfprotect=<num></code>	Enable self-protection on the agent by preventing local end-users from uninstalling, stopping, or otherwise controlling the agent. Command-line instructions must include the authentication password when self-protection is enabled. (1: enable, 0: disable). This is a Windows-only feature.
<code>-t <num>, --retries=<num></code>	If dsa_control cannot contact the agent service to carry out accompanying instructions, this parameter instructs dsa_control to retry <code><num></code> number of times. There is a 1 second pause between retries.
<code>-u <user>:<password></code>	If the agent connects through a proxy to the manager, provide the proxy user name and password, separated by a colon (:). To remove the username and password, type an empty string (""). Basic authentication only. Digest and NTLM are not supported.
<code>-w <user>:<password></code>	If the agent connects through a proxy to a relay for security updates and software, provide the proxy user name and password, separated by a colon (:).
<code>-x dsm_ proxy://<str>:<num></code>	If the agent connects through a proxy to the manager, provide the proxy's IPv4/IPv6 address or FQDN and port number , separated by a colon (:). To remove the address, instead of a URL, type an empty string (""). Square brackets must surround IPv6 addresses. For example: <code>dsa_control -x "dsm_proxy://[fe80::340a:7671:64e7:14cc]:808/"</code>
<code>-y relay_</code>	If the agent connects through a proxy to a relay for security updates and software,

Parameter	Description
<code>proxy://<str>:<num></code>	provide the proxy's IP address or FQDN and port number , separated by a colon (:).
<code>--buildBaseline</code>	Build the baseline for integrity monitoring.
<code>--scanForChanges</code>	Scan for changes for integrity monitoring.
<code>--max-dsm-retries</code>	Number of times to retry an activation. Valid values are 0 to 100, inclusive. The default value is 30.
<code>--dsm-retry-interval</code>	Approximate delay in seconds between retrying activations. Valid values are 1 to 3600, inclusive. The default value is 300.

Agent-initiated activation ("dsa_control -a")

The agent installed on a computer must be activated before the manager can assign rules and policies to protect the computer. Activation includes the exchange of unique fingerprints between the agent and the manager to authenticate each other for encrypted channels. This ensures that only one manager (or one of the other Deep Security Manager nodes that are connected to the same database) can send instructions to and communicate with the agent.

Activation can be either manager-initiated or agent-initiated (AIA), if enabled. AIA is useful if either a firewall/NAT prevents the manager from initiating the connection to agents, or if you deploy many agents at once, and you want to write a script to automate activation.

1. On Deep Security Manager, go to **Administration > System Settings > Agents**.
2. Select **Allow Agent-Initiated Activation**.
3. In your deployment script, after you install Deep Security Agent on the computer, run the activation command, such as:

```
dsa_control -a dsm://<host>:<port>/
```

where:

- `<host>` could be either the manager's fully qualified domain name (FQDN), IPv4 address, or IPv6 address

- `<port>` is the agent-to-manager communication [port number](#).)

For example:

```
dsa_control -a dsm://dsm.example.com:4120/ hostname:www12 "description:Long  
Description With Spaces"
```

```
dsa_control -a dsm://fe80::ad4a:af37:17cf:8937:4120
```

Optionally, you can also specify some settings such as the description to send during activation. See ["Agent-initiated heartbeat command \("dsa_control -m"\)"](#) below.

Agent-initiated activation via proxy

If agents must connect through a proxy to the manager, you can configure agent-initiated communication via a proxy.

1. On Deep Security Manager, go to **Administration > System Settings > Agents**.
2. In the **Agent-Initiated Activation** area:
 - Select **Allow Agent-Initiated Activation**.
 - Select **Allow Agent to specify hostname**.
 - From the **If a computer with the same name exists** list, select **Activate a new Computer with the same name**.
3. Click **Save**.
4. In your deployment script, after you install Deep Security Agent on the computer but *before* you activate it, run the proxy configuration commands, such as:

```
dsa_control -x "dsm_proxy://proxy.example.com:808/"  
dsa_control -u "root:Passw0rd!"  
dsa_control -a "dsm://dsm.example.com:4120/"
```

Agent-initiated heartbeat command ("dsa_control -m")

You can force the agent to immediately send a heartbeat to the manager.

Like activation, the heartbeat command can also send settings to the manager during the connection.

Parameter	Description	Example	Use during Activation	Use during Heartbeat
<code>AntiMalwareCancelManualScan</code>	Boolean. Cancels an on-demand ("manual") scan that is currently occurring on the computer.	"AntiMalwareCancelManualScan:true"	no	yes
<code>AntiMalwareManualScan</code>	Boolean. Initiates an on-demand ("manual") anti-malware scan on the computer.	"AntiMalwareManualScan:true"	no	yes
<code>description</code>	String. Sets the computer's description. Maximum length 2000 characters.	"description:Extra information about the host"	yes	yes
<code>displayname</code>	String. Sets the display name shown in parentheses next to the	"displayname:the_name"	yes	yes

Parameter	Description	Example	Use during Activation	Use during Heartbeat
	hostname on Computers . Maximum length 2000 characters.			
<code>externalid</code>	Integer. Sets the <code>externalid</code> value. This value can be used to uniquely identify an agent. The value can be accessed using the SOAP web service API.	"externalid:123"	yes	yes
<code>group</code>	String. Sets which group the computer belongs to on Computers . Maximum length 254 characters per	"group:Zone A web servers"	yes	yes

Parameter	Description	Example	Use during Activation	Use during Heartbeat
	<p>group name per hierarchy level.</p> <p>The forward slash ("/") indicates a group hierarchy. The <code>group</code> parameter can read or create a hierarchy of groups. This parameter can only be used to add computers to standard groups under the main "Computers" root branch. It cannot be used to add computers to groups belonging to directories</p>			

Parameter	Description	Example	Use during Activation	Use during Heartbeat
	(Microsoft Active Directory), VMware vCenters, or cloud provider accounts.			
groupid	Integer.	"groupid:33"	yes	yes
hostname	String. Maximum length 254 characters. The hostname can specify an IP address, hostname or FQDN that the manager can use to connect to the agent.	"hostname:www1"	yes	no
IntegrityScan	Boolean. Initiates an integrity scan on the computer.	"IntegrityScan:true"	no	yes
policy	String.	"policy:Policy Name"	yes	yes

Parameter	Description	Example	Use during Activation	Use during Heartbeat
	<p>Maximum length 254 characters.</p> <p>The policy name is a case-insensitive match to the policy list. If the policy is not found, no policy will be assigned.</p> <p>A policy assigned by an event-based task will override a policy assigned during agent-initiated activation.</p>			
<code>policyid</code>	Integer.	"policyid:12"	yes	yes
<code>relaygroup</code>	<p>String.</p> <p>Links the computer to a</p>	"relaygroup:Custom Relay Group"	yes	yes

Parameter	Description	Example	Use during Activation	Use during Heartbeat
	<p>specific relay group. Maximum length 254 characters.</p> <p>The relay group name is a case-insensitive match to existing relay group names. If the relay group is not found, the default relay group will be used.</p> <p>This does not affect relay groups assigned during event-based tasks. Use either this option or event-based tasks, not</p>			

Trend Micro Deep Security On-Premise 11.3

Parameter	Description	Example	Use during Activation	Use during Heartbeat
	both.			
relaygroupid	Integer.	"relaygroupid:123"	yes	yes
relayid	Integer.	"relayid:123"	yes	yes
tenantIDand token	String. If using agent-initiated activation as a tenant, both tenantID and token are required. The tenantID and token can be obtained from the deployment script generation tool.	"tenantID:12651ADC-D4D5" and "token:8601626D-56EE"	yes	yes
RecommendationScan	Boolean. Initiate a recommendation scan on the computer.	"RecommendationScan:true"	no	yes
UpdateComponent	Boolean. Instructs Deep Security Manager to	"UpdateComponent:true"	no	yes

Parameter	Description	Example	Use during Activation	Use during Heartbeat
	perform a security update.			
<code>RebuildBaseline</code>	Boolean. Rebuilds the integrity monitoring baseline on the computer.	"RebuildBaseline:true"	no	yes
<code>UpdateConfiguration</code>	Boolean. Instructs Deep Security Manager to perform a "Send Policy" operation.	"UpdateConfiguration:true"	no	yes

Activate an agent

To activate an agent from the command line, you need to know the tenant ID and password. You can get them from the deployment script.

1. In the top right corner of Deep Security Manager, click **Support > Deployment Scripts**.
2. Select your platform.
3. Select **Activate Agent automatically after installation**.
4. In the deployment script, locate the strings for `tenantID` and `token`.

Windows

In PowerShell:

Trend Micro Deep Security On-Premise 11.3

```
& $Env:ProgramFiles"\Trend Micro\Deep Security Agent\dsa_control" -a <manager URL>  
<tenant ID> <token>
```

In cmd.exe:

```
C:\Windows\system32>"\Program Files\Trend Micro\Deep Security Agent\dsa_control" -a  
<manager URL> <tenant ID> <token>
```

Linux

```
/opt/ds_agent/dsa_control -a <manager URL> <tenant ID> <token>
```

Configure a proxy for anti-malware and rule updates

If the agent must connect to its relay through a proxy, you must configure the proxy connection.

Windows

1. Open a command prompt (cmd.exe) as Administrator.
2. Enter these commands:

```
cd C:\Program Files\Trend Micro\Deep Security Agent\  
dsa_control -w myUserName:MTPassw0rd  
dsa_control -y relay_proxy://squid.example.com:443
```

Linux

```
/opt/ds_agent/dsa_control -w myUserName:MTPassw0rd  
  
/opt/ds_agent/dsa_control -y relay_proxy://squid.example.com:443
```

Configure a proxy for connections to the manager

If the agent must connect to its manager through a proxy, you must configure the proxy connection.

Windows

1. Open a command prompt (cmd.exe) as Administrator.
2. Enter these commands:

Trend Micro Deep Security On-Premise 11.3

```
cd C:\Program Files\Trend Micro\Deep Security Agent\  
dsa_control -u myUserName:MTPassw0rd  
dsa_control -x dsm_proxy://squid.example.com:443
```

Linux

```
/opt/ds_agent/dsa_control -u myUserName:MTPassw0rd  
/opt/ds_agent/dsa_control -x dsm_proxy://squid.example.com:443
```

Force the agent to contact the manager

Windows

In PowerShell:

```
& "& "\Program Files\Trend Micro\Deep Security Agent\dsa_control" -m
```

In cmd.exe:

```
C:\Windows\system32>"\Program Files\Trend Micro\Deep Security Agent\dsa_control" -m
```

Linux

```
/opt/ds_agent/dsa_control -m
```

Initiate a manual anti-malware scan

Windows

1. Open a command prompt (cmd.exe) as Administrator.
2. Enter these commands:

```
cd C:\Program Files\Trend Micro\Deep Security Agent\  
dsa_control -m "AntiMalwareManualScan:true"
```

Linux

```
/opt/ds_agent/dsa_control -m "AntiMalwareManualScan:true"
```


Create a diagnostic package

If you need to troubleshoot a Deep Security Agent issue, your support provider might ask you to create and send a diagnostic package from the computer. For more detailed instructions, see ["Create an agent diagnostic package via CLI on a protected computer" on page 1487](#).

Note: You can produce a diagnostic package for a Deep Security Agent computer through the Deep Security Manager but if the agent computer is configured to use [Agent/Appliance Initiated communication](#), then the manager cannot collect all the required logs. So when Technical Support asks for a diagnostic package, you need to run the command directly on the agent computer.

Reset the agent

This command will remove the activation information from the target agent and deactivate it.

Windows

In PowerShell:

```
& "& "Program Files\Trend Micro\Deep Security Agent\dsa_control" -r
```

In cmd.exe:

```
C:\Windows\system32>"Program Files\Trend Micro\Deep Security Agent\dsa_control" -r
```

Linux

```
/opt/ds_agent/dsa_control -r
```

dsa_query

You can use the `dsa_query` command to display agent information:

- License-status of each component
- Scan progress
- Version information of security update components

Usage

```
dsa_query [-c <str>] [-p <str>] [-r <str>]
```

Parameter	Description
<p><code>-p, --passwd</code> <code><string></code></p>	<p>Authentication password. Required when agent self-protection is enabled.</p> <p>Note: For some query-commands, authentication can be bypassed directly, in such case, password is not required.</p>
<p><code>-c, --cmd</code> <code><string></code></p>	<p>Execute query-command against the agent. The following commands are supported:</p> <ul style="list-style-type: none"> • <code>"GetHostInfo"</code>: to query which identity is returned to the manager during a heartbeat • <code>"GetAgentStatus"</code>: to query which protection modules are enabled and other miscellaneous information • <code>"GetComponentInfo"</code>: to query version information of anti-malware patterns and engines • <code>"GetPluginVersion"</code>: to query version information of the agent and protection modules
<p><code>-r, --raw</code> <code><string></code></p>	<p>Returns the same query-command information as <code>"-c"</code> but in raw data format for third party software interpretation.</p>
<p><code>pattern</code></p>	<p>Wild card pattern to filter result. Optional.</p> <p>Example:</p> <pre>dsa_query -c "GetComponentInfo" -r "au" "AM*"</pre>

Check CPU usage and RAM usage

Windows

Use the Task Manager or procmon.

Linux

`top`

Check that ds_agent processes or services are running

Windows

Use the Task Manager or procmon.

Linux

```
ps -ef|grep ds_agent
```

Restart an agent on Linux

```
service ds_agent restart
```

or

```
/etc/init.d/ds_agent restart
```

Some actions require either a `-tenantname` parameter or a `-tenantid` parameter. If execution problems occur when you use the tenant name, try the command using the associated tenant ID.

Deep Security Manager

You can use the `dsm_c` command to configure some settings on the manager, and to unlock user accounts.

Note: Some commands may cause the Deep Security Manager to restart. Once the commands have been run, ensure the Deep Security Manager has started up again.

Usage

```
dsm_c -action actionname
```

Tip: To print help on the command, use the `-h` option: `dsm_c -h`

Note: All of the parameters shown in brackets in the table below are mandatory.

Some actions require either a `-tenantname` parameter or a `-tenantid` parameter. If execution problems occur when you use the tenant name, try the command using the associated tenant ID.

Action Name	Description	Usage
<code>addcert</code>	Add a trusted certificate.	<code>dsm_c -action addcert -purpose PURPOSE -cert CERT</code>
<code>addregion</code>	Add a private cloud provider region.	<code>dsm_c -action addregion -region REGION -display DISPLAY -endpoint ENDPOINT</code>
<code>changesetting</code>	<p>Change a setting.</p> <p>Warning: Back up your deployment before running the command. Don't use this command unless you understand the effects of the setting. Some misconfigurations can make your service unavailable, or your data unreadable.</p>	<pre>dsm_c -action changesetting -name NAME [-value VALUE -valuefile FILENAME] [-computerid COMPUTERID] [-computername COMPUTERTNAME] [-policyid POLICYID] [-policyname POLICYNAME] [-tenantname TENANTNAME -tenantid TENANTID]</pre>

Action Name	Description	Usage
	Usually, you should only use this command if requested by your technical support provider, who will tell you which setting <code>NAME</code> to change. Sometimes this command is required during normal use. If so, the setting will be described in that section of the documentation, such as masterkey .	
<code>createinsertstatements</code>	Create insert statements (for export to a different	<code>dsm_c -action createinsertstatements [-file FILEPATH] [-generateDDL] [-databaseType sqlserver oracle] [-maxresultfromdb count]</code>

Action Name	Description	Usage
	database).	<code>[-tenantname TENANTNAME -tenantid TENANTID]</code>
<code>diagnostic</code>	<p>Create a diagnostic package for the system.</p> <p>Note: If needed, you can "Increase verbose diagnostic package process memory" on page 1489.</p>	<code>dsm_c -action diagnostic [-verbose 0 1] [-tenantname TENANTNAME -tenantid TENANTID]</code>
<code>fullaccess</code>	Give an administrator the full access role.	<code>dsm_c -action fullaccess -username USERNAME [-tenantname TENANTNAME -tenantid TENANTID]</code>
<code>listcerts</code>	List trusted certificates.	<code>dsm_c -action listcerts [-purpose PURPOSE]</code>
<code>listregions</code>	List private cloud provider regions.	<code>dsm_c -action listregions</code>
<code>masterkey</code>	Generate, import, export, or use a custom master key to encrypt the:	<p>If you already configured a custom master key during a new install, the installer has completed this setup for you. If you skipped master key creation, and want to configure one now, start with the commands in step 1. Enter all commands in order.</p>

Action Name	Description	Usage
	<ul style="list-style-type: none"> • database password • keystore password • personal data <p>Note: If a custom master key is not configured, Deep Security will use a hard-coded seed, and personal data will not be encrypted by default.</p>	<p>If you configured the master key during an upgrade, back up your database and properties files, and then start with the commands in step 4.</p> <ol style="list-style-type: none"> 1. <code>dsm_c -action masterkey -subaction [generatekmskey -arn AWSARN generatelocalkey]</code> – Generate the master key using either the Amazon Resource Name (ARN) of a Key Management System (KMS) key, or a local environment variable named <code>LOCAL_KEY_SECRET</code>. If using the local environment variable on a multi-node Deep Security Manager, it must be configured on all nodes, system-level (not user-level), and not more than 64 characters. <p>Note: Permissions and reliable network access to KMS or <code>LOCAL_KEY_SECRET</code> are required by Deep Security Manager if you configure the master key. The manager uses them to encrypt and decrypt the master key during use. If they temporarily cannot be reached, Deep Security Manager will be unable to decrypt required data, and the service will be unavailable. Symptoms can include intermittent event logs and alerts for restart failures and various other errors.</p> <ol style="list-style-type: none"> 2. <code>dsm_c -action masterkey -subaction export -file FILEPATH</code> – Export the

Action Name	Description	Usage
		<p>master key to a password-encrypted file for backup. You will be prompted for the password.</p> <p>Warning: Back up the master key by exporting it to a safe location. If the master key is lost or destroyed, and you do not have a backup, all encrypted data will be unreadable. If that happens, you must reinstall Deep Security Manager, all relays, and all agents/appliances. If the key is stolen, security of your Deep Security deployment is compromised. Some compliance regulations such as General Data Protection Regulation (GDPR) in Europe may require you by law to notify law enforcement of personal data breaches within 72 hours, and noncompliance can result in fines. Consult your lawyer for more information.</p> <p>To verify your backup for disaster recovery, you can test it by importing the master key:</p> <pre>dsm_c -action masterkey -subaction [importkmskey -file FILEPATH -arn AWSARN importlocalkey -file FILEPATH] – Import a backup of the master key. This can be useful either for disaster recovery of a corrupted key, or to migrate the master key to another KMS. Before you run this command, you must delete the existing master key from the primary</pre>

Action Name	Description	Usage
		<p>tenant (T0) database.</p> <p>For example, you might enter the SQL command:</p> <pre>delete from systemsettings where uniquekey = 'settings.configuration.keyEncryptin gKey'</pre> <p>3. <code>dsm_c -action masterkey -subaction encryptproperties</code> – Use the master key to encrypt keystore and database passwords in <code>dsm.properties</code> and <code>configuration.properties</code>. Restart Deep Security Manager for this setting to take effect.</p> <p>4. <code>dsm_c -action masterkey -subaction encrypttenantkey -tenantid [all TENANTNUM]</code> – Use the master key to encrypt existing tenant key seeds (if you have a multi-tenant deployment). Tenant key seeds are used to derive sub-keys that you can use in the next step. Safe to run multiple times; it will not apply multiple layers of encryption if the seed has already been encrypted.</p> <p>Tip: Optionally, if you want to encrypt only for new tenants while you slowly roll out to each existing tenant, you can enter this command first:</p>

Action Name	Description	Usage
		<pre>dsm_c -action changesetting -name settings.configuration.encryptTenantKeyForNewTenants -value true</pre> <ol style="list-style-type: none"> 5. <code>dsm_c -action masterkey -subaction encryptpii -tenantid [all TENANTNUM]</code> – Use each tenant's key to encrypt their administrators' and contacts' personal data in the database. 6. <code>dsm_c -action masterkey -subaction encryptdsmprivatekey -tenantid [all TENANTNUM]</code> – Use the master key to encrypt the private key used for activation and other agent-manager communications via SSL/TLS.
<code>removecert</code>	Remove a trusted certificate.	<code>dsm_c -action removecert -id ID</code>
<code>removeregion</code>	Remove a private cloud provider region.	<code>dsm_c -action removeregion -region REGION</code>
<code>resetcounters</code>	Reset counter tables to an empty state.	<code>dsm_c -action resetcounters [-tenantname TENANTNAME -tenantid TENANTID]</code>
<code>script</code>	Perform batch processing of <code>dsm_c</code> commands in a script file.	<code>dsm_c -action script -scriptfile FILEPATH [-tenantname TENANTNAME -tenantid TENANTID]</code>
<code>setports</code>	Set Deep Security Manager port(s) .	<code>dsm_c -action setports [-managerPort port] [-heartbeatPort port]</code>
<code>trustdirectorycert</code>	Trust the certificate of a	<code>dsm_c -action trustdirectorycert -directoryaddress DIRECTORYADDRESS -</code>

Action Name	Description	Usage
	directory.	<pre>directoryport DIRECTORYPORT [-username USERNAME] [-password PASSWORD] [-tenantname TENANTNAME -tenantid TENANTID]</pre>
unlockout	Unlock a user account.	<pre>dsm_c -action unlockout -username USERNAME [-newpassword NEWPASSWORD] [-disablemfa] [-tenantname TENANTNAME -tenantid TENANTID]</pre>
upgradetasks	Runs the upgrade task actions which may be required as part of an in-service upgrade.	<pre>dsm_c -action upgradetasks [-listtasksets] [-listtasks -taskset UPGRADE_TASK_SET [-force]] [-tenantlist] [-tenantsummary] [-run -taskset UPGRADE_TASK_SET [-force] [-filter REGULAR_EXPRESSION]] [-showrollbackinfo -task TASKNAME] [-purgehistory [-task TASKNAME]] [-showhistory [-task TASKNAME]] [-tenantname TENANTNAME -tenantid TENANTID]</pre> <ul style="list-style-type: none"> • <code>[-listtasksets]</code>: List sets of tasks for the system as a whole or the tenant specified by <code>-tenantname</code>. • <code>[-listtasks -taskset UPGRADE_TASK_SET [-force]]</code>: List the modifications to run. Include <code>-force</code> to list all tasks. • <code>[-tenantlist]</code>: Shows the version of outstanding upgrade actions for the specified tenant. • <code>[-tenantsummary]</code>: Shows a summary of the tenants that are not up to date. • <code>[-run -taskset UPGRADE_TASK_SET [-force] [-filter REGX]]</code>: Run the upgrade actions for each tenant. Include <code>-force</code> to run all tasks even if they have already been done. Include <code>-filter</code> to limit the

Action Name	Description	Usage
		<p>actions to a regular expression.</p> <ul style="list-style-type: none"> <code>[-showrollbackinfo -task TASKNAME]</code>: Shows rollback information for the specified task. One tenant or all tenants can be shown. <code>[-purgehistory [-task TASKNAME]]</code>: Purge the history for the tenant specified and the task specified. If no tenant or task is specified, all items are matched. <code>[-showhistory [-task TASKNAME]]</code>: Show the history for the tenant specified and the task specified. If no tenant or task is specified, all items are matched.
<code>versionget</code>	View information about the current software version, the database schema version, or both.	<code>dsm_c -action versionget [-software] [-dbschema]</code>
<code>viewsetting</code>	View a setting value.	<code>dsm_c -action viewsetting -name NAME [-computerid COMPUTERID] [-computername COMPUTERTNAME] [-policyid POLICYID] [-policyname POLICYNAME] [-tenantname TENANTNAME -tenantid TENANTID]</code>

Return codes

The `dsm_c` command returns an integer value that indicates whether the command executed successfully. The following values can be returned:

- **0**: Successful execution.
- **-1**: Failure of an unknown nature, such as corrupt software installation.

- 1: Failure during execution, such as the database is not currently accessible.
- 2: Invalid arguments were provided.

Use the Deep Security API to automate tasks

Deep Security 11.1 and higher have a new RESTful API that enables you to automate the provisioning and maintenance of security via Deep Security. Go to the [Deep Security Automation Center](#) to download the SDKs in the language of your choice and learn how to use the API:

- API Reference
- Task-oriented guides with ample code examples
- Support resources

The API is continuously updated with new features and improvements. When you start new automation projects, if the new API meets your needs you should use it to benefit from continued support and maintenance in the long term.

To get started with the API, see the [First Steps Toward Deep Security Automation](#) guide in the Deep Security Automation Center.

Legacy REST and SOAP APIs

Note: The REST and SOAP APIs that were provided before Deep Security 11.1 have not changed. They have been deprecated, so new features will not be added but the existing API functionality will continue to function as usual.

Deep Security still includes the legacy REST and SOAP APIs. For guidance on using them, see the following guides on the Deep Security Automation Center:

- [Transition from the SOAP API](#)
- [Use the Legacy REST API](#)

The following sections explain how to use Deep Security Manager to accomplish tasks that are related to using the SOAP and REST API. For more information about when you need to perform these tasks, see the guides listed above.

Enable the Status Monitoring API (optional)

To use status monitoring with the legacy REST API, you must enable it. The API is disabled by default as it does not require authentication.

Note: On Deep Security as a Service, the status monitoring API is already enabled for the primary tenant (t0), so you don't need to enable it. It is not configurable for other tenants.

1. On Deep Security Manager, go to **Administration > System Settings > Advanced**.
2. In the Status Monitoring API section, select **Enabled**, then click **Save**.

Create a Web Service user account

Create a role for Web Service-only access, and assign it to a new user.

1. On Deep Security Manager, go to **Administration > User Management > Roles**.
2. Click **New**.
3. Deselect the **Allow Access to Deep Security Manager User Interface** check box and select the **Allow Access to Web Service API** check box.
4. When all other configuration is complete, click **Save**.
5. Go to **Administration > User Management > Users** and click **New**.
6. Create a new user for use only with the Web Service API. Assign the new Role previously created to this user.

Make note of the new user account user name and password.

Schedule Deep Security to perform tasks

Deep Security has many tasks that you might want to perform automatically on a regular basis. Scheduled tasks are useful when deploying Deep Security in your environment and also later, to keep your system up to date and functioning smoothly. They are especially useful for running scans on a regular basis during off-peak hours.

Tip: You can automate scheduled task creation and configuration using the Deep Security API. For examples, see the [Maintain Protection Using Scheduled Tasks](#) guide in the Deep Security Automation Center.

Create scheduled tasks

To set up a scheduled task in the Deep Security Manager, click **Administration > Scheduled Tasks > New**. This opens the "New Scheduled Task Wizard", which takes you through the steps to create a scheduled task.

Check for Security Updates: Regularly check for security updates and import them into Deep Security when they are available. For most organizations, performing this task once daily is ideal.

Note: With Deep Security 11.0 Update 2 or later, the "Check for Security Updates" task ignores offline hosts that have been uncommunicative for 30 days or more.

Check for Software Updates: Regularly check for Deep Security Agent software updates and download them when they are available.

Discover Computers: Periodically check for new computers on the network by scheduling a Discovery operation. You will be prompted for an IP range to check and asked to specify which computer group the new computer will be added to. This task is useful for discovering computers that are not part of your cloud connector.

Generate and Send Report: Automatically generate reports and optionally have them emailed to a list of users.

Run Script: If the Syslog options do not meet your event notification requirements, it may be possible for Trend Micro to provide a solution using custom-written scripts. Contact Trend Micro for more information.

Scan Computers for Integrity Changes: Causes the Deep Security Manager to perform an Integrity Scan to compare a computer's current state against its baseline.

Scan computers for Malware: Schedules a Malware Scan. The configuration of the scan is specified on the Policy or Computer Editor > Anti-Malware page for each computer. For most

organizations, performing this task once weekly (or according to your organization's policies) is ideal. When you configure this task, you can specify a timeout value for the scan. The timeout option is available for daily, weekly, monthly, and once-only scans. It is not available for hourly scans. When a scheduled malware scan is running and the timeout limit has been reached, any tasks that are currently running or pending are canceled.

Tip: When a **Scan Computers for Malware** task times out, the next scheduled scan starts over from the beginning (it does not start where the previous scan ended). The goal is to perform a complete scan, so consider making some configuration changes if your scans regularly reach the timeout limit. You can change the malware scan configuration to add some exceptions, or extend the timeout period.

Scan Computers for Open Ports: Schedule periodic port scans on one or more computers. You can specify individual computers or all computers belonging to a particular computer group. Deep Security Manager will scan the port numbers defined on the Scanning tab in the Policy or Computer Editor > Settings page.

Scan Computers for Recommendations: Causes the Deep Security Manager to scan the computer(s) for common applications and then make recommendations based on what is detected. Performing regular recommendation scans ensures that your computers are protected by the latest relevant rule sets and that those that are no longer required are removed. If you have set the "Automatically implement Recommendations" option for each of the three protection modules that support it, Deep Security will assign and unassign rules that are required. If rules are identified that require special attention, an alert will be raised to notify you. For most organizations, performing this task once a week is ideal.

Note: Recommendation Scans can be CPU-intensive, so when scheduling Recommendation Scans, it is best practice to set the task by group (for example, per policy or for a group of computers, no more than 1,000 machines per group) and spread it in different days (for example, database server scans scheduled every Monday; mail server scans scheduled every Tuesday, and so on). Schedule Recommendation Scans more frequently for systems that change often.

Send Outstanding Alert Summary: Generate an email listing all outstanding (unresolved) alerts.

Send Policy: Regularly check for and send updated policies. Scheduled updates allow you to follow an existing change control process. Scheduled tasks can be set to update machines during maintenance windows, off hours, etc.

Synchronize Cloud Account: Synchronize the Computers list with an added cloud account. (only available if you have added a cloud account to the Deep Security Manager.)

Synchronize Directory: Synchronize the Computers list with an added LDAP directory. (Only available if you have added an LDAP directory to the Deep Security Manager.)

Synchronize Users/Contact: Synchronize the Users and Contacts lists with an added Active Directory. (Only available if you have added an Active Directory to the Deep Security Manager.)

Synchronize VMware vCenter: Synchronize the Computers list with an added VMware vCenter. (Only available if you have added a VMware vCenter to the Deep Security Manager.)

Enable or disable a scheduled task

Existing scheduled tasks can be enabled or disabled. For example, you might want to temporarily disable a scheduled task while you perform certain administrative duties during which you don't want any activity to occur. The control to enable or disable a scheduled task is on the General tab of the Task's Properties window.

Set up recurring reports

Recurring Reports are simply scheduled tasks that periodically generate and distribute reports to users and contacts. Most of the options are identical to those for single reports, with the exception of the time filter.

Tip: To generate a report on specific computers from multiple computer groups, create a user who has viewing rights only to the computers in question and then either create a scheduled task to regularly generate an "All Computers" report for that user or sign in as that user and run an "All Computers" report. Only the computers to which that user has viewing rights will be included in the report.

Automatically perform tasks when a computer is added or changed

Note: In this article, references to protecting virtual machines apply only to Deep Security On-Premise software installations.

Event-based tasks let you monitor protected computers for specific events and perform tasks based on certain conditions.

Create an event-based task

In Deep Security Manager, click **Administration > Event-Based Tasks > New**. The wizard that appears will guide you through the steps of creating a new task. You will be prompted for different information depending on the type of task.

Edit or stop an existing event-based task

To change the properties for an existing event-based task, go to click **Administration > Event-Based Tasks**. Select the event-based task from the list and click **Properties**.

Events that you can monitor

- **Computer Created (by System):** A computer being added to the manager during synchronization with an Active Directory or Cloud Provider account, or the creation of a virtual machine on a managed ESXi server running a virtual appliance.
- **Computer Moved (by System):** A virtual machine being moved from one vApp to another within the same ESXi, or a virtual machine on an ESXi being move from one datacenter to another or from one ESXi to another (including from an unmanaged ESXi server to a managed ESXi server running a virtual appliance.)
- **Agent-Initiated Activation:** An agent is activated using agent-initiated activation.
- **IP Address Changed:** A computer has begun using a different IP.
- **NSX Security Group Changed:** The following situations will trigger this event (the event will be recorded on each affected VM):

- A VM is added to a group that is (indirectly) associated with the NSX Deep Security Service Profile
 - A VM is removed from an NSX Group that is associated with the NSX Deep Security Service Profile
 - An NSX Policy associated with the NSX Deep Security Service Profile is applied to an NSX Group
 - An NSX Policy associated with the NSX Deep Security Service Profile is removed from an NSX Group
 - An NSX Policy is associated with the NSX Deep Security Service Profile
 - An NSX Policy is removed from the NSX Deep Security Service Profile
 - An NSX Group that is associated with an NSX Deep Security Service Profile changes name
- **Computer Powered On (by System):** Enables users to trigger activation by the VMware Virtual Machine power on event.

Note: The Computer Powered On event is only compatible with virtual machines hosted on ESX environments in VMWare. Use this event cautiously because if a large number of computers are turned on at the same time, this event could cause a slowdown.

Conditions

You can require specific match conditions to be met in order for the task to be carried out. (Add additional conditions by pressing the "plus" button.) If you specify multiple conditions, each of the conditions must be met for the task to be carried out. (In other words, multiple conditions are "AND" conditions, not "OR".)

Use **Java regular expression syntax**

(<https://docs.oracle.com/javase/6/docs/api/java/util/regex/Pattern.html>) to match patterns in the following fields:

- **Cloud Instance Image ID:** AWS cloud instance AMI ID.

Note: This match condition is only available for AWS cloud instances.

- **Cloud Instance Metadata:** The metadata being matched corresponds to AWS "tags" in the Amazon environment.

Note: This match condition is only available for AWS cloud instances. Metadata currently associated with a computer is displayed on the **Overview** page in its editor window. To define the conditions to match for, you must provide two pieces of information: the metadata tag key and the metadata tag value. For example, to match a computer which has a metadata key named "AlphaFunction" that has a value of "DServer", you would enter "AlphaFunction" and "DServer" (without the quotes). If you wanted match more than one possible condition, you could use regular expressions and enter "AlphaFunction" and ".*Server", or "AlphaFunction" and "D.*".

- **Cloud Instance Security Group Name:** The security group the cloud instance applies to.

Note: This match condition is only available for AWS cloud instances.

- **Cloud Account Name:** The "Display Name" field in the Cloud Account properties window.
- **Computer Name:** The "Hostname" field in the computer properties window.
- **ESXi Name:** The "Hostname" field of the ESXi server on which the VM computer is hosted.
- **ESXi Name:** The "Hostname" field of the ESXi server on which the VM computer is hosted.
- **Folder Name:** The name of the folder or directory in which the computer is located in its local environment.

Note: This match condition looks for a match against the name of **any** parent folder of the computer, including the root datacenter for vCenter server integrations. If you add a "" character to the beginning of the regular expression, the condition must match the name on **all** parent folders. This is particularly useful when combined with negation in a regular expression. For example, if you want to match computers in folders that do not include "Linux" in the folder name, you could use a regular expression like `^(?!Linux).*`.

- **NSX Security Group Name:** The list of potential groups in this condition refers only to NSX Groups associated with NSX Policies associated with the NSX Deep Security Service Profile. The VM may be a member of other NSX Groups but for the purposes of this match, condition it is not relevant.
- **Platform:** The operating system of the computer.

- **vCenter name:** The "Name" field of the computer's vCenter properties that was added to Deep Security Manager.

Java regular expression examples:

To match:	Use this:
any string (but not nothing)	.+
empty string (no text)	^\$
Folder Alpha	Folder\ Alpha
FIN-1234	FIN-\d+ or FIN-.*
RD-ABCD	RD-\w+ or RD-.*
AB or ABC or ABCCCCCCCCC	ABC*
Microsoft Windows 2003 or Windows XP	.*Windows.*
Red Hat 7 or Some_Linux123	.*Red.* .Linux.*

These next two conditions match True or False conditions:

- **Appliance Protection Available:** A Deep Security Virtual Appliance is available to protect VMs on the ESXi on which the VM is hosted. The VM may or may not be in a "Activated" state.
- **Appliance Protection Activated:** A Deep Security Virtual Appliance is available to protect VMs on the ESXi on which the VM is hosted and the VM is "Activated".

The last condition option looks for matches to an IP in an IP list:

- **Last Used IP Address:** The current or last known IP address of the computer.

Note: Depending on the source of the new computer, some fields may not be available. For example, "Platform" would not be available for computers added as a result of the synchronization with an Active Directory.

Actions

The following actions can be taken depending on which of the above events is detected:

- **Activate Computer:** Deep Security protection is activated on the computer.
 - **Delay activation by (minutes):** Activation is delayed by a specified number of minutes.
- **Note:** If the event-based task is intended to apply protection to a VM that is being vMotioned to an ESXi protected by a Deep Security Virtual Appliance, add a delay before activation to allow any pending VMware administrative tasks to complete. The amount of delay varies depending on your environment.
- **Deactivate Computer:** Deep Security protection is deactivated on the computer.
- **Assign Policy:** The new computer is automatically assigned a policy. (The computer must be activated first.)
- **Assign Relay Group:** The new computer is automatically assigned a relay group from which to receive security updates.
- **Assign to Computer Group:** The computer is placed in one of the computer groups on the Computers page.

Order of execution

If multiple event-based tasks are triggered by the same condition, the tasks are executed in alphabetical order by task name.

Temporarily disable an event-based task

To prevent an existing event-based task from running, right-click it and then click **Disable**. For example, you may want to temporarily disable an event-based task while you perform certain

administrative duties during which you don't want any activity to occur.

To re-enable an event-based task, right-click it and then click **Enable**.

AWS Auto Scaling and Deep Security

You can set up automatic protection in Deep Security for new instances created by AWS Auto Scaling.

Each instance created by Auto Scaling will need to have a Deep Security agent installed on it. There are two ways that you can do this: you can include a pre-installed agent in the EC2 instance used to create the AMI, or you install the agent by including a deployment script in the launch configuration for the AMI. There are pros and cons for each option:

- If you include a pre-installed agent, instances will spin up more quickly because there is no need to download and install the agent software.
- If you use a deployment script to install the agent, it will always get the latest version of the agent software from the Deep Security Manager. If you use a pre-installed agent, it will use the version included in the AMI.

Pre-install the agent

If you have an EC2 instance already configured with a Deep Security Agent, you can use that instance to create the AMI for Auto Scaling. Before creating the AMI, you must deactivate the agent on the EC2 instance and stop the instance:

```
dsa_control -r
```

Note: Don't create an AMI that contains an activated agent. Each agent must be activated individually.

Each new EC2 instance created by Auto Scaling needs to have its agent activated and a policy applied to it, if it doesn't have one already. There are two ways to do this:

- You can create a deployment script that activates the agent and optionally applies a policy. Then add the deployment script to the AWS launch configuration so that it is run when a new instance is created. For instructions, see the "Install the Agent with a deployment

script" section below, but omit the section of the deployment script that gets and installs the agent. You will only need the `dsa_control -a` section of the script.

Note: For the deployment scripts to work, agent-initiated communication must be enabled on your Deep Security Manager. For details on this setting, see ["Use agent-initiated communication with cloud accounts" on page 350](#)

- You can set up an Event-Based Task in Deep Security Manager that will activate the agent and optionally apply a policy when an instance is launched and the "Computer Created (By System)" event occurs.

Install the agent with a deployment script

Deep Security provides the ability to generate customized deployment scripts that you can run when EC2 instances are created. If the EC2 instance does not contain a pre-installed agent, the deployment script should install the agent, activate it, apply a policy, and optionally assign the machine to a computer group and relay group.

There are several ways to run the deployment script on your instances. The method described below is to add the deployment script to the launch configuration for the AMI but, alternatively, you could run it using an orchestration tool like Chef, Puppet, or Ansible. For Windows machines, you could also run it using Microsoft GPO or System Center.

In order for the deployment script to work:

- You must create AMIs from machines that are stopped.
- Agent-initiated communication must be enabled on your Deep Security Manager. For details on this setting, see ["Use agent-initiated communication with cloud accounts" on page 350](#).

To set up automatic protection for instances using a deployment script:

1. Sign in to the Deep Security Manager.
2. From **Support** menu in the top right-hand corner, select **Deployment Scripts**.
3. Select your platform.
4. Select **Activate Agent automatically after installation**.
5. Select the appropriate **Security Policy**, **Computer Group** and **Relay Group**.

6. Click **Copy to Clipboard**.

7. Go to the AWS launch configuration, expand **Advanced Details** and paste the deployment script into **User Data**.

The screenshot shows the 'Create Launch Configuration' page in the AWS Management Console. The 'Advanced Details' section is expanded, and the 'User data' field is highlighted with a red box. The 'User data' field contains a PowerShell script for installing and running the Trend Micro Deep Security agent. The script includes commands to set the environment, download the agent from a specific URL, and install it using rpm.

Create Launch Configuration

Name

Purchasing option ☐ Request Spot Instances

IAM role

Monitoring ☐ Enable CloudWatch detailed monitoring [Learn more](#)

▼ **Advanced Details**

Kernel ID

RAM Disk ID

User data ☒ As text ☐ As file ☐ Input is already base64 encoded

```
#!/usr/bin/env bash
wget
https://app.deepsecurity.trendmicro.com:443/software/agent/amzn1/
x86_64/ -O /tmp/agent.rpm --no-check-certificate --quiet
rpm -ihv /tmp/agent.rpm
```

IP Address Type ☒ Only assign a public IP address to instances launched in the default VPC and subnet. (default)
☐ Assign a public IP address to every instance.
☐ Do not assign a public IP address to any instances.
 Note: this option only affects instances launched into an Amazon VPC

Link to VPC ☐

Note: If you are encountering issues getting the PowerShell deployment script to run on a Microsoft Windows-based AMI, the issues may be caused by creating the AMI from a running instance. AWS supports creating AMIs from running instances, but this option disables ALL of the `Ec2Config` tasks that would run at start time on any instance created from the AMI. This behavior prevents the instance from attempting to run the PowerShell script.

Note: When you build an AMI on Windows, you need to re-enable user-data handling manually or as part of your image-building process. The user-data handling only runs in the first boot of the Windows base AMI unless it's explicitly told otherwise (it's disabled during the initial boot process), so instances built from a custom AMI won't run user-data unless the feature is re-enabled. [Configuring a Windows Instance Using the EC2Config Service](#) has a detailed explanation and instructions for how to reset the feature or ensure it's not disabled on first boot. The easiest mechanism is to include `<persist>true</persist>` in your user data, providing that you have EC2Config version 2.1.10 or later.

Delete instances from Deep Security as a result of Auto Scaling

After you have added an AWS Account in the Deep Security Manager, instances that no longer exist in AWS as a result of Auto Scaling will be automatically removed from the Deep Security Manager.

See ["Add AWS cloud accounts" on page 455](#) for details on adding an AWS account.

Azure virtual machine scale sets and Deep Security

Azure virtual machine scale sets (VMSS) provide the ability to deploy and manage a set of identical VMs. The number of VMs can increase or decrease automatically based on configurable scaling rules. For more information, see [What are virtual machine scale sets in Azure?](#)

You can set up your VMSS to include a base VM image that has the Deep Security Agent pre-installed and pre-activated. As the VMSS scales up, the new VM instances in the scale set automatically include the agent.

To add the agent to your VMSS:

- ["Step 1: \(Recommended\) Add your Azure account to Deep Security Manager" below](#)
- ["Step 2: Prepare a deployment script" on the next page](#)
- ["Step 3: Add the agent through a custom script extension to your VMSS instances" on the next page](#)

Step 1: (Recommended) Add your Azure account to Deep Security Manager

When you add your Azure account to Deep Security Manager, all the Azure instances created under that account are loaded into Deep Security Manager and appear under **Computers**. The instances appear regardless of whether they have an agent installed or not. The ones that do not include an agent have a **Status** of **No Agent/Appliance**. After you install and activate the agent on them, their **Status** changes to **Managed (Online)**.

If the scale set is manually or automatically scaled up after adding your Azure account, Deep Security detects the new Azure instances and adds them to its list under **Computers**. Similarly, if the scale set is scaled down, the instances are removed from view. Thus, Deep Security Manager always shows the current list of available Azure instances in your scale set.

However, if you do not add your Azure account to Deep Security Manager, but instead add individual Azure instances using another method, then Deep Security does not detect any scaling down that might occur, and does not remove the non-existent Azure instances from its list. To prevent an ever-expanding list of Azure VMs in your Deep Security Manager, and to always show exactly which Azure instances are available in your scale set at any one time, it is highly recommended that you add your Azure account to Deep Security Manager.

For instructions on adding your Azure account, see ["Add a Microsoft Azure account to Deep Security" on page 477](#).

Step 2: Prepare a deployment script

In Deep Security Manager, prepare a deployment script from Deep Security Manager. For instructions, see ["Use deployment scripts to add and protect computers" on page 437](#). This deployment script will be referenced in a custom script extension that you'll configure next.

Note: To run a custom script with the following VMSS script, the script must be stored in Azure Blob storage or in any other location accessible through a valid URL. For instructions on how to upload a file to Azure Blob storage, see [Perform Azure Blob storage operations with Azure PowerShell](#).

Step 3: Add the agent through a custom script extension to your VMSS instances

Below are a couple of examples on how to use PowerShell to add the agent.

- [Example 1](#) shows how to create a new VMSS that includes the agent
- [Example 2](#) shows how to add the agent to an existing VMSS

Both examples:

Trend Micro Deep Security On-Premise 11.3

- use the [Add-AzureRmVmssExtension cmdlet](#) to add an extension to the VMSS
- use Azure PowerShell version 5.1.1

Note: For instructions on creating a new VMSS using PowerShell cmdlets, refer to [this Microsoft tutorial](#). For the Linux platform, see <https://github.com/Azure/custom-script-extension-linux>.

Example 1: Create a new VMSS that includes the agent

```
$resourceGroupName = <The resource group of the VMSS>

$vmssname = <The name of the VMSS>

# Create ResourceGroup

New-AzureRmResourceGroup -ResourceGroupName $resourceGroupName -Location EastUS

# Create a config object

$vmssConfig = New-AzureRmVmssConfig `
    -Location EastUS `
    -SkuCapacity 2 `
    -SkuName Standard_DS2 `
    -UpgradePolicyMode Automatic

# Define the script for your Custom Script Extension to run on the Windows Platform

$customConfig = @{
    "fileUri" = ("A URL of your copy of deployment script, ex.
    deploymentscript.ps1");

    "commandToExecute" = "powershell -ExecutionPolicy Unrestricted -File
    deploymentscript.ps1"
}

# Define the script for your Custom Script Extension to run on the Linux Platform
```

Trend Micro Deep Security On-Premise 11.3

```
# $customConfig = @{  
  
# "fileUri" = ("A URL of your copy of deployment script, ex.  
deploymentscript.sh");  
  
# "commandToExecute" = "bash deploymentscript.sh"  
  
#}  
  
# The section is required only if deploymentscript has been located within Azure  
StorageAccount  
  
$storageAccountName = <StorageAccountName if deploymentscript is locate in Azure  
Storage>  
  
$key = (Get-AzureRmStorageAccountKey -Name $storageAccountName -ResourceGroupName  
$resourceGroupName).Value[0]  
  
$protectedConfig = @{  
  
    "storageAccountName" = $storageAccountName;  
  
    "storageAccountKey" = $key  
  
}  
  
# Use Custom Script Extension to install Deep Security Agent (Windows)  
  
Add-AzureRmVmssExtension -VirtualMachineScaleSet $vmssConfig `  
    -Name "customScript" `  
    -Publisher "Microsoft.Compute" `  
    -Type "CustomScriptExtension" `  
    -TypeHandlerVersion 1.8 `  
    -Setting $customConfig `  
    -ProtectedSetting $protectedConfig  
  
# Use Custom Script Extension to install Deep Security Agent (Linux)  
# Add-AzureRmVmssExtension -VirtualMachineScaleSet $vmssConfig `  
# -Name "customScript" `
```

Trend Micro Deep Security On-Premise 11.3

```
# -Publisher "Microsoft.Azure.Extensions" `
# -Type "customScript" `
# -TypeHandlerVersion 2.0 `
# -Setting $customConfig `
# -ProtectedSetting $protectedConfig

# Create a public IP address
# Create a frontend and backend IP pool
# Create the load balancer
# Create a load balancer health probe on port 80
# Create a load balancer rule to distribute traffic on port 80
# Update the load balancer configuration
# Reference a virtual machine image from the gallery
# Set up information for authenticating with the virtual machine
# Create the virtual network resources
# Attach the virtual network to the config object

# Create the scale set with the config object (this step might take a few minutes)
New-AzureRmVmss `
    -ResourceGroupName $resourceGroupName `
    -Name $vmssname `
    -VirtualMachineScaleSet $vmssConfig
```

Example 2: Add the agent to an existing VMSS

```
$resourceGroupName = <The resource group of the VMSS>
$vmssname = <The name of the VMSS>

# Get the VMSS model
```

Trend Micro Deep Security On-Premise 11.3

```
$vmssobj = Get-AzureRmVmss -ResourceGroupName $resourceGroupName -VMSSetName
$vmssname

# Show model data if you prefer

# Write-Output $vmssobj

# Define the script for your Custom Script Extension to run on the Windows platform
$customConfig = @{

    "fileUri" = (,"A URL of your copy of deployment script, ex.
deploymentscript.ps1");

    "commandToExecute" = "powershell -ExecutionPolicy Unrestricted -File
deploymentscript.ps1"

}

# Define the script for your Custom Script Extension to run on the Linux platform
#$customConfig = @{

# "fileUri" = (,"A URL of your copy of deployment script, ex.
deploymentscript.sh");

# "commandToExecute" = "bash deploymentscript.sh"

#}

# The section is required only if deploymentscript has been located within Azure
StorageAccount

$storageAccountName = <StorageAccountName if deploymentscript is locate in Azure
Storage>

$key= (Get-AzureRmStorageAccountKey -Name $storageAccountName -ResourceGroupName
$resourceGroupName).Value[0]

$protectedConfig = @{

    "storageAccountName" = $storageAccountName;

    "storageAccountKey" = $key
```

Trend Micro Deep Security On-Premise 11.3

```
}

# Use Custom Script Extension to install Deep Security Agent (Windows)

$newvmssobj = Add-AzureRmVmssExtension `
    -VirtualMachineScaleSet $vmssobj `
    -Name "customScript" `
    -Publisher "Microsoft.Compute" `
    -Type "CustomScriptExtension" `
    -TypeHandlerVersion 1.8 `
    -Setting $customConfig `
    -ProtectedSetting $protectedConfig

# Use Custom Script Extension to install Deep Security Agent (Linux)

#$newvmssobj = Add-AzureRmVmssExtension `
#     -VirtualMachineScaleSet $vmssobj `
#     -Name "customScript" `
#     -Publisher "Microsoft.Azure.Extensions" `
#     -Type "customScript" `
#     -TypeHandlerVersion 2.0 `
#     -Setting $customConfig `
#     -ProtectedSetting $protectedConfig

# Update the virtual machine scale set model

Update-AzureRmVmss -ResourceGroupName $resourceGroupName -name $vmssname -
VirtualMachineScaleSet $newvmssobj -Verbose

# Get Instance ID for all instances in this VMSS, and decide which instance you'd
like to update
```


Trend Micro Deep Security On-Premise 11.3

```
# Get-AzureRmVmssVM -ResourceGroupName $resourceGroupName -VMScaleSetName $vmssname
```

```
# Now start updating instances
```

```
# If upgradePolicy is Automatic in the VMSS, do NOT execute the next command  
Update-AzureRmVmssInstance. Azure will auto-update the VMSS.
```

```
# There's no PowerShell command to update all instances at once. But you could  
refer to the output of Update-AzureRmVmss, and loop all instances into this  
command.
```

```
Update-AzureRmVmssInstance -ResourceGroupName $resourceGroupName -VMScaleSetName  
$vmssname -InstanceId 0
```

Use deployment scripts to add and protect computers

Adding a computer to your list of protected resources in Deep Security and implementing protection is a multi-step process. Almost all of these steps can be performed from the command line on the computer and can therefore be scripted. The Deep Security Manager contains a deployment script writing assistant which can be accessed from the **Support** menu.

Enable agent-initiated activation

If your deployment script will automatically activate the Deep Security Agent after it is installed, you must configure Deep Security Manager to allow agent-initiated activation. For information on this setting, see ["Use agent-initiated communication with cloud accounts" on page 350](#) and ["Agent settings" on page 374](#).

1. Go to **Administration > System Settings > Agents**.
2. Select **Allow Agent-Initiated Activation**.

Generate a deployment script

1. In the upper right corner of the Deep Security Manager console, click **Support > Deployment Scripts**.

2. Select the platform on which you are deploying the software.

The platforms in the list correspond to the agent software that you have imported into Deep Security Manager. For information on importing Deep Security software, see ["Get Deep Security Agent software" on page 318](#).

3. Select **Activate agent automatically after installation**.

Agents must be activated before you apply a policy to protect the computer. Activation registers the agent with the manager during an initial communication.

4. Optionally, select the **Security Policy, Computer Group, Relay Group, Proxy to contact Deep Security Manager**, and **Proxy to contact Relay(s)**.
5. Optionally (but highly recommended), select **Validate Deep Security Manager TLS certificate**.

When this option is selected, it checks that Deep Security Manager is using a valid TLS certificate from a trusted certificate authority (CA) when downloading the agent software, which can help prevent a "man in the middle" attack. You can check whether Deep Security Manager is using a valid CA certificate by looking at the browser bar in the Deep Security Manager console. By default, Deep Security Manager uses a self-signed certificate, which is not compatible with the **Validate Deep Security Manager TLS certificate** option. If your Deep Security Manager is not behind a load balancer, see ["Replace the Deep Security Manager SSL certificate" on page 1035](#) for instructions on replacing the default self-signed certificate with a certificate from a trusted certificate authority. If the manager is behind a load balancer, you will need to replace the load balancer's certificates.

6. The deployment script generator displays the script. Click **Copy to Clipboard** and paste the deployment script in your preferred deployment tool, or click **Save to File**.

Deployment Scripts

Deep Security Agents can be deployed using tools such as RightScale, Chef, Puppet, or SSH. Use this deployment script generator to generate the scripts required.

For platforms other than Windows and Linux, please see the installation guide.

Platform: Linux Agent Deployment

NOTE Deployment scripts contain instructions to download agent software from the Deep Security Manager. The agent software must be imported into Deep Security Manager prior to running the deployment script. Please note that you will have to run the script with administrator privileges. [Import More Software...](#)

☐ Activate Agent automatically after installation. (Required if you want to assign a security policy)

☐ Validate Deep Security Manager TLS certificate. [Learn More](#)

```
#!/bin/bash
# This script detects platform and architecture, then downloads and installs the matching Deep Security Agent package
if [[ $(/usr/bin/id -u) -ne 0 ]]; then echo You are not running as the root user. Please try again with root privileges.;
  logger -t You are not running as the root user. Please try again with root privileges.;
  exit 1;
fi;
if type curl >/dev/null 2>&1; then
  SOURCEURL='https://10.203.183.69:4119'
  curl $SOURCEURL/software/deploymentscript/platform/linux/ -o /tmp/DownloadInstallAgentPackage --insecure --silent --tlsv1.2

  if [ -s /tmp/DownloadInstallAgentPackage ]; then
    ./tmp/DownloadInstallAgentPackage
```

[Save to File...](#) [Copy to Clipboard](#) [Close](#)

Note: The deployment scripts generated by Deep Security Manager for Windows agent deployments require Windows PowerShell version 4.0 or later. You must run PowerShell as an Administrator and you may have to run the following command to be able to run scripts:

```
Set-ExecutionPolicy RemoteSigned
```

Note: If you want to deploy an agent to an early version of Windows or Linux that doesn't include PowerShell 4.0 or curl 7.34.0 at a minimum, remove the `--tlsv1.2` tag (Linux) or `[Net.ServicePointManager]::SecurityProtocol = [Net.SecurityProtocolType]::Tls12;` line (Windows) so that early TLS (version 1.0) is used to communicate with the manager. Also make sure that early TLS is allowed on the manager and relays. See ["Determine whether TLS 1.2 is enforced" on page 1414](#) and ["Enable early TLS \(1.0\)" on page 1412](#) for details.

If you are using Amazon Web Services and deploying new Amazon EC2, Amazon WorkSpace, or VPC instances, copy the generated script and paste it into the **User Data** field. This will let you launch existing Amazon Machine Images (AMIs) and automatically install and activate the agent at startup. The new instances must be able to access the URLs specified in the generated deployment script. This means that your Deep Security Manager must be either Internet-facing,

connected to AWS via VPN or Direct Link, or that your Deep Security Manager be deployed on Amazon Web Services too.

When copying the deployment script into the **User Data** field for a **Linux** deployment, copy the deployment script as-is into the "User Data" field and CloudInit will execute the script with sudo. (If there are failures, they will be noted in `/var/log/cloud-init.log`.)

Note: The **User Data** field is also used with other services like CloudFormation. For more information, see:

<https://docs.aws.amazon.com/AWSCloudFormation/latest/UserGuide/aws-properties-waitcondition.html>

Troubleshooting and tips

- If you are attempting to run a deployment script and see exit code 2 **"TLS certificate validation for the agent package download has failed. Please check that your Deep Security Manager TLS certificate is signed by a trusted root certificate authority. For more information, search for "deployment scripts" in the Deep Security Help Center."**, the deployment script was created with the **Validate Deep Security Manager TLS certificate** checkbox selected. This error appears if Deep Security Manager is using a certificate that is not publicly trusted (such as the default self-signed certificate) for the connection between Deep Security Manager and its agents, or if there is a problem with a third-party certificate, such as a missing certificate in the trust chain between your certificate and the trusted CA. For information on certificates, see **"Replace the Deep Security Manager SSL certificate" on page 1035**. As an alternative to replacing the trusted certificate, you can clear the **Validate Deep Security Manager TLS certificate** checkbox when generating a deployment script. Note that this is not recommended for security reasons.
- If you are attempting to deploy the agent from PowerShell (x86), you will receive the following error: `C:\Program Files (x86)\Trend Micro\Deep Security Agent\dsa_control' is not recognized as the name of a cmdlet, function, script file, or operable program. Check the spelling of the name, or if a path was included, verify that the path is correct and try again.`

The PowerShell script expects the environment variable for `ProgramFiles` to be set to "Program Files", not "Program Files (x86)". To resolve the issue, close PowerShell (x86) and run the script in PowerShell as an administrator.

- On Windows computers, the deployment script will use the same proxy settings as the local operating system. If the local operating system is configured to use a proxy and the Deep Security Manager is accessible only through a direct connection, the deployment script will fail.

Automatically assign policies by AWS instance tags


AWS tags allows you to categorize your resources by [assigning metadata to AWS EC2 instances](#) in the form of keys and values. You can also [tag Amazon WorkSpaces](#) with the similar key and value pair. Deep Security can use this metadata to trigger the automatic assigning of a policy to a Deep Security Agent when that agent is activated. This is done by creating an event-based task in Deep Security and defining the event, policy, and metadata. Event-based tasks are used to monitor protected resources for specific events and then perform tasks based on certain conditions: in this case the event is agent-initiated activation and a specific AWS instance tag is the condition.

This article describes how to do this using the following examples:

- Policy: AIA_Policy
- AWS tag key: Group
- AWS tag value: development

Note: The example below is based on the assumption that the policy AIA_Policy has already been created.

1. Go to **Administration -> Event-Based Tasks** in the Deep Security Manager console and click **New**.
2. Select **Agent-Initiated Activation** from the **Event** list and click **Next**.
3. Select the **Assign Policy** check box, select **AIA_Policy** from the list, and click **Next**.
4. Select **Cloud Instance Metadata** from the list, type **Group** and **development** into the key and value fields, and click **Next**.



Specify any match condition(s). (All conditions have to be met before the task is carried out.)

Cloud Instance Metadata matches Group development +

< Back Next > Cancel

5. Type and name for the event-based task and click **Finish** to save it.

You have now created an event-based task that will apply the AIA_Policy to an instance tagged with the key "Group" and the value "development" when the agent is activated on that instance.

Integrate Deep Security with AWS Elastic Beanstalk

If you are using [AWS Elastic Beanstalk](#) to deploy and manage your applications in the AWS cloud, you can integrate Deep Security into your system so that services are scaled and your servers are automatically protected.

To help you integrate Deep Security Agent into your AWS Elastic Beanstalk configuration, we've provided extension configuration files in GitHub: [deep-security/elastic-beanstalk](#). Follow the instructions in the repository's `README.md` file to edit and deploy the extension configuration files.

For more information

- [Customizing Software on Windows Servers - AWS Elastic Beanstalk](#)
- [Customizing Software on Linux Servers - AWS Elastic Beanstalk](#)

Deep Security Smart Check

Deep Security Smart Check is a container image scanner from Trend Micro. It performs pre-runtime scans of Docker images to detect OS vulnerabilities and malware, enabling you to fix issues before they reach the orchestration environment (for example, Kubernetes).

Deep Security Smart Check has two types of documentation:

- The [Deployment Guide](#) describes how Smart Check works and provides instructions on how to install and configure it.
- The [API documentation](#) provides information on using the Smart Check API.

Protect

Trend Micro Deep Security has tightly integrated modules that easily expand your security capabilities:

- "Intrusion Prevention " on the next page
- "Anti-Malware " on the next page
- "Firewall " on the next page
- "Web Reputation " on page 445
- "Integrity Monitoring " on page 445
- "Log Inspection " on page 445
- "Application Control" on page 445

Intrusion Prevention

The Intrusion Prevention module inspects incoming and outgoing traffic to detect and block suspicious activity. This prevents exploitation of known and zero-day vulnerabilities. Deep Security supports "virtual patching": you can use Intrusion Prevention rules to shield from known vulnerabilities until they can be patched, which is required by many compliance regulations. You can configure Deep Security to automatically receive new rules that shield newly discovered vulnerabilities within hours of their discovery.

The Intrusion Prevention module also protects your web applications and the data that they process from SQL injection attacks, cross-site scripting attacks, and other web application vulnerabilities until code fixes can be completed.

For more information, see ["Set up intrusion prevention" on page 728](#).

Anti-Malware

The Anti-Malware module protects your Windows and Linux workloads against malicious software, such as malware, spyware, and Trojans. Powered by the Trend Micro™ Smart Protection Network™, the Anti-Malware module helps you instantly identify and remove malware and block domains known to be command and control servers.

For more information, see ["Enable and configure anti-malware" on page 665](#).

Firewall

The Firewall Module is for controlling incoming and outgoing traffic and it also maintains firewall event logs for audits.

For more information, see ["Set up the Deep Security firewall" on page 771](#).

Web Reputation

The majority of today's attacks start with a visit to a URL that's carrying a malicious payload. The Web Reputation module provides content filtering by blocking access to malicious domains and known communication and control (C&C) servers used by criminals. The Web Reputation module taps into the Trend Micro Smart Protection Network, which identifies new threats quickly and accurately.

For more information, see ["Block access to malicious URLs with web reputation" on page 920](#).

Integrity Monitoring

The Integrity Monitoring module provides the ability to track both authorized and unauthorized changes made to an instance and enables you to receive alerts about unplanned or malicious changes. The ability to detect unauthorized changes is a critical component in your cloud security strategy because it provides visibility into changes that could indicate the compromise of an instance.

For more information, see ["Set up integrity monitoring" on page 824](#).

Log Inspection

The Log Inspection module captures and analyzes system logs to provide audit evidence for PCI DSS or internal requirements that your organization may have. It helps you to identify important security events that may be buried in multiple log entries. You can configure Log Inspection to forward suspicious events to an SIEM system or centralized logging server for correlation, reporting, and archiving.

For more information, see ["Set up log inspection" on page 890](#).

Application Control

The Application Control module monitors changes - "drift" or "delta" - compared to the computer's original software. Once application control is enabled, all software changes are

logged and events are created when it detects new or changed software on the file system. When Deep Security Agent detects changes, you can allow or block the software, and optionally lock down the computer.

For more information, see ["Verify that application control is enabled" on page 639](#).

Manage protected computers

Perform the following tasks to protect and monitor computers using Deep Security:

- ["Add computers and other resources to Deep Security Manager" below](#)
- ["Computer and agent statuses" on page 494](#)
- ["Connect agents behind a proxy" on page 351](#)

Add computers and other resources to Deep Security Manager

The **Computers** page in Deep Security Manager enables you to manage and monitor the computers you are protecting with Deep Security.

This page regularly refreshes itself to display the most current information. (You can modify the refresh rate on a per-user basis. Go to **Administration > User Management > Users** and then double-click on a user account to open its **Properties** window. On the **Settings** tab, in the **Refresh Rate** section, modify the page refresh rate.)

Add computers to the manager

Note: After being installed on a computer, an agent must be activated by the Deep Security Manager. During activation, the Deep Security Manager sends a fingerprint to the agent, after which the agent accepts instructions only from a manager with that unique fingerprint.

Note: If you install an agent on a virtual machine that was previously being protected agentlessly by a Deep Security Virtual Appliance, the virtual machine has to be activated again from the manager to register the presence of the agent on the computer. Agentless protection is not available with Deep Security as a Service.

You can add computers in many different ways.

- ["Add local network computers" on the next page](#)

If you are protecting computers on a locally accessible network you can add them individually by supplying their IP address or hostname or you can perform a Discovery operation to search for all computers visible to the Deep Security Manager.

- ["Add computer groups from Microsoft Active Directory" on page 486](#)

You can import computer groups from Microsoft Active Directory or any other LDAP-based directory service.

- ["Add a VMware vCenter" on page 451](#)

Deep Security Manager supports a tight integration with VMware vCenter and ESXi server. You can import the organizational and operational information from vCenter and ESXi nodes and allow detailed application of security to an enterprise's VMware infrastructure.

- ["Add virtual machines hosted on VMware vCloud" on page 483](#)

- ["Add AWS cloud accounts" on page 455](#)

- ["Add a Microsoft Azure account to Deep Security" on page 477](#)

- ["Bake the agent into your AMI or WorkSpace bundle" on page 337](#)

You can install a preactivated Deep Security Agent onto the instance that your Amazon Machine Image (AMI) is based on.

- ["Use deployment scripts to add and protect computers" on page 437](#)

If you are going to be adding and protecting a large number of computers you may want to automate the process of installing and activating agents. You can use the Deep Security Manager's deployment script generator to generate scripts you can run on your computers which will install the agents and optionally perform subsequent tasks like activation and policy assignment. The scripts are also useful as a starting template to create your own customized scripts to execute various additional available commands.

Group computers

Creating computer groups is useful from an organizational point of view and it speeds up the process of applying and managing policies. Groups are displayed in the tree structure on the left side of the Computers page. To create a new group, select the computer group under which you want to create the new computer group and then click **Add > Create Group(s)**.

To move a computer to a group, select the computer and click **Actions > Move to Group**. Keep in mind that policies are applied at the computer level, not the computer group level. Moving a computer from one computer group to another has no effect on the policy assigned to that computer.

To remove a group, right-click it and click **Remove Group**. You can only remove a computer group if it contains no computers and has no sub-groups.

You can also ["Group computers dynamically with smart folders" on page 1351](#).

Export your computers list

You can click **Export** on the Computers page to export your computers list to an XML or CSV file. Exporting is useful when you want to back up your computer information, integrate it with other reporting systems, or to migrate computers to another Deep Security Manager. (If you export, you do not have to re-discover and scan computers from the new manager.)

Note: The exported computers file does **not** include any assigned policies, firewall rules, firewall stateful configurations or intrusion prevention rules. To export this configuration information use the Policy export option in the **Policies** page.

Delete a computer

If you delete a computer (by selecting it and clicking **Delete**), all information pertaining to that computer is deleted along with it. If you re-discover the computer, you will have to re-assign a policy and whatever rules were assigned previously.

Add local network computers

Agent-initiated activation

If the Deep Security Manager cannot initiate communication with computers that you want to protect (for example, if computers are on a different local network or are protected by a firewall), then computers must initiate connections to the manager instead. This includes the connection for agent activation. To use agent-initiated activation, you must install the Deep Security Agent on the computer and then run a set of command-line instructions which tell the agent to

communicate with the Deep Security Manager. During the communication, the Deep Security Manager activates the agent and can be further instructed to perform a number of other actions such as assigning a security policy, making the computer a member of a computer group, and so on.

If you are going to add a large number of computers to the Deep Security Manager at one time, you can use the command-line instructions to create scripts to automate the process. For more information on agent-initiated activation, scripting, and command line options, see "[Command-line basics](#)" on page 390.

Manually add a computer

You can manually add an individual computer by specifying its IP address or hostname.

1. Go to the **Computers** page and click **Add > Add Computer** in the toolbar to display the **New Computer** wizard.
2. Enter the new computer's IP address or hostname.
3. Select a policy to assign to it from the list.
4. Select a relay group from which the new computer will download security updates.
5. Click **Next** to begin the search for the computer.

If the computer is detected and an agent is installed and running on that computer, the computer will be added to your computers list and the agent will be activated.

Note: "Activating" an agent means that the manager communicates with the agent sending it a unique "fingerprint". The agent will then use this fingerprint to uniquely identify the Deep Security Manager and will not accept instructions from any other managers that might try to contact it.

If a policy has been assigned to the computer, the policy will be deployed to the agent and the computer will be protected with all the rules and configurations that make up the policy.

By default, the security updates delivered by relay groups include new malware patterns. If you have enabled the **Support 9.0 (and earlier) agents** option (on the **Administration > System Settings > Updates** page), updates to the engines will also be included.

If the computer is detected but no Deep Security Agent is present, you will be told that the computer can still be added to your computers list but that you still have to install an agent on the

computer. Once you install an agent on the computer, you will have to find the computer in your computers list, right-click it, and choose **Activate/Reactivate** from the context menu.

If the computer is not detected (not visible to the manager), you will be told that you can still add the computer but that when it becomes visible to the manager you will have to activate it as above.

Discover computers

A discovery operation scans the network for visible computers. To initiate a discovery operation, go to the **Computers** page, click **Add > Discover**. The Discover Computers dialog will appear.

You are provided several options to restrict the scope of the scan. You can choose to perform a port scan of each discovered computer.

Note: If you are discovering or scanning a large number of computers, a port scan can take time and reduce performance until it is complete.

When discovering computers, you can specify a computer group to which they should be added. Depending on how you have chosen to organize your computer groups, it may be convenient to create a computer group called "Newly Discovered Computers", or "Newly Discovered Computers on Network Segment X" if you will be scanning multiple network segments. You can then move your discovered computers to other computer groups based on their properties and activate them.

During discovery, the manager searches the network for any visible computers that are not already listed. When a computer is found, the manager attempts to detect whether an agent is present. When discovery is complete, the manager displays all the computers it has detected and displays their status in the **Status** column.

Note: The Discovery operation only checks the status of newly-discovered computers. To update the status of already-listed computers, right-click the selected computer(s) and click **Actions > Check Status**.

After discovery operations, a computer can be in one of the following states:

- **Discovered (No Agent):** The computer has been detected but no agent is present. The computer may also be in this state if an agent is installed but has been previously activated and is configured for agent initiated communications. In this case, you will have to deactivate and then reactivate the agent. ("No Agent" will also be reported if the agent is installed but not running.)
- **Discovered (Activation Required):** The agent is installed and listening, and has been activated, but is not yet being managed by the manager. This state indicates that this manager was at one point managing the agent, but the agent's public certificate is no longer in the manager's database. This may be the case if the computer was removed from the manager and then discovered again. To begin managing the agent on this computer, right-click the computer and select **Activate/Reactivate**. Once reactivated, the **Status** will change to "Online".
- **Discovered (Deactivation Required):** The agent is installed and listening, but it has already been activated by another manager. In this case, the agent must be deactivated (reset) prior to activation by this manager. Deactivating an agent can be done using the manager that originally activated it or it can be reset through the command line. To deactivate the agent from the manager, right-click the computer and choose **Actions > Deactivate**. To deactivate the agent from the command line, see ["Reset the agent" on page 405](#).

Note: The discovery operation does not discover computers running as virtual machines in a vCenter, computers in a Microsoft Active Directory or in other LDAP directories.

Add a VMware vCenter

You can import a VMware vCenter into Deep Security Manager and then protect its virtual machines either agentlessly, with an agent, or in combined mode. (For information on those options, see ["Choose agentless vs. combined mode protection" on page 133](#).)

Note: If you are using Deep Security in FIPS mode, follow the instructions in ["Add a vCenter when Deep Security Manager is in FIPS mode" on page 453](#) instead.

Note: You cannot import a vCenter that is using vShield Manager. For information on migrating from vShield Manager to a supported VMware product, see ["Install or upgrade Deep Security" on page 144](#).

1. In Deep Security Manager, go to **Computers > Add > Add VMware vCenter**.
2. Enter the vCenter server information. Specify:
 - the vCenter server's IP address (or host name if DNS is configured and able to resolve FQDNs to IP addresses)
 - the [port number to connect to the vCenter](#) (443 by default)
 - the user name and password of a vCenter user account. This user must have the vCenter **Administrator** role at the data center level. (Applying this role at the cluster level causes errors.) This user is required to synchronize the VM inventory between vCenter and Deep Security Manager.
3. Click **Next**.
4. Accept the vCenter TLS (SSL) certificate.
5. Enter the NSX information. Specify:
 - the NSX Manager IP address (or host name if DNS is configured and able to resolve FQDNs to IP addresses)
 - the [port number to connect to NSX Manager](#) (443 by default)
 - the user name and password of an NSX or vCenter user account. This account must be either the NSX built-in administrator account (which has full permissions) or a vCenter user account with the following two roles:
 - **Enterprise Administrator** role assigned in NSX Manager. For information on assigning roles in NSX Manager, see [this VMWare article](#).
 - **Administrator** role assigned at the data center level in vCenter. (Applying this role at the cluster level causes errors.)

This user is required to synchronize NSX security policies and security groups between NSX and Deep Security Manager.

Click **Next**.

6. Accept the NSX Manager's TLS (SSL) certificate.
7. Review the vCenter information and click **Finish**.

8. The **VMware vCenter has been successfully added** message will be displayed. Click **Close**. The vCenter will appear on the **Computers** page.

Tip: If you select **Create an Event Based task to automatically activate VMs added to protected NSX Security Groups in this vCenter** when adding the vCenter, Deep Security Manager will create two event-based tasks. One activates VMs when protection is added and the other deactivates VMs when protection is removed. For more information, see ["Automated policy management in NSX environments" on page 276](#).

When Deep Security Manager adds the vCenter to its inventory, it also registers the Deep Security service within NSX Manager. This permits the deployment of the Deep Security service to the ESXi servers.

In a large environment with more than 3000 machines reporting to a vCenter Server, this process may take 20 to 30 minutes to complete. You can check the vCenter's Recent Task section to verify if there are activities running.

Deep Security Manager will maintain real-time synchronization with this VMware vCenter to keep the information displayed in Deep Security Manager (number of VMs, their status, etc.) up to date.

Add a vCenter when Deep Security Manager is in FIPS mode

Note: If you are using Deep Security in FIPS mode, you must import the vCenter and NSX Manager TLS (SSL) certificates into Deep Security Manager before adding the vCenter to the manager. See ["Manage trusted certificates" on page 364](#).

1. In Deep Security Manager, go to **Computers > Add > Add VMware vCenter**.
2. Enter the vCenter server information. Specify:
 - the vCenter server's IP address (or host name if DNS is configured and able to resolve FQDNs to IP addresses)
 - the [port number to connect to the vCenter](#) (443 by default)
 - the user name and password of a vCenter user account. This user must have the vCenter **Administrator** role at the data center level. (Applying this role at the cluster level causes errors.) This user is required to synchronize the VM inventory between vCenter and Deep Security Manager.

3. In the Trusted Certificate section, click **Test Connection** to check whether the vCenter's SSL certificate has been imported successfully into Deep Security Manager. If there are no errors, click **Next**.
4. Accept the vCenter's TLS (SSL) certificate.
5. Enter the NSX information. Specify:
 - the NSX Manager IP address (or host name if DNS is configured and able to resolve FQDNs to IP addresses)
 - the [port number to connect to NSX Manager](#) (443 by default)
 - the user name and password of an NSX or vCenter user account. This account must be either the NSX built-in administrator account (which has full permissions) or a vCenter user account with the following two roles:
 - **Enterprise Administrator** role assigned in NSX Manager. For information on assigning roles in NSX Manager, see [this VMWare article](#).
 - **Administrator** role assigned at the data center level in vCenter. (Applying this role at the cluster level causes errors.)

This user is required to synchronize NSX security policies and security groups between NSX and Deep Security Manager.

6. Click **Next**.
7. Accept the NSX Manager's TLS (SSL) certificate.
8. Review the vCenter information and click **Finish**.
9. The **VMware vCenter has been successfully added** message is displayed. Click **Close**. The vCenter appears on the **Computers** page.

In a large environment with more than 3000 machines reporting to a vCenter server, this process may take 20 to 30 minutes to complete. You can check the vCenter's Recent Task section to verify if there are activities running.

The manager maintains real-time synchronization with this VMware vCenter to keep the information displayed in Deep Security Manager (number of VMs, their status, etc.) up to date.

Add an ESXi to a protected NSX cluster

1. Add the ESXi to the Data Center *but not directly to the cluster*.
2. Connect ESXi to the virtual distributed switch (vDS).
3. Move the ESXi into the cluster.

Once the ESXi host is moved into the cluster, NSX should automatically deploy the Deep Security service.

Note: Connecting to an NSX Manager is supported in FIPS mode. See ["FIPS 140-2 support" on page 1381](#)

Add AWS cloud accounts

When you add an AWS account to Deep Security, all the Amazon EC2 and Amazon WorkSpace instances under that account are imported into Deep Security Manager and become visible in one of these locations:

- EC2 instances appear on the left under **Computers** > *your_AWS_account* > *your_region* > *your_VPC* > *your_subnet*
- Amazon WorkSpaces appear on the left under **Computers** > *your_AWS_account* > *your_region* > **WorkSpaces**

Once imported, the EC2 and WorkSpace instances can be managed like any other computer.

Note: If you previously added Amazon EC2 instances or Amazon WorkSpaces as individual computers, and they are part of your AWS account, after importing the account, the instances are moved into the [tree structure](#) described above.

There are several ways to add AWS accounts to Deep Security Manager:

- ["Method: Manager instance role and cross-account role" on page 457](#). Use this method if you want to add other AWS accounts that **don't** belong to Deep Security Manager.

You can use this method with:

- Deep Security as a Service
- Deep Security AMI from AWS Marketplace
- Deep Security on-premise on an EC2 instance *inside* AWS
- ["Method: IAM user and cross-account role" on page 463](#). Use this method if you want to add several AWS accounts, and **Deep Security Manager server is outside of AWS**.

You can use this method with:

- Deep Security VM for Azure Marketplace
- Deep Security on-premise on a server *outside* AWS
- ["Method: Manager instance role \(single AWS account\)" on page 469](#). Use this method if you want to add the AWS account that Deep Security Manager belongs to.

You can use this method with:

- Deep Security AMI from AWS Marketplace
- Deep Security on-premise on an EC2 instance *inside* AWS
- ["Method: AWS access keys" on page 471](#). This method works with all deployment types, but is only recommended if your Deep Security Manager is on a server outside of AWS and you only have one AWS account to add, or if you have tried another method and it doesn't work.

For all other scenarios, we recommend you use another method. Specifying access keys in Deep Security Manager is discouraged because the keys need to be updated periodically (for security reasons), which creates management overhead.

You can use this method with:

- Deep Security as a Service
- Deep Security AMI from AWS Marketplace
- Deep Security on-premise
- Deep Security Manager VM for Azure Marketplace

Method: Manager instance role and cross-account role

The instructions below assume you have two different AWS accounts, and both accounts contain Amazon EC2 instances and Amazon WorkSpaces that you want to protect. In this example, the account names are:

- AWS DSM Account (where Deep Security Manager or Deep Security as a Service resides)
- AWS Account A

Follow these high-level steps, which are described in detail below:

1. ["Configure the AWS DSM account" below](#) (Skip if using Deep Security as a Service): Log in to the AWS DSM Account, create an IAM policy, create a manager instance role that references the IAM policy and attach it to the Deep Security Manager EC2 instance.
2. ["Configure AWS Account A" on page 460](#): Log in to AWS Account A, configure an IAM policy, and create a cross account role that references the manager instance role.
3. ["Add the AWS accounts to Deep Security Manager" on page 462](#): In Deep Security Manager, indicate that you're using a manager instance role, and then add AWS DSM Account and AWS Account A.

After completing these steps, Deep Security Manager can use the manager instance role to access AWS DSM Account and see its Amazon EC2 instances and Amazon WorkSpaces. Additionally, Deep Security Manager can access the resources under AWS Account A (indirectly) by way of the cross account roles that reference the manager instance role.

Configure the AWS DSM account

Skip this section if you are using Deep Security as a Service. Deep Security as a Service already has an IAM policy and manager instance role that you can use.

First, log in to AWS DSM Account (the account under which your Deep Security Manager is located) and configure an IAM policy:

1. Log in to your Amazon Web Services Console and go to the **IAM** service.
2. In the left navigation pane, click **Policies**.

Note: If this is your first time on this page, you'll need to click **Get Started**.

3. Click **Create policy**.
4. Select the **JSON** tab.
5. Copy the following JSON code into the text box:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "cloudconnector",
      "Action": [
        "ec2:DescribeImages",
        "ec2:DescribeInstances",
        "ec2:DescribeRegions",
        "ec2:DescribeSubnets",
        "ec2:DescribeTags",
        "ec2:DescribeVpcs",
        "ec2:DescribeAvailabilityZones",
        "ec2:DescribeSecurityGroups",
        "workspaces:DescribeWorkspaces",
        "workspaces:DescribeWorkspaceDirectories",
        "workspaces:DescribeWorkspaceBundles",
        "workspaces:DescribeTags",
        "iam:ListAccountAliases",
        "iam:GetRole",
        "iam:GetRolePolicy",
        "sts:AssumeRole"
      ],
      "Effect": "Allow",
      "Resource": "*"
    }
  ]
}
```

Note: The "sts:AssumeRole" permission is required only if you are using cross account roles.

Note: The "iam:GetRole" and "iam:GetRolePolicy" permissions are optional, but recommended because they allow Deep Security to determine whether you have the

correct policy when an update to the manager occurs that requires additional AWS permissions.

6. Click **Review policy**.
7. Give the policy a name and description. Example name: Deep_Security_Policy.
8. Click **Create policy**. Your policy is now ready to use.

Next, create an EC2 instance role for the EC2 instance where your Deep Security Manager is running:

1. Go to the **IAM** service.
2. Click **Roles**.
3. Click **Create role**.
4. Make sure the **AWS service** box is selected.
5. Click **EC2** from the list of services. More options are revealed.
6. Click **EC2 Allows EC2 instances to call AWS services on your behalf**. Click **Next: Permissions**.
7. Select the check box next to the IAM policy you just created. Click **Next: Review**.
8. Enter a **Role name** and **Role description**.
Example role name: Deep_Security_Manager_Instance_Role
9. Click **Create role**.
10. Select the role in the list to reveal its details.
11. Look for the **Role ARN** field at the top of the page. Its value is similar to:
arn:aws:iam::1234567890:role/Deep_Security_Manager_Instance_Role
12. Note the role's account ID in the ARN. It is the number (1234567890). You'll need it later.

Next, attach the manager instance role to the EC2 instance:

1. Go to the **EC2** service.
2. Click **Instances** on the left, and select the check box next to the EC2 instance that where your Deep Security Manager is installed.
3. Click **Actions > Instance Settings > Attach/Replace IAM Role**.
4. From the **IAM role** drop-down list, select the manager instance role (Deep_Security_Manager_Instance_Role).
5. Click **Apply**.

You have now created a manager instance role with the correct IAM policy, and attached it to the Deep Security Manager's EC2 instance.

Configure AWS Account A

First, log out of AWS and log back in using AWS Account A. This is the account under which some or all of your Amazon EC2 instances and Amazon WorkSpaces are located.

Next, while logged in to AWS Account A, configure an IAM policy for AWS Account A. It is the same as the policy for the AWS DSM account, except it does not require the `sts:AssumeRole` permission:

1. Log in to your Amazon Web Services Console and go to the **IAM** service.
2. In the left navigation pane, click **Policies**.

Note: If this is your first time on this page, you'll need to click **Get Started**.

3. Click **Create policy**.
4. Select the **JSON** tab.
5. Copy the following JSON code into the text box:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "cloudconnector",
      "Action": [
        "ec2:DescribeImages",
        "ec2:DescribeInstances",
        "ec2:DescribeRegions",
        "ec2:DescribeSubnets",
        "ec2:DescribeTags",
        "ec2:DescribeVpcs",
        "ec2:DescribeAvailabilityZones",
        "ec2:DescribeSecurityGroups",
        "workspaces:DescribeWorkspaces",
        "workspaces:DescribeWorkspaceDirectories",
        "workspaces:DescribeWorkspaceBundles",
        "workspaces:DescribeTags",
        "iam:ListAccountAliases",

```



```
        "iam:GetRole",
        "iam:GetRolePolicy"
    ],
    "Effect": "Allow",
    "Resource": "*"
  }
]
```

Note: The "iam:GetRole" and "iam:GetRolePolicy" permissions are optional, but recommended because they allow Deep Security to determine whether you have the correct policy when an update to the manager occurs that requires additional AWS permissions.

6. Click **Review policy**.
7. Give the policy a name and description. Example name: Deep_Security_Policy_2.
8. Click **Create policy**. Your policy is now ready to use.

Next, create a cross account role that references the manager instance role:

1. Go to the **IAM** service.
2. In the left navigation pane, click **Roles**.
3. In the main pane, click **Create role**.
4. Click the **Another AWS account** box.
5. In the **Account ID** field, enter the account ID of the manager instance role.
If you are using Deep Security as a Service, the manager instance role account ID is:
147995105371
If you are using Deep Security AMI from AWS Marketplace or an on-premise version of Deep Security Manager inside AWS, you should have noted the manager instance role's account ID when you created it previously. In this example, it is: 1234567890
6. Next to **Options**, enable **Require external ID**. In the **External ID** field, enter a long, random secret string.
7. Note the external ID. You'll need this information later.
8. Click **Next: Permissions**.
9. Select the IAM policy that you just created (the example name was Deep_Security_Policy_2) and then click **Next: Review**.

10. On the **Review** page, enter a role name and description. Example role name: Deep_Security_Role_2.
11. On the main role page, search for the role you just created (Deep_Security_Role_2).
12. Click it.
13. Find the **Role ARN** field at the top and note the value. You'll need it later. It looks similar to:
arn:aws:iam::1234567890:role/Deep_Security_Role

You now have a cross account role under AWS Account A that includes the correct policy and references the manager instance role.

Add the AWS accounts to Deep Security Manager

First, indicate that you want to use a manager instance role:

1. In Deep Security Manager, click **Administration** at the top.
2. Click **System Settings** on the left.
3. Click the **Advanced** tab in the main pane.
4. Scroll to the bottom and look for the **Manager AWS Identity** section.
5. Make sure **Use Manager Instance Role** is selected.

Note: If **Use Manager Instance Role** does not appear, make sure that you attached the role to the EC2 instance where Deep Security Manager is installed, and then "[Restart the Deep Security Manager](#)" on page 979. On restart, Deep Security detects the role of the manager's EC2 instance and displays the **Use Manager Instance Role** option.

6. Click **Save**.

Next, add the AWS DSM Account:

1. In Deep Security Manager, click **Computers** at the top.
2. In the main pane, click **Add > Add AWS Account**.
3. Select **Use Manager Instance Role**.
4. If AWS DSM Account includes Amazon WorkSpaces, select **Include Amazon WorkSpaces** to include them with your Amazon EC2 instances. By enabling the check box, you ensure that your Amazon WorkSpaces appear in the correct location in the [tree structure](#) in Deep Security Manager and are billed at the correct rate.
5. Click **Next**.

Deep Security Manager uses the manager instance role that is attached to its Amazon EC2 instance to add AWS DSM Account's EC2 and WorkSpace instances to Deep Security Manager.

Finally, add AWS Account A using its cross account role:

1. Click **Computers** at the top.
2. Click **Add > Add AWS Account**.
3. Select **Use Cross Account Role**.
4. Enter AWS Account A's **Cross Account Role ARN** and **External ID**. You noted these earlier, when you created the cross account role.
5. If AWS Account A includes Amazon WorkSpaces, select **Include Amazon WorkSpaces** to include them with your Amazon EC2 instances. By enabling the check box, you ensure that your Amazon WorkSpaces appear in the correct location in the [tree structure](#) in Deep Security Manager and are billed at the correct rate.
6. Click **Next**.

AWS Account A's Amazon EC2 instances and Amazon WorkSpaces are loaded.

You have now added AWS DSM Account and AWS Account A to Deep Security Manager.

Method: IAM user and cross-account role

The instructions below assume that your Deep Security Manager is outside of AWS, and that you have two different AWS accounts that contain Amazon EC2 and WorkSpace instances that you want to protect. In this example, the account names are:

- AWS Account X (primary)
- AWS Account Y

Follow these high-level steps, which are described in detail below:

1. ["Configure AWS Account X" on the next page](#): Log in to AWS Account X (the primary account), configure an IAM policy, create an IAM user with an access keys.
2. ["Configure AWS Account Y" on page 466](#): Log in to AWS Account Y, configure an IAM policy, and create a cross account role to AWS Account X.
3. ["Add the access keys to Deep Security Manager" on page 468](#): In Deep Security Manager, add AWS Account X's access key ID and secret

4. ["Add the AWS accounts to Deep Security Manager" on page 468](#): In Deep Security Manager, add AWS Account X and Y.

After completing these steps, Deep Security Manager can use AWS Account X's access key ID and secret to log in to AWS Account X and see its Amazon EC2 and Amazon WorkSpace instances. Additionally, Deep Security Manager can access the resources under AWS Account Y (indirectly) by way of the cross account roles that reference AWS Account X.

Configure AWS Account X

First, while logged in to AWS Account X, configure an IAM policy:

1. Log in to your Amazon Web Services Console and go to the **IAM** service.
2. In the left navigation pane, click **Policies**.

Note: If this is your first time on this page, you'll need to click **Get Started**.

3. Click **Create policy**.
4. Select the **JSON** tab.
5. Copy the following JSON code into the text box:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "cloudconnector",
      "Action": [
        "ec2:DescribeImages",
        "ec2:DescribeInstances",
        "ec2:DescribeRegions",
        "ec2:DescribeSubnets",
        "ec2:DescribeTags",
        "ec2:DescribeVpcs",
        "ec2:DescribeAvailabilityZones",
        "ec2:DescribeSecurityGroups",
        "workspaces:DescribeWorkspaces",
        "workspaces:DescribeWorkspaceDirectories",
        "workspaces:DescribeWorkspaceBundles",
        "workspaces:DescribeTags",
        "iam:ListAccountAliases",

```

```
        "iam:GetRole",
        "iam:GetRolePolicy",
        "sts:AssumeRole"
    ],
    "Effect": "Allow",
    "Resource": "*"
}
]
```

Note: The "sts:AssumeRole" permission is required only if you are using cross account roles.

Note: The "iam:GetRole" and "iam:GetRolePolicy" permissions are optional, but recommended because they allow Deep Security to determine whether you have the correct policy when an update to the manager occurs that requires additional AWS permissions.

6. Click **Review policy**.
7. Give the policy a name and description. Example name: Deep_Security_Policy.
8. Click **Create policy**. Your policy is now ready to use.

Next, create an IAM user with an access key ID and secret:

1. Go to the **IAM** service.
2. Click **Users**.
3. Click **Add user**.
4. Enter a user name. Example: Deep_Security_IAM_User.
5. For **Access type**, select **Programmatic access**.
6. Click **Next: Permissions**.
7. Click the **Attach existing policies directly** box.
8. Find the IAM policy you just created and select the check box next to it.
9. Click **Next: Review**.
10. Click **Create user**. Your access key ID and secret access key are shown in the table.
11. Copy the access key ID and secret access key to a safe location. You'll need them later.

Next, determine AWS Account X's account ID:

1. At the top-right of AWS, click **Support > Support Center**.
2. Note the **Account Number** shown at the top-right (1234567890, in this example). You'll need it later to create the cross account role.

Configure AWS Account Y

First, while logged in to AWS Account Y, configure an IAM policy. It is the same as the policy for AWS Account X, except it does not require the `sts:AssumeRole` permission:

1. Log in to your Amazon Web Services Console and go to the **IAM** service.
2. In the left navigation pane, click **Policies**.

Note: If this is your first time on this page, you'll need to click **Get Started**.

3. Click **Create policy**.
4. Select the **JSON** tab.
5. Copy the following JSON code into the text box:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "cloudconnector",
      "Action": [
        "ec2:DescribeImages",
        "ec2:DescribeInstances",
        "ec2:DescribeRegions",
        "ec2:DescribeSubnets",
        "ec2:DescribeTags",
        "ec2:DescribeVpcs",
        "ec2:DescribeAvailabilityZones",
        "ec2:DescribeSecurityGroups",
        "workspaces:DescribeWorkspaces",
        "workspaces:DescribeWorkspaceDirectories",
        "workspaces:DescribeWorkspaceBundles",
        "workspaces:DescribeTags",
        "iam:ListAccountAliases",
        "iam:GetRole",
        "iam:GetRolePolicy"
      ]
    }
  ],
```

```
        "Effect": "Allow",
        "Resource": "*"
    }
]
```

Note: The "iam:GetRole" and "iam:GetRolePolicy" permissions are optional, but recommended because they allow Deep Security to determine whether you have the correct policy when an update to the manager occurs that requires additional AWS permissions.

6. Click **Review policy**.
7. Give the policy a name and description. Example name: Deep_Security_Policy_2.
8. Click **Create policy**. Your policy is now ready to use.

Next, create a cross account role that references the Account X:

1. Go to the **IAM** service.
2. In the left navigation pane, click **Roles**.
3. In the main pane, click **Create role**.
4. Click the **Another AWS account** box.
5. In the **Account ID** field, enter the account ID of AWS Account X (1234567890, in this example).
6. Next to **Options**, enable **Require external ID**. In the **External ID** field, enter a long, random secret string.
7. Note the external ID. You'll need this information later when adding this account to Deep Security Manager.
8. Click **Next: Permissions**.
9. Select the IAM policy that you created previously and then click **Next: Review**.
10. On the **Review** page, enter a role name and description. Example role name: Deep_Security_Role.
11. On the main role page, search for the role you just created (Deep_Security_Role).
12. Click it.
13. Find the **Role ARN** field at the top and note the value. You'll need it later when adding this account to Deep Security Manager. It looks similar to:
`arn:aws:iam::544739704774:role/Deep_Security_Role`

Add the access keys to Deep Security Manager

1. Log in to Deep Security Manager.
2. Click **Administration** at the top.
3. Click **System Setting** on the left.
4. Click the **Advanced** tab in the main pane.
5. Scroll to the bottom and look for the **Manager AWS Identity** heading.
6. Next to **Access Key - The Access Key of an AWS User used for the manager identity**, enter the access key of the IAM user you created previously.
7. Next to **Secret Key - The Secret Access Key of an AWS User used for the manager identity**, enter the secret key of the IAM user that you created previously.
8. Click **Save**.

Add the AWS accounts to Deep Security Manager

First, add Account X using its access keys:

1. Click **Computers** at the top.
2. Click **Add > Add AWS Account**.
3. Select **Use AWS Access Keys**.
4. Enter AWS Account X's IAM user **Access Key ID** and **Secret Access Key** that you created previously.
5. If your AWS account includes Amazon WorkSpaces, select **Include Amazon WorkSpaces** to include them with your Amazon EC2 instances. By enabling the check box, you ensure that your Amazon WorkSpaces appear in the correct location in the [tree structure](#) in Deep Security Manager and are billed at the correct rate.
AWS Account X's Amazon EC2 instances and Amazon WorkSpaces are loaded.

Next, add AWS Account Y using its cross account role:

1. Click **Computers** at the top.
2. Click **Add > Add AWS Account**.
3. Select **Use Cross Account Role**.
4. Enter AWS Account Y's **Cross Account Role ARN** and **External ID**.
5. If your AWS account includes Amazon WorkSpaces, select **Include Amazon WorkSpaces** to include them with your Amazon EC2 instances. By enabling the check box, you ensure

that your Amazon WorkSpaces appear in the correct location in the [tree structure](#) in Deep Security Manager and are billed at the correct rate.

6. Click **Next**.

AWS Account Y's Amazon EC2 instances and Amazon WorkSpaces are loaded.

You have now added AWS Account X and Y to Deep Security Manager.

Method: Manager instance role (single AWS account)

First, log in to AWS using the account that holds your Deep Security Manager and configure an IAM policy:

1. Log in to your Amazon Web Services Console and go to the **IAM** service.
2. In the left navigation pane, click **Policies**.

Note: If this is your first time on this page, you'll need to click **Get Started**.

3. Click **Create policy**.
4. Select the **JSON** tab.
5. Copy the following JSON code into the text box:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "cloudconnector",
      "Action": [
        "ec2:DescribeImages",
        "ec2:DescribeInstances",
        "ec2:DescribeRegions",
        "ec2:DescribeSubnets",
        "ec2:DescribeTags",
        "ec2:DescribeVpcs",
        "ec2:DescribeAvailabilityZones",
        "ec2:DescribeSecurityGroups",
        "workspaces:DescribeWorkspaces",
        "workspaces:DescribeWorkspaceDirectories",
        "workspaces:DescribeWorkspaceBundles",
        "workspaces:DescribeTags",
        "iam:ListAccountAliases",

```

```
        "iam:GetRole",
        "iam:GetRolePolicy"
    ],
    "Effect": "Allow",
    "Resource": "*"
  }
]
```

Note: The "iam:GetRole" and "iam:GetRolePolicy" permissions are optional, but recommended because they allow Deep Security to determine whether you have the correct policy when an update to the manager occurs that requires additional AWS permissions.

6. Click **Review policy**.
7. Give the policy a name and description. Example name: Deep_Security_Policy_2.
8. Click **Create policy**. Your policy is now ready to use.

Next, create an IAM role that includes the IAM policy. This is called the 'manager instance role'.

Next, attach the manager instance role to the EC2 instance where Deep Security Manager is installed.

1. Log in to AWS using the account that holds your Deep Security Manager.
2. Go to the **EC2** service.
3. Click **Instances** on the left, and select the check box next to the EC2 instance where Deep Security Manager is installed.
4. Click **Actions > Instance Settings > Attach/Replace IAM Role**.
5. From the **IAM role** drop-down list, select the manager instance role.
6. Click **Apply**.

Finally, add your AWS account to Deep Security Manager:

1. In the Deep Security Manager, click **Computers** at the top.
2. Click **Add > Add AWS Account**
3. Select **Use Manager Instance Role**.

Note: If **Use Manager Instance Role** does not appear, make sure that you attached the manager instance role to the EC2 instance where Deep Security Manager is installed,

and then ["Restart the Deep Security Manager" on page 979](#). On restart, Deep Security detects the role of the manager's EC2 instance and displays the **Use Manager Instance Role** option.

4. If your AWS account includes Amazon WorkSpaces, select **Include Amazon WorkSpaces** to include them with your Amazon EC2 instances. By enabling the check box, you ensure that your Amazon WorkSpaces appear in the correct location in the [tree structure](#) in Deep Security Manager and are billed at the correct rate.
5. Click **Next**.

Your Amazon EC2 instances and Amazon WorkSpaces under your AWS account are loaded.

Method: AWS access keys

First, log in to AWS using the account that holds the Amazon EC2 instances and Amazon WorkSpaces that you want to protect.

Next, configure an IAM policy:

1. Log in to your Amazon Web Services Console and go to the **IAM** service.
2. In the left navigation pane, click **Policies**.

Note: If this is your first time on this page, you'll need to click **Get Started**.

3. Click **Create policy**.
4. Select the **JSON** tab.
5. Copy the following JSON code into the text box:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "cloudconnector",
      "Action": [
        "ec2:DescribeImages",
        "ec2:DescribeInstances",
        "ec2:DescribeRegions",
        "ec2:DescribeSubnets",
        "ec2:DescribeTags",
```

```
        "ec2:DescribeVpcs",
        "ec2:DescribeAvailabilityZones",
        "ec2:DescribeSecurityGroups",
        "workspaces:DescribeWorkspaces",
        "workspaces:DescribeWorkspaceDirectories",
        "workspaces:DescribeWorkspaceBundles",
        "workspaces:DescribeTags",
        "iam:ListAccountAliases",
        "iam:GetRole",
        "iam:GetRolePolicy"
    ],
    "Effect": "Allow",
    "Resource": "*"
}
]
```

Note: The "iam:GetRole" and "iam:GetRolePolicy" permissions are optional, but recommended because they allow Deep Security to determine whether you have the correct policy when an update to the manager occurs that requires additional AWS permissions.

6. Click **Review policy**.
7. Give the policy a name and description. Example name: Deep_Security_Policy_2.
8. Click **Create policy**. Your policy is now ready to use.

Next, create an IAM user account:

1. Go to the **IAM** service.
2. Click **Users**.
3. Click **Add user**.
4. Enter a user name. Example: Deep_Security_IAM_User.
5. For **Access type**, select **Programmatic access**.
6. Click **Next: Permissions**.
7. Click the **Attach existing policies directly** box.
8. Find the IAM policy you just created and select the check box next to it.
9. Click **Next: Review**.
10. Click **Create user**. Your access key ID and secret access key are shown in the table.
11. Copy the access key ID and secret access key to a safe location. You'll need them later.

Finally, add your AWS account to Deep Security:

1. In the Deep Security Manager, click **Computers** at the top.
2. In the main pane, click **Add > Add AWS Account**.
3. Select **Use AWS Access Keys**.
4. Specify the **Access Key ID** and **Secret Access Key** that you generated when you created the IAM user.
5. If your AWS account includes Amazon WorkSpaces, select **Include Amazon WorkSpaces** to include them with your Amazon EC2 instances. By enabling the check box, you ensure that your Amazon WorkSpaces appear in the correct location in the [tree structure](#) in Deep Security Manager and are billed at the correct rate.
6. Click **Next**.

Your Amazon EC2 instances and Amazon WorkSpaces under your AWS account are loaded.

Edit a cloud account

You can edit a cloud account's settings in Deep Security Manager. You might need to do this if, for example, your AWS account needs to be configured to include Amazon WorkSpaces. To edit a cloud account:

1. Log in to Deep Security Manager.
2. Click **Computers** at the top.
3. On the left, right-click your cloud account name and select **Properties**.
4. Edit the settings and click **OK**.

Remove a cloud account from the manager

Removing a cloud account from Deep Security Manager permanently removes the account from the Deep Security database as well as its underlying computers. Your account with your cloud provider is unaffected and any Deep Security Agents that were installed on the instances are still installed, running, and providing protection (although they will no longer receive security updates). If you decide to re-import computers from the cloud account, the Deep Security Agents download the latest security updates at the next scheduled opportunity.

1. In Deep Security Manager, click **Computers** at the top.
2. In the navigation panel, right-click the cloud account and select **Remove Cloud Account**.
3. Confirm that you want to remove the account.

The account is removed from the Deep Security Manager.

Add Amazon WorkSpaces

Amazon WorkSpaces are virtual cloud desktops that run in Amazon Web Services (AWS). You can protect them with Deep Security following the instructions in one of these sections:

- ["Protect Amazon WorkSpaces if you already added your AWS account" below](#)
- ["Protect Amazon WorkSpaces if you have not yet added your AWS account" on the next page](#)

Note: The Deep Security Agent only supports Amazon WorkSpaces Windows desktops—it does not support Linux desktops.

After completing the steps in one of the above-mentioned sections:

- your Amazon WorkSpaces are displayed in Deep Security Manager on the left under **Computers** > *your_AWS_account* > *your_region* > **WorkSpaces**
- your Amazon WorkSpaces are protected by the Deep Security Agent

Protect Amazon WorkSpaces if you already added your AWS account

If you already added your AWS account to Deep Security Manager (to protect your Amazon EC2 instances), complete the steps in this section to configure Deep Security to work with Amazon WorkSpaces.

1. Upgrade Deep Security Manager to version 10.3. See ["Install or upgrade Deep Security" on page 144](#).
2. Launch an Amazon WorkSpace, and then install and activate Deep Security Agent 10.2 or later on it. See ["Install the agent on Amazon EC2 and WorkSpaces" on page 330](#) for details. Optionally, create a custom WorkSpace bundle so that you can deploy it to many people. See ["Bake the agent into your AML or Workspace bundle" on page 337](#) for details on installation, activation, and bundle creation.
3. Modify your IAM policy to include Amazon WorkSpaces permissions:
 - a. Log in to AWS with the account that was added to Deep Security Manager.
 - b. Go to the **IAM** service.

- c. Find the Deep Security IAM policy. You can find it under **Policies** on the left, or you can look for the Deep Security IAM role or IAM user that references the policy and then click the policy within it.
 - d. Modify the Deep Security IAM policy to look like the one shown in ["Add AWS cloud accounts" on page 455](#). The policy includes Amazon WorkSpaces permissions. If you added more than one AWS account to Deep Security, the IAM policy must be updated under all the AWS accounts.
4. In Deep Security Manager, edit your AWS account:
 - a. On the left, right-click your AWS account and select **Properties**.
 - b. Enable **Include Amazon WorkSpaces**.
 - c. Click **Save**.

You have now added Amazon WorkSpaces to Deep Security.

Protect Amazon WorkSpaces if you have not yet added your AWS account

If you have not yet added your AWS account to Deep Security Manager, complete the steps in one of the following sections:

- If you want to protect existing Amazon WorkSpaces, read ["Install the agent on Amazon EC2 and WorkSpaces" on page 330](#)
- If you want to be able to launch new Amazon WorkSpaces with the agent 'baked in', read ["Bake the agent into your AMI or Workspace bundle" on page 337](#).

How do I migrate to the new cloud connector functionality?

If you previously used the "Add Cloud Account" wizard to import Amazon Web Services resources into Deep Security Manager, those resources are organized by AWS region on **Computers**. You may have run the wizard more than once if you have multiple AWS regions.

The latest versions of Deep Security provide the ability to display your AWS instances under your AWS account name, organized in a hierarchy that includes the AWS Region, VPC, and subnet.

Before migrating your AWS resources, you will need to edit the policy that allows Deep Security to access your AWS account:

1. Log in to your Amazon Web Services Console and go to **Identity and Access Management (IAM)**.
2. In the left navigation pane, click **Policies**.
3. In the list of policies, select the policy that allows Deep Security to access your AWS account.
4. Go to the **Policy Document** tab and click **Edit**.
5. Edit the policy document to include this JSON code:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Sid": "cloudconnector",
      "Effect": "Allow",
      "Action": [
        "ec2:DescribeImages",
        "ec2:DescribeInstances",
        "ec2:DescribeRegions",
        "ec2:DescribeSubnets",
        "ec2:DescribeTags",
        "ec2:DescribeVpcs",
        "iam:ListAccountAliases",
        "sts:AssumeRole"
      ],
      "Resource": [
        "*"
      ]
    }
  ]
}
```

Note: The "sts:AssumeRole" permission is required only if you are using cross-account role access. For more information on IAM roles, see [Tutorial: Delegate Access Across AWS Accounts Using IAM Roles](#).

6. Select **Save as default version**.

To migrate your AWS resources in the Deep Security Manager:

1. In the Deep Security Manager, go to the **Computers** page.
2. In the Computers tree, right-click an AWS region and select **Upgrade to Amazon Account**.
3. Click **Finish** and then **Close**. Your AWS instances will now appear under your AWS account name, organized in a hierarchy that includes the AWS Region, VPC, and subnet.

Add a Microsoft Azure account to Deep Security

Once you've installed Deep Security Manager, you can add and protect Microsoft Azure virtual machines by connecting a Microsoft Azure account to the Deep Security Manager. Virtual machines appear on the Computers page, where you can manage them like any other computer.

Topics in this article:

- ["Configure a proxy setting for the Azure account" below](#)
- [" Add virtual machines from a Microsoft Azure account to Deep Security" below](#)
- ["Manage Azure classic virtual machines with the Azure Resource Manager connector" on page 479](#)
- ["Remove an Azure account" on page 480](#)

Configure a proxy setting for the Azure account

You can configure the Deep Security Manager to [use a proxy server](#) to access resources in Azure accounts.

1. Go to **Administration > System Settings > Proxies**.
2. In the **Proxy Server Use** section, select your proxy from the **Deep Security Manager (Cloud Accounts - HTTP Protocol Only)** list.

Add virtual machines from a Microsoft Azure account to Deep Security

You can add virtual machines to the Deep Security Manager using either the Quick or Advanced method. The **Quick** method requires an Azure account that has been assigned the Global Administrator role for the Azure Active Directory and the Subscription Owner role for the Azure subscription to access your Azure resources. The **Advanced** method involves creating an Azure app for the Deep Security Manager that provides read-only access to Azure resources.

1. On the Computers page, click **Add > Add Azure Account**.
2. Select either the **Quick** method or the **Advanced** method, and then click **Next**. Follow the corresponding procedure below:

Quick

Note: Trend Micro recommends creating a dedicated Azure account for adding Azure resources into the Deep Security Manager. This allows you to change the user rights of the dedicated account independently of Azure accounts used to access and manage Azure resources.

1. Enter your Azure portal account credentials and click **Sign in**.

Note: The account must have been assigned the Global Administrator role for the Azure Active Directory and the Subscription Owner role for the Azure subscription. These privileges are required for Deep Security to automate the provisioning of a Service Principal object in the Azure Active Directory. Deep Security uses the Service Principal object to authenticate itself to your Azure subscription so that it can invoke the necessary Azure APIs to synchronize your Azure virtual machines in the Deep Security Manager console. For information on creating a user with a Global Administrator role, see Microsoft's [Add new users or users with Microsoft accounts to Azure Active Directory](#) article.

2. On the Deep Security Azure Connector permissions page, click **Accept**.
3. Select the **Azure Active Directory** and **Subscription Name**, and then click **Next**.
4. Review the summary information, and then click **Finish**.

Note: If you have previously added virtual machines from this Azure account, they will be moved under this account in the Computers tree.

Advanced

1. Log in to the Azure portal.
2. Follow the procedures in "[Create an Azure app for Deep Security](#)" on page 480 to create a new Azure app for the Deep Security Manager.
3. Enter a **Display name**, and then enter the following Azure access information you recorded in step 2:

- **Active Directory ID**
- **Subscription ID**
- **Application ID**
- **Application Password**

Note: If you are upgrading from the Azure classic connector to the Azure Resource Manager connector, the Display name and the Subscription ID of the existing connector will be used.

4. Click **Next**.
5. Review the summary information, and then click **Finish**.

The Azure virtual machines will appear in the Deep Security Manager under their own branch on the Computers page.

Tip: You will see all the virtual machines in the account. If you'd like to only see certain virtual machines, use smart folders to limit your results. See ["Group computers dynamically with smart folders" on page 1351](#) for more information.

Note: If you have previously added virtual machines from this Azure account, they will be moved under this account in the Computers tree.

Manage Azure classic virtual machines with the Azure Resource Manager connector

You can also manage virtual machines that were added with the Azure classic connector with the Azure Resource Manager connector, allowing you to manage both your Azure classic and Azure Resource Manager virtual machines with a single connector.

For more information, see ["Why should I upgrade to the new Azure Resource Manager connection functionality?" on page 482](#)

1. On the **Computers** page, in the **Computers tree**, right-click the **Azure classic portal** and then click **Properties**.
2. Click **Enable Resource Manager connection**.
3. Select either the **Quick** method or the **Advanced** method, and then click **Next**. Follow the corresponding procedure above.

Remove an Azure account

Removing an Azure account from the Deep Security Manager will permanently remove the account from the Deep Security database. This will not affect the Azure account. Virtual machines with Deep Security agents will continue to be protected, but will not receive security updates. If you later import these virtual machines from the same Azure account, the Deep Security agents will download the latest security updates at the next scheduled update.

1. Go to the **Computers** page, right-click on the Microsoft Azure account in the navigation panel, and select **Remove Cloud Account**.
2. Confirm that you want to remove the account.
3. The account is removed from the Deep Security Manager.

Create an Azure app for Deep Security

In your operating environment, it may not be desirable to allow the Deep Security Manager to access Azure resources with an account that has both the Global Administrator role for the Azure Active Directory and the Subscription Owner role for the Azure subscription. As an alternative, you can create an Azure app for the Deep Security Manager that provides read-only access to Azure resources.

Note: To create an Azure app, your account must have been assigned the User Administrator role for the Azure Active Directory and the User Access Administrator role for the Azure subscription.

To do this you will need to:

1. ["Record the Azure Active Directory ID" on the next page.](#)
2. ["Create the Azure app" on the next page.](#)
3. ["Record the Azure app ID and password" on the next page.](#)
4. ["Record the Subscription ID" on the next page.](#)
5. ["Assign the Azure app a reader role and add it to your Azure Subscription" on page 482.](#)

Record the Azure Active Directory ID

1. On the Hub menu, click **Azure Active Directory** and select your Azure Active Directory.
2. In the **Azure Active Directory** blade, click **Properties**.

3. Record the **Directory ID**.

Create the Azure app

1. In the **Azure Active Directory** blade, click **App registrations**.
2. Click **Add**.
3. Enter a **Name** (for example, Deep Security Azure Connector).
4. For the **Application Type**, select **Web app/API**.
5. Enter a **Sign-on URL**. The URL can be any value, but it must begin with the `http` prefix.

Note: You must enter a URL in the **Sign-on URL** field, even though it is not used by Deep Security Azure integration. The value does not need to resolve to a valid address.

6. Click **Create**. The **Deep Security Azure Connector** app will appear in the **App registrations** list.

Record the Azure app ID and password

1. In the **App registrations** list, click on the **Deep Security Azure Connector**.
2. Record the **Application ID**.
3. Click on **All settings**.
4. On the **Settings** blade, click **Keys**.
5. Enter a **Description** for the key.
6. Select an appropriate **Duration**.
7. Click **Save**.

The key **Value** will appear.

8. Record the key **Value**. This will be used as the Application Password when registering the Azure app with Deep Security.

Record the Subscription ID

1. On the Hub menu, go to **All Services** and click **Subscriptions**, then select the subscription you added the Deep Security Azure Connector app to.
2. Record the **Subscription ID**.

Assign the Azure app a reader role and add it to your Azure Subscription

1. In the **Subscriptions** blade, click on **Access Control (IAM)**.
2. Click **Add**.
3. Click on the **Reader** role.
4. Select the **Deep Security Azure Connector** app. If it is not already in the list, enter it in the search field and select it when it appears.
5. Click **OK**.

You can now continue configuring Deep Security to add Azure virtual machines by following the remaining steps of the Advanced procedure in ["Add a Microsoft Azure account to Deep Security" on page 477](#).

Why should I upgrade to the new Azure Resource Manager connection functionality?

The next time you try to add an Azure cloud account to Deep Security Manager you will be shown a message suggesting that you upgrade to the new Resource Manager connection functionality. Basically, this new functionality allows Deep Security to connect to Azure virtual machines using the Resource Manager interface. As an Azure user, you are probably aware that the new Azure deployment model Resource Manager is now the default deployment model, replacing the classic model. Since new resources are deployed using this model by default, Deep Security is only able to display these VM resources on the Computers page if it is able to communicate with the Resource Manager interface. So, if you allow Deep Security to upgrade to this new functionality then VM resources deployed with either the Resource Manager deployment model or the classic deployment model will be visible on the Computers page.

- You can upgrade to this new functionality in Deep Security as a Service (DSaaS) and in Deep Security 10. It is already available in the new Deep Security Manager VM for Azure Marketplace console and no upgrade is needed.
- Until you perform this upgrade VMs deployed using Resource Manager are still being fully protected by Deep Security but for you to see them on the Computers page they have to be added as a computer object. For more information, see ["Why can't I view all of the VMs in an Azure subscription in Deep Security?" on page 1451](#)

Add virtual machines hosted on VMware vCloud

Once you have imported the resources from the cloud provider account into the Deep Security Manager, the computers in the account are managed like any computer on a local network.

To import cloud resources into their Deep Security Manager, Deep Security users must first have an account with which to access the cloud provider service resources. For each Deep Security user who will import a cloud account into the Deep Security Manager, Trend Micro recommends creating dedicated account for that Deep Security Manager to access the cloud resources. That is, users should have one account to access and control the virtual machines themselves, and a separate account for their Deep Security Manager to connect to those resources.

Note: Having a dedicated account for Deep Security ensures that you can refine the rights and revoke this account at any time. It is recommended to give Deep Security an access key or secret key with read-only rights at all times.

Note: The Deep Security Manager only requires read-only access to import the cloud resources and manage their security.

Note: When FIPS mode is enabled, you cannot add virtual machines hosted on VMware vCloud. See ["FIPS 140-2 support" on page 1381](#).

Proxy setting for cloud accounts

You can configure Deep Security Manager to use a proxy server specifically for connecting to instances being protected in cloud accounts. The proxy setting can be found in **Administration > System Settings > Proxies > Proxy Server Use > Deep Security Manager (Cloud Accounts - HTTP Protocol Only)**.

Create a VMware vCloud Organization account for the manager

1. Log in to VMware vCloud Director.
2. On the **System** tab, go to **Manage And Monitor**.
3. In the left navigation pane, click **Organizations**.
4. Double-click the Organization you wish to give the Deep Security user access to.
5. On the **Organizations** tab, click **Administration**.
6. In the left navigation pane, go to **Members > Users**.

7. Click the " plus " sign to create a new user.
8. Enter the new user's credentials and other information, and select **Organization Administrator** as the user's **Role**.

Note: **Organization Administrator** is a simple pre-defined Role you can assign to the new user account, but the only privilege required by the account is **All Rights > General > Administrator View** and you should consider creating a new vCloud role with just this permission. For more detailed information on preparing vCloud resources for Deep Security integration, see ["Deploy agentless protection in a vCloud environment" on page 283](#).

9. Click **OK** to close the new user's properties window.

The vCloud account is now ready for access by a Deep Security Manager.

Note:

To import the VMware vCloud resources into the Deep Security Manager, users will be prompted for the **Address** of the vCloud, their **User name** , and their **Password** .

The **User name** must include "@orgName". For example if the vCloud account's username is **kevin** and the vCloud Organization you've given the account access to is called **CloudOrgOne**, then the Deep Security user must enter **kevin@CloudOrgOne** as their username when importing the vCloud resources.

(For a vCloud administrator view, use **@system**.)

Import computers from a VMware vCloud Organization Account

1. In the Deep Security Manager, go to **Computers**.
2. Right-click **Computers** in the navigation panel and select **Add vCloud Account** to display the **Add vCloud Cloud Account** wizard.
3. In **Name** and **Description**, enter the resources you are adding. (These are only used for display purposes in the Deep Security Manager.)
4. In **Address**, enter the hostname or address of vCloud Director.
5. In **User Name** and **Password**, enter vCloud authentication credentials. User names should have the format **username@vcloudorganization**.
6. Click **Next**.

7. Deep Security Manager will verify the connection to the cloud resources and display a summary of the import action. Click **Finish**.

The VMware vCloud resources now appear in the Deep Security Manager under their own branch on **Computers**.

Import computers from a VMware vCloud Air data center

1. In the Deep Security Manager, go to the **Computers** section, right-click **Computers** in the navigation panel and select **Add vCloud Account** to display the **Add vCloud Account** wizard.
2. Enter a **Name** and **Description** of the vCloud Air data center you are adding. (These are only used for display purposes in the Deep Security Manager.)
3. Enter the **Address** of the vCloud Air data center.

To determine the address of the vCloud Air data center:

- a. Log in to your vCloud Air portal.
 - b. On the **Dashboard** tab, click on the data center you want to import into Deep Security. This will display the **Virtual Data Center Details** information page.
 - c. In the Related Links section of the **Virtual Data Center Details** page, click on **vCloud Director API URL**. This will display the full URL of the vCloud Director API.
 - d. Use the hostname only (not the full URL) as the Address of the vCloud Air data center that you are importing into Deep Security.
4. In **User Name** and **Password**, enter virtual data center credentials. User names should have the format **username@virtualdatacenterid**.
 5. Click **Next**.
 6. Deep Security Manager will verify the connection to the vCloud Air data center and display a summary of the import action. Click **Finish**.

The VMware vCloud Air data center now appears in the Deep Security Manager under its own branch on **Computers**.

Configure software updates for cloud accounts

Relays are modules within Deep Security Agents that are responsible for the download and distribution of Security and Software updates. Normally, the Deep Security Manager informs the

relays when new updates are available, the relays get the updates and then the agents get their updates from the relays.

However, if your Deep Security Manager is in an enterprise environment and you are managing computers in a cloud environment, relays in the cloud may not be able to communicate with Deep Security Manager. You can solve this problem by allowing the relays to obtain software updates directly from the Trend Micro Download Center when they cannot connect to the Deep Security Manager. To enable this option, go to **Administration > System Settings > Updates** and under **Software Updates**, select **Allow Relays to download software updates from Trend Micro Download Center when Deep Security Manager is not accessible**.

Remove a cloud account

Removing a cloud provider account from Deep Security Manager permanently removes the account from the Deep Security database. Your account with your cloud provider is unaffected and any Deep Security agents that were installed on the instances will still be installed, running, and providing protection (although they will no longer receive security updates.) If you decide to re-import computers from the Cloud Provider Account, the Deep Security Agents will download the latest Security Updates at the next scheduled opportunity.

1. Go to the **Computers** page, right-click on the Cloud Provider account in the navigation panel, and select **Remove Cloud Account**.
2. Confirm that you want to remove the account.
3. The account is removed from the Deep Security Manager.

Add computer groups from Microsoft Active Directory

Deep Security can use an LDAP server such as Microsoft Active Directory for computer discovery and to create user accounts and their contacts. Deep Security Manager queries the server, and then displays computer groups according to the structure in the directory.

Note: If you are using Deep Security in FIPS mode, you must import the Active Directory's SSL certificate into Deep Security Manager before connecting the manager with the directory. See ["Manage trusted certificates" on page 364](#).

1. In Deep Security Manager, click **Computers**.
2. In the main pane, click **Add > Add Active Directory**.

3. Type the host name or IP address, name, description, and port number of your Active Directory server. Also enter your access method and credentials. Follow these guidelines:
 - The **Server Address** must be the same as the Common Name (CN) in the Active Directory's SSL certificate if the access method is LDAPS.
 - The **Name** doesn't have to match the directory's name in Active Directory.
 - The **Server Port** is [Active Directory's LDAP or LDAPS port](#). The defaults are 389 (LDAP and StartTLS) and 636 (LDAPS).
 - The **Username** must include your domain name. Example: `EXAMPLE/Administrator`.
 - If you are using Deep Security in FIPS mode, click **Test Connection** in the Trusted Certificate section to check whether the Active Directory's SSL certificate has been imported successfully into Deep Security Manager.

Click **Next** to continue.

4. Specify your directory's schema. (If you haven't customized the schema, you can use the default values for a Microsoft Active Directory server.)

Note: The **Details** window of each computer in the Deep Security Manager has a "Description" field. To use an attribute of the "Computer" object class from your Active Directory to populate the "Description" field, type the attribute name in the **Computer Description Attribute** text box.

Select **Create a Scheduled Task to Synchronize this Directory** if you want to automatically keep this structure in the Deep Security Manager synchronized with your Active Directory server. A **Scheduled Task** wizard will appear when you are finished adding the directory. (You can set this up later using the **Scheduled Tasks** wizard: **Administration > Scheduled Tasks**.)

5. Click **Next** to continue.
6. When the Manager has imported your directory, it will display a list of computers that it added. Click **Finish**.

The directory structure will appear on the **Computers** page.

Additional Active Directory options

Right-clicking an Active Directory structure gives you options that are not available for non-directory computer groups:

- **Remove Directory**
- **Synchronize Now**

Remove Directory

When you remove a directory from the Deep Security Manager, you have these options:

- **Remove directory and all subordinate computers/groups from DSM:** Remove all traces of the directory.
- **Remove directory but retain computer data and computer group hierarchy:** Turn the imported directory structure into identically organized regular computer groups, no longer linked with the Active Directory server.
- **Remove directory, retain computer data, but flatten hierarchy:** Remove links to the Active Directory server, discards directory structure, and places all the computers into the same computer group.

Synchronize Now

You can manually trigger Deep Security Manager to synchronize with the Active Directory server to refresh information on computer groups.

Tip: You can automate this procedure by creating a scheduled task.

Server certificate usage

If it is not already enabled, enable SSL on your Active Directory server.

Computer discovery can use either SSL or TLS or unencrypted clear text, but importing user accounts (including passwords and contacts) requires authentication and SSL or TLS.

SSL or TLS connections require a server certificate on your Active Directory server. During the SSL or TLS handshake, the server will present this certificate to clients to prove its identity. This certificate can be either self-signed or signed by a certificate authority (CA). If you don't know if

your server has a certificate, on the Active Directory server, open the Internet Information Services (IIS) Manager, and then select **Server Certificates**. If the server doesn't have a signed server certificate, you must install it.

Filter Active Directory objects

When importing Active Directory objects, search filters are available to manage the objects that will be returned. By default the wizard will only show groups. You can add additional parameters to the filter to further refine the selections. For additional information about search filter syntax, refer to [https://msdn.microsoft.com/en-us/library/aa746475\(v=vs.85\).aspx](https://msdn.microsoft.com/en-us/library/aa746475(v=vs.85).aspx)

Import users and contacts

Deep Security can import user account information from Active Directory and create corresponding Deep Security users or contacts. This offers the following advantages:

- Users can use their network passwords as defined in Active Directory.
- Administrators can centrally disable accounts from within Active Directory.
- Maintenance of contact information is simplified (e.g., email, phone numbers, etc.) by leveraging information already in Active Directory.

Both users and contacts can be imported from Active Directory. Users have configuration rights on the Deep Security Manager. Contacts can only receive Deep Security Manager notifications. The synchronization wizard allows you to choose which Active Directory objects to import as users and which to import as contacts.

Note: To successfully import an Active Directory user account into Deep Security as a Deep Security user or contact, the Active Directory user account must have a **userPrincipalName** attribute value. (The **userPrincipalName** attribute corresponds to an Active Directory account holder's "User logon name".)

1. Click **Administration > User Management** and then click either **Users** or **Contacts**.
2. Click **Synchronize with Directory**.

If this is the first time user or contact information is imported, the server information page is displayed. Otherwise, the Synchronize with Directory wizard is displayed.

3. Select the appropriate access options, provide logon credentials, and click **Next**.

4. Select the groups you want to synchronize by selecting them from the left column and clicking >> to add them to the right column and then click **Next**.

Tip: You can select multiple groups by holding down shift or control while clicking on them.

5. Select whether to assign the same Deep Security role to all Directory group members or to assign Deep Security roles based on Directory Group membership and then select a default role from the list and click **Next**.
6. If you assigned Deep Security roles based on Directory Group membership, specify the synchronization options for each group and click **Next**.

After synchronization, the wizard generates a report showing the number of objects imported.

Tip: Before you finish the synchronization, you can choose to create a scheduled task to regularly synchronize users and contacts.

7. Click **Finish**.

Once imported, you will be able to tell the difference between organic (non-imported) Deep Security accounts and imported accounts because you will not be able to change any general information for these accounts.

Keep Active Directory objects synchronized

Once imported, Active Directory objects must be continually synchronized with their Active Directory servers to reflect the latest updates for these objects. This ensures, for example, that computers that have been deleted in Active Directory are also deleted in Deep Security Manager. To keep the Active Directory objects that have been imported to the Deep Security Manager synchronized with Active Directory, it is essential to set up a scheduled task that synchronizes directory data. The wizard to import computers includes the option to create these scheduled tasks.

Alternatively, you can create this task using the Scheduled Task wizard. On-demand synchronization can be performed using the **Synchronize Now** option for computers and **Synchronize with Directory** button for users and contacts.

Note: You do not need to create a scheduled task to keep users and contacts synchronized. At log in, Deep Security Manager checks whether the user exists in Active Directory. If the username and password are valid, and the user belongs to a group that has synchronization enabled, the user will be added to Deep Security Manager and allowed to log in.

Disable Active Directory synchronization

You can stop Deep Security Manager from synchronizing with Active Directory for both computer groups and user accounts.

Remove computer groups from Active Directory synchronization

1. Go to **Computers**.
2. Right-click the directory, and select **Remove Directory**.
3. Select what to do with the list of computers from this directory when Deep Security Manager stops synchronizing with it:
 - **Remove directory and all subordinate computers/groups from Deep Security Manager:** Remove this directory's structure.
 - **Remove directory but retain computer data and group hierarchy:** Keep the existing structure, including its user and role access to folders and computers.
 - **Remove directory, retain computer data, but flatten hierarchy:** Convert the directory's structure to a flat list of computers inside a group that is named after the directory. The new computer group has the same user and role access as the old structure.
4. Confirm the action.

Delete Active Directory users and contacts

Unlike when you remove directory queries for computer groups, if you delete the query for users and contacts, all those accounts will be deleted from Deep Security Manager. As a result, you can't delete while logged into Deep Security Manager with a user account that was imported from the directory server. Doing so will result in an error.

1. On either **Users** or **Contacts**, click **Synchronize with Directory**.
2. Select **Discontinue Synchronization** and then click **OK**.
3. Click **Finish**.

Protect Docker containers

The benefits of a Docker deployment are real, but so is the concern about the significant attack surface of the Docker host's operating system (OS) itself. Like any well-designed software deployment, OS hardening and the use of best practices for your deployment, such as the [Center for Internet Security \(CIS\) Docker Benchmark](#), provide a solid foundation as a starting point. Once you have a secure foundation in place, adding Deep Security to your deployment gives you access to Trend Micro's extensive experience protecting physical, virtual, and cloud workloads as well as to real-time threat information from the [Trend Micro Smart Protection Network](#). Deep Security both protects your deployment as well as helps meet and maintain continuous compliance requirements. See "[Docker support](#)" on page 83 for information on supported Docker editions and releases.

Deep Security protects your Docker hosts and containers running on Linux distributions. Deep Security can do the following:

- Identify, find, and protect Docker hosts within your deployment through the use of [badges](#) and [smart folders](#)
- Protect Docker hosts and containers from vulnerabilities to [protect them against known and zero-day exploits](#) by virtually patching new found vulnerabilities
- Provide [real-time anti-malware detection](#) for the file systems used on Docker hosts and within the containers
- Assert the integrity of the Docker host for continuous compliance and to protect your deployment using the following techniques:
 - Prevent the unauthorized execution of applications on Docker hosts by helping you [control which applications are allowed to run](#) in addition to the Docker daemon
 - Monitor Docker hosts for [unexpected changes to system files](#)
 - [Notify you of suspicious events in your OS logs](#)

Note: Deep Security Docker protection works at the OS level. This means that the Deep Security Agent must be installed on the Docker host's OS, not inside a container.

Beginning with Deep Security 10.1, Deep Security supports Docker in swarm mode while using an overlay network.

Deep Security protection for the Docker host

The following Deep Security modules can be used to protect the Docker host:

- Intrusion Prevention (IPS)
- Anti-Malware
- Integrity Monitoring
- Log Inspection
- Application Control
- Firewall
- Web Reputation

Deep Security protection for Docker containers

The following Deep Security modules can be used to protect Docker containers:

- Intrusion Prevention
- Anti-Malware

Limitation on Intrusion Prevention recommendation scans

Although Deep Security Intrusion Prevention controls work at the host level, it also protects container traffic on the exposed container port numbers. Since Docker allows multiple applications to run on the same Docker host, a single Intrusion Prevention policy is applied to all Docker applications. This means that recommendation scans should not be relied upon for Docker deployments.

Computer and agent statuses

On the **Computers** page in Deep Security Manager:

- The **Status** column displays the state of the computer's network connectivity and the state (in parentheses) of the agent or appliance providing protection, if present. The status column might also display system or agent events. See ["Status column - computer states" below](#) and ["Status column - agent or appliance states" on the next page](#)
- The **Task(s)** column displays the state of the tasks. See ["Task\(s\) column" on page 496](#).

For a list of the events, see ["Agent events" on page 1215](#) and ["System events" on page 1220](#).

Also on this page:

- ["Computer errors" on page 499](#)
- ["Protection module status" on page 500](#)
- ["Perform other actions on your computers" on page 501](#)
- ["Computers icons" on page 505](#)
- ["Status information for different types of computers" on page 507](#)

Status column - computer states

State	Description
Activated	The agent or appliance is activated. See "Perform other actions on your computers" on page 501 .
Discovered	Computer has been added to the computers list via the discovery process. (See "Discover computers" on page 450 .)
Filter Driver Offline	The filter driver on the ESXi is offline.
Managed	An agent is present and activated, with no pending operations or errors.
Multiple Errors	Multiple errors have occurred on this computer. See the computer's system events for details.
Multiple Warnings	Multiple warnings are in effect on this computer. See the computer's system events for details.
Prepared	The ESXi has been prepared for the installation of the virtual appliance. (The filter driver has been installed.)
Reactivation Required	The agent or appliance is installed and listening and is waiting to be reactivated a Deep Security Manager.
Unmanaged	The computer's agent is not managed by this Deep Security Manager because it hasn't been activated. Deep Security Manager can't communicate with the agent until you activate it.
Unprepared	The ESXi has not been prepared for the installation of the virtual appliance. (The Filter Driver has not been installed.)
Upgrade Recommended	A newer version of the agent or appliance is available. An software upgrade is recommended.
Upgrading Agent	The agent software on this computer is in the process of being upgraded to a newer version.

Status column - agent or appliance states

State	Description
Activated	The agent or appliance has been successfully activated and is ready to be managed by the Deep Security Manager.
Activation Required	An unactivated agent or appliance has been detected on the target machine. It must be activated before it can be managed by the Deep Security Manager.
Deactivation Required	The manager has attempted to activate an agent or appliance that has already been activated by another Deep Security Manager. The original Deep Security Manager must deactivate the agent or appliance before it can be activated by the new manager.
No Agent /Appliance	No agent or appliance was detected on the computer.
Offline	<p>The agent or appliance has not connected to the manager for the number of heartbeats specified on Computer or Policy editor¹ > Settings > General.</p> <p>This can occur when connectivity is interrupted by a network firewall or proxy, AWS security group, agent software update, or when a computer is powered down for repair.</p> <p>Verify that firewall settings allow the required port numbers, and that the computer is powered on. If you use Deep Security as a Service, also see "Use agent-initiated communication with cloud accounts" on page 350.</p>
Online	The agent or appliance is online and operating as expected.
Unknown	No attempt has been made to determine whether an agent or appliance is present.
VM Paused	The virtual machine is in a "paused" state.
VM Stopped	The virtual machine is in a "stopped" state.

Task(s) column

State	Description
Activating	The manager is activating the agent or appliance.
Activating (Delayed)	The activation of the agent or appliance is delayed by the amount of time specified in the relevant event-based task.
Activation Pending	A command to activate the agent or appliance has been queued.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

State	Description
Agent Software Deployment Pending	An instruction to deploy the agent software is queued to be sent to the computer.
Agent Software Removal Pending	An instruction to remove the agent software is queued to be sent to the computer.
Application Control Inventory Scan In Progress	An application control inventory scan is being performed.
Application Control Inventory Scan Pending (Heartbeat)	An instruction to start an application control inventory scan will be sent from the manager during the next heartbeat.
Application Control Inventory Scan Pending (Offline)	The agent or appliance is currently offline. The manager will initiate an application control inventory scan when communication is reestablished.
Application Control Ruleset Update In Progress	The application control ruleset is being updated.
Application Control Ruleset Update Pending (Heartbeat)	An instruction to perform an application control ruleset update will be sent from the manager during the next heartbeat.
Application Control Ruleset Update Pending (Offline)	The agent or appliance is currently offline. The manager will initiate an application control ruleset update when communication is reestablished.
Baseline Rebuild In Progress	The Integrity Monitoring engine is currently rebuilding a system baseline.
Baseline Rebuild Paused	A baseline rebuild has been paused
Baseline Rebuild Pending	An instruction to rebuild a system baseline for Integrity Monitoring is queued to be sent.
Baseline Rebuild Pending (Offline)	The agent or appliance is currently offline. The Integrity Monitoring engine will rebuild a system baseline when communication between the manager and this computer is reestablished.
Baseline Rebuild Queued	The instruction to perform a baseline rebuild is queued.
Checking Status	The agent state is being checked.
Deactivate Pending (Heartbeat)	A deactivate instruction will be sent from the manager during the next heartbeat.
Deactivating	The manager is deactivating the agent or appliance. This means that the agent or appliance is available for activation and management by another Deep Security Manager.
Deploying Agent Software	Agent software is being deployed on the computer.
File Backup Cancellation In Progress	A file backup is being canceled.
File Backup Cancellation Pending	An instruction to cancel a file backup is queued to be sent.
File Backup Cancellation Pending (Offline)	The agent or appliance is currently offline. The manager will initiate the cancellation of the file backup when communication is reestablished.
File Backup In Progress	A file backup is being performed.
File Backup Pending	An instruction to start a file backup is queued to be sent.
File Backup Pending (Offline)	The agent or appliance is currently offline. The manager will initiate a file backup when communication is reestablished.
File Backup Queued	The instruction to perform a file backup is queued.
Getting Events	The manager is retrieving events from the agent or appliance.

Trend Micro Deep Security On-Premise 11.3

State	Description
Integrity Scan In Progress	An Integrity Scan is currently in progress.
Integrity Scan Paused	An integrity scan has been paused.
Integrity Scan Pending	A command to start an integrity scan is queued to be sent.
Integrity Scan Pending (Offline)	The agent or appliance is currently offline. The manager will initiate an Integrity Scan when communication is reestablished.
Integrity Scan Queued	An instruction to start an integrity scan is queued to be sent.
Malware Manual Scan Cancellation In Progress	The instruction to cancel a manually-initiated Malware Scan has been sent.
Malware Manual Scan Cancellation Pending	The command to cancel a manually-initiated malware scan is queued to be sent.
Malware Manual Scan Cancellation Pending (Offline)	The appliance is offline. The instruction to cancel a manually-initiated Malware Scan will be sent when communication is reestablished.
Malware Manual Scan In Progress	A manually-initiated Malware Scan is in progress.
Malware Manual Scan Paused	A manually-initiated Malware Scan has been paused.
Malware Manual Scan Pending	The instruction to perform a manually-initiated Malware Scan has not yet been sent.
Malware Manual Scan Pending (Offline)	The agent or appliance is offline. The instruction to start a manually-initiated Malware Scan will be sent when communication is reestablished.
Malware Manual Scan Queued	The instruction to perform a manually-initiated Malware Scan is queued.
Malware Scheduled Scan Cancellation In Progress	The instruction to cancel a scheduled Malware Scan has been sent.
Malware Scheduled Scan Cancellation Pending	The instruction to cancel a scheduled Malware Scan is queued to be sent.
Malware Scheduled Scan Cancellation Pending (Offline)	The agent or appliance is offline. The instruction to cancel a scheduled Malware Scan will be sent when communication is reestablished.
Malware Scheduled Scan In Progress	A scheduled Malware Scan is in progress.
Malware Scheduled Scan Paused	A scheduled Malware Scan has been paused.
Malware Scheduled Scan Pending	The command to cancel a scheduled malware scan has not yet been sent.
Malware Scheduled Scan Pending (Offline)	The agent or appliance is offline. The instruction to start a scheduled Malware Scan will be sent when communication is reestablished.
Malware Scheduled Scan Queued	The instruction to cancel a scheduled Malware Scan is queued.
Quick Malware Scan Cancellation In Progress	A quick malware scan is being canceled.
Quick Malware Scan Cancellation Pending	An instruction to cancel a quick malware scan is queued to be sent.
Quick Malware Scan	The agent or appliance is currently offline. The manager will initiate the cancellation of a

Trend Micro Deep Security On-Premise 11.3

State	Description
Cancellation Pending (Offline)	quick malware scan when communication is reestablished.
Quick Malware Scan In Progress	A quick malware scan is being performed.
Quick Malware Scan Paused	A quick malware scan has been paused.
Quick Malware Scan Pending	An instruction to start a quick malware scan is queued to be sent.
Quick Malware Scan Pending (Offline)	The agent or appliance is currently offline. The manager will initiate a quick malware scan when communication is reestablished.
Quick Malware Scan Queued	The instruction to perform a quick malware scan is queued.
Removing Agent Software	The agent software is being removed from the computer.
Rollback of Security Update In Progress	A security update is being rolled back.
Rollback of Security Update Pending	An instruction to roll back a security update is queued to be sent.
Rollback of Security Update Pending (Heartbeat)	An instruction to roll back a security update will be sent from the manager during the next heartbeat.
Rollback of Security Update Pending (Offline)	The agent or appliance is currently offline. The manager will initiate a rollback of the security update when communication is reestablished.
Scan for Recommendations Pending (Heartbeat)	The manager will initiate a recommendation scan at the next heartbeat.
Scan for Recommendations Pending (Offline)	The agent or appliance is currently offline. The manager will initiate a recommendation scan when communication is reestablished.
Scan for Recommendations Pending (VM Offline)	The appliance is currently offline. The manager will initiate a recommendation scan when communication is reestablished.
Scanning for Open Ports	The manager is scanning the computer for open ports.
Scanning for Recommendations	A recommendation scan is underway.
Security Update In Progress	A security update is being performed.
Security Update Pending	An instruction to perform a security update is queued to be sent.
Security Update Pending (Heartbeat)	An instruction to perform a security update will be sent from the manager during the next heartbeat.
Security Update Pending (Offline)	The agent or appliance is currently offline. The manager will initiate a security update when communication is reestablished.
Sending Policy	A policy is being sent to the computer.
Update of Configuration Pending (Heartbeat)	An instruction to update the configuration to match the policy changes will be sent from the manager during the next heartbeat.
Update of Configuration	The agent or appliance is currently offline. The manager will initiate the configuration

Trend Micro Deep Security On-Premise 11.3

State	Description
Pending (Offline)	update to match the policy changes when communication is reestablished.
Upgrading Software (In Progress)	A software upgrade is being performed.
Upgrading Software (Install Program Sent)	A software upgrade is being performed. The install program has been sent to the computer.
Upgrading Software (Pending)	An instruction to perform a software upgrade is queued to be sent.
Upgrading Software (Results Received)	A software upgrade is being performed. The results have been received.
Upgrading Software (Schedule)	A software upgrade will be performed once the computer's access schedule permits.


Computer errors

State	Description
Communication error	General network error.
No route to computer	Typically the computer cannot be reached because of a firewall between the manager and computer, or if a router between them is down.
Unable to resolve hostname	Unresolved socket address.
Activation required	An instruction was sent to the agent or appliance when it was not yet activated.
Unable to communicate with Agent /Appliance	Unable to communicate with agent or appliance.
Protocol Error	Communication failure at the IP, TCP, or HTTP layer. For example, if the Deep Security Manager IP address is unreachable because the connection is being blocked by a firewall, router, or AWS security group, then it would cause a connection to fail. To resolve the error, verify that the activation port number is allowed and that a route exists.
Deactivation Required	The agent or appliance is currently activated by another Deep Security Manager.
No Agent /Appliance	No agent or appliance was detected on the target.
No valid software	Indicates that no installer can be found for the platform and version requested.

Trend Micro Deep Security On-Premise 11.3

State	Description
version	
Send software failed	There was an error in sending a binary package to the computer.
Internal error	Internal error. Please contact your support provider.
Duplicate Computer	Two computers in the Deep Security Manager's computers list share the same IP address.
VMware Tools Not Installed	VMware Tools (with the VMware Endpoint Driver) is not installed on a guest virtual machine. The VMware Endpoint Driver is required to provide Deep Security anti-malware and integrity monitoring protection. This error status will only be displayed when Deep Security is deployed in a VMware NSX environment.
Unresolved software change limit reached	Software changes detected on the file system exceeded the maximum amount. Application control will continue to enforce existing rules, but will not record any more changes, and it will stop displaying any of that computer's software changes. See "Reset application control after too much software change" on page 649.

Protection module status

When you hover over a computer name on the **Computers** page, the **Preview** icon () is displayed. Click the icon to display the state of the computer's protection modules.

On and Off States:

State	Description
On	Module is configured in Deep Security Manager and is installed and operating on the Deep Security Agent.
Off	Module is either not configured in Deep Security Manager, not installed and operating on the Deep Security Agent, or both.
Unknown	Indicates an error with the protection modules.

Install state:

State	Description
Not Installed	The software package containing the module has been downloaded in Deep Security Manager, but the module has not been turned on in Deep Security Manager or installed on the agent.
Installation Pending	Module is configured in the manager but is not installed on the agent.
Installation in Progress	Module is being installed on the agent.
Installed	Module is installed on the agent. This state is only displayed when the state of the module is "Off". (If the state is "On", the module has been installed on the agent.)

State	Description
Matching Module Plug-In Not Found	The version of the software package containing the module imported into the manager does not match the version reported by the agent.
Not Supported/Update Not Supported	A matching software package was found on the agent, but it does not contain a module supported by the platform. "Not Supported" or "Update Not Supported" is displayed depending on whether there is already a version of this module installed on the agent.

Perform other actions on your computers

On the **Computers** page, the **Actions** button provides several actions that you can perform on the selected computers.

Action	Description
Check Status	Checks the status of a computer without performing a scan or activation attempt.
Activate/Reactivate	Activates or reactivates the agent or appliance on the computer. See "Activate the agent" on page 370
Deactivate	You may want to transfer control of a computer from one Deep Security Manager installation to another. If so, the agent or appliance has to be deactivated and then activated again by the new manager.
Assign Policy	<p>Opens a window with a list that allows you to assign a policy to the computer. The name of the policy assigned to the computer will appear in the Policy column on the Computers page.</p> <p>Note: If you apply other settings to a computer (for example, adding additional Firewall Rules, or modifying Firewall Stateful Configuration settings), the name of the policy will be in bold, indicating that the default settings have been changed.</p>
Send Policy	When you use Deep Security Manager to change the configuration of an agent or appliance on a computer (apply a new intrusion prevention rule, change logging settings, etc.), the Deep Security Manager has to send the new information to the agent or appliance. This is a Send Policy instruction. Policy updates usually happen immediately but you can force an update by clicking Send Policy .

Action	Description
Download Security Update	Downloads the latest security update from the configured relay to the agent or appliance. See "Get and distribute security updates" on page 1018 .
Rollback Security Update	Rolls back the latest security update for the agent or appliance.
Get Events	Override the normal event retrieval schedule (usually every heartbeat) and retrieve the event logs from the computer(s) now.
Clear Warnings/Errors	<p>Use this command to clear all warnings and errors for the computer. This command is useful in these situations:</p> <ul style="list-style-type: none"> • If the agent for the computer has been reset locally • If the computer has been removed from the network before you had a chance to deactivate or delete it from the list of computers
Upgrade Agent Software	To upgrade an agent or appliance, you first need to import a newer version of the agent or appliance software package into the Deep Security Manager (see "About upgrades" on page 981).
Scan for Recommendations	Deep Security Manager can scan computers and then make recommendations for Security Rules. The results of a recommendation scan appear in the computer's Details window in the Rules pages. See "Manage and run recommendation scans" on page 529 .
Clear Recommendations	<p>Clears rule recommendations resulting from a recommendation scan on this computer. Clearing also removes the computer from those listed in an alert produced as a result of a recommendation scan.</p> <p>Note: This action will not un-assign any rules that were assigned because of past recommendations.</p>
Full Scan for Malware	Performs a full malware scan on the selected computers. The actions taken by a full scan depend on the Malware Manual Scan Configuration in effect on this computer. See "Configure malware scans" on page 668 .

Action	Description
Quick Scan for Malware	<p>Scans critical system areas for currently active threats. Quick Scan looks for currently-active malware but does not perform deep file scans to look for dormant or stored infected files. On larger drives, Quick Scan is significantly faster than a Full Scan.</p> <p>Note: Quick Scan is only available on-demand. You cannot schedule a Quick Scan as part of a scheduled task.</p>
Scan for Open Ports	<p>Performs a port scan on all selected computers and checks the agent installed on the computer to determine whether its state is either Deactivation Required, Activation Required, Agent Reactivate Required, or Online. The scan operation, by default, scans ports 1-1024. This range can be changed in Computer or Policy editor¹ > Settings > General.</p> <p>Note: The agent's listening port number for heartbeats is always scanned regardless of port range settings. When the Manager connects to communicate with the agent, it uses that port number. If communication direction is set to "Agent/Appliance Initiated" for a computer (Computer or Policy editor² > Settings > General > Communication Direction), however, that port number will not be open. For a list of ports used, see "Deep Security port numbers" on page 111.</p> <p>Note: New computers on the network will not be detected. To find new computers, use the Discover tool.</p>
Cancel Currently Executing Port	<p>If you have initiated a set of port scans to a large number of computers or over a large range of ports and the scan is taking too long, use the Cancel Currently Executing Port Scans</p>

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Action	Description
Scans	option to cancel the scans.
Scan for integrity	Integrity Monitoring tracks changes to a computer's system and files. It does by creating a baseline and then performing periodic scans to compare the current state of the computer to the baseline. For more information see "Set up integrity monitoring" on page 824 .
Rebuild Integrity Baseline	Rebuilds a baseline for Integrity Monitoring on this computer.
Assign Asset Value	Asset values allow you to sort computers and events by importance. The various security rules have a severity value. When rules are triggered on a computer, the severity values of the rules are multiplied by the asset value of the computer. This value is used to rank events in order of importance. See "Rank events to quantify their importance" on page 1109 .
Assign a Relay Group	To select a relay group for this computer to download updates from, right-click the computer and choose Actions > Assign a Relay Group .

Computers icons



Ordinary computer



Deep Security Relay (a computer with a Relay-enabled Agent)



Deep Security Scanner (a computer with a Scanner-enabled agent)



Docker host (physical computer)



Azure virtual machine with Docker



Amazon EC2 with Docker

Trend Micro Deep Security On-Premise 11.3



VMware virtual machine with Docker



Azure virtual machine with Scanner



Azure virtual machine with Scanner (started)



Azure virtual machine with Scanner (stopped)



Azure virtual machine with Scanner (suspended)



Amazon EC2 with Scanner



Amazon EC2 with Scanner (started)



Amazon EC2 with Scanner (stopped)



Amazon EC2 with Scanner (suspended)



Amazon WorkSpace (started)

Additional computer icons for vSphere environments:



ESXi server



Virtual computer (a virtual machine managed by VMware vCenter)



Virtual computer (started)



Virtual computer (stopped)



Virtual computer (suspended)



Virtual computer (with Relay enabled)



Virtual computer (started, Relay enabled)



Virtual computer (stopped, Relay enabled)



Virtual computer (suspended, Relay enabled)



Virtual computer (Scanner enabled)



Virtual computer (started, Scanner enabled)



Virtual computer (stopped, Scanner enabled)



Virtual computer (suspended, Scanner enabled)



Virtual Appliance



Virtual Appliance (started)



Virtual Appliance (stopped)



















Virtual Appliance (suspended)

Status information for different types of computers

Ordinary computer


















The preview pane for an ordinary computer displays the presence of an agent, its [status](#), and the [status of the protection modules](#).

Trend Micro Deep Security On-Premise 11.3

		Agent
		Managed (Online)
		On, Real Time
		On
		On, 41 rules
		On, Prevent, 193 rules
		On, no rules
		On, 5 rules
		Off, not supported

Relay


The preview pane for a Deep Security relay-enabled agent displays its [status](#), the number of security update components it has available for distribution, and the status of the protection modules provided by its embedded Deep Security agent.


		Agent			Relay 192 components available
		Managed (Online)			
		On, Real Time			
		On			
		On, 41 rules			
		On, Prevent, 316 rules			
		On, 30 rules			
		On, 6 rules			
		Off, not supported			


Deep Security Scanner


The preview pane for a Deep Security Scanner displays the presence of an agent or combined mode (agent and appliance), its [status](#), the status of the protection modules, and the scanner status (SAP).


Trend Micro Deep Security On-Premise 11.3


 **Agent**


 Managed (Online)


 Anti-Malware


 On, Real Time


 Web Reputation


 On


 Firewall


 On, 41 rules


 Intrusion Prevention


 On, Prevent, 316 rules


 Integrity Monitoring


 On, 30 rules

 Log Inspection

 On, 6 rules


 Application Control


 Off, not supported


 Scanner(SAP): On


Docker hosts


The preview pane for a Docker host displays the presence of an agent and its [status](#), the status of the protection modules, and the Docker status.


 **Agent**


 Managed (Online)


 Anti-Malware


 On, Real Time


 Web Reputation


 On


 Firewall


 On, 16 rules


 Intrusion Prevention


 On, Prevent, 145 rules


 Integrity Monitoring


 On, 21 rules

 Log Inspection

 On, 4 rules

 Application Control


 Off, not supported


 Docker Host detected

ESXi server

The preview pane for an ESXi server displays its [status](#) and the version number of the ESXi software. In the **Guests** area are displayed the presence of a Deep Security Virtual Appliance, and the virtual machines running on this host.


508


**ESXi**


Managed


ESXi Version6.0.0

Guests

bh-2012r2-1.matrix.local (bh-2012r2-1)


bh-rhel-71-64-2 (bh-rhel-7.1-64-2)


localhost (Guest Introspection (1))

localhost.localdom (Trend Micro Deep Security (

Virtual appliance


The preview pane for a Virtual Appliance displays its [status](#) and the version number of the Appliance. In the **Protected Guests On** area the protected virtual machines are displayed.


**Appliance**

Managed (Online)

Appliance Version10.0.0.2074


Protected Guests On


lab1-esx1a.matrix.local



bh-rhel-71-64-2 (bh-rhel-7.1-64-2)



Virtual machine with agentless protection



The preview pane for a virtual machine displays whether it is being protected by a Virtual Appliance, an in-guest Agent, or both. It displays details about the components running on the virtual machine.



**Appliance**



Managed (Online)



Anti-MalwareOn, Real Time


Web ReputationOff


FirewallOn, 22 rules

Intrusion PreventionOn, Prevent, 595 rules

Integrity MonitoringOn, 28 rules

Log InspectionNot Supported

**ESXi**lab1-esx1a.matrix.local

**Appliance**localhost.localdom (Trend Micro Deep Security (

Using Deep Security with iptables

When Deep Security Agent 10.1 or earlier was installed on Linux, it disabled the iptables service to avoid firewall conflicts unless you added a configuration file that prevented that change. However, the iptables service is used for more than just firewall (for example, Docker manages iptables rules as part of its normal operation), so disabling it sometimes had negative consequences.

With Deep Security 10.2 and higher (including Deep Security 11), the functionality around iptables has changed. Deep Security Agent no longer disables iptables. (If iptables is enabled, it stays enabled after the agent installation. If iptables is disabled, it stays disabled.) However, if the iptables service is running, Deep Security Agent and Deep Security Manager require certain iptables rules, as described below.

Rules required by Deep Security Manager

If iptables is enabled on the computer where Deep Security Manager is being installed, there are two required iptables rules. By default, these rules are added when Deep Security Manager starts up and removed when the manager is stopped or uninstalled. Alternatively, you can ["Prevent Deep Security from automatically adding iptables rules" on the next page](#) and add them manually instead:

- Allow incoming traffic on port 4119. This is required for access to the Deep Security Manager web UI and API.
- Allow incoming traffic on port 4120. This is required to listen for agent heartbeats. (For more information, see ["Agent-manager communication" on page 344.](#))

Note: These are the default port numbers - yours may be different. For a complete list of ports used in Deep Security, see ["Port numbers, URLs, and IP addresses" on page 111.](#)

Rules required by Deep Security Agent

If iptables is enabled on the computer where Deep Security Agent is being installed, iptables may require additional rules. By default, these rules are added when Deep Security Agent starts up and removed when the agent is stopped or uninstalled. Alternatively, you can ["Prevent Deep](#)

[Security from automatically adding iptables rules](#) on the next page and add them manually instead:

- Allow incoming traffic on port 4118. This is required when the agent uses manager-initiated or bidirectional communication. (For more information, see ["Agent-manager communication" on page 344.](#))
- Allow incoming traffic on port 4122. This is required when the agent is acting as a relay, so that the relay can distribute software updates. (For more information, see ["Distribute security and software updates with relays" on page 380.](#))

Note: These are the default port numbers - yours may be different. For a complete list of ports used in Deep Security, see ["Port numbers, URLs, and IP addresses" on page 111.](#)

Prevent Deep Security from automatically adding iptables rules

You can prevent Deep Security Manager and Deep Security Agent from modifying iptables if you would rather add the required rules manually. To prevent the automatic modification of iptables, create the following file on the computers where you plan to install Deep Security Manager and Deep Security Agent:

```
/etc/do_not_open_ports_on_iptables
```

Enable or disable agent self-protection

Note: The agent self-protection feature is only available for agents on Windows. It is not available on Linux.

To update or uninstall Deep Security Agent or Relay, or to create a diagnostic package for support (see ["Create a diagnostic package and logs" on page 1484](#)), you must temporarily disable agent self-protection.

Agent self-protection prevents local users from tampering with the agent. When enabled, if a user tries to tamper with the agent, a message such as "Removal or modification of this application is prohibited by its security settings" will be displayed.

Note: Anti-Malware protection must be "On" to prevent users from stopping the agent, and from modifying agent-related files and Windows registry entries. It isn't required, however, to prevent uninstalling the agent.

You can configure agent self-protection using either the Deep Security Manager, or the command line on the agent's computer.

Via Deep Security Manager

1. Open the **Computer or Policy editor**¹ where you want to enable agent self-protection.
2. Click **Settings > General**.
3. In the **Agent Self-Protection** section, for **Prevent local end-users from uninstalling, stopping, or otherwise modifying the Agent**, select **Yes**.
4. To password-protect agent self protection, for **Local override requires password**, select **Yes** and type the password.
5. Click **Save**.
6. To disable the setting, select **No**. Click **Save**.

Via command line

1. Log in to the Windows computer locally.
2. Open the Command Prompt (`cmd.exe`) as Administrator.
3. Change the current directory to the Deep Security Agent installation folder. (The default install folder is shown below.)

```
cd C:\Program Files\Trend Micro\Deep Security Agent
```

4. Enter this command:

```
dsa_control --selfprotect=1 --passwd=<password>
```

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

where <password> is a password that will be required in order to override this setting. (See ["Command-line basics" on page 390](#).) The password is optional, but strongly recommended.

Warning: Store this password in a safe location. If you lose or forget the password you will have to contact your support provider for assistance in overriding this protection.

5. To disable the setting, enter this command:

```
dsa_control -s=0 -p "<password>"
```


Are "Offline" agents still protected by Deep Security?

Agents showing as "Offline" in the Deep Security Manager are still being protected according to their last known configuration. However, they will not receive any software, security or policy updates until communication with the Deep Security Manager is restored.

For more information on how to bring an agent out of "Offline" status, see [""Offline" agent" on page 1452](#).

Deep Security Notifier

The Deep Security Notifier is a Windows System Tray application that communicates the state of the Deep Security Agent and Deep Security Relay to client machines. The notifier displays popup user notifications when the Deep Security Agent begins a scan, or blocks malware or access to malicious web pages.

The notifier has a small footprint on the client machine, requiring less than 1MB of disk space and 1MB of memory. When the notifier is running the notifier icon () appears in the system tray. The notifier is automatically installed by default with the Deep Security Agent on Windows computers. Use the **Administration > Updates > Software > Local** page to import the latest version for distribution and upgrades.

Note: On computers running a relay-enabled agent, the notifier displays the components that are being distributed to agents or appliances, *not* which components are in effect on the local computer.

A standalone version of the notifier can be downloaded and installed on virtual machines that are receiving protection from a Deep Security Virtual Appliance. See ["Install the Deep Security Notifier" on page 377](#).

Note: On VMs protected by a virtual appliance, the anti-malware module must be licensed and enabled on the VM for the Deep Security Notifier to display information.


How the notifier works

When malware is detected or a malicious site is blocked, the Deep Security Agent sends a message to the notifier, which displays a popup message in the system tray.

If malware is detected, the notifier displays a message in a system tray popup similar to the following:




If the user clicks on the message, a dialog box with detailed information about anti-malware events is displayed:




When a malicious web page is blocked, the notifier displays a message in a system tray popup similar to the following:



If the user clicks on the message, a dialog box with detailed information about web reputation events is displayed:




The notifier also provides a console utility for viewing the current protection status and component information, including pattern versions. The console utility allows the user to turn on and off the popup notifications and access detailed event information.




Tip: You can also turn off pop-up notifications for certain computers or for computers that are assigned a particular policy by going to the Deep Security Manager **Computer/Policy editor > Settings > General** and settings **Suppress all pop-up notifications on host** to **Yes**. The messages still appear as alerts or events in Deep Security Manager.

When the notifier is running on a computer hosting Deep Security Relay, the notifier's display shows the components being distributed by the relay and not the components that in effect on the computer.



When the notifier is running on a computer hosting Deep Security Scanner, the notifier shows that the scanner feature is enabled and the computer cannot be a relay.



Create policies to protect your computers and other resources

Policies allow collections of rules and configuration settings to be saved for easier assignment to multiple computers. You can use the **Policy editor**¹ to create and edit policies that you can then apply to one or more computers. You can also use the **Computer editor**² (which is very similar to the Policy editor) to apply settings to a specific computer, but the recommended method is to create specialized policies rather than edit the settings in the Computer editor.

¹To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

²To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Tip: You can automate policy creation and configuration using the Deep Security API. For examples, see the [Create and Configure Policies](#) guide in the Deep Security Automation Center.

In this article:

- ["Create a new policy" below](#)
- ["Other ways to create a policy" on the next page](#)
- ["Edit the settings for a policy or individual computer" on the next page](#)
- ["Assign a policy to a computer" on page 522](#)
- ["Disable automatic policy updates" on page 523](#)
- ["Send policy changes manually" on page 523](#)
- ["Export a policy" on page 524](#)

Create a new policy

1. Click **Policies > New > New Policy**.
2. Enter a name for the policy. If you want the new policy to inherit its settings from an existing policy, select a policy from the **Inherit from** list. Click **Next**.

Tip: For information on inheritance, see ["Policies, inheritance, and overrides" on page 524](#).

3. Select whether you want to base this policy on an existing computer's configuration and then click **Next**.
4. If you selected **Yes** in step 3:
 - a. Select a computer to use as the basis for the new policy and click **Next**.
 - b. Specify which protection modules will be enabled for the new policy. If this policy is inheriting its settings from an existing policy, those settings will be reflected here. Click **Next**.
 - c. On the next screen, select the properties that you want to carry into the new policy and click **Next**. Review the configuration and click **Finish**.

5. If you selected **No** in step 3, specify which protection modules will be enabled for the new policy. If this policy is inheriting its settings from an existing policy, those settings will be reflected here. Click **Finish**.
6. Click **Close**. Next, you can edit the settings for the policy, as described in ["Edit the settings for a policy or individual computer" below](#).

Other ways to create a policy

There are several ways to create a policies on the **Policies** page:

- Create a new policy as described above.
- Click **New > Import From File** to import policies from an XML file.
- **Note:** When importing policies, ensure that the system where you created the policies and the system that will receive them both have the latest security updates. If the system that is receiving the policies is running an older security update, it may not have some of the rules referenced in the policies from the up-to-date system.
- Duplicate (and then modify and rename) an existing policy. To do so, right-click an existing policy you want to duplicate and then click **Duplicate**.
- Create a new policy based on a recommendation scan of a computer. To do so, go to the **Computers** page, right-click a computer and select **Actions > Scan for Recommendations**. When the scan is complete, return to the **Policies** page and click **New** to display the **New Policy** wizard. When prompted, choose to base the new policy on "an existing computer's current configuration". Then select "Recommended Application Types and Intrusion Prevention Rules", "Recommended Integrity Monitoring Rules", and "Recommended Log Inspection Rules" from among the computer's properties.
- **Note:** The Policy will consist only of recommended elements on the computer, regardless of what Rules are currently assigned to that computer.

Edit the settings for a policy or individual computer

The **Policies** page shows your existing policies in their hierarchical tree structure. To edit the settings for a policy, select it and click **Details** to open the policy editor.

These sections are available in the **Computer or Policy editor**¹:

- Overview (the "Overview section of the policy editor" on page 547 and "Overview section of the computer editor" on page 541 sections are different)
- "Configure malware scans" on page 668
- [Web Reputation settings](#)
- "Firewall settings" on page 801
- [Intrusion Prevention](#)
- [Integrity Monitoring](#)
- [Log Inspection settings](#)
- "Detect and configure the interfaces available on a computer" on page 540
- "Network engine settings" on page 549
- "Overrides" on page 526

Assign a policy to a computer

1. Go to **Computers**.
2. Select your computer from the Computers list, right click and choose **Actions > Assign Policy**.
3. Select the policy from the hierarchy tree and click **OK**.

One of the following occurs:

- If you set the [communication direction](#) to **Manager Initiated** or **Bidirectional**, the policy is sent immediately to the agent computer.
- If you set the communication direction to **Agent/Appliance Initiated**, then the policy is sent when the next agent heartbeat occurs.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

For more information on how child policies in a hierarchy tree can inherit or override the settings and rules of parent policies, see ["Policies, inheritance, and overrides" on the next page](#).

After assigning a policy to a computer, you should still run periodic recommendation scans on your computer to make sure that all vulnerabilities on the computer are protected. See ["Manage and run recommendation scans" on page 529](#) for more information.

Disable automatic policy updates

By default, any changes to a security policy are automatically sent to the computers that use the policy. You can change this so automatic sending is disabled, and you must manually send the policy.

1. Open the **Policy editor**¹ for the policy to configure.
2. Go to **Settings > General > Send Policy Changes Immediately**.
3. Next to **Automatically send Policy changes to computers**, select **Yes** to allow automatic sending of policy changes. To disable automatic sending, and only allow manually sending, select **No**.
4. Click **Save** to apply the changes.

Send policy changes manually

If you make a policy change and want to send the policy changes manually to a particular computer, follow the instructions below.

1. Go to **Computers**.
2. Double-click your computer from the Computers list.
3. In the navigation pane, make sure **Overview** is selected.
4. In the main pane, click the **Actions** tab.
5. Under **Policy**, click **Send Policy**.

One of the following occurs:

¹To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

- If you set the [communication direction](#) to **Manager Initiated** or **Bidirectional**, the policy is sent immediately to the agent computer.
- If you set the communication direction to **Agent/Appliance Initiated**, then the policy is sent when the next agent heartbeat occurs.

Export a policy

To export a policy to an XML file, select a policy from the policies tree and click **Export > Export Selected to XML (For Import)**.


Note: When you export a selected policy to XML, any child policies that the policy may have are included in the exported package. The export package contains all the actual objects associated with the policy except: intrusion prevention rules, log inspection rules, integrity monitoring rules, and application types.

Policies, inheritance, and overrides

Policies in Deep Security are intended to be created in a hierarchical structure. As an administrator, you begin with one or more base policies from which you create multiple levels of child policies that get progressively more granular in their detail. You can assign broadly applicable rules and other configuration settings at the top-level policies and then get more targeted and specific as you go down through levels of child policies, eventually arriving at rule and configuration assignments at the individual computer level.

As well as assigning more granular settings as you move down through the policy tree, you can also override settings from higher up the policy tree.

Deep Security provides a collection of policies that you can use as initial templates for the design of your own policies tailored to your environment:




In this topic:

- ["Inheritance" below](#)
- ["Overrides" on the next page](#)
- ["View the overrides on a computer or policy at a glance" on page 528](#)

Inheritance

Child policies inherit their settings from their parent policies. This allows you to create a policy tree that begins with a base parent policy configured with settings and rules that will apply to all computers. This parent policy can then have a set of child and further descendant policies which have progressively more specific targeted settings. Your policy trees can be built based on any kind of classification system that suits your environment. For example, the branch in the policy tree that comes with Deep Security has two child policies, one designed for a server hosting the Deep Security Manager and one designed for the Deep Security Virtual Appliance. This is a role-based tree structure. Deep Security also has three branches designed for specific operating systems, Linux, Solaris, and Windows. The windows branch has further child policies for various sub-types of Windows operating systems.

In the **Windows** policy editor on the **Overview** page, you can see that the **Windows** policy was created as a child of the **Base** policy. The policy's anti-malware setting is **Inherited (Off)**:




This means that the setting is inherited from the parent **Base** policy, and that if you were to change the anti-malware setting in the **Base** policy from **Off** to **On**, the setting would change in the **Windows** policy as well. (The **Windows** policy setting would then read **Inherited (On)**. The value in parentheses always shows you what the current inherited setting is.)

Overrides

The **Overrides** page shows you how many settings have been overridden at this policy or specific computer level. To undo the overrides at this level, click the **Remove** button.

In this example, the **Windows Server** policy is a child policy of the **Windows** policy. Here, the anti-malware setting is no longer inherited; it is overridden and hard-set to **On**.



Tip: You can automate override checking, creation, and removal using the Deep Security API. For examples, see the [Configure Computers to Override Policies](#) guide in the Deep Security Automation Center.

Override object properties

The intrusion prevention rules that are included in this policy are copies of the intrusion prevention rules stored by the Deep Security Manager which are available for use by any other policies. If you want to change the properties of a particular rule, you have two choices: modify the properties of the rule globally so that the changes you make apply to all instances where the rule is in use, or modify the properties locally so that the changes you make only apply locally. The default editing mode in a Computer or policy editor is **local**. If you click **Properties** on the **Assigned Intrusion Prevention Rules** area toolbar, any changes you make in the Properties window that appears will only apply locally. (Some properties like the rule name can't be edited locally, only globally.)

Right-clicking a rule displays a context menu which gives you the two Properties editing mode options: selecting **Properties** will open the local editor window and **Properties (Global)** will open the global editor window.

Most of the shared common objects in Deep Security can have their properties overridden at any level in the policy hierarchy right down to the individual computer level.


Override rule assignments

You can always assign additional rules at any policy or computer level. However, rules that are in effect at a particular policy or computer level because their assignment is inherited from a parent policy cannot be unassigned locally. They must be unassigned at the policy level where they were initially assigned.

Tip: If you find yourself overriding a large number of settings, you should probably consider branching your parent policy.

View the overrides on a computer or policy at a glance

You can see the number of settings that have been overridden on a policy or a computer by going to the **Overrides** page in the computer or policy Editor:



Overrides are displayed by protection module. You can revert system or module overrides by clicking the **Remove** button.

Manage and run recommendation scans

Deep Security can run recommendation scans on computers to help identify intrusion prevention, integrity monitoring, and log inspection rules that should be applied or removed.

Tip: Recommendation scans provide a good starting point for establishing a list of rules that you should implement, but there are some important additional rules that are not identified by recommendation scans. You should implement those rules manually. See ["Implement additional rules for common vulnerabilities" on page 537](#)

You can configure recommendation scans and implement the recommended rules for individual computers or at the policy level. For large deployments, Trend Micro recommends managing recommendations through policies. This way, you can make all your rule assignments from a single source (the policy) rather than having to manage individual rules on individual computers. This can mean that some rules are assigned to computers on which they are not required; however, the minimal effect on performance is outweighed by the ease of management that results from using policies. If you enable recommendation scans in policies, use separate policies for scanning Windows and Linux computers, to avoid assigning Windows rules to Linux computers, and vice-versa.

- ["What gets scanned?" on the next page](#)
- ["Scan limitations" on the next page](#)
- ["Run a recommendation scan" on page 532](#)
- ["Automatically implement recommendations" on page 535](#)
- ["Check scan results and manually assign rules" on page 536](#)
- ["Configure recommended rules" on page 537](#)
- ["Implement additional rules for common vulnerabilities" on page 537](#)
- ["Troubleshooting: Recommendation Scan Failure" on page 539](#)

What gets scanned?

During a recommendation scan, Deep Security Agents scan the operating system for:

- installed applications
- the Windows registry
- open ports
- the directory listing
- the file system
- running processes and services
- environment variables
- users

The Deep Security Virtual Appliance can perform agentless recommendation scans on virtual machines but only on Windows platforms and is limited to scanning the operating system for:

- installed applications
- the Windows registry
- the file system

Scan limitations

Certain technical or logical limitations result in the rules for some types of software not being accurately recommended, or not recommended at all:

- On Unix/Linux systems, the recommendation scan engine might have trouble detecting software that is not installed through the operating system's default package manager, for example, Apache Struts, Wordpress, or Joomla. Applications installed using standard package managers are not a problem.
- On Unix/Linux systems, rules for desktop application vulnerabilities or local vulnerabilities (for example, browsers and media players) are not included in recommendation scans.
- Generic web application protection rules are not included in recommendation scans.

- Smart rules are generally not included in recommendation scans unless they address a major threat or a specific vulnerability. Smart rules address one or more known and unknown (zero-day) vulnerabilities. Rule lists in Deep Security Manager identify smart rules with "Smart" in the Type column.
- When dealing with rules related to a content management system (CMS), the recommendation scan cannot detect the CMS installation and installed version. It also cannot detect the plug-ins installed with a CMS and their versions. As a result, whenever a recommendation scan finds a web server installed and PHP installed or running on a system, all CMS-related intrusion prevention rules get recommended. This may result in the over-recommendation of rules, but balances the need for security vs. accuracy.
- The recommendations for the following web technologies may suggest more rules than necessary, so some tailoring may be required:
 - Red Hat JBoss
 - Eclipse Jetty
 - Apache Struts
 - Oracle WebLogic
 - WebSphere
 - Oracle Application Testing Suite
 - Oracle Golden Gate
 - Nginx
- OpenSSL rules are recommended on Windows only when OpenSSL is explicitly installed. If OpenSSL is being used internally by an application but it was not installed as a separate package, a recommendation scan does not detect it.
- On Linux systems, rules for Java-related vulnerabilities do not get recommended if web browsers are the only applicable vector.
- Recommendation scans cannot detect the Adobe Flash Player plug-in that is included in a default Chrome installation. Recommendations are based on the Chrome version, which means some unnecessary rules may be recommended.

Run a recommendation scan

Because changes to your environment can affect which rules are recommended, it's best to run recommendation scans on a regular basis (the best practice is to perform recommendation scans on a weekly basis). Trend Micro releases new intrusion prevention rules on Tuesdays, so it's recommended that you schedule recommendation scans shortly after those releases. The use of system resources, including CPU cycles, memory, and network bandwidth, increases during a recommendation scan so it's best to schedule the scans at non-peak times.

There are several ways to run recommendation scans:

- **Scheduled task:** Create a scheduled task that runs recommendation scans according to a schedule that you configure. You can assign the scheduled task to all computers, one individual computer, a defined computer group, or all computers protected by a particular policy. See ["Create a scheduled task to regularly run recommendation scans" on the next page](#).
- **Ongoing scans:** Configure a policy so that all computers protected by the policy are scanned for recommendations on a regular basis. You can also configure ongoing scans for individual computers. This type of scan checks the timestamp of the last scan that occurred and then follows the configured interval thereafter to perform future scans. This results in recommendation scans occurring at different times in your environment. This setting is helpful in environments where an agent might not be online for more than a few days (for example, in cloud environments that are building and decommissioning instances frequently). See ["Configure an ongoing scan" on the next page](#).
- **Manual scans:** Run a single recommendation scan on one or more computers. A manual scan is useful if you've recently made significant platform or application changes and want to force a check for new recommendations instead of waiting for a scheduled task. See ["Manually run a recommendation scan" on page 534](#).
- **Command line:** Initiate a recommendation scan via the Deep Security command-line interface. See ["Command-line basics" on page 390](#).
- **API:** Initiate a recommendation scan via the Deep Security API. See ["Use the Deep Security API to automate tasks" on page 417](#).

Note: Use either the scheduled tasks or ongoing scans, but not both.

Once a recommendation scan has run, alerts are raised on the all computers for which recommendations have been made.

Create a scheduled task to regularly run recommendation scans

1. In the Deep Security Manager, go to the **Administration > Scheduled Tasks** page.
2. Click **New** on the toolbar and select **New Scheduled Task** to display the **New Scheduled Task** wizard.
3. In the **Type** list, select **Scan Computers for Recommendations** and then select how often you want the scan to occur. Click **Next**.
4. Depending on your choice in step 3, the next page lets you be more specific about the scan frequency. Make your selection and click **Next**.
5. Now select which computer(s) to scan and click **Next**.

Note: You can select all computers, choose one individual computer, select a group of computers, or select computers that are assigned a particular policy. For large deployments, it's best to perform all actions, including recommendation scans, through policies.

6. Give a name to your new scheduled task, select whether or not to **Run Task on 'Finish'**, click **Finish**.

Configure an ongoing scan

1. In the Deep Security Manager, open the **Computer or Policy editor**¹, depending on whether you want to configure the scan for an individual computer or for all computers that are using a policy.

Note: For large deployments, it's best to perform all actions, including recommendation scans, through policies.

2. Click **Settings**. On the **General** tab, under **Recommendations**, the **Perform ongoing Recommendation Scans** setting enables or disables recommendation scans. The **Ongoing Scan Interval** setting specifies how often the scans occur. Both of those settings

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

can be inherited from the computer or policy's parent (see "[Policies, inheritance, and overrides](#)" on page 524 for details about how inheritance works).

Manually run a recommendation scan

1. In the Deep Security Manager, go to the **Computers** page.
2. Select the computer or computers you want to scan.
3. Click **Actions > Scan for Recommendations**.

Cancel a recommendation scan

You can cancel a recommendation scan before it starts running.

1. In the Deep Security Manager, go to the **Computers** page.
2. Select the computer or computers where you want to cancel the scans.
3. Click **Actions > Cancel Recommendation Scan**.

Exclude a rule or application type from recommendation scans

If you don't want a particular rule or application type to be included in recommendation scan results, you can exclude it from scans.

1. In the Deep Security Manager, open the **Computer or Policy editor**¹.

Note: For large deployments, it's best to perform all actions, including recommendation scans, through policies.

2. Depending on which type of rule you want to exclude, go to the **Intrusion Prevention**, **Integrity Monitoring**, or **Log Inspection** page.
3. On the **General** tab, click **Assign/Unassign** (for rules) or **Application Types** (for application types).
4. Double-click the rule or application type that you want to exclude.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

5. Go to the **Options** tab. For rules, set **Exclude from Recommendations** to "Yes" or "Inherited (Yes)". For application types, select the **Exclude from Recommendations** checkbox.

Automatically implement recommendations

You can configure Deep Security to automatically implement recommendation scan results when it is appropriate to do so:

1. In the Deep Security Manager, open the **Computer or Policy editor**¹.

Note: For large deployments, it's best to perform all actions, including recommendation scans, through policies.

2. Depending on which type of rules you want to implement automatically, go to the **Intrusion Prevention**, **Integrity Monitoring**, and/or **Log Inspection** pages. (You can change the setting independently for each protection module.)
3. On the **General** tab, under **Recommendations**, change the setting to "Yes" or "Inherited (Yes)".

Not all recommendations can be implemented automatically. The exceptions are:

- Rules that require configuration before they can be applied.
- Rules that are excluded from recommendation scans.
- Rules that have been automatically assigned or unassigned but that a user has overridden. For example, if Deep Security automatically assigns a rule and you subsequently unassign it, the rule is not reassigned after the next recommendation scan.
- Rules that have been assigned at a higher level in the policy hierarchy cannot be unassigned at a lower level. A rule assigned to a computer at the policy level must be unassigned at the policy level.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the **Polices** page and double-click the policy that you want to edit (or select the policy and click **Details**). To change the settings for a computer, go to the **Computers** page and double-click the computer that you want to edit (or select the computer and click **Details**).


- Rules that Trend Micro has issued but which may pose a risk of producing false positives. (This will be addressed in the rule description.)

Check scan results and manually assign rules



The results of the latest recommendation scan are displayed in the **Computer or Policy editor**¹, on the **General** tab of the protection module (**Intrusion Prevention**, **Integrity Monitoring**, and **Log Inspection**).

The example below describes how to deal with intrusion prevention recommendation scan results via a policy:

1. Once a recommendation scan is complete, open the policy that is assigned to the computers you have just scanned.
2. Go to **Intrusion Prevention > General**. The number of unresolved recommendations (if any) is displayed in the **Recommendations** section.
3. Click **Assign/Unassign** to open the rule assignment window.
4. Sort the rules **By Application Type** and select **Recommended for Assignment** from the display filter menu:



This displays a list of rules that are recommended for assignment but that have not been assigned.

5. To assign a rule to the policy, select the checkbox next to the rule name. Rules flagged with a  icon have configuration options that you can set. Rules flagged with a  icon have settings that **must** be configured before the rule is enabled.)



Alternatively, to assign several rules at once, use the Shift or Control keys to select the rules, right-click the selection, and click **Assign Rule(s)**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Tip: The results of a recommendation scan can also include recommendations to unassign rules. This can happen when applications are uninstalled, when security patches from a manufacturer are applied, or when unnecessary rules have been applied manually. To view rules that are recommended for unassignment, select **Recommended for Unassignment** from the display filter menu.

Note: Recommended rules are indicated by a full flag (▬). A partial flag (▬) identifies an application type where only some of the rules that are part of the application type have been recommended.

Configure recommended rules

Some rules require configuration before they can be applied. For example, some log inspection rules require that you specify the location of the log files to be inspected for change. If this is the case, an alert is raised on the computer on which the recommendation has been made. The text of the alert will contain the information required to configure the rule. In the policy or computer editor, rules flagged with a  icon have configuration options that you can set. Rules flagged with a  icon have settings that **must** be configured before the rule is enabled.

Implement additional rules for common vulnerabilities

Recommendation scans provide a good starting point for establishing a list of rules that you should implement, but there are some additional rules for common vulnerabilities that are not identified by recommendation scans because they need to be carefully configured and tested before being implemented in "prevent" (block) mode. Trend Micro recommends that you configure and test these rules, then manually enable them in your policies (or for individual computers):

Tip: This list includes the most common of the additional rules you should configure. You can find others in Deep Security Manager by searching for rules whose type is "Smart" or "Policy".

Rule name	Application type
1007598 - Identified Possible Ransomware File Rename Activity Over Network Share	DCERPC Services

Trend Micro Deep Security On-Premise 11.3

Rule name	Application type
1007596 - Identified Possible Ransomware File Extension Rename Activity Over Network Share	DCERPC Services
1006906 - Identified Usage Of PsExec Command Line Tool	DCERPC Services
1007064 - Executable File Uploaded On System32 Folder Through SMB Share	DCERPC Services
1003222 - Block Administrative Share	DCERPC Services
1001126 - DNS Domain Blocker	DNS Client
1000608 - Generic SQL Injection Prevention See " Configure an SQL injection prevention rule " on page 746 for details.	Web Application Common
1005613 - Generic SQL Injection Prevention - 2	Web Application Common
1000552 - Generic Cross Site Scripting (XSS) Prevention	Web Application Common
1006022 - Identified Suspicious Image With Embedded PHP Code	Web Application Common
1005402 - Identified Suspicious User Agent In HTTP Request	Web Application Common
1005934 - Identified Suspicious Command Injection Attack	Web Application Common
1006823 - Identified Suspicious Command Injection Attack - 1	Web Application Common
1005933 - Identified Directory Traversal Sequence In Uri Query Parameter	Web Application Common
1006067 - Identified Too Many HTTP Requests With Specific HTTP Method	Web Server Common
1005434 - Disallow Upload Of A PHP File	Web Server Common
1003025 - Web Server Restrict Executable File Uploads	Web Server Common

Rule name	Application type
1007212 - Disallow Upload Of An Archive File	Web Server Common
1007213 - Disallow Upload Of A Class File	Web Server Common

Troubleshooting: Recommendation Scan Failure

If you are receiving a Recommendation Scan Failure on your server, follow the steps below to resolve the issue. If the issue continues to persist after troubleshooting, [create a diagnostic package from the agent](#) and contact support.

Communication

Typically for communication issues "protocol error" will appear in the body of the error message.

If you don't have open inbound firewall ports from the Deep Security Manager to the agent, open the [ports](#) or switch to agent-initiated communication. For more information, see "[Use agent-initiated communication with cloud accounts](#)" on page 350.

Server resources

Monitor the CPU and memory resources on the server. If the memory or CPU is becoming exhausted during the scan, increase the resources.

Timeout values

Increase the timeout values for the recommendation scan.

Note: dsm_c commands are not available on Deep Security as a Service.

1. Open the command prompt and navigate to the Deep Security Manager installation folder.
2. Enter the commands below (if this is a multi-tenant environment, add the tenant name):

```
dsm_c -action changesetting -name
settings.configuration.agentSocketTimeoutOverride -value 1200
```

```
dsm_c -action changesetting -name
settings.configuration.defaultSocketChannelTimeout -value 1200000
```

```
dsm_c -action changesetting -name  
settings.configuration.recoScanKeepAliveTimeInterval -value 180000
```

3. If you are using the Deep Security Virtual Appliance, also enter these commands:

```
dsm_c -action changesetting -name  
settings.configuration.timeoutEpsecScanRequest -value 1770
```

```
dsm_c -action changesetting -name  
settings.configuration.timeoutDsamCommandChannel -value 1800
```

Detect and configure the interfaces available on a computer

The Computer and Policy editors contain an **Interfaces** (in the Computer editor) and **Interface Types** (in the Policy editor) section that displays the interfaces detected on the computer. If a policy with multiple interface assignments has been assigned to the computer, interfaces that match the patterns defined in the policy will be identified.

The **Interface Types** section of the Policy editor provides additional capabilities:

Configure a policy for multiple interfaces

If you have computers with more than one interface, you can assign various elements of a policy (firewall rules, etc.) to each interface.

1. In the Policy editor, click **Interface Types**.
2. In the Network Interface Specificity section, select **Rules can apply to specific interfaces**.
3. In the Interface Type sections that appear, type the names and pattern matching strings.

The interface type name is used only for reference. Common names include "LAN", "WAN", "DMZ", and "Wi-Fi", though any name can be used to map to your network's topology.

The interface name used for all container network interfaces and host virtual interfaces is "integrated_veth", which has a MAC address of 02:00:00:00:00:00.

The matches define a wildcard-based interface name to auto map the interfaces to the appropriate interface type. Examples would be "Local Area Connection *", "eth*", or "Wireless *". When an interface cannot be mapped automatically, an alert is triggered. You can manually map it from the **Interfaces** page in the computer editor for a particular computer.

Note: If Deep Security detects interfaces on the computer that don't match any of these entries, the manager will trigger an alert.

Enforce interface isolation

When Interface Isolation is enabled, the firewall will try to match the regular expression patterns to interface names on the local computer. To enforce interface isolation, click **Enable Interface Isolation** option on the **Policy or Computer Editor > Firewall > Interface Isolation** tab and enter string patterns that will match the names of the interfaces on a computer (in order of priority).

Warning: Before you enable Interface Isolation make sure that you have configured the interface patterns in the proper order and that you have removed or added all necessary string patterns. Only interfaces matching the highest priority pattern will be permitted to transmit traffic. Other interfaces (which match any of the remaining patterns on the list) will be "restricted". Restricted Interfaces will block all traffic unless an Allow Firewall Rule is used to allow specific traffic to pass through.

Selecting **Limit to one active interface** will restrict traffic to only a single interface even if more than one interface matches the highest priority pattern.

Note: Deep Security uses POSIX basic regular expressions to match interface names. For information on basic POSIX regular expressions, see http://pubs.opengroup.org/onlinepubs/009695399/basedefs/xbd_chap09.html#tag_09_03

Overview section of the computer editor

The computer editor **Overview** page has the following tabbed sections:

- ["General tab" on the next page](#)
- ["Actions tab" on page 545](#)
- ["TPM tab" on page 547](#)
- ["System Events tab" on page 547](#)

General tab

- **Hostname:** Appears in the **Name** column on the **Computers** page. The name must be either the IP address of the computer or the hostname of the computer. Either a fully qualified hostname or a relative hostname can be used if a hostname is used instead of an IP address. You have to specify a hostname that can be resolved or a valid IP address that the Deep Security Manager can access. This is because the communication between the Deep Security Manager and the agent computers are based on the hostname. For relay-enabled agents, all of the computers within the relay group should be able to reach the specified IP address or hostname. If the Deep Security Manager cannot access the target computer the communication direction should be set to Agent/Appliance Initiated (Settings > Computer).
- **(Last IP Used: <IP_address>):** The last IP used by the computer. **Last IP Used** may not always show the IP address of the Deep Security Agent's host. Instead, it could be the IP address of a proxy, load balancer, elastic load balancer (ELB), etc., that the agent uses to communicate with Deep Security Manager.
- **Display Name:** Appears in the Display Name column and in brackets next to the Hostname value.
- **Description:** a description of the computer.
- **Platform:** Details of the computer's OS will appear here.
- **Group:** The computer group to which the computer belongs appears in the list. You can reassign the computer to any other existing computer group.
- **Policy:** The policy (if any) that has been assigned to this computer.

Note: Keep in mind that if you unassign a policy from a computer, rules may still be in effect on the computer if they were assigned independently of the policy.

- **Asset Importance:** Deep Security Manager uses a ranking system to quantify the importance of security events. Rules are assigned a severity level (high, medium, low, etc.), and assets (computers) are assigned an "asset importance" level. These levels have numerical values. When a rule is triggered on a computer the asset importance value and the severity level value are multiplied together. This produces a score which is used to sort events by importance. (Event ranking can be seen in the **Events** pages.) Use this **Asset**

Importance list to assign an asset importance level to this computer. (To edit the numerical values associated with severity and importance levels, go to **Administration > System Settings > Ranking**.)

- **Download Security Updates From:** Use the dropdown list to select which relay group the agent/appliance on this computer will download security updates from. (not displayed if agent is acting as a relay.)

Computer status

The Status area displays the latest available information about the computer and the protection modules in effect on it. Whether the computer is protected by an agent or an appliance (or both in the case of combined mode) is displayed in the top row.

- **Status:**
 - When the computer is unmanaged the status represents the state of the agent or appliance with respect to activation. The status will display either "Discovered" or "New" followed by the agent or appliance state in brackets ("No Agent/Appliance", "Unknown", "Reactivation Required", "Activation Required", or "Deactivation Required").
 - When the computer is managed and no computer errors are present, the status will display "Managed" followed by the state of the agent or appliance in brackets ("Online" or "Offline").
 - When the computer is managed and the agent or appliance is in the process of performing an action (e.g. "Integrity Scan in Progress", "Upgrading Agent (Install Program Sent)", etc.) the task status will be displayed.
 - When there are errors on the computer (e.g., "Offline", "Update Failed", etc.) the status will display the error. When more than one error is present, the status will display "Multiple Errors" and each error will be listed beneath.

Protection module status

The software that implements Deep Security 9.5 or later protection modules is deployed to agents on an as-needed basis. Only core functionality is included when an agent is first installed.

The **Status** area provides information about the state of the Deep Security modules. The status reflects the state of a module on the agent as well as its configuration in Deep Security Manager. A status of "On" indicates that the module is configured in Deep Security Manager and is installed and operating on the Deep Security Agent.

A green status light is displayed for a module when it is "On" and working. In addition, modules that allow individual rule assignment must have at least one rule assigned before they will display a green light.

- **Anti-Malware:** Whether anti-malware protection is on or off and whether it is configured for real-time or on-demand scans.
- **Web Reputation:** Whether web reputation is on or off.
- **Firewall:** Whether the firewall is on or off and how many rules are in effect.
- **Intrusion Prevention:** Whether intrusion prevention is on or off and how many rules are in effect.
- **Integrity Monitoring:** Whether integrity monitoring is on or off and how many rules are in effect.
- **Log Inspection:** Whether log inspection is on or off and how many rules are in effect.
- **Application Control:** Whether application control is on or off.
- **Scanner (SAP):** Status of the Deep Security Scanner SAP feature.
- **Online:** Indicates whether the manager can currently communicate with the agent or appliance.
- **Last Communication:** The last time the manager successfully communicated with the agent or appliance on this computer.
- **Check Status:** This button allows you to force the manager to perform an immediate heartbeat operation to check the status of the agent or appliance. Check Status will not perform a security update of the agent or appliance. When manager to agent or appliance communications is set to "Agent/Appliance Initiated" the **Check Status** button is disabled. Checking status will not update the logs for this computer. To update the logs for this computer, go to the **Actions** tab.
- **Clear Warnings/Errors:** Dismisses any alerts or errors on this computer.

- **ESXi server:** If the computer is a virtual machine protected by a virtual appliance, the ESXi server that hosts them is displayed.
- **Appliance:** If the computer is a virtual machine protected by a virtual appliance, the protecting appliance is displayed.
- **ESXi Version:** If the computer is an ESXi server, the ESXi version number is displayed.
- **Filter Driver version:** If the computer is an ESXi server, the filter driver version number is displayed. If you are using Deep Security Virtual Appliance 10.0 or later with ESXi 6.0 or later, "N/A" will be displayed because no filter driver is in use.
- **Guests:** If the computer is an ESXi server, the virtual appliance and guests are displayed.
- **Appliance Version:** If the computer is a virtual appliance, the appliance version number is displayed.
- **Protected Guests On:** If the computer is a virtual appliance, the IP of the ESXi server and the protected guest are displayed.

VMware virtual machine summary

This section displays a summary of hardware and software configuration information about the virtual machine on which the agent or appliance is running (VMware virtual machines only).

Actions tab

Activation

A newly installed Deep Security agent or appliance needs to be "activated" by the Deep Security Manager before policies, rules, requests for event logs, etc. can be sent to it. The activation procedure includes the exchange of SSL keys which uniquely identify a manager (or one of its nodes) and an agent/appliance to each other. Once activated by a Deep Security Manager, an agent/appliance will only accept instructions or communicate with the Deep Security Manager which activated it (or one of its nodes).

An unactivated agent or appliance can be activated by any Deep Security Manager.

Agents and appliances can only be deactivated locally on the computer or from the Deep Security Manager which activated it. If an agent or appliance is already activated, the button in this area will read **Reactivate** rather than **Activate**. Reactivation has the same effect as

activation. A reactivation will reset the agent or appliance to the state it was in after first being installed and initiate the exchange of a new set of SSL keys.

Policy

When you change the configuration of an agent or appliance on a computer using the Deep Security Manager (apply a new intrusion prevention rule, change logging settings, etc.) the Deep Security Manager has to send the new information to the agent or appliance. This is a "Send Policy" instruction. Policy updates usually happen immediately but you can force an update by clicking the **Send Policy** button.

Agent Software

This displays the version of the agent or appliance currently running on the computer. If a newer version of the agent or appliance is available for the computer's platform you can click the **Upgrade Agent** or **Upgrade Appliance** button to remotely upgrade the agent or appliance from the Deep Security Manager. You can configure the Deep Security Manager to trigger an alert if new versions of the agent or appliance software running on any of your computers by going to the **Administration > System Settings > Updates** tab.

Note: Before updating or uninstalling a Deep Security Agent or Relay on Windows, you must disable agent self-protection. To do this, on the Deep Security Manager, go to **Computer editor**¹ > **Settings > General**. In **Agent Self Protection**, and then either deselect **Prevent local end-users from uninstalling, stopping, or otherwise modifying the Agent** or enter a password for local override.

Support

The **Create Diagnostic Package** button creates a snapshot of the state of the agent or appliance on the computer. Your support provider may request this for troubleshooting purposes.

If you have lost communication with the computer, a diagnostics package can be created locally. For more information, see ["Create a diagnostic package and logs" on page 1484](#).

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

TPM tab

Note: The TPM tab will appear in place of the Actions tab for ESXi servers.

A Trusted Platform Module (TPM) is a type of chip that is used for hardware authentication. VMware uses the TPM with its ESXi hypervisors. During the boot sequence, an ESXi writes a SHA-1 hash of each hypervisor component to a set of registers as it loads. An unexpected change in these values from one boot sequence to the next can indicate a possible security issue worth investigating. Deep Security can monitor the TPM on an ESXi after every boot and raise an Alert if it detects any changes. If you select the option to enable TPM monitoring on an ESXi that doesn't support it, the option will be automatically disabled.

Enable TPM Monitoring: Select to enable Trusted Platform Module monitoring.

Raise an alert when TPM Monitoring fails to obtain valid register values: Select to have Deep Security raise an alert if the Trusted Platform Module fails to obtain valid register values for the hypervisor components during the ESXi boot sequence.

TPM Register Data Imported: Indicates whether the Trusted Protection Module data has been imported.

TPM Last Checked: Indicates when the Trusted Protection Module was last checked. You can click **Check Now** to start a check of the Trusted Platform Module.

Note: The minimum requirements for TPM monitoring are

- TPM/TXT installed and enabled on the ESXi (consult your VMware documentation for details)
- The Deep Security integrity monitoring and application control module must be properly licensed.

System Events tab

For information about events, see ["System events" on page 1220](#).

Overview section of the policy editor

The Overview section of the policy editor has the following tabbed sections:

- ["General tab" below](#)
- ["Computer\(s\) Using This Policy tab" below](#)
- ["Events tab" below](#)

General tab

General

- **Name:** Appears in the Display Name column and in brackets next to the Hostname value.
- **Description:** a description of the computer.

Inheritance

Identifies the parent policy (if any) from which the current policy inherits its settings.

Modules

- **Anti-Malware:** Whether anti-malware protection is on or off and whether it is configured for real-time or on-demand scans.
- **Web Reputation:** Whether web reputation is on or off.
- **Firewall:** Whether the firewall is on or off and how many rules are in effect.
- **Intrusion Prevention:** Whether intrusion prevention is on or off and how many rules are in effect.
- **Integrity Monitoring:** Whether integrity monitoring is on or off and how many rules are in effect.
- **Log Inspection:** Whether log inspection is on or off and how many rules are in effect.
- **Application Control:** Whether application control is on or off.

Computer(s) Using This Policy tab

Lists computers to which this policy has been assigned.

Events tab

For information about events, see ["System events" on page 1220](#).

Network engine settings

To edit the network engine settings of a policy or computer, open the **Policy editor**¹ or the **Computer editor**² for the policy or computer to configure and click **Settings > Advanced**.


Note: The **Advanced** tab also contains **Events** settings. For information on those settings, see ["Limit log file sizes" on page 1097](#). It also contains the **Generate an Alert when Agent configuration package exceeds maximum size** setting, which controls the display of the "Agent configuration package too large" setting.

The following settings are available:

- **Network Engine Mode** : The network engine is a component within the Intrusion Prevention, Firewall, and Web Reputation modules that decides whether to block or allow packets. For the Firewall and Intrusion Prevention modules, the network engine performs a packet sanity check and also makes sure each packet passes the firewall and intrusion prevention rules (called, rules matching). The network engine can operate Inline or in tap mode. When operating Inline, the packet stream passes through the network engine. Stateful tables are maintained, firewall rules are applied and traffic normalization is carried out so that intrusion prevention and firewall rules can be applied. When operating in tap mode, the packet stream is cloned and diverted from the main stream. In tap mode, the packet stream is not modified; all operations are carried out on the cloned stream.

¹To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

²To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).



- **Failure Response:** The settings here determine how the network engine behaves when it finds faulty packets. The default is to block them (Fail closed), but you can let some of them through (Fail open) for the reasons explained below.
 - **Network Engine System Failure:** This setting determines whether the network engine blocks or allows faulty packets that occur as a result of system failures on the network engine host, such as out of memory failures, allocated memory failures, and network engine (DPI) decoding failures occur. The options are:
 - **Fail closed** (default): The network engine blocks the faulty packet. It does not perform rules matching. This option provides the highest level of security.
 - **Fail open:** The network engine allows the faulty packet through, does not perform rules matching, and logs an event. Consider using **Fail open** if your agent or virtual appliance frequently encounters network exceptions because of heavy loads or lack of resources.
 - **Network Packet Sanity Check Failure:** This setting determines whether the network engine blocks or allows packets that fail the packet sanity checks. Examples of sanity check failures: firewall sanity check failures, network layer 2, 3, or 4 attribute check failures, TCP state check failures. The options are:

- **Fail closed** (default): The network engine blocks the failed packet. It does not perform any rules matching. This option provides the highest level of security.
- **Fail open**: The network engine allows the failed packet, does not perform any rules matching on it, and logs an event. Consider using **Fail open** if you want to disable the packet sanity checks, but preserve rules matching functionality.
- **Anti-Evasion Posture**: The anti-evasion setting controls the network engine handling of abnormal packets that may be attempting to evade analysis. For details, see ["Configure anti-evasion settings" on page 765](#).
- **Advanced Network Engine Options**: If you deselect the **Inherited** check box, you can customize these settings:
 - **CLOSED timeout**: For gateway use. When a gateway passes on a "hard close" (RST), the side of the gateway that received the RST will keep the connection alive for this amount of time before closing it.
 - **SYN_SENT Timeout**: How long to stay in the SYN-SENT state before closing the connection.
 - **SYN_RCVD Timeout**: How long to stay in the SYN_RCVD state before closing the connection.
 - **FIN_WAIT1 Timeout**: How long to stay in the FIN-WAIT1 state before closing the connection.
 - **ESTABLISHED Timeout**: How long to stay in the ESTABLISHED state before closing the connection.
 - **ERROR Timeout**: How long to maintain a connection in an Error state. (For UDP connections, the error can be caused by any of a variety of UDP problems. For TCP connections, the errors are probably due to packets being dropped by the firewall.)
 - **DISCONNECT Timeout**: How long to maintain idle connections before disconnecting.
 - **CLOSE_WAIT Timeout**: How long to stay in the CLOSE-WAIT state before closing the connection.
 - **CLOSING Timeout**: How long to stay in the CLOSING state before closing the connection.

- **LAST_ACK Timeout:** How long to stay in the LAST-ACK state before closing the connection.
- **ACK Storm timeout:** The maximum period of time between retransmitted ACKs within an ACK Storm. In other words, if ACKs are being retransmitted at a lower frequency then this timeout, they will NOT be considered part of an ACK Storm.
- **Boot Start Timeout:** For gateway use. When a gateway is booted, there may already exist established connections passing through the gateway. This timeout defines the amount of time to allow non-SYN packets that could be part of a connection that was established before the gateway was booted to close.
- **Cold Start Timeout:** Amount of time to allow non-SYN packets that could belong to a connection that was established before the stateful mechanism was started.
- **UDP Timeout:** Maximum duration of a UDP connection.
- **ICMP Timeout:** Maximum duration of an ICMP connection.
- **Allow Null IP:** Allow or block packets with no source or destination IP address.
- **Block IPv6 on Agents and Appliances versions 8 and earlier:** Block or Allow IPv6 packets on older version 8.0 agents and appliances.

Note: Deep Security Agents and Appliances versions 8.0 and older are unable to apply firewall or DPI rules to IPv6 network traffic and so the default setting for these older versions is to block IPv6 traffic.

Block IPv6 on Agents and Appliances versions 8 and earlier: Block or Allow IPv6 packets on older version 8.0 Agents and Appliances.

Note: Deep Security Agents and Appliances versions 8.0 and older are unable to apply firewall or DPI Rules to IPv6 network traffic and so the default setting for these older versions is to block IPv6 traffic.

- **Block IPv6 on Agents and Appliances versions 9 and later:** Block or Allow IPv6 packets on agents and appliances that are version 9 or later.
- **Connection Cleanup Timeout:** Time between cleanup of closed connections (see next).

- **Maximum Connections per Cleanup:** Maximum number of closed connections to cleanup per periodic connection cleanup (see previous).
- **Block Same Src-Dest IP Address:** Block or allow packets with same source and destination IP address. (Doesn't apply to loopback interface.)
- **Maximum TCP Connections:** Maximum simultaneous TCP Connections.
- **Maximum UDP Connections:** Maximum simultaneous UDP Connections.
- **Maximum ICMP Connections:** Maximum simultaneous ICMP Connections.
- **Maximum Events per Second:** Maximum number of events that can be written per second.
- **TCP MSS Limit:** The MSS is the Maximum Segment Size (or largest amount of data) that can be sent in a TCP packet without being fragmented. This is usually established when two computers establish communication. However, in some occasions, the traffic goes through a router or switch that has a smaller MSS. In this case the MSS can change. This causes retransmission of the packets and the agent or appliance logs them as "Dropped Retransmit". In cases where there are large numbers of dropped retransmit event entries, you may wish to lower this limit and see if the volume is reduced.
- **Number of Event Nodes:** The maximum amount of kernel memory the driver will use to store log/event information for folding at any one time.

Note: Event folding occurs when many events of the same type occur in succession. In such cases, the agent/appliance will "fold" all the events into one.

- **Ignore Status Code:** This option lets you ignore certain types of events. If, for example, you are getting a lot of "Invalid Flags" you can simply ignore all instances of that event.
- **Ignore Status Code:** Same as above.
- **Ignore Status Code:** Same as above.
- **Advanced Logging Policy:**
 - **Bypass:** No filtering of events. Overrides the "Ignore Status Code" settings (above) and other advanced settings, but does not override logging settings defined in the Deep Security Manager. For example, if firewall stateful configuration logging

options set from a Firewall Stateful Configuration Properties window in the Deep Security Manager will not be affected.

- **Normal:** All events are logged except dropped retransmits.
- **Default:** Will switch to "Tap Mode" (below) if the engine is in tap mode, and will switch to "Normal" (above) if the engine is in inline mode.
- **Backwards Compatibility Mode:** For support use only.
- **Verbose Mode:** Same as "Normal" but including dropped retransmits.
- **Stateful and Normalization Suppression:** Ignores dropped retransmit, out of connection, invalid flags, invalid sequence, invalid ack, unsolicited udp, unsolicited ICMP, out of allowed policy.
- **Stateful, Normalization, and Frag Suppression:** Ignores everything that "Stateful and Normalization Suppression" ignores as well as events related to fragmentation.
- **Stateful, Frag, and Verifier Suppression:** Ignores everything "Stateful, Normalization, and Frag Suppression" ignores as well as verifier-related events.
- **Tap Mode:** Ignores dropped retransmit, out of connection, invalid flags, invalid sequence, invalid ack, max ack retransmit, packet on closed connection.

Note: For a more comprehensive list of which events are ignored in **Stateful and Normalization Suppression**; **Stateful, Normalization, and Frag Suppression**; **Stateful, Frag, and Verifier Suppression**; and **Tap** modes, see ["Reduce the number of logged events" on page 1107](#).

- **Silent TCP Connection Drop:** When Silent TCP Connection Drop is on, a RST packet is only sent to the local stack. No RST packet is sent on the wire. This reduces the amount of information sent back to a potential attacker.

Note: If you enable the Silent TCP Connection Drop you must also adjust the DISCONNECT Timeout. Possible values for DISCONNECT Timeout range from 0 seconds to 10 minutes. This must be set high enough that the connection is closed by the application before it is closed by the Deep Security agent/appliance. Factors

that will affect the DISCONNECT Timeout value include the operating system, the applications that are creating the connections, and network topology.

- **Enable Debug Mode:** When in debug mode, the agent/appliance captures a certain number of packets (specified by the setting below: Number of Packets to retain in Debug Mode). When a rule is triggered and debug mode is on, the agent/appliance will keep a record of the last X packets that passed before the rule was triggered. It will return those packets to the manager as debug events.

Note: Debug mode can very easily cause excessive log generation and should only be used under Client Services supervision.

- **Number of Packets to retain in Debug Mode:** The number of packets to retain and log when debug mode is on.
- **Log All Packet Data:** Record the packet data for events that are not associated with specific firewall or intrusion prevention rules. That is, log packet data for events such as "Dropped Retransmit" or "Invalid ACK".

Note: Events that have been aggregated because of event folding cannot have their packet data saved.

- **Log only one packet within period:** If this option is enabled and **Log All Packet Data** is not, most logs will contain only the header data. A full packet will be attached periodically, as specified by the **Period for Log only one packet within period** setting.
- **Period for Log only one packet within period:** When **Log only one packet within period** is enabled, this setting specifies how often the log will contain full packet data.
- **Maximum data size to store when packet data is captured:** The maximum size of header or packet data to be attached to a log.
- **Generate Connection Events for TCP:** Generates a firewall event every time a TCP connection is established.
- **Generate Connection Events for ICMP:** Generates a firewall event every time an ICMP connection is established.

- **Generate Connection Events for UDP:** Generates a firewall event every time a UDP connection is established.
- **Bypass CISCO WAAS Connections:** This mode bypasses stateful analysis of TCP sequence numbers for connections initiated with the proprietary CISCO WAAS TCP option selected. This protocol carries extra information in invalid TCP Sequence and ACK numbers that interfere with stateful firewall checks. Only enable this option if you are using CISCO WAAS and you are seeing connections with Invalid SEQ or Invalid ACK in the firewall logs. When this option is selected, TCP stateful sequence number checks are still performed for non WAAS enabled connections.
- **Drop Evasive Retransmit:** Incoming packets containing data that has already been processed will be dropped to avoid possible evasive retransmit attack techniques.
- **Verify TCP Checksum:** The segment's checksum field data will be used to assess the integrity of the segment.
- **Minimum Fragment Offset:** Defines the minimum acceptable IP fragment offset. Packets with offsets less than this will be dropped with reason "IP fragment offset too small". If set to 0 no limit is enforced. (default 60)
- **Minimum Fragment Size:** Defines the minimum acceptable IP fragment size. Fragmented packets that are smaller than this will be dropped with reason "First fragment too small" as potentially malicious. (default 120)
- **SSL Session Size:** Sets the maximum number of SSL session entries maintained for SSL session keys.
- **SSL Session Time:** Sets how long SSL session renewal keys are valid before they expire.
- **Filter IPv4 Tunnels:** Not used by this version of Deep Security.
- **Filter IPv6 Tunnels:** Not used by this version of Deep Security.
- **Strict Teredo Port Check:** Not used by this version of Deep Security.
- **Drop Teredo Anomalies:** Not used by this version of Deep Security.
- **Maximum Tunnel Depth:** Not used by this version of Deep Security.
- **Action if Maximum Tunnel Depth Exceeded:** Not used by this version of Deep Security.

- **Drop IPv6 Extension Type 0:** Not used by this version of Deep Security.
- **Drop IPv6 Fragments Lower Than minimum MTU:** Drop IPv6 fragments that do not meet the minimum MTU size specified by IETF RFC 2460.
- **Drop IPv6 Reserved Addresses:** Drop these reserved addresses:
 - IETF reserved 0000::/8
 - IETF reserved 0100::/8
 - IETF reserved 0200::/7
 - IETF reserved 0400::/6
 - IETF reserved 0800::/5
 - IETF reserved 1000::/4
 - IETF reserved 4000::/2
 - IETF reserved 8000::/2
 - IETF reserved C000::/3
 - IETF reserved E000::/4
 - IETF reserved F000::/5
 - IETF reserved F800::/6
- **Drop IPv6 Site Local Addresses:** Drop site local addresses FEC0::/10.
- **Drop IPv6 Bogon Addresses:** Drop these addresses:
 - "loopback ::1
 - "IPv4 compatible address", ::/96
 - "IPv4 mapped address" ::FFFF:0.0.0.0/96
 - "IPv4 mapped address", ::/8
 - "OSI NSAP prefix (deprecated by RFC4048)" 0200::/7
 - "6bone (deprecated)", 3ffe::/16
 - "Documentation prefix", 2001:db8::/32

- **Drop 6to4 Bogon Addresses:** Drop these addresses:
 - "6to4 IPv4 multicast", 2002:e000:: /20
 - "6to4 IPv4 loopback", 2002:7f00:: /24
 - "6to4 IPv4 default", 2002:0000:: /24
 - "6to4 IPv4 invalid", 2002:ff00:: /24
 - "6to4 IPv4 10.0.0.0/8", 2002:0a00:: /24
 - "6to4 IPv4 172.16.0.0/12", 2002:ac10:: /28
 - "6to4 IPv4 192.168.0.0/16", 2002:c0a8:: /32
- **Drop IP Packet with Zero Payload:** Drop IP packets that have a zero-length payload.
- **Drop Unknown SSL Protocol:** Drop connection if a client attempts to connect to the Deep Security Manager with the wrong protocol. By default, any protocol other than "http/1.1" will cause an error.
- **Force Allow DHCP DNS:** Controls whether the following hidden firewall rules are enabled:

Rule type	Priority	Direction	Protocol	Source port	Destination port
Force Allow	4	Outgoing	DNS	Any	53
Force Allow	4	Outgoing	DHCP	68	67
Force Allow	4	Incoming	DHCP	67	68

When the rules are enabled, agent computers can connect with the manager using the listed protocols and ports. The following values for this property are available:

- **Inherited:** Inherits the setting from the policy
- **Turn off rules:** Disables the rules. Note that this setting can cause agent computers to appear offline
- **Allow DNS Query:** Enable only the DNS-related rule
- **Allow DNS Query and DHCP Client:** Enable all 3 rules

- **Force Allow ICMP type3 code4:** Controls whether the following hidden firewall rules are enabled:

Rule type	Priority	Direction	Protocol	Type	Code
Force Allow	4	Incoming	ICMP	3	4

When enabled, these rules allow relay computers to connect with the manager so that the relay's heartbeat is transmitted. The following values are available:

- **Inherited:** Inherits the setting from the policy.
 - **Turn off rules:** Disables the rule. This value can cause connection timeouts or "Destination cannot be reached" responses.
 - **Add Force Allow rule for ICMP type3 code4:** Enables the rule.
- **Fragment Timeout:** If configured to do so, the intrusion prevention rules will inspect the content of a packet (or packet fragment) if that content is considered suspicious. This setting determines how long after inspecting to wait for the remaining packet fragments before discarding the packet.
 - **Maximum number of fragmented IP packets to keep:** Specifies the maximum number of fragmented packets that Deep Security will keep.
 - **Send ICMP to indicate fragmented packet timeout exceeded:** When this setting is enabled and the fragment timeout is exceeded, an ICMP packet is sent to the remote computer.
 - **Bypass MAC addresses that don't belong to host:** Bypass incoming packets whose destination MAC address does not belong to the host. Enabling this option reduces the number of network events caused by fetching packets that are created due to NIC teaming or a NIC in promiscuous mode on agents and appliances that are version 10.2 or later.

Define rules, lists, and other common objects used by policies

The Common Objects pages (located under **Policies > Common Objects** in Deep Security Manager) provide a way to define objects once so that you can reuse them various policies and rules. When you use one of the common objects in the policy or computer editor, its settings can

be overridden for that specific policy or computer. For more information on how common object properties can be inherited and overridden at the policy or computer level, see ["Policies, inheritance, and overrides"](#) on page 524.

Tip: You can automate common object creation and configuration using the Deep Security API. For examples, see the [Create and Configure Common Objects for Policies and Computers](#) guide in the Deep Security Automation Center.

Rules

Some protection modules make use of rules:

- ["Create a firewall rule" on page 786](#)
- [Configure an intrusion prevention rule for use in policies](#)
- ["Create an integrity monitoring rule" on page 832](#)
- ["Define a log inspection rule for use in policies" on page 893](#)

Lists

- ["Create a list of directories for use in policies" on page 608](#)
- ["Create a list of file extensions for use in policies" on page 611](#)
- ["Create a list of files for use in policies" on page 612](#)
- ["Create a list of IP addresses for use in policies" on page 615](#)
- ["Create a list of MAC addresses for use in policies" on page 617](#)
- ["Create a list of ports for use in policies" on page 616](#)

Other

- ["Define contexts for use in policies" on page 618](#)
- ["Define stateful firewall configurations" on page 814](#)
- ["Configure malware scans" on page 668](#)
- ["Define a schedule that you can apply to rules" on page 625](#)

Create a firewall rule

Firewall rules examine the control information in individual packets, and either block or allow them according to the criteria that you define. Firewall rules can be assigned to a policy or directly to a computer.

Note: This article specifically covers how to create a firewall rule. For information on how to configure the firewall module, see ["Set up the Deep Security firewall" on page 771](#).

To create a new firewall rule, you need to:

1. ["Add a new rule" below](#).
2. ["Select the behavior and protocol of the rule" on the next page](#).
3. ["Select a Packet Source and Packet Destination" on page 564](#).

When you're done with your firewall rule, you can also learn how to:

- ["Configure rule events and alerts" on page 565](#)
- ["Set a schedule for the rule" on page 566](#)
- ["See policies and computers a rule is assigned to" on page 566](#)
- ["Assign a context to the rule " on page 566](#)

Add a new rule

There are three ways to add a new firewall rule on the **Policies > Common Objects > Rules > Firewall Rules** page. You can:

- Create a new rule. Click **New > New Firewall Rule**.
- Import a rule from an XML file. Click **New > Import From File**.
- Copy and then modify an existing rule. Right-click the rule in the Firewall Rules list and then click **Duplicate**. To edit the new rule, select it and then click **Properties**.

Select the behavior and protocol of the rule

1. Enter a **Name** and **Description** for the rule.

Tip: It is good practice to document all firewall rule changes in the Description field of the firewall rule. Make a note of when and why rules were created or deleted for easier firewall maintenance.

2. Select the **Action** that the rule should perform on packets. You can select from one of the following five actions:

Note: Only one rule action is applied to a packet, and rules (of the same priority) are applied in the order of precedence listed below.

- The rule can allow traffic to **bypass** the firewall. A bypass rule allows traffic to pass through the firewall and intrusion prevention engine at the fastest possible rate. Bypass rules are meant for traffic using media intensive protocols where filtering may not be desired or for traffic originating from trusted sources.

Tip: For an example of how to create and use a bypass rule for trusted sources in a policy, see ["Allow trusted traffic to bypass the firewall" on page 792](#).

Note: Bypass rules are unidirectional. Explicit rules are required for each direction of traffic.

Tip: You can achieve maximum throughput performance on a bypass rule with the following settings:

- **Priority:** Highest
- **Frame Type:** IP
- **Protocol:** TCP, UDP, or other IP protocol. (Do not use the "Any" option.)
- **Source and Destination IP and MAC:** all "Any"
- If the protocol is TCP or UDP and the traffic direction is "incoming", the destination ports must be one or more specified ports (not "Any"), and the source ports must be "Any".

- If the protocol is TCP or UDP and the traffic direction is "outgoing", the source ports must be one or more specified ports (Not "Any"), and the destination ports must be "Any".
- **Schedule:** None.

- The rule can **log only**. This action will make entries in the logs but will not process traffic.
- The rule can **force allow** defined traffic (it will allow traffic defined by this rule without excluding any other traffic.)
- The rule can **deny** traffic (it will deny traffic defined by this rule.)
- The rule can **allow** traffic (it will exclusively allow traffic defined by this rule.)

Note: If you have no allow rules in effect on a computer, all traffic is permitted unless it is specifically blocked by a deny rule. Once you create a single allow rule, all other traffic is blocked unless it meets the requirements of the allow rule. There is one exception to this: ICMPv6 traffic is always permitted unless it is specifically blocked by a deny rule.

3. Select the **Priority** of the rule. The priority determines the order in which rules are applied. If you have selected "force allow", "deny", or "bypass" as your rule action, you can set a priority of 0 (low) to 4 (highest). Setting a priority allows you to combine the actions of rules to achieve a cascading rule effect.

Note: Log only rules can only have a priority of 4, and Allow rules can only have a priority of 0.

Note: High priority rules get applied before low priority rules. For example, a port 80 incoming deny rule with a priority of 3 will drop a packet before a port 80 incoming force allow rule with a priority of 2 gets applied to it.

For detailed information on how actions and priority work together, see ["Firewall rule actions and priorities" on page 794](#).

4. Select a **Packet Direction**. Select whether this rule will be applied to **incoming** (from the

network to the computer) or **outgoing**(from the computer to the network) traffic.

Note: An individual firewall rule only apply to a single direction of traffic. You may need to create incoming and outgoing firewall rules in pairs for specific types of traffic.

5. Select an Ethernet **Frame Type**. The term "frame" refers to Ethernet frames, and the available protocols specify the data that the frame carries. If you select "Other" as the frame type, you need to specify a [frame number](#).
6. **Note:** IP covers both IPv4 and IPv6. You can also select **IPv4** or **IPv6** individually

Note: Linux Agents will only examine packets with IP or ARP frame types. Packets with other frame types will be allowed through. Note that the Virtual Appliance does not have these restrictions and can examine all frame types, regardless of the operating system of the virtual machine it is protecting.

If you select the Internet Protocol (IP) frame type, you need to select the transport **Protocol**. If you select "Other" as the protocol, you also need to enter a [protocol number](#).

Select a Packet Source and Packet Destination

Select a combination of **IP** and **MAC** addresses, and if available for the frame type, **Port** and **Specific Flags** for the Packet Source and Packet Destination.

Tip: You can use a previously created [IP](#), [MAC](#) or [port](#) list.

Support for IP-based frame types is as follows:

	IP	MAC	Port	Flags
Any	✓	✓		
ICMP	✓	✓		✓
ICMPV6	✓	✓		✓
IGMP	✓	✓		
GGP	✓	✓		

	IP	MAC	Port	Flags
TCP	✓	✓	✓	✓
PUP	✓	✓		
UDP	✓	✓	✓	
IDP	✓	✓		
ND	✓	✓		
RAW	✓	✓		
TCP+UDP	✓	✓	✓	✓

Note: ARP and REVARP frame types only support using MAC addresses as packet sources and destinations.

You can select **Any Flags** or individually select the following flags:

- URG
- ACK
- PSH
- RST
- SYN
- FIN

Configure rule events and alerts

When a firewall rule is triggered, it logs an event in the Deep Security Manager and records the packet data.

Note: Note that rules using the "Allow", "Force Allow" and "Bypass" actions will not log any events.

Alerts

You can configure rules to also trigger an alert if they log an event. To do so, open the properties for a rule, click on **Options**, and then select **Alert when this rule logs an event**.

Note: Only firewall rules with an action set to "Deny" or "Log Only" can be configured to trigger an alert.

Set a schedule for the rule

Select whether the firewall rule should only be active during a scheduled time.

For more information on how to do so, see ["Define a schedule that you can apply to rules" on page 625](#).

Assign a context to the rule

Rule contexts allow you to set firewall rules uniquely for different network environments. Contexts are commonly used to allow for different rules to be in effect for laptops when they are on and off-site.

For more information on how to create a context, see ["Define contexts for use in policies" on page 618](#).

Tip: For an example of a policy that implements firewall rules using contexts, look at the properties of the "Windows Mobile Laptop" Policy.

See policies and computers a rule is assigned to

You can see which policies and computers are assigned to a firewall rule on the **Assigned To** tab. Click on a policy or computer in the list to see their properties.

Export a rule

You can export all firewall rules to a .csv or .xml file by clicking **Export** and selecting the corresponding export action from the list. You can also export specific rules by first selecting them, clicking **Export** and then selecting the corresponding export action from the list.

Delete a rule

To delete a rule, right-click the rule in the Firewall Rules list, click **Delete** and then click **OK**.

Note: Firewall Rules that are assigned to one or more computers or that are part of a policy cannot be deleted.

Configure intrusion prevention rules

Perform the following tasks to configure and work with intrusion prevention rules:

- ["See the list of intrusion prevention rules" below](#)
- ["See information about an intrusion prevention rule" on the next page](#)
- ["See information about the associated vulnerability \(Trend Micro rules only\)" on page 570](#)
- ["Assign and unassign rules" on page 570](#)
- ["Automatically assign updated required rules" on page 571](#)
- ["Configure event logging for rules" on page 571](#)
- ["Generate alerts" on page 572](#)
- ["Setting configuration options \(Trend Micro rules only\)" on page 573](#)
- ["Schedule active times" on page 573](#)
- ["Exclude from recommendations" on page 574](#)
- ["Set the context for a rule" on page 574](#)
- ["Override the behavior mode for a rule" on page 575](#)
- ["Override rule and application type configurations" on page 575](#)
- ["Export and import rules" on page 576](#)
- ["Configure an SQL injection prevention rule" on page 746](#)

For an overview of the intrusion prevention module, see ["Block exploit attempts using intrusion prevention" on page 724](#).

See the list of intrusion prevention rules

The Policies page provides a list of intrusion prevention rules. You can search for intrusion prevention rules, and open and edit rule properties. In the list, rules are grouped by application type, and some rule properties appear in different columns.

Tip: The "TippingPoint" column contains the equivalent Trend Micro TippingPoint rule ID. In the Advanced Search for intrusion prevention, you can search on the TippingPoint rule ID. You can also see the TippingPoint rule ID in the list of assigned intrusion prevention rules in the policy and computer editor.

To see the list, click **Policies**, and then below **Common Objects/Rules** click **Intrusion Prevention Rules**.

See information about an intrusion prevention rule



The properties of intrusion prevention rules include information about the rule and the exploit against which it protects.

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.

General Information

- **Name:** The name of the intrusion prevention rule.
- **Description:** The description of the intrusion prevention rule.
- **Minimum Agent/Appliance Version:** The minimum version of the Deep Security **Agent or Appliance**¹ required to support this intrusion prevention rule.

Details

Clicking **New** () or **Properties** () displays the **Intrusion Prevention Rule Properties** window.

Note: Note the **Configuration** tab. Intrusion Prevention Rules from Trend Micro are not directly editable through Deep Security Manager. Instead, if the Intrusion Prevention Rule requires (or allows) configuration, those configuration options will be available on the **Configuration** tab. Custom Intrusion Prevention Rules that you write yourself will be editable, in which case the **Rules** tab will be visible.

¹The Deep Security Agent and Deep Security Virtual Appliance are the components that enforce the Deep Security policies that you have defined. Agents are deployed directly on a computer. Appliances are used in VMware vSphere environments to provide agentless protection. They are not available with Deep Security as a Service.

See the list of intrusion prevention rules

The Policies page provides a list of intrusion prevention rules. You can search for intrusion prevention rules, and open and edit rule properties. In the list, rules are grouped by application type, and some rule properties appear in different columns.

Tip: The "TippingPoint" column contains the equivalent Trend Micro TippingPoint rule ID. In the Advanced Search for intrusion prevention, you can search on the TippingPoint rule ID. You can also see the TippingPoint rule ID in the list of assigned intrusion prevention rules in the policy and computer editor.

To see the list, click **Policies**, and then below **Common Objects/Rules** click **Intrusion Prevention Rules**.

General Information

- **Application Type:** The application type under which this intrusion prevention rule is grouped.

Tip: You can edit application types from this panel. When you edit an application type from here, the changes are applied to all security elements that use it.

- **Priority:** The priority level of the rule. Higher priority rules are applied before lower priority rules.
- **Severity:** Setting the severity of a rule has no effect on how the rule is implemented or applied. Severity levels can be useful as sorting criteria when viewing a list of intrusion prevention rules. More importantly, each severity level is associated with a severity value; this value is multiplied by a computer's Asset Value to determine the Ranking of an Event. (See **Administration > System Settings > Ranking**.)
- **CVSS Score:** A measure of the severity of the vulnerability according to the [National Vulnerability Database](#).

Identification (Trend Micro rules only)

- **Type:** Can be either Smart (one or more known and unknown (zero day) vulnerabilities), Exploit (a specific exploit, usually signature based), or Vulnerability (a specific vulnerability)

for which one or more exploits may exist).

- **Issued:** The date the rule was released. This does not indicate when the rule was downloaded.
- **Last Updated:** The last time the rule was modified either locally or during Security Update download.
- **Identifier:** The rule's unique identification tag.

See information about the associated vulnerability (Trend Micro rules only)

Rules that Trend Micro provides can include information about the vulnerability against which the rule protects. When applicable, the Common Vulnerability Scoring System (CVSS) is displayed. (For information on this scoring system, see the CVSS page at the [National Vulnerability Database](#).)

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the **Vulnerabilities** tab.

Assign and unassign rules

To apply intrusion prevention rules during agent scans, you assign them to the appropriate policies and computers. When the rule is no longer necessary because the vulnerability has been patched you can unassign the rule.

If you cannot unassign intrusion prevention rules from a **Computer editor**¹, it is likely because the rules are currently assigned in a policy. Rules assigned at the policy level must be removed using the **Policy editor**² and cannot be removed at the computer level.

When you make a change to a policy, it affects all computers using the policy. For example, when you unassign a rule from a policy you remove the rule from all computers that are protected by that policy. To continue to apply the rule to other computers, create a new policy for that group of computers. (See "[Policies, inheritance, and overrides](#)" on page 524.)

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

Tip: To see the policies and computers to which a rule is assigned, see the Assigned To tab of the rule properties.

1. Go to the **Policies** page, right-click the policy to configure and click **Details**.
2. Click **Intrusion Prevention > General**.
The list of rules that are assigned to the policy appear in the **Assigned Intrusion Prevention Rules** list.
3. Under **Assigned Intrusion Prevention Rules**, click **Assign/Unassign**.
4. To assign a rule, select the check box next to the rule.
5. To unassign a rule, deselect the check box next to the rule.
6. Click **OK**.

Automatically assign updated required rules

Security updates can include new or updated application types and intrusion prevention rules which require the assignment of secondary intrusion prevention rules. Deep Security can automatically assign these rules if they are required. You enable these automatic assignments in the the policy or computer properties.

1. Go to the **Policies** page, right-click the policy to configure and click **Details**.
2. Click **Intrusion Prevention > Advanced**.
3. To enable the automatic assignments, in the **Rule Updates** area, select **Yes**.
4. Click **OK**.

Configure event logging for rules

Configure whether events are logged for a rule, and whether to include packet data in the log.

Note: Deep Security can display X-Forwarded-For headers in intrusion prevention events when they are available in the packet data. This information can be useful when the Deep Security Agent is behind a load balancer or proxy. The X-Forwarded-For header data appears in the event's Properties window. To include the header data, include packet data in the log. In addition, rule 1006540 " Enable X-Forwarded-For HTTP Header Logging" must be assigned.

Because it would be impractical to record all packet data every time a rule triggers an event, Deep Security records the data only the first time the event occurs within a specified period of time. The default time is five minutes, however you can change the time period using the "Period

for Log only one packet within period" property of a policy's Advanced Network Engine settings. (See [Advanced Network Engine Options](#).)

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see "[Override rule and application type configurations](#)" on [page 575](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. On the General tab, go to the Events area and select the desired options:
 - To disable logging for the rule, select **Disable Event Logging**.
 - To log an event when a packet is dropped or blocked, select **Generate Event on Packet Drop**.
 - To include the packet data in the log entry, select **Always Include Packet Data**.
 - To log several packets that precede and follow the packet that the rule detected, select **Enable Debug Mode**. Use debug mode only when your support provider instructs you to do so.

Additionally, to include packet data in the log, the policy to which the rule is assigned must allow rules to capture packet data:

1. On the Policies page, open the policy that is assigned the rule.
2. Click **Intrusion Prevention > Advanced**.
3. In the **Event Data** area, select **Yes**.

Generate alerts

Generate an alert when an intrusion prevention rule triggers an event.

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see "[Override rule and application type configurations](#)" on [page 575](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the Options tab, and in the **Alert** area select **On**.
4. Click **OK**.

Setting configuration options (Trend Micro rules only)

Some intrusion prevention rules that Trend Micro provides have one or more configuration options such as header length, allowed extensions for HTTP, or cookie length. Some options require you to configure them. If you assign a rule without setting a required option, an alert is generated that informs you about the required option. (This also applies to any rules that are downloaded and automatically applied by way of a Security Update.)


Intrusion prevention rules that have configuration options appear in the Intrusion Prevention Rules list with a small gear over their icon .

Note: Custom intrusion prevention rules that you write yourself include a **Rules** tab where you can edit the rules.

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" on page 575](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the **Configuration** tab.
4. Configure the properties and then click **OK**.

Schedule active times

Schedule a time during which an intrusion prevention rule is active. Intrusion prevention rules that are active only at scheduled times appear in the Intrusion Prevention Rules page with a small clock over their icon .

Note: With Agent-based protection, schedules use the same time zone as the endpoint operating system. With Agentless protection, schedules use the same time zone as the Deep Security Virtual Appliance. Agentless protection is not available with Deep Security as a Service.

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" on the next page](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the **Options** tab.
4. In the **Schedule** area, select **New** or select a frequency.
5. Edit the schedule as required.
6. Click **OK**.

Exclude from recommendations

Exclude intrusion prevention rules from rule recommendations of recommendation scans.

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" on the next page](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the **Options** tab.
4. In the **Recommendations Options** area, select **Exclude from Recommendations**.
5. Click **OK**.

Set the context for a rule

Set the context in which the rule is applied.

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" on the next page](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the **Options** tab.
4. In the **Context** area, select **New** or select a context.

5. Edit the context as required.
6. Click **OK**.

Override the behavior mode for a rule

Set the behavior mode of an intrusion prevention rule to Detect when testing new rules. In Detect mode, the rule creates a log entry prefaced with the words "detect only:" and does not interfere with traffic. Some intrusion prevention rules are designed to operate only in Detect mode. For these rules, you cannot change the behavior mode.

Note: If you disable logging for the rule, the rule activity is not logged regardless of the behavior mode.

For more information about behavior modes, see ["Use behavior modes to test rules" on page 726](#).

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" below](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Select **Detect Only**.

Override rule and application type configurations

From a **Computer or Policy editor**¹, you can edit an intrusion prevention rule so that your changes apply only in the context of the policy or computer. You can also edit the rule so that the changes apply globally so that the changes affect other policies and computers that are assigned the rule. Similarly, you can configure application types for a single policy or computer, or globally.

1. Go to the **Policies** page, right-click the policy to configure and click **Details**.
2. Click **Intrusion Prevention**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

3. To edit a rule, right-click the rule and select one of the following commands:
 - **Properties**: Edit the rule only for the policy.
 - **Properties (Global)**: Edit the rule globally, for all policies and computers.
4. To edit the application type of a rule, right-click the rule and select one of the following commands:
 - **Application Type Properties**: Edit the application type only for the policy.
 - **Application Type Properties (Global)**: Edit the application type globally, for all policies and computers.
5. Click **OK**.

Tip: When you select the rule and click **Properties**, you are editing the rule only for the policy that you are editing.

Note: You cannot assign one port to more than eight application types. If they are, the rules will not function on that port.

Export and import rules

You can export one or more intrusion prevention rules to an XML or CSV file, and import rules from an XML file.

1. Click **Policies > Intrusion Prevention Rules**.
2. To export one or more rules, select them and click **Export > Export Selected to CSV** or **Export > Export Selected to XML**.
3. To export all rules, click **Export > Export to CSV** or **Export > Export to XML**.
4. To import rules, click **New > Import From File** and follow the instructions on the wizard.

Create an integrity monitoring rule

Integrity Monitoring rules describe how Deep Security Agents should scan for and detect changes to a computer's files, directories, and registry keys and values, as well as changes in installed software, processes, listening ports, and running services. Integrity Monitoring rules can be assigned directly to computers or can be made part of a policy.

Note: This article specifically covers how to create an Integrity Monitoring rule. For information on how to configure the Integrity Monitoring module, see ["Set up integrity monitoring" on page 824](#).

There are two types of Integrity Monitoring rules: those that you have created, and those that are issued by Trend Micro. For more information on how to configure rules issued by Trend Micro, see the ["Configure Trend Micro Integrity Monitoring rules" on page 579](#) section.

To create a new Integrity Monitoring rule, you need to:

1. ["Add a new rule" below](#).
2. ["Enter Integrity Monitoring rule information " on the next page](#).
3. ["Select a rule template and define rule attributes" on the next page](#).

When you're done with your rule, you can also learn how to

- ["Configure rule events and alerts" on page 580](#)
- ["See policies and computers a rule is assigned to" on page 581](#)
- ["Export a rule" on page 581](#)
- ["Delete a rule" on page 581](#)

Add a new rule

There are three ways to add an Integrity Monitoring rule on the **Policies > Common Objects > Rules > Integrity Monitoring Rules** page. You can:

- Create a new rule. Click **New > New Integrity Monitoring Rule**.
- Import a rule from an XML file. Click **New > Import From File**.
- Copy and then modify an existing rule. Right-click the rule in the Integrity Monitoring Rules list and then click **Duplicate**. To edit the new rule, select it and then click **Properties**.

Enter Integrity Monitoring rule information

1. Enter a **Name** and **Description** for the rule.

Tip: It is good practice to document all Integrity Monitoring rule changes in the Description field of the firewall rule. Make a note of when and why rules were created or deleted for easier maintenance.

2. Set the **Severity** of the rule.

Note: Setting the severity of a rule has no effect on how the rule is implemented or applied. Severity levels can be useful as sorting criteria when viewing a list of Integrity Monitoring rules. More importantly, each severity level is associated with a severity value; this value is multiplied by a computer's Asset Value to determine the ranking of an event. (See **Administration > System Settings > Ranking**.)

Select a rule template and define rule attributes

Go to the **Content** tab and select from one of the following three templates:

Registry Value template

Create an Integrity Monitoring rule to specifically monitor changes to registry values.

Note: The Registry Value template is only for Windows-based computers .

1. Select the **Base Key** to monitor and whether or not to monitor contents of sub keys.
2. List **Value Names** to be included or excluded. You can use "?" and "*" as wildcard characters.
3. Enter **Attributes** to monitor. Entering "STANDARD" will monitor changes in registry size, content and type. For more information on Registry Value template attributes see the ["RegistryValueSet" on page 871](#) documentation.

File template

Create an Integrity Monitoring rule to specifically monitor changes to files.

1. Enter a **Base Directory** for the rule (for example, `C:\Program Files\MySQL\.`) Select **Include Sub Directories** to include the contents of all subdirectories relative to the base directory.
2. Use the **File Names** fields to include or exclude specific files. You can use wildcards (" ? " for a single character and " * " for zero or more characters).

Note: Leaving the **File Names** fields blank will cause the rule to monitor all files in the base directory. This can use significant system resources if the base directory contains numerous or large files.


3. Enter **Attributes** to monitor. Entering "STANDARD" will monitor changes in file creation date, last modified date, permissions, owner, group, size, content, flags (Windows), and SymLinkPath (Linux). For more information on File template attributes see the ["FileSet" on page 854](#) documentation.

Custom (XML) template

Create a custom Integrity Monitoring rule template to monitor [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) using the Deep Security XML-based ["Integrity monitoring rules language" on page 837](#).

Tip: You can create your rule in your preferred text editor and paste it to the **Content** field when you are done.

Configure Trend Micro Integrity Monitoring rules

Integrity Monitoring rules issued by Trend Micro cannot be edited in the same way as the custom rules you create. Some Trend Micro rules cannot be modified at all, while other rules may offer limited configuration options. Both of these rule types will show as "Defined" under the "Type" column, but rules that can be configured will display a gear in the Integrity Monitoring icon (.

Integrity Monitoring Rules

No Grouping

Search this page









New

Delete...

Properties...

Duplicate

Export

NAME	SEVERITY	TYPE	LAST UPDATED
 New Integrity Monitoring Rule	 Medium	Custom	N/A
 1002784 - Microsoft Windows - IE A...	 Medium	Defined	June 23, 2009
 1002781 - Microsoft Windows - Attri...	 Medium	Defined	June 23, 2009
 1002778 - Microsoft Windows - Syst...	 High	Defined	June 23, 2009

You can access the configuration options for a rule by opening the properties for the rule and clicking on the **Configuration** tab.

Rules issued by Trend Micro also show the following additional information under the **General** tab:

- When the rule was first issued and last updated, as well as a unique identifier for the rule.
- The minimum versions of the Agent and the Deep Security Manager that are required for the rule to function.

Although you cannot edit rules issued by Trend Micro directly, you can duplicate them and then edit the copy.

Configure rule events and alerts

Any changes detected by an Integrity Monitoring rule is logged as an event in the Deep Security Manager.

Real-time event monitoring

By default, events are logged at the time they occur. If you only want events to be logged when you manually perform a scan for changes, deselect **Allow Real Time Monitoring**.

Alerts

You can also configure the rules to trigger an alert when they log an event. To do so, open the properties for a rule, click on **Options**, and then select **Alert when this rule logs an event**.

See policies and computers a rule is assigned to

You can see which policies and computers are assigned to an Integrity Monitoring rule on the **Assigned To** tab. Click on a policy or computer in the list to see their properties.

Export a rule

You can export all Integrity Monitoring rules to a .csv or .xml file by clicking **Export** and selecting the corresponding export action from the list. You can also export specific rules by first selecting them, clicking **Export** and then selecting the corresponding export action from the list.

Delete a rule

To delete a rule, right-click the rule in the Integrity Monitoring Rules list, click **Delete** and then click **OK**.

Note: Integrity Monitoring rules that are assigned to one or more computers or that are part of a policy cannot be deleted.

Define a log inspection rule for use in policies

The OSSEC log inspection engine is integrated into Deep Security Agents and gives Deep Security the ability to inspect the logs and events generated by the operating system and applications running on the computer. Deep Security Manager ships with a standard set of OSSEC log inspection rules that you can assign to computers or policies. You can also create custom rules if there is no existing rule that fits your requirements.

Log Inspection Rules issued by Trend Micro are not editable (although you can duplicate them and then edit them.)

Note: Log Inspection Rules that are assigned to one or more computers or that are part of a policy cannot be deleted.

To create log inspection rules, perform these basic steps:

- ["Create a new log inspection rule" below](#)
- ["Decoders" on page 584](#)
- ["Subrules" on page 585](#)
- ["Real world examples" on page 593](#)
- ["Log inspection rule severity levels and their recommended use" on page 602](#)
- ["strftime\(\) conversion specifiers " on page 603](#)
- ["Examine a log inspection rule" on page 604](#)

For an overview of the log inspection module, see ["Analyze logs with log inspection" on page 889](#).

Create a new log inspection rule

1. In the Deep Security Manager, go to **Policies > Common Objects > Rules > Log Inspection Rules**.
2. Click **New > New Log Inspection Rule**.
3. On the **General** tab, enter a name and an optional description for the rule.
4. The **Content** tab is where you define the rule. The easiest way to define a rule is to select **Basic Rule** and use the options provided to define the rule. If you need further customization, you can select **Custom (XML)** to switch to an XML view of the rule that you are defining.

Note: Any changes you make in the Custom (XML) view will be lost if you switch back to the Basic Rule view.

For further assistance in writing your own log inspection rules using the XML-based language, consult the [OSSEC](#) documentation or contact your support provider.

These options are available for the Basic Rule template:

- **Rule ID:** The Rule ID is a unique identifier for the rule. OSSEC defines 100000 - 109999 as the space for user-defined rules. Deep Security Manager will pre-populate the field with a new unique Rule ID.
- **Level:** Assign a level to the rule. Zero (0) means the rule never logs an event, although other rules that watch for this rule may fire.
- **Groups:** Assign the rule to one or more comma-separated groups. This can be useful when dependency is used because you can create rules that fire on the firing of a rule, or a rule that belongs to a specific group.
- **Rule Description:** Description of the rule.
- **Pattern Matching:** This is the pattern the rule will look for in the logs. The rule will be triggered on a match. Pattern matching supports Regular Expressions or simpler String Patterns. The "String Pattern" pattern type is faster than RegEx but it only supports three special operations:
 - **^ (caret):** specifies the beginning of text
 - **\$ (dollar sign):** specifies the end of text
 - **| (pipe):** to create a "OR" between multiple patterns

For information on the regular expression syntax used by the Log Inspection module, see <https://www.ossec.net/docs/syntax/regex.html>.

- **Dependency:** Setting a dependency on another rule will cause your rule to only log an event if the rule specified in this area has also triggered.
- **Frequency** is the number of times the rule has to match within a specific time frame before the rule is triggered.
- **Time Frame** is the period of time in seconds within which the rule has to trigger a certain number of times (the frequency, above) to log an event.

Note: The **Content** tab only appears for log inspection rules that you create yourself. Log inspection rules issued by Trend Micro have a **Configuration** tab instead that displays the log inspection rule's configuration options (if any).

1. On the **Files** tab, type the full path to the file(s) you want your rule to monitor and specify the type of file it is.
2. On the **Options** tab, in the **Alert** section, select whether this rule triggers an alert in the Deep Security Manager.

The **Alert Minimum Severity** setting is only used if you have written "multiple rules" within your rule - something that cannot be done using the Basic template. However, if after creating your rule using the Basic template, you edit the XML of the rule and add additional rules to the XML that have different severity levels, you can use the **Alert Minimum Severity Level** setting to set the minimum severity from the multiple rules that will trigger an Alert.

3. The **Assigned To** tab lists the policies and computers that are using this log inspection rule. Because you are creating a new rule, it has not been assigned yet.
4. Click **OK**. The rule is ready to be assigned to policies and computers.

Decoders

A log inspection rule consists of a list of files to monitor for changes and a set of conditions to be met for the rule to trigger. When the log inspection engine detects a change in a monitored log file, the change is parsed by a decoder. Decoders parse the raw log entry into the following fields:

- **log**: the message section of the event
- **full_log**: the entire event
- **location**: where the log came from
- **hostname**: hostname of the event source
- **program_name**: program name from the syslog header of the event
- **srcip**: the source IP address within the event
- **dstip**: the destination IP address within the event
- **srcport**: the source port number within the event
- **dstport**: the destination port number within the event
- **protocol**: the protocol within the event
- **action**: the action taken within the event

- **srcuser**: the originating user within the event
- **dstuser**: the destination user within the event
- **id**: any ID decoded as the ID from the event
- **status**: the decoded status within the event
- **command**: the command being called within the event
- **url**: the URL within the event
- **data**: any additional data extracted from the event
- **systemname**: the system name within the event

Rules examine this decoded data looking for information that matches the conditions defined in the rule.

If the matches are at a sufficiently high severity level, any of the following actions can be taken:

- An alert can be raised. (Configurable on the **Options** tab of the Log Inspection Rule's **Properties** window.)
- The event can be written to syslog. (Configurable in the **SIEM** area on **Administration > System Settings > Event Forwarding** tab.)
- The event can be sent to the Deep Security Manager. (Configurable in the **Log Inspection Syslog Configuration** setting on the **Policy or Computer Editor > Settings > Event Forwarding** tab.)

Subrules

A single log inspection rule can contain multiple subrules. These subrules can be of two types: atomic or composite. An atomic rule evaluates a single event and a composite rule examines multiple events and can evaluate frequency, repetition, and correlation between events.

Groups

Each rule, or grouping of rules, must be defined within a **<group></group>** element. The attribute name must contain the rules you want to be a part of this group. In the following example we have indicated that our group contains the syslog and sshd rules:

```
<group name="syslog,sshd,">
</group>
```

Note: Notice the trailing comma in the group name. Trailing commas are required if you intend to use the `<if_group></if_group>` tag to conditionally append another sub-rule to this one.

Note: When a set of log inspection rules are sent to an agent, the log inspection engine on the agent takes the XML data from each assigned rule and assembles it into what becomes essentially a single long log inspection rule. Some group definitions are common to all log inspection rules written by Trend Micro. For this reason Trend Micro has included a rule called "Default Rules Configuration" which defines these groups and which always gets assigned along with any other Trend Micro rules. (If you select a rule for assignment and haven't also selected the "Default Rules Configuration" rule, a notice will appear informing you that the rule will be assigned automatically.) *If you create your own log inspection rule and assign it to a Computer without assigning any Trend Micro-written rules, you must either copy the content of the "Default Rules Configuration" rule into your new rule, or also select the "Default Rules Configuration" rule for assignment to the Computer.*

Rules, ID, and Level

A group can contain as many rules as you require. The rules are defined using the `<rule></rule>` element and must have at least two attributes, the **id** and the **level**. The **id** is a unique identifier for that signature and the **level** is the severity of the alert. In the following example, we have created two rules, each with a different rule ID and level:

```
<group name="syslog,sshd,">
  <rule id="100120" level="5">
  </rule>
  <rule id="100121" level="6">
  </rule>
</group>
```

Note: Custom rules must have ID values of 100,000 or greater.

You can define additional subgroups within the parent group using the `<group></group>` tag. This subgroup can reference any of the groups listed in the following table:

Group Type	Group Name	Description
Reconnaissance	connection_attempt	Connection attempt
	web_scan	Web scan
	recon	Generic scan

Trend Micro Deep Security On-Premise 11.3

Group Type	Group Name	Description
Authentication Control	authentication_success	Success
	authentication_failed	Failure
	invalid_login	Invalid
	login_denied	Login Denied
	authentication_failures	Multiple Failures
	adduser	User account added
	account_changed	User Account changed or removed
Attack/Misuse	automatic_attack	Worm (nontargeted attack)
	exploit_attempt	Exploit pattern
	invalid_access	Invalid access
	spam	Spam
	multiple_spam	Multiple spam messages
	sql_injection	SQL injection
	attack	Generic attack
Access Control	virus	Virus detected
	access_denied	Access denied
	access_allowed	Access allowed
	unknown_resource	Access to nonexistent resource
	firewall_drop	Firewall drop
	multiple_drops	Multiple firewall drops
	client_misconfig	Client misconfiguration
Network Control	client_error	Client error
	new_host	New computer detected
System Monitor	ip_spoof	Possible ARP spoofing
	service_start	Service start
	system_error	System error
	system_shutdown	Shutdown
	logs_cleared	Logs cleared
	invalid_request	Invalid request
	promisc	Interface switched to promiscuous mode
	policy_changed	Policy changed
	config_changed	Configuration changed
	low_diskspace	Low disk space
	time_changed	Time changed

Note: If event auto-tagging is enabled, the event will be labeled with the group name. Log inspection rules provided by Trend Micro make use of a translation table that changes the group to a more user-friendly version. So, for example, "login_denied" would appear as "Login Denied". Custom rules will be listed by their group name as it appears in the rule.

Description

Include a **<description></description>** tag. The description text will appear in the event if the rule is triggered.

Trend Micro Deep Security On-Premise 11.3

```
<group name="syslog,sshd,">
  <rule id="100120" level="5">
    <group>authentication_success</group>
    <description>SSHD testing authentication success</description>
  </rule>
  <rule id="100121" level="6">
    <description>SSHD rule testing 2</description>
  </rule>
</group>
```

Decoded As

The `<decoded_as></decoded_as>` tag instructs the log inspection engine to only apply the rule if the specified decoder has decoded the log.

```
<rule id="100123" level="5">
  <decoded_as>sshd</decoded_as>
  <description>Logging every decoded sshd message</description>
</rule>
```

Note: To view the available decoders, go to the **Log Inspection Rule** page and click **Decoders**. Right-click on **1002791-Default Log Decoders** and select **Properties**. Go the **Configuration** tab and click **View Decoders**.

Match

To look for a specific string in a log, use the `<match></match>`. Here is a Linux sshd failed password log:

```
Jan 1 12:34:56 linux_server sshd[1231]: Failed password for invalid
user jsmith from 192.168.1.123 port 1799 ssh2
```

Use the `<match></match>` tag to search for the "password failed" string.

```
<rule id="100124" level="5">
  <decoded_as>sshd</decoded_as>
  <match>^Failed password</match>
  <description>Failed SSHD password attempt</description>
</rule>
```

Note: Notice the regex caret ("^") indicating the beginning of a string. Although "Failed password" does not appear at the beginning of the log, the log inspection decoder will have broken up the log into sections. See ["Decoders" on page 584](#) for more information. One of those sections is "log" which is the message part of the log as opposed to "full_log" which is the log in its entirety.

The following table lists supported regex syntax:

Regex Syntax	Description
\w	A-Z, a-z, 0-9 single letters and numerals
\d	0-9 single numerals
\s	single space
\t	single tab
\p	()*+,-.::;<=>?[]
\W	not \w
\D	not \d
\S	not \s
\.	anything
+	match one or more of any of the above (for example, \w+, \d+)
*	match zero or more of any of the above (for example, \w*, \d*)
^	indicates the beginning of a string (^somestring)
\$	specify the end of a string (somestring\$)
	indicate an "OR" between multiple strings

Conditional Statements

Rule evaluation can be conditional upon other rules having been evaluated as true. The `<if_sid></if_sid>` tag instructs the log inspection engine to only evaluate this subrule if the rule identified in the tag has been evaluated as true. The following example shows three rules: 100123, 100124, and 100125. Rules 100124 and 100125 have been modified to be children of the 100123 rule using the `<if_sid></if_sid>` tag:

```
<group name="syslog,sshd,">
  <rule id="100123" level="2">
    <decoded_as>sshd</decoded_as>
    <description>Logging every decoded sshd message</description>
  </rule>
  <rule id="100124" level="7">
    <if_sid>100123</if_sid>
    <match>^Failed password</match>
```



```

        <group>authentication_failure</group>
        <description>Failed SSHD password attempt</description>
    </rule>
    <rule id="100125" level="3">
        <if_sid>100123</if_sid>
        <match>^Accepted password</match>
        <group>authentication_success</group>
        <description>Successful SSHD password attempt</description>
    </rule>
</group>

```

Hierarchy of Evaluation

The `<if_sid></if_sid>` tag essentially creates a hierarchical set of rules. That is, by including an `<if_sid></if_sid>` tag in a rule, the rule becomes a child of the rule referenced by the `<if_sid></if_sid>` tag. Before applying any rules to a log, the log inspection engine assesses the `<if_sid></if_sid>` tags and builds a hierarchy of parent and child rules.

Note: The hierarchical parent-child structure can be used to improve the efficiency of your rules. If a parent rule does not evaluate as true, the log inspection engine will ignore the children of that parent.

Note: Although the `<if_sid></if_sid>` tag can be used to refer to subrules within an entirely different log inspection rule, you should avoid doing this because it makes the rule very difficult to review later on.

The list of available atomic rule conditional options is shown in the following table:

Tag	Description	Notes
match	A pattern	Any string to match against the event (log).
regex	A regular expression	Any regular expression to match against the event(log).
decoded_as	A string	Any prematched string.
srcip	A source IP address	Any IP address that is decoded as the source IP address. Use "!" to negate the IP address.
dstip	A destination IP address	Any IP address that is decoded as the destination IP address. Use "!" to negate the IP address.
srcport	A source port number	Any source port (match format).
dstport	A destination port number	Any destination port (match format).
user	A username	Any username that is decoded as a username.
program_	A program name	Any program name that is decoded from the syslog process name.

Trend Micro Deep Security On-Premise 11.3

Tag	Description	Notes
name		
hostname	A system hostname	Any hostname that is decoded as a syslog hostname.
time	A time range in the format hh:mm - hh:mm or hh:mm am - hh:mm pm	The time range that the event must fall within for the rule to trigger.
weekday	A weekday (sunday, monday, tuesday, etc.)	Day of the week that the event must fall on for the rule to trigger.
id	An ID	Any ID that is decoded from the event.
url	A URL	Any URL that is decoded from the event.

Use the `<if_sid>100125</if_sid>` tag to make this rule depend on the 100125 rule. This rule will be checked only for sshd messages that already matched the successful login rule.

```
<rule id="100127" level="10">
  <if_sid>100125</if_sid>
  <time>6 pm - 8:30 am</time>
  <description>Login outside business hours.</description>
  <group>policy_violation</group>
</rule>
```

Restrictions on the Size of the Log Entry

The following example takes the previous example and adds the **maxsize** attribute which tells the log inspection engine to only evaluate rules that are less than the maxsize number of characters:

```
<rule id="100127" level="10" maxsize="2000">
  <if_sid>100125</if_sid>
  <time>6 pm - 8:30 am</time>
  <description>Login outside business hours.</description>
  <group>policy_violation</group>
</rule>
```

The following table lists possible atomic rule tree-based options:

Tag	Description	Notes
if_sid	A rule ID	Adds this rule as a child rule of the rules that match the specified signature ID.
if_group	A group ID	Adds this rule as a child rule of the rules that match the specified group.
if_level	A rule level	Adds this rule as a child rule of the rules that match the specified severity level.
description	A string	A description of the rule.
info	A string	Extra information about the rule.

Tag	Description	Notes
cve	A CVE number	Any Common Vulnerabilities and Exposures (CVE) number that you would like associated with the rule.
options	alert_by_email no_email_alert no_log	Additional rule options to indicate if the Alert should generate an e-mail, alert_by_email, should not generate an email, no_email_alert, or should not log anything at all, no_log.

Composite Rules

Atomic rules examine single log entries. To correlate multiple entries, you must use composite rules. Composite rules are supposed to match the current log with those already received.

Composite rules require two additional options: the **frequency** option specifies how many times an event or pattern must occur before the rule generates an alert, and the **timeframe** option tells the log inspection engine how far back, in seconds, it should look for previous logs. All composite rules have the following structure:

```
<rule id="100130" level="10" frequency="x" timeframe="y">
</rule>
```

For example, you could create a composite rule that creates a higher severity alert after five failed passwords within a period of 10 minutes. Using the `<if_matched_sid></if_matched_sid>` tag you can indicate which rule needs to be seen within the desired frequency and timeframe for your new rule to create an alert. In the following example, the **frequency** attribute is set to trigger when five instances of the event are seen and the **timeframe** attribute is set to specify the time window as 600 seconds.

The `<if_matched_sid></if_matched_sid>` tag is used to define which other rule the composite rule will watch:

```
<rule id="100130" level="10" frequency="5" timeframe="600">
  <if_matched_sid>100124</if_matched_sid>
  <description>5 Failed passwords within 10 minutes</description>
</rule>
```

There are several additional tags that you can use to create more granular composite rules. These rules, as shown in the following table, allow you to specify that certain parts of the event must be the same. This allows you to tune your composite rules and reduce false positives:

Tag	Description
same_source_ip	Specifies that the source IP address must be the same.
same_dest_ip	Specifies that the destination IP address must be the same.
same_dst_port	Specifies that the destination port must be the same.
same_location	Specifies that the location (hostname or agent name) must be the same.
same_user	Specifies that the decoded username must be the same.
same_id	Specifies that the decoded id must be the same.

If you wanted your composite rule to alert on every authentication failure, instead of a specific rule ID, you could replace the `<if_matched_sid></if_matched_sid>` tag with the `<if_matched_group></if_matched_group>` tag. This allows you to specify a category, such as **authentication_failure**, to search for authentication failures across your entire infrastructure.

```
<rule id="100130" level="10" frequency="5" timeframe="600">
  <if_matched_group>authentication_failure</if_matched_group>
  <same_source_ip />
  <description>5 Failed passwords within 10 minutes</description>
</rule>
```

In addition to `<if_matched_sid></if_matched_sid>` and `<if_matched_group></if_matched_group>` tags, you can also use the `<if_matched_regex></if_matched_regex>` tag to specify a regular expression to search through logs as they are received.

```
<rule id="100130" level="10" frequency="5" timeframe="600">
  <if_matched_regex>^Failed password</if_matched_regex>
  <same_source_ip />
  <description>5 Failed passwords within 10 minutes</description>
</rule>
```

Real world examples

Deep Security includes many default log inspection rules for dozens of common and popular applications. Through Security Updates, new rules are added regularly. In spite of the growing list of applications supported by log inspection rules, you may find the need to create a custom rule for an unsupported or custom application.

In this section we will walk through the creation of a custom CMS (content management system) hosted on Microsoft Windows Server with IIS and .Net platform, with a Microsoft SQL Server database as the data repository.

The first step is to identify the following application logging attributes:

1. Where does the application log to?
2. Which log inspection decoder can be used to decode the log file?
3. What is the general format of a log file message?

For our custom CMS example the answers are as follows:

1. Windows Event Viewer
2. Windows Event Log (eventlog)
3. Windows Event Log Format with the following core attributes:
 - Source: CMS
 - Category: None
 - Event: <Application Event ID>

The second step is to identify the categories of log events by application feature, and then organize the categories into a hierarchy of cascading groups for inspection. Not all inspected groups need to raise events; a match can be used as a conditional statement. For each group, identify the log format attributes which the rule can use as matching criteria. This can also be performed by inspecting all application logs for patterns and logical groupings of log events.

For example, the CMS application supports the following functional features which we will create log inspection rules for:

- CMS Application Log (Source: CMS)
 - Authentication (Event: 100 to 119)
 - User Login successful (Event: 100)
 - User Login unsuccessful (Event: 101)
 - Administrator Login successful (Event: 105)
 - Administrator Login unsuccessful (Event: 106)
 - General Errors (Type: Error)
 - Database error (Event: 200 to 205)
 - Runtime error (Event: 206-249)

- Application Audit (Type: Information)
 - Content
 - New content added (Event: 450 to 459)
 - Existing content modified (Event: 460 to 469)
 - Existing content deleted (Event: 470 to 479)
 - Administration
 - User
 - New User created (Event: 445 to 446)
 - Existing User deleted (Event: 447 to 449)

This structure will provide you with a good basis for rule creation. Now to create a new log inspection rule in Deep Security Manager.

To create the new CMS Log Inspection Rule:

1. In the Deep Security Manager, go to **Policies > Common Objects > Rules > Log Inspection Rules** and click **New** to display the **New Log Inspection Rule Properties** window.
2. Give the new rule a name and a description, and then click the **Content** tab.
3. The quickest way to create a new custom rule is to start with a basic rule template. Select the **Basic Rule** radio button.
4. The **Rule ID** field will be automatically populated with an unused ID number of 100,000 or greater, the IDs reserved for custom rules.
5. Set the **Level** setting to **Low (0)**.
6. Give the rule an appropriate Group name. In this case, "cms".

7. Provide a short rule description.

General	Content	Files	Options	Assigned To
Template <input checked="" type="radio"/> Basic Rule <input type="radio"/> Custom (XML)				
General Information Rule ID: <input type="text" value="100000"/> Level: <input type="text" value="Low (0)"/> Groups (comma separated): <input type="text" value="cms"/> Rule Description: <input type="text" value="windows events for 'cms' group"/>				
Pattern Matching Pattern to Match: <input type="text"/> Pattern Type: <input type="text" value="String Pattern"/>				
Dependency <input checked="" type="radio"/> None <input type="radio"/> Trigger event on the triggering of another rule: <input type="radio"/> Trigger event on the triggering of any rule belonging to a specific group:				
Composite (optional) <small>Only trigger if this rule matches its dependent rule the specified frequency of times in the specified time frame (in seconds).</small> Frequency (1 to 128): <input type="text"/> Time Frame (1 to 86400): <input type="text"/>				
<div>OK Cancel</div>				

8. Now select the **Custom (XML)** option. The options you selected for your "Basic" rule will be converted to XML.

The screenshot shows the 'Content' tab of a configuration window. At the top, there are five tabs: 'General', 'Content', 'Files', 'Options', and 'Assigned To'. The 'Content' tab is selected. Below the tabs, there is a 'Template' section with two radio buttons: 'Basic Rule' and 'Custom (XML)'. The 'Custom (XML)' option is selected. Below this is a 'Content:' label followed by a text area containing XML code. At the bottom right, there are 'OK' and 'Cancel' buttons.

General **Content** Files Options Assigned To

Template

☐ Basic Rule

☒ Custom (XML)

Content:

```
<group name="cms">
  <rule id="100000" level="0">
    <description>windows events for 'cms' groups</description>
  </rule>
</group>
```

OK Cancel

9. Click the **Files** tab and click the **Add File** button to add any application log files and log types which the rule will be applied to. In this case, "Application", and "eventlog" as the file type.

The screenshot shows the 'Files' tab of the same configuration window. The 'Files' tab is selected. Below the tabs, there is a 'Files:' label. Underneath, there is a text input field containing 'Application', a dropdown menu showing 'eventlog', and a 'Remove' button. Below these, there is an 'Add File' button. At the bottom right, there are 'OK' and 'Cancel' buttons.

General **Content** **Files** Options Assigned To

Files:

Application eventlog Remove

Add File

OK Cancel

Note: Eventlog is a unique file type in Deep Security because the location and filename of the log files don't have to be specified. Instead, it is sufficient to type the log name as it

is displayed in the Windows Event Viewer. Other log names for the eventlog file type might be "Security", "System", "Internet Explorer", or any other section listed in the Windows Event Viewer. Other file types will require the log file's location and filename. (C/C++ *strftime()* conversion specifiers are available for matching on filenames. See the table below for a list of some of the more useful ones.)

10. Click **OK** to save the basic rule.
11. Working with the basic rule Custom (XML) created, we can begin adding new rules to the group based on the log groupings identified previously. We will set the base rule criteria to the initial rule. In the following example, the CMS base rule has identified Windows Event Logs with a Source attribute of "CMS":

```
<group name="cms">
  <rule id="100000" level="0">
    <category>windows</category>
    <extra_data>^CMS</extra_data>
    <description>Windows events from source 'CMS' group messages.</description>
  </rule>
```

12. Now we build up subsequent rules from the identified log groups. The following example identifies the authentication and login success and failure and logs by Event IDs.

```
<rule id="100001" level="0">
  <if_sid>100000</if_sid>
  <id>^100|^101|^102|^103|^104|^105|^106|^107|^108|^109|^110</id>
  <group>authentication</group>
  <description>CMS Authentication event.</description>
</rule>

<rule id="100002" level="0">
  <if_group>authentication</if_group>
  <id>100</id>
  <description>CMS User Login success event.</description>
</rule>

<rule id="100003" level="4">
  <if_group>authentication</if_group>
  <id>101</id>
  <group>authentication_failure</group>
  <description>CMS User Login failure event.</description>
```

```
</rule>
<rule id="100004" level="0">
  <if_group>authentication</if_group>
  <id>105</id>
  <description>CMS Administrator Login success event.</description>
</rule>
<rule id="100005" level="4">
  <if_group>authentication</if_group>
  <id>106</id>
  <group>authentication_failure</group>
  <description>CMS Administrator Login failure event.</description>
</rule>
```

13. Now we add any composite or correlation rules using the established rules. The following example shows a high severity composite rule that is applied to instances where the repeated login failures have occurred 5 times within a 10 second time period:

```
<rule id="100006" level="10" frequency="5" timeframe="10">
  <if_matched_group>authentication_failure</if_matched_group>
  <description>CMS Repeated Authentication Login failure event.</description>
</rule>
```

14. Review all rules for appropriate severity levels. For example, error logs should have a severity of level 5 or higher. Informational rules would have a lower severity.
15. Finally, open the newly created rule, click the **Configuration** tab and copy your custom rule XML into the rule field. Click **Apply** or **OK** to save the change.

Once the rule is assigned to a policy or computer, the log inspection engine should begin inspecting the designated log file immediately.

The complete Custom CMS Log Inspection Rule:

```
<group name="cms">
  <rule id="100000" level="0">
    <category>windows</category>
    <extra_data>^CMS</extra_data>
    <description>Windows events from source 'CMS' group messages.</description>
  </rule>
  <rule id="100001" level="0">
    <if_sid>100000</if_sid>
    <id>^100|^101|^102|^103|^104|^105|^106|^107|^108|^109|^110</id>
```

```
<group>authentication</group>
<description>CMS Authentication event.</description>
</rule>

<rule id="100002" level="0">
  <if_group>authentication</if_group>
  <id>100</id>
  <description>CMS User Login success event.</description>
</rule>

<rule id="100003" level="4">
  <if_group>authentication</if_group>
  <id>101</id>
  <group>authentication_failure</group>
  <description>CMS User Login failure event.</description>
</rule>

<rule id="100004" level="0">
  <if_group>authentication</if_group>
  <id>105</id>
  <description>CMS Administrator Login success event.</description>
</rule>

<rule id="100005" level="4">
  <if_group>authentication</if_group>
  <id>106</id>
  <group>authentication_failure</group>
  <description>CMS Administrator Login failure event.</description>
</rule>

<rule id="100006" level="10" frequency="5" timeframe="10">
  <if_matched_group>authentication_failure</if_matched_group>
  <description>CMS Repeated Authentication Login failure event.</description>
</rule>

<rule id="100007" level="5">
  <if_sid>100000</if_sid>
  <status>^ERROR</status>
  <description>CMS General error event.</description>
  <group>cms_error</group>
```

```

</rule>

<rule id="100008" level="10">
  <if_group>cms_error</if_group>
  <id>^200|^201|^202|^203|^204|^205</id>
  <description>CMS Database error event.</description>
</rule>

<rule id="100009" level="10">
  <if_group>cms_error</if_group>
  <id>^206|^207|^208|^209|^230|^231|^232|^233|^234|^235|^236|^237|^238|^
    ^239|^240|^241|^242|^243|^244|^245|^246|^247|^248|^249</id>
  <description>CMS Runtime error event.</description>
</rule>

<rule id="100010" level="0">
  <if_sid>100000</if_sid>
  <status>^INFORMATION</status>
  <description>CMS General informational event.</description>
  <group>cms_information</group>
</rule>

<rule id="100011" level="5">
  <if_group>cms_information</if_group>
  <id>^450|^451|^452|^453|^454|^455|^456|^457|^458|^459</id>
  <description>CMS New Content added event.</description>
</rule>

<rule id="100012" level="5">
  <if_group>cms_information</if_group>
  <id>^460|^461|^462|^463|^464|^465|^466|^467|^468|^469</id>
  <description>CMS Existing Content modified event.</description>
</rule>

<rule id="100013" level="5">
  <if_group>cms_information</if_group>
  <id>^470|^471|^472|^473|^474|^475|^476|^477|^478|^479</id>
  <description>CMS Existing Content deleted event.</description>
</rule>

```

Trend Micro Deep Security On-Premise 11.3

```
<rule id="100014" level="5">
  <if_group>cms_information</if_group>
  <id>^445|^446</id>
  <description>CMS User created event.</description>
</rule>

<rule id="100015" level="5">
  <if_group>cms_information</if_group>
  <id>^447|449</id>
  <description>CMS User deleted event.</description>
</rule>

</group>
```

Log inspection rule severity levels and their recommended use

Level	Description	Notes
Level 0	Ignored, no action taken	Primarily used to avoid false positives. These rules are scanned before all the others and include events with no security relevance.
Level 1	no predefined use	
Level 2	System low priority notification	System notification or status messages that have no security relevance.
Level 3	Successful or authorized events	Successful login attempts, firewall allow events, etc.
Level 4	System low priority errors	Errors related to bad configurations or unused devices or applications. They have no security relevance and are usually caused by default installations or software testing.
Level 5	User-generated errors	Missed passwords, denied actions, etc. These messages typically have no security relevance.
Level 6	Low relevance attacks	Indicate a worm or a virus that provide no threat to the system such as a Windows worm attacking a Linux server. They also include frequently triggered IDS events and common error events.
Level 7	no predefined use	
Level 8	no predefined use	
Level 9	Error from invalid source	Include attempts to login as an unknown user or from an invalid source. The message might have security relevance especially if repeated. They also include errors regarding the admin or root account.
Level 10	Multiple user generated errors	Include multiple bad passwords, multiple failed logins, etc. They might indicate an attack, or it might be just that a user forgot his or her credentials.

Trend Micro Deep Security On-Premise 11.3

Level	Description	Notes
Level 11	no predefined use	
Level 12	High-importance event	Include error or warning messages from the system, kernel, etc. They might indicate an attack against a specific application.
Level 13	Unusual error (high importance)	Common attack patterns such as a buffer overflow attempt, a larger than normal syslog message, or a larger than normal URL string.
Level 14	High importance security event	Typically the result of the correlation of multiple attack rules and indicative of an attack.
Level 15	Attack Successful	Very small chance of false positive. Immediate attention is necessary.

strftime() conversion specifiers

Specifier	Description
%a	Abbreviated weekday name (e.g., Thu)
%A	Full weekday name (e.g., Thursday)
%b	Abbreviated month name (e.g., Aug)
%B	Full month name (e.g., August)
%c	Date and time representation (e.g., Thu Sep 22 12:23:45 2007)
%d	Day of the month (01 - 31) (e.g., 20)
%H	Hour in 24 h format (00 - 23) (e.g., 13)
%I	Hour in 12 h format (01 - 12) (e.g., 02)
%j	Day of the year (001 - 366) (e.g., 235)
%m	Month as a decimal number (01 - 12) (e.g., 02)
%M	Minute (00 - 59) (e.g., 12)
%p	AM or PM designation (e.g., AM)
%S	Second (00 - 61) (e.g., 55)
%U	Week number with the first Sunday as the first day of week one (00 - 53) (e.g., 52)
%w	Weekday as a decimal number with Sunday as 0 (0 - 6) (e.g., 2)
%W	Week number with the first Monday as the first day of week one (00 - 53) (e.g., 21)
%x	Date representation (e.g., 02/24/79)
%X	Time representation (e.g., 04:12:51)
%y	Year, last two digits (00 - 99) (e.g., 76)
%Y	Year (e.g., 2008)
%Z	Time zone name or abbreviation (e.g., EST)
%%	A % sign (e.g., %)

More information can be found at the following websites:

<https://secure.php.net/manual/en/function.strftime.php>

www.cplusplus.com/reference/clibrary/ctime/strftime.html

Examine a log inspection rule

Log inspection rules are found in the Deep Security Manager at **Policies > Common Objects > Rules > Log Inspection Rules**.

Log inspection rule structure and the event matching process

This screen shot displays the contents of the **Configuration** tab of the Properties window of the "Microsoft Exchange" log inspection rule:

General Configuration Options Assigned To

Configuration Options

Log Files to monitor:

Add

Remove

C:\Windows\system32\LogFiles\SMTPSVC1\ex%y%m%d.l

Type of Log File(s): syslog

This rule matches events decoded as: msexchange

3800 - Grouping of Exchange rules

Default - Ignore

3801 - E-mail RCPT is not valid (invalid account)

Default - Medium (5)

3851 - Multiple e-mail attempts to an invalid account

Default - High (10)

Frequency (1 to 128): 10

Time Frame (1 to 86400): 120 secs

Time to ignore this rule after triggering it once - to avoid excessive logs (1 to 86400): 120 secs

3802 - E-mail 500 error code

Default - Medium (4)

3852 - Multiple e-mail 500 error code (spam)

Default - High (9)

Frequency (1 to 128): 12

Time Frame (1 to 86400): 120 secs

Time to ignore this rule after triggering it once - to avoid excessive logs (1 to 86400): 240 secs

View Rules...

OK Cancel Apply

Here is the structure of the rule:

- 3800 - Grouping of Exchange Rules - Ignore
 - 3801 - Email rcpt is not valid (invalid account) - Medium (4)
 - 3851 - Multiple email attempts to an invalid account - High (9)
 - Frequency - 10
 - Time Frame - 120
 - Ignore - 120
 - 3802 - Email 500 error code - Medium (4)
 - 3852 - Email 500 error code (spam) - High (9)
 - Frequency - 12
 - Time Frame - 120
 - Ignore - 240

The log inspection engine will apply log events to this structure and see if a match occurs. For example, if an Exchange event occurs, and this event is an email receipt to an invalid account, the event will match line 3800 (because it is an Exchange event). The event will then be applied to line 3800's sub-rules: 3801 and 3802.

If there is no further match, this "cascade" of matches will stop at 3800. Because 3800 has a severity level of "Ignore", no log inspection event would be recorded.

However, an email receipt to an invalid account does match one of 3800's sub-rules: sub-rule 3801. Sub-rule 3801 has a severity level of "Medium(4)". If the matching stopped here, a log inspection event with a severity level of "Medium(4)" would be recorded.

But there is still another sub-rule to be applied to the event: sub-rule 3851. Sub-rule 3851 with its three attributes will match if the same event has occurred 10 times within the last 120 seconds. If so, a log inspection event with a severity "High(9)" is recorded. (The "Ignore" attribute tells sub-rule 3851 to ignore individual events that match sub-rule 3801 for the next 120 seconds. This is useful for reducing "noise".)


Assuming the parameters of sub-rule 3851 have been matched, a log inspection event with Severity "High(9)" is now recorded.

Looking at the Options tab of the Microsoft Exchange Rule, we see that Deep Security Manager will raise an alert if any sub-rules with a severity level of "Medium(4)" have been matched. Since this is the case in our example, the alert will be raised (if "Alert when this rule logs an event" is selected).

Duplicate Sub-rules

Some log inspection rules have duplicate sub-rules. To see an example, open the "Microsoft Windows Events" rule and click on the **Configuration** tab. Note that sub-rule 18125 (Remote access login failure) appears under sub-rules 18102 and 18103. Also note that in both cases sub-rule 18125 does not have a severity value, it only says "See Below".

Instead of being listed twice, Rule 18125 is listed once at the bottom of the **Configuration** page:



Create a list of directories for use in policies

Create lists of directory paths so that you can use them in multiple policies. A single list is easier to manage than several identical lists that are each created in a different policy.

Tip: To create a directory list that is similar to an existing one, duplicate the list and then edit it.

The following table describes the syntax for defining directory list items. The use of forward slashes "/" and backslashes "\" are supported for both Windows and Linux conventions:

Directory	Format	Description	Examples
Directory	DIRECTORY	Includes all files in the specified directory and all files in all subdirectories.	C:\Program Files\ Includes all files in the "Program Files" directory and all subdirectories.
Network Resource	\\NETWORK RESOURCE	Includes files on a computer included as a network resource on a targeted computer.	\\12.34.56.78\ \\some-comp-name\ Includes all files on a network resource identified using an IP or a hostname. \\12.34.56.78\somefolder\ \\some-comp-name\somefolder\ Includes all files in the folder "somefolder" on a network resource identified using an IP or a hostname.
Directory with wildcard (*)	DIRECTORY*	Includes any subdirectories with any subdirectory name, but does not include the files in the specified directory.	C:\abc* Includes all files in all subdirectories of "abc" but does not include the files in the "abc" directory. C:\abc\wx*z\ <i>Matches:</i> C:\abc\wxz\ C:\abc\wx123z\ <i>Does not match:</i> C:\abc\wxz C:\abc\wx123z C:\abc*wx\ <i>Matches:</i> C:\abc\wx\ C:\abc\123wx\ <i>Does not match:</i> C:\abc\wx C:\abc\123wx
Directory with wildcard (*)	DIRECTORY*	Includes any subdirectories with a matching name, but does not include the files in that directory and any subdirectories.	C:\abc* <i>Matches:</i> C:\abc\ C:\abc\1 C:\abc\123 <i>Does not match:</i> C:\abc C:\abc\123\

Directory	Format	Description	Examples
			<p>C:\abc\123\456 C:\abx\ C:\xyz\</p> <p>C:\abcl*wx <i>Matches:</i> C:\abc\wx C:\abc\123wx <i>Does not match:</i> C:\abc\wx\ C:\abc\123wx\</p> <p>C:\abclwx*z <i>Matches:</i> C:\abc\wxz C:\abc\wx123z <i>Does not match:</i> C:\abc\wxz\ C:\abc\wx123z\</p> <p>C:\abclwx* <i>Matches:</i> C:\abc\wx C:\abc\wx\ C:\abc\wx12 C:\abc\wx12\345\ C:\abc\wxz\ <i>Does not match:</i> C:\abc\wx123z\</p>
Environment variable	\${ENV VAR}	Includes all files and subdirectories defined by an environment variable with the format \${ENV VAR}. For a Virtual Appliance, the value pairs for the environment variable must be defined in Policy or Computer Editor > Settings > General > Environment Variable Overrides .	<p>\${windir} If the variable resolves to "c:\windows", Includes all the files in "c:\windows" and all its subdirectories.</p>
Comments	DIRECTORY #Comment	Allows you to add comments to your inclusion definitions.	c:\abc #Include the abc directory

1. Click **Policies > Common Objects > Lists > Directory Lists**.
2. Click **New > New Directory List**.
3. Type a name and, optionally, a description.
4. In the **Directory(s)** list, add the directory paths, one per line.
5. Click **OK**.

Import and export directory lists

You can export one or more directory lists to an XML or CSV file, and import lists from an XML file.

1. Click **Policies > Common Objects > Lists > Directory Lists**.
2. To export one or more lists, select them and click **Export > Export Selected to CSV** or **Export > Export Selected to XML**.
3. To export all lists, click **Export > Export to CSV** or **Export > Export to XML**.
4. To import lists, click **New > Import From File** and follow the instructions on the wizard.

See which policies use a directory list

It is useful to see which policies use a directory list to be aware of which policies are affected by any changes you make. For example, you can ensure no policies use a directory list before deleting it.

1. Click **Policies > Common Objects > Lists > Directory Lists**.
2. Select the directory list and click **Properties**.
3. Click the **Assigned To** tab.

Create a list of file extensions for use in policies

Create lists of file extensions so that you can use them in multiple malware scan configurations. A single list is easier to manage than several identical lists that are each created in a different rule. For example, one list of file extensions can be used by multiple malware scan configurations as files to include in a scan. Another list of file extensions can be used by multiple malware scan configurations as files to exclude from a scan.

Tip: To create a file extension list that is similar to an existing one, duplicate the list and then edit it.

You can insert comments into your list by preceding the text with a pound sign ("#").

1. Click **Policies > Common Objects > Lists > File Extension Lists**.
2. Click **New > New File Extension List**.
3. Type a name and, optionally, a description.

4. In the **File Extension(s)** list, add the extensions, one per line.
5. Click **OK**.

Import and export file extension lists

You can export one or more file extension lists to an XML or CSV file, and import lists from an XML file.

1. Click **Policies > Common Objects > Lists > File Extension Lists**.
2. To export one or more lists, select them and click **Export > Export Selected to CSV** or **Export > Export Selected to XML**.
3. To export all lists, click **Export > Export to CSV** or **Export > Export to XML**.
4. To import lists, click **New > Import From File** and follow the instructions on the wizard.

See which malware scan configurations use a file extension list

It is useful to see which malware scan configurations use a file extension list to be aware of which rules are affected by any changes you make. For example, you can ensure no scan configurations use a file extension list before deleting it.

1. Click **Policies > Common Objects > Lists > File Extension Lists**.
2. Select the list and click **Properties**.
3. Click the **Assigned To** tab.

Create a list of files for use in policies

Create lists of file paths so that you can use them in multiple policies. A single list is easier to manage than several identical lists that are each created in a different policy.

Tip: To create a file list that is similar to an existing one, duplicate the list and then edit it.

The following table describes the syntax for defining file list items. The use of forward slashes "/" and backslashes "\" are supported for both Windows and Linux conventions:

Inclusion	Format	Description	Example
File	FILE	Includes all files with the specified file name regardless of its location or directory.	<i>abc.doc</i> Includes all files named "abc.doc" in all directories. Does not include "abc.exe".

Inclusion	Format	Description	Example
File path	FILEPATH	Includes the specific file specified by the file path.	C:\Documents\abc.doc Includes only the file named "abc.doc" in the "Documents" directory.
File with wildcard (*)	FILE*	Includes all files with a matching pattern in the file name.	abc*.exe Includes any file that has prefix of "abc" and extension of ".exe". *.db <i>Matches:</i> 123.db abc.db <i>Does not match:</i> 123db 123.abd cbc.dba *db <i>Matches:</i> 123.db 123db ac.db acdb db <i>Does not match:</i> db123 wxy*.db <i>Matches:</i> wxy.db wxy123.db <i>Does not match:</i> wxydb
File with wildcard (*)	FILE.EXT*	Includes all files with a matching pattern in the file extension.	abc.v* Includes any file that has file name of "abc" and extension beginning with ".v". abc.*pp <i>Matches:</i> abc.pp abc.app <i>Does not match:</i> wxy.app

Inclusion	Format	Description	Example
			<i>abc.a*p</i> <i>Matches:</i> abc.ap abc.a123p <i>Does not match:</i> abc.pp <i>abc.*</i> <i>Matches:</i> abc.123 abc.xyz <i>Does not match:</i> wxy.123
File with wildcard (*)	FILE*.EXT*	Includes all files with a matching pattern in the file name and in the extension.	<i>a*c.a*p</i> <i>Matches:</i> ac.ap a123c.ap ac.a456p a123c.a456p <i>Does not match:</i> ad.aa
Environment variable	\${ENV VAR}	Includes files specified by an environment variable with the format \${ENV VAR}. These can be defined or overridden using Policy or Computer Editor > Settings > General > Environment Variable Overrides .	<i>\${myDBFile}</i> Includes the file "myDBFile".
Comments	FILEPATH #Comment	Allows you to add comments to your inclusion definitions.	<i>C:\Documents\abc.doc</i> <i>#This a comment</i>

1. Click **Policies > Common Objects > Lists > File Lists**.
2. Click **New > New File List**.
3. Type a name and, optionally, a description.
4. In the **File(s)** list, add the file paths, one per line.
5. Click **OK**.

Import and export file lists

You can export one or more file lists to an XML or CSV file, and import lists from an XML file.

1. Click **Policies > Common Objects > Lists > File Lists**.
2. To export one or more lists, select them and click **Export > Export Selected to CSV** or **Export > Export Selected to XML**.
3. To export all lists, click **Export > Export to CSV** or **Export > Export to XML**.
4. To import lists, click **New > Import From File** and follow the instructions on the wizard.

See which policies use a file list

It is useful to see which policies use a file list to be aware of which policies are affected by any changes you make. For example, you can ensure no policies use a file list before deleting it.

1. Click **Policies > Common Objects > Lists > File Lists**.
2. Select the file list and click **Properties**.
3. Click the **Assigned To** tab.

Create a list of IP addresses for use in policies

Create lists of IP addresses so that you can use them in multiple firewall rules. A single list is easier to manage than several identical lists that are each defined in a different rule.

Tip: To create an IP list that is similar to an existing one, duplicate the list and then edit it.

You can enter an individual IP address, or you can enter IP ranges and masked IPs. You can also insert comments into your IP list by preceding the text with a hash sign ("#").

Masked IP examples are 192.168.0/24, 192.168.2.0/255.255.255.0, and for IPV6 2001:0DB8::CD30:0:0:0/60. IP range examples are 192.168.0.2 - 192.168.0.125 and, for IPV6, FF01::101 - FF01::102

1. Click **Policies > Common Objects > Lists > IP Lists**.
2. Click **New > New IP List**.
3. Type a name and, optionally, a description.
4. In the **IP(s)** list, add the IP addresses, masked IP addresses, or IP ranges (one per line).
5. Click **OK**.

Import and export IP lists

You can export one or more IP lists to an XML or CSV file, and import lists from an XML file.

1. Click **Policies > Common Objects > Lists > IP Lists**.
2. To export one or more lists, select them and click **Export > Export Selected to CSV** or **Export > Export Selected to XML**.
3. To export all lists, click **Export > Export to CSV** or **Export > Export to XML**.
4. To import lists, click **New > Import From File** and follow the instructions on the wizard.

See which rules use an IP list

It is useful to see which firewall rules use an IP list to be aware of which rules are affected by any changes you make. For example, you can ensure no firewall rules use an IP list before deleting it.

1. Click **Policies > Common Objects > Lists > IP Lists**.
2. Select the IP list and click **Properties**.
3. Click the **Assigned To** tab.

Create a list of ports for use in policies

Create lists of port numbers so that you can use them in multiple rules. A single list is easier to manage than several identical lists that are each created in a different rule.

Tip: To create a port list that is similar to an existing one, duplicate the list and then edit it.

Individual ports and port ranges can be included on the list, for example 80, and 20-21. You can insert comments into your port list by preceding the text with a pound sign ("#").

Note: For a listing commonly accepted port number assignments, see the [Internet Assigned Numbers Authority \(IANA\)](#). For a list of port numbers used by Deep Security Manager, Relay, or Agent, see "[Port numbers, URLs, and IP addresses](#)" on page 111.

1. Click **Policies > Common Objects > Lists > Port Lists**.
2. Click **New > New Port List**.
3. Type a name and, optionally, a description.
4. In the **Port(s)** list, add the port numbers, one per line.
5. Click **OK**.

Import and export port lists

You can export one or more port lists to an XML or CSV file, and import lists from an XML file.

1. Click **Policies > Common Objects > Lists > Port Lists**.
2. To export one or more lists, select them and click **Export > Export Selected to CSV** or **Export > Export Selected to XML**.

3. To export all lists, click **Export > Export to CSV** or **Export > Export to XML**.
4. To import lists, click **New > Import From File** and follow the instructions on the wizard.

See which rules use a port list

It is useful to see which rules use a port list to be aware of which rules are affected by any changes you make. For example, you can ensure no rules use a port list before deleting it.

1. Click **Policies > Common Objects > Lists > Port Lists**.
2. Select the port list and click **Properties**.
3. Click the **Assigned To** tab.

Create a list of MAC addresses for use in policies

Create lists of MAC addresses so that you can use them in multiple policies. A single list is easier to manage than several identical lists that are each created in a different policy.

Tip: To create a MAC list that is similar to an existing one, duplicate the list and then edit it.

MAC lists support MAC addresses in both hyphen- and colon-separated formats, for example 0A-0F-FF-F0-A0-AF and 0A:0F:FF:F0:A0:AF. You can insert comments into your MAC list by preceding the text with a pound sign ("#").

1. Click **Policies > Common Objects > Lists > MAC Lists**.
2. Click **New > New MAC List**.
3. Type a name and, optionally, a description.
4. In the **MAC(s)** list, add the MAC addresses, one per line.
5. Click **OK**.

Import and export MAC lists

You can export one or more MAC lists to an XML or CSV file, and import lists from an XML file.

1. Click **Policies > Common Objects > Lists > MAC Lists**.
2. To export one or more lists, select them and click **Export > Export Selected to CSV** or **Export > Export Selected to XML**.
3. To export all lists, click **Export > Export to CSV** or **Export > Export to XML**.
4. To import lists, click **New > Import From File** and follow the instructions on the wizard.

See which policies use a MAC list

It is useful to see which policies use a MAC list to be aware of which policies are affected by any changes you make. For example, you can ensure no policies use a MAC list before deleting it.

1. Click **Policies > Common Objects > Lists > MAC Lists**.
2. Select the MAC list and click **Properties**.
3. Click the **Assigned To** tab.

Define contexts for use in policies

Contexts are a powerful way of implementing different security policies depending on a computer's network environment.

Contexts are designed to be associated with firewall and intrusion prevention rules. If the conditions defined in the context associated with a rule are met, the rule is applied.

Configure settings used to determine whether a computer has internet connectivity

1. In the Deep Security Manager, go to **Administration > System Settings > Contexts**.
2. In the **URL for testing Internet Connectivity Status** box, enter the URL to which an HTTP request will be sent to test for internet connectivity. (You must include "http://".)
3. In the **Regular Expression for returned content used to confirm Internet Connectivity Status** box, enter a regular expression that will be applied to the returned content to confirm that HTTP communication was successful. (If you are certain of the returned content, you can use a simple string of characters.)
4. In the **Test Interval** list, select the time interval between connectivity tests.

For example, to test Internet connectivity, you could use the URL "**http://www.example.com**", and the string "**This domain is established to be used for illustrative examples in documents**" which is returned by the server at that URL.

Define a context

1. In the Deep Security Manager, go to **Policies > Common Objects > Other > Contexts** and then click **New > New Context**.

2. In the **General Information** area, enter the name and description of the context rule. This area also displays the earliest version of the Deep Security Agent the rule will be compatible with.
3. In the **Options** area, specify when the context will be applied:
 - **Context applies when connection is:** Specifying an option here will determine whether the Firewall rule is in effect depending on the ability of the computer to connect to its domain controller or its internet connectivity. (Conditions for testing internet connectivity can be configured in **Administration > System Settings > Contexts**.)

If the domain controller can be contacted directly (via ICMP), the connection is "Local". If it can be contacted via VPN only, then the connection is "Remote".

The time interval between domain controller connectivity tests is the same as the internet connectivity test interval, which is configurable in **Administration > System Settings > Contexts**. The internet connectivity test is only performed if the computer is unable to connect to its domain controller.

- **Context Applies to Interface Isolation Restricted Interfaces:** This context will apply to network interfaces on which traffic has been restricted through the use of interface isolation. This is primarily used for "Allow" or "Force Allow" Firewall rules. See ["Detect and configure the interfaces available on a computer" on page 540](#).

After you assign the context to a rule, it is displayed on the **Assigned To** tab for the context. (To link a security rule to a context, go to the **Options** tab in the security rule's **Properties** window and select the context from the "Context" list.)

Define stateful firewall configurations

Deep Security's stateful firewall configuration mechanism analyzes each packet in the context of traffic history, correctness of TCP and IP header values, and TCP connection state transitions. In the case of stateless protocols like UDP and ICMP, a pseudo-stateful mechanism is implemented based on historical traffic analysis. Packets are handled by the stateful mechanism as follows:

1. A packet is passed to the stateful routine if it has been allowed through by the static firewall rule conditions,

2. The packet is examined to determine whether it belongs to an existing connection, and
3. The TCP header is examined for correctness (e.g. sequence numbers, flag combinations, etc.).

To create a new stateful configuration, you need to:

1. ["Add a stateful configuration " below.](#)
2. ["Enter stateful configuration information" below.](#)
3. ["Select packet inspection options" below.](#)

When you're done with your stateful configuration, you can also learn how to

- ["See policies and computers a stateful configuration is assigned to" on page 625](#)
- ["Export a stateful configuration " on page 624](#)
- ["Delete a stateful configuration " on page 625](#)

Add a stateful configuration

There are three ways to define a stateful configuration on the **Policies > Common Objects > Other > Firewall Stateful Configurations** page:

- Create a new configuration. Click **New > New Firewall Stateful Configuration**.
- Import a configuration from an XML file. Click **New > Import From File**.
- Copy and then modify an existing configuration. Right-click the configuration in the Firewall Stateful Configurations list and then click **Duplicate**. To edit the new configuration, select it and then click **Properties**.

Enter stateful configuration information

Enter a **Name** and **Description** for the configuration.

Select packet inspection options

You can define options for IP, TCP, UDP and ICMP packet inspection, and enable Active or Passive FTP.

IP packet inspection

Under the **General** tab, select the **Deny all incoming fragmented packets** to drop any fragmented packets. Dropped packets will bypass fragmentation analysis and generate an "IP fragmented packet" log entry. Packets with a total length smaller than the IP header length are dropped silently.

Warning: Attackers sometimes create and send fragmented packets in an attempt to bypass Firewall Rules.

Note: The Firewall Engine, by default, performs a series of checks on fragmented packets. This is default behavior and cannot be reconfigured. Packets with the following characteristics are dropped:

- **Invalid fragmentation flags/offset:** A packet is dropped when either the **DF** and **MF** flags in the IP header are set to 1, or the header contains the **DF** flag set to 1 and an **Offset** value different than 0.
- **First fragment too small:** A packet is dropped if its **MF** flag is set to 1, its **Offset** value is at 0, and it has total length of less than 120 bytes (the maximum combined header length).
- **IP fragment out of boundary:** A packet is dropped if its **Offset** flag value combined with the total packet length exceeds the maximum datagram length of 65535 bytes.
- **IP fragment offset too small:** A packet is dropped if it has a non-zero **Offset** flag with a value that is smaller than 60 bytes.

TCP packet inspection

Under the **TCP** tab, select which of the following options you would like to enable:

- **Deny TCP packets containing CWR, ECE flags:** These flags are set when there is network congestion.

Note: RFC 3168 defines two of the six bits from the Reserved field to be used for ECN (Explicit Congestion Notification), as follows:

- Bits 8 to 15: CWR-ECE-URG-ACK-PSH-RST-SYN-FIN
- TCP Header Flags Bit Name Reference:
 - Bit 8: CWR (Congestion Window Reduced) [RFC3168]
 - Bit 9: ECE (ECN-Echo) [RFC3168]

Warning: Automated packet transmission (such as that generated by a denial of service attack, among other things) will often produce packets in which these flags are set.

- **Enable TCP stateful inspection:** Enable stateful inspection at the TCP level. If you enable stateful TCP inspection, the following options become available:
 - **Enable TCP stateful logging:** TCP stateful inspection events will be logged.
 - **Limit the number of incoming connections from a single computer to:** Limiting the number of connections from a single computer can lessen the effect of a denial of service attack.
 - **Limit the number of outgoing connections to a single computer to:** Limiting the number of outgoing connections to a single computer can significantly reduce the effects of Nimda-like worms.
 - **Limit the number of half-open connections from a single computer to:** Setting a limit here can protect you from DoS attacks like SYN Flood. Although most servers have timeout settings for closing half-open connections, setting a value here can prevent half-open connections from becoming a significant problem. If the specified limit for SYN-SENT (remote) entries is reached, subsequent TCP packets from that specific computer will be dropped.

Note: When deciding on how many open connections from a single computer to allow, choose your number from somewhere between what you would consider a reasonable number of half-open connections from a single computer for the type of protocol being used, and how many half-open connections from a single computer your system can maintain without getting congested.

- **Enable ACK Storm protection when the number of already acknowledged packets exceeds:** Set this option to log an event that an ACK Storm attack has occurred.
 - **Drop Connection when ACK Storm detected:** Set this option to drop the connection if such an attack is detected.

Note: ACK Storm protection options are only available on Deep Security Agent 8.0 and earlier.

FTP Options

Under the **FTP Options** tab, you can enable the following options:

Note: The following FTP options are available in Deep Security Agent version 8.0 and earlier.

- **Active FTP**
 - **Allow Incoming:** Allow Active FTP when this computer is acting as a server.
 - **Allow Outgoing:** Allow Active FTP when this computer is acting as client.
- **Passive FTP**
 - **Allow Incoming:** Allow Passive FTP when this computer is acting as a server.
 - **Allow Outgoing:** Allow Passive FTP when this computer is acting as a client.

UDP packet inspection

Under the **UDP** tab, you can enable the following options:

- **Enable UDP stateful inspection:** Select to enable stateful inspection of UDP traffic.

Note: The UDP stateful mechanism drops unsolicited incoming UDP packets. For every outgoing UDP packet, the rule will update its UDP "stateful" table and will then only allow a UDP response if it occurs within 60 seconds of the request. If you wish to allow specific incoming UDP traffic, you will have to create a **Force Allow** rule. For example, if you are running a DNS server, you will have to create a **Force Allow** rule to allow incoming UDP packets to destination port 53.

Warning: Without stateful inspection of UDP traffic, an attacker can masquerade as a DNS server and send unsolicited UDP "replies" from source port 53 to computers behind a firewall.

- **Enable UDP stateful logging:** Selecting this option will enable the logging of UDP stateful inspection events.

ICMP packet inspection

Under the **ICMP** tab, you can enable the following options:

Note: ICMP stateful inspection is available in Deep Security Agent version 8.0 or earlier.

- **Enable ICMP stateful inspection:** Select to enable stateful inspection of ICMP traffic.

Note: The ICMP (pseudo-)stateful mechanism drops incoming unsolicited ICMP packets. For every outgoing ICMP packet, the rule will create or update its ICMP "stateful" table and will then only allow a ICMP response if it occurs within 60 seconds of the request. (ICMP pair types supported: Type 0 & 8, 13 & 14, 15 & 16, 17 & 18.)

Warning: With stateful ICMP inspection enabled, you can, for example, only allow an ICMP echo-reply in if an echo-request has been sent out. Unrequested echo-replies could be a sign of several kinds of attack including a Smurf amplification attack, a Tribe Flood Network communication between master and daemon, or a Loki 2 back-door.

- **Enable ICMP stateful logging:** Selecting this option will enable the logging of ICMP stateful inspection events.

Export a stateful configuration

You can export all stateful configurations to a .csv or .xml file by clicking **Export** and selecting the corresponding export action from the list. You can also export specific stateful configurations by first selecting them, clicking **Export** and then selecting the corresponding export action from the list.

Delete a stateful configuration

To delete a stateful configuration, right-click the configuration in the Firewall Stateful Configurations list, click **Delete** and then click **OK**.

Note: Stateful configurations that are assigned to one or more computers or that are part of a policy cannot be deleted.

See policies and computers a stateful configuration is assigned to

You can see which policies and computers are assigned to a stateful inspection configuration on the **Assigned To** tab. Click on a policy or computer in the list to see their properties.

Define a schedule that you can apply to rules

Schedules are reusable timetables that you can assign to rules, agent upgrades, and more.

1. In Deep Security Manager, go to **Policies > Common Objects > Other > Schedules**.
2. Click **New > New Schedule**.
3. In the **General Information** area, enter a name and description used to identify the schedule.
4. Click a time block in the grid to select it. To deselect it, click it while pressing Shift.
Schedule periods are defined by hour-long time blocks.

After you assign the schedule to a rule, it is displayed on the **Assigned To** tab for the schedule. To link a security rule to a schedule, go to the **Options** tab in the security rule's **Properties** window and select the schedule from the "Schedule" list.

Note: With agent-based protection, schedules use the same time zone as the protected computer's operating system. With agentless protection, schedules use the same time zone as the Deep Security Virtual Appliance.

Lock down software with application control

Note: You can enable application control for computers running Deep Security Agent 10.0 or higher. For a list of operating systems where application control is supported, see "[Supported](#)"

[features by platform" on page 85.](#)

Application control continuously monitors for software changes on your protected servers. Based on your policy configuration, application control either prevents unauthorized software from running until it is explicitly allowed, or allows unauthorized software until it is explicitly blocked. Which option you choose depends on the level of control you want over your environment.

Tip: Application control is intended for use on stable servers that are not updated frequently, and not for workstations or servers that undergo a lot of software changes.

Key concepts

Targeted protection state: One of the main decisions you need to make when setting up application control is deciding your targeted protection state. Do you want to prevent all new or changed software from running, unless you manually specify that it is allowed? Or do you want it to run by default unless you specifically block it? One approach is to initially allow unrecognized software to run when you first enable application control and there's a lot of unrecognized software. As you add application control rules and the volume of unrecognized software decreases, you could switch to block mode.

Application control rule: Rules specify whether software is allowed or blocked on a particular computer.


Inventory: Initial list of software that is installed on the computer. Make sure only software that you want to allow is installed on the computer. When you enable application control, all currently installed software is added to the computer's inventory and allowed to run. When a computer is in maintenance mode, any software changes made to the computer are added to the computer's inventory and allowed to run. A computer's software inventory is stored on the Deep Security Agent and is not displayed in Deep Security Manager.

Unrecognized software: Software that isn't in a computer's inventory and isn't already covered by an application control rule. See ["What does application control detect as a software change?" on page 631](#)

Maintenance mode: If you are planning to install or update software, we strongly advise that you turn on maintenance mode. In maintenance mode, application control will continue to enforce

rules that block software, but it will allow new or updated software to run and automatically add it to the computer's inventory. See ["Turn on maintenance mode when making planned changes" on page 637](#).

How does application control work?



1. You enable application control in a policy and assign the policy to a computer that is protected by a Deep Security Agent (see ["Turn on application control" on page 633](#)).
2. When the agent receives the policy, it creates an inventory of all software installed on the computer. All software listed in the inventory is assumed to be safe and is allowed to run on that computer. This inventory is not visible from Deep Security Manager, which means you need to be absolutely certain that only good software is installed on a computer where you intend to enable application control.
3. After the inventory is finished, application control is aware of any software changes on the computer. A software change could be new software that appears on the computer or changes to existing software.
4. If the computer is in maintenance mode, the Deep Security Agent adds the software to its inventory and it is allowed to run. This change is not visible in Deep Security Manager. See ["Turn on maintenance mode when making planned changes" on page 637](#).

5. If the change was made by a trusted installer, the Deep Security Agent adds the software to its inventory and allows it to run. For example, when Microsoft Windows self-initiates a component update, hundreds of new executable files may be installed. Application control auto-authorizes many file changes that are created by well-known Windows processes and does not list these changes in Deep Security Manager. Removing the "noise" associated with expected software changes provides you with clearer visibility into changes that may need your attention.

Note: The trusted installer feature is available with Deep Security Agent 10.2 or later.

6. If the computer's ruleset contains a rule for this exact piece of software, the software is allowed or blocked according to the rule that's in place. See ["What does application control detect as a software change?" on page 631](#)
7. If software is not in the computer's inventory and is not covered by an existing rule, it's considered unrecognized software. The policy assigned to the computer specifies how unrecognized software is handled. Depending on the policy configuration, it's either allowed to run or is blocked. If the software is blocked and it is able to produce error messages in the OS, an error message on the protected computer indicates that the software does not have permissions to run or that access is denied.


The unrecognized software appears on the **Application Control - Software Changes** page in Deep Security Manager. On that page, an administrator can click **Allow** or **Block** to create an allow or block rule for that piece of software on a particular computer. An allow or block rule takes precedence over the default action specified in the policy. See ["Monitor new and changed software" on page 634](#).

A tour of the application control interface

There are a few places in Deep Security Manager where you can see changes related to application control:

- ["Application Control: Software Changes \(Actions\)" on the next page](#)
- ["Application Control Rulesets" on page 630](#)
- ["Security Events" on page 631](#)

Application Control: Software Changes (Actions)



The **Application Control: Software Changes** page is displayed when you click **Actions** in Deep Security Manager. It displays all unrecognized software (software that isn't in a computer's inventory and doesn't have a corresponding application control rule). Software changes are allowed or blocked at the computer level, so if a particular piece of software is installed on fifty computers, it will appear on that page fifty times. However, if you know that a certain piece of software should be allowed or blocked everywhere, you can filter the **Actions** page to sort the changes by file hash and then click **Allow All** to allow it on all computers where the software is installed.

The policy applied to a computer specifies whether it will allow all unrecognized software to run by default, or block all unrecognized software, but no explicit application control rule is created until you click "Allow" or "Block" on the Actions page. When you click Allow or Block, a corresponding rule appears in the ruleset for the computer. The rulesets are displayed on the **Application Control Rulesets** page.

Application Control Rulesets

Dashboard

Actions

Alerts

Events & Reports

Computers

Policies

Administration

Policies

Common Objects

Rules

Firewall Rules

Intrusion Prevention Rules

Integrity Monitoring Rules

Log Inspection Rules

Application Control Rulesets

Lists

Other

Application Control Rulesets

By Type

Search

Properties...

Delete...

Columns...

	NAME	CREATED	LAST UPDATED
Local (2)			
		October 18, 2016 15:03	October 18, 2016 15:03
		October 18, 2016 13:32	October 18, 2016 14:12
Shared (15)			
	ActionableEventsSecurityEvent...	October 18, 2016 14:04	October 18, 2016 14:05
	ActionableEventsSecurityEvent...	October 18, 2016 14:06	October 18, 2016 14:07
	ActionableEventsSecurityEvent...	October 18, 2016 14:09	October 18, 2016 14:09
	ActionableEventsSecurityEvent...	October 18, 2016 14:05	October 18, 2016 14:06
	ActionableEventsSecurityEvent...	October 18, 2016 14:08	October 18, 2016 14:08
	inventoryName1476811733	October 18, 2016 13:31	October 18, 2016 13:31

To see the ruleset for a computer, go to **Policies > Common Objects > Rules > Application Control Rulesets**. To see which rules are part of a ruleset, double-click the ruleset and go to the **Rules** tab. The Rules tab displays the pieces of software that have rules associated with them and enables you to change allow rules to block, and vice versa.

629

Security Events

The screenshot shows the 'Events & Reports' section of the Trend Micro Deep Security On-Premise 11.3 interface. The left sidebar lists various event categories, with 'Security Events' highlighted. The main panel displays 'Application Control Events' for the 'Last Hour' period, filtered by 'All Computers'. The table shows multiple entries for 'Execution of Unrecognized Software Allowed' on February 16, 2018. Each entry has a 'View rules...' link and a 'None' rule set. The bottom of the table indicates 'Item 1 to 100 of 1,961'.

TIME	COMPUTER	EVENT	RULES	RULESET
February 16, 2018 12:4...	...	Execution of Unrecognized Software Allowed	View rules...	None
February 16, 2018 12:3...	(...	Execution of Unrecognized Software Allowed	View rules...	None
February 16, 2018 12:3...	...	Execution of Unrecognized Software Allowed	View rules...	None
February 16, 2018 12:3...	...	Execution of Unrecognized Software Allowed	View rules...	None
February 16, 2018 12:3...	...	Execution of Unrecognized Software Allowed	View rules...	None
February 16, 2018 12:3...	...	Execution of Unrecognized Software Allowed	View rules...	None

Events & Reports > Events > Application Control Events > Security Events displays all unrecognized software that either has been run on a computer or has been prevented from running by a block rule. You can filter this list by time period and other criteria.

For each event (except aggregated events), you can click **View rules** to change the rule from Allow to Block or vice versa. Deep Security Agent 10.2 or later includes event aggregation logic to reduce the volume of logs when the same event occurs repeatedly.

What does application control detect as a software change?

Unlike [integrity monitoring](#), which monitors any file, application control looks only for software files when examining the initial installation and monitoring for change.

Software can be:

- Windows applications (.exe, .com, .dll, .sys), Linux libraries (.so) and other compiled binaries and libraries
- Java .jar and .class files, and other compiled byte code

Trend Micro Deep Security On-Premise 11.3

- PHP, Python, and shell scripts, and other web apps and scripts that are interpreted or compiled on the fly
- Windows PowerShell scripts, batch files (.bat), and other Windows-specific scripts (.wsf, .vbs, .js)

For example, WordPress and its plug-ins, Apache, IIS, nginx, Adobe Acrobat, app.war, and /usr/bin/ssh would all be detected as software.

Application control checks a file's extension to determine whether it's a script. Additionally, on Linux, application control treats any file with execute permissions as if it's a script.

Note: On Windows computers, application control tracks changes on the local file system, but not on network locations, CD or DVD drives, or USB devices.

Application control is integrated with the kernel (on Linux computers) and file system, so it has permissions to monitor the whole computer, including software installed by root or administrator accounts. The agent watches for disk write activity on software files, and for attempts to execute software.

Differences in how Deep Security Agent 10.x and 11.x compare files

To determine whether software is new or has changed, Deep Security 10.x agents compare the file with the initially installed software's SHA-256 hash, file size, path, and file name (they have a "file-based" ruleset). Deep Security 11.x agents compare only the file's SHA-256 hash and file size (they have a "hash-based" ruleset). Because the rules created by Deep Security 11.x agents compare only the unique hash and file size, a rule will continue to be applied even if the software file is renamed or moved. As a result, using Deep Security 11.x agents reduces the number of software changes that you need to deal with.

A Deep Security 10.x agent continues to use a file-based ruleset until it is upgraded to Deep Security 11.0 or newer. When you upgrade an agent to version 11.0 or newer, its ruleset is converted to use hash-based rules. If there are multiple file-based rules for the same hash value, they are consolidated into one hash-based rule. If the rules being consolidated conflict with each other (one rule blocks the file and another allows it), the new hash-based rule will be an "allow" rule.

Set up application control

For information about how application control works, see ["Lock down software with application control" on page 625](#).

To enable application control and monitor software changes:

1. ["Turn on application control" below](#)
2. ["Monitor new and changed software" on the next page](#)
3. ["Turn on maintenance mode when making planned changes" on page 637](#)

This article also provides ["Application control tips and considerations" on page 638](#) that you should be aware of when working with application control.

Once you've enabled application control, you can also learn how to:


- ["View and change application control rulesets" on page 644](#)
- ["Reset application control after too much software change" on page 649](#)
- ["Monitor application control events" on page 641](#)
- ["Use the API to create shared and global rulesets" on page 650](#)

Turn on application control

You can enable application control in the settings for a computer or in policies:

1. Open the **Computer or Policy editor**¹ and go to **Application Control > General**.
2. Set the **Application Control State** to "On" or "Inherited (On)".
3. Under **Enforcement**, select your targeted protection state:
 - **Block unrecognized software until it is explicitly allowed**
 - **Allow unrecognized software until it is explicitly blocked** (we recommend that you choose this option when initially setting up application control)
4. Click **Save**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).



The next time that the Deep Security Manager and agent connect, the agent scans and then generates an inventory of all software installed on the computer and creates rules that allow all the software that it finds. This initial inventory can take 15 minutes or longer, depending on your environment.

To check that application control is working as expected, follow the instructions in ["Verify that application control is enabled" on page 639](#).

Monitor new and changed software

After the inventory has finished on a protected computer, any software executable files that are added or changed are classified as a "software change" and appear on the **Actions** page in Deep Security Manager. When unrecognized software runs, or attempts to run and is blocked, the event is listed under **Events & Reports > Events > Application Control Events > Security Events**.

After you initially enable application control, you will likely see a lot of software changes on the **Actions** page. This can happen when allowed software creates new executables, renames files, or relocates files through the normal course of operation. As you add rules to tune application control, you should see fewer software changes.

To quickly find all software changes on all computers and easily create allow or block rules for them, use the **Actions** tab.

1. In Deep Security Manager, go to **Actions**.
2. There are several ways you can filter to see only specific occurrences of unrecognized software.

Tip: Instead of evaluating each software change on each computer individually, use the filters described below to find software changes that you know are good, and allow them in bulk.

The screenshot shows the Trend Micro Deep Security Manager interface. The top navigation bar includes 'Dashboard', 'Actions', 'Alerts', 'Events & Reports', 'Computers', 'Policies', and 'Administration'. The main content area is titled 'Application Control: Software Changes' and features a time range filter set to 'Last 7 Days'. A search bar shows 'Host Name BEGINS WITH 10.203'. A bar chart displays software changes over time, with a callout indicating '15080 files'. Below the chart, a table lists software changes with columns for file name, path, and actions (Allow/Block). The right sidebar shows details for a selected file, 'curl-config.dpkg-new', including its product name, install path, and change event time. The bottom status bar shows 'Application Control Ruleset Update in Progress on 2 Computers' and 'Processing 19 Malware Scans'.

To reduce the number of software changes being displayed:

- From the drop-down list next to **Application Control: Software Changes**, select a time range such as **Last 7 Days**. You can also click a bar in the graph near the top of the page to display the changes for that time period.
- In the pane on the left, click **Computers** and select an individual computer or group, or click **Smart Folders** to display only the computers that are included in a particular smart folder (see ["Group computers dynamically with smart folders" on page 1351](#)).

Note: Unlike the **Computers** tab, the **Software Changes** pane usually does not show all computers. It only displays computers where application control has detected software changes that don't already have allow or block rules.

- Enter search terms and operators in the search filter field. You search for these attributes: Change By Process, Change By User, File Name, Host Name, Install Path, MD5, SHA1, and SHA256. For example, you could find all changes made by a particular user that you trust and click **Allow All** to allow all of their changes. Or if a particular software update was installed across your organization (while [maintenance mode](#) was not enabled), filter the page according to the hash value of the file and click **Allow All** to allow all occurrences.

Tip: Details about a software change are displayed in the right pane. You can click the file name or computer name in the details to add it to your search filter.

- Select whether to **Group by File (Hash)** or **Group by Computer**.
3. Click either **Allow** or **Block** to add an allow or block rule on that computer, for that software. If you need more information to decide whether to allow or block, click the software name, then use the details panel on the right side.

The next time that the agent connects with the Deep Security Manager, it receives the new rules.

Tips for handling changes

- For most environments, we suggest that you select the **Allow unrecognized software until it is explicitly blocked** option to allow software changes by default when you first enable application control and add allow and block rules for changes that you see on the **Actions** page. Eventually, the rate of software changes should decrease. At that point, you could consider blocking software changes by default and creating allow rules for the software that you know is good. Some organizations prefer to continue to allow changes by default and monitor the **Actions** page for software that should be blocked.
- You may prefer to start by evaluating security events, rather than dealing with unrecognized software first. Security events show you which unrecognized software has

run (or attempted to run). For information on security events, see ["Monitor application control events" on page 641](#).

- When an unrecognized file is allowed to execute and you want to continue to allow it, create an Allow rule. In addition to allowing the file's execution, the event is no longer logged for that file, which reduces noise and makes important events easier to find.
- When a known file's execution is blocked, consider cleaning that file from the computer, especially for repeated occurrences.
- Keep in mind that software changes are listed for each computer where they occur. You must allow or block the software for each computer.
- Rules are assigned to computers, not to policies. For example, if `helloworld.py` is detected on three computers, when you click **Allow All** or **Block All**, this would affect only three computers. It won't affect future detections on other computers, because they have their own rulesets.
- If you see changes related to software updates that you can control, use the maintenance mode feature when performing those updates. See ["Turn on maintenance mode when making planned changes" below](#).

Turn on maintenance mode when making planned changes

When you install patches, upgrade software, or deploy web applications, application control will detect them. Depending on your setting for how to handle unrecognized software, this could block that software until you use the **Actions** tab to create allow rules.

To avoid extra down time and alerts during deployment and maintenance windows, you can put application control into a mode designed for maintenance windows. While maintenance mode is enabled, application control will continue to enforce rules that block software, but it will allow new or updated software to run and automatically add it to the computer's inventory.

1. In Deep Security Manager, go to **Computers**.
2. Select one or more computers, then click **Actions > Turn On Maintenance Mode**.
3. Select the duration of your maintenance window.

Maintenance mode will automatically disable itself when your maintenance window is scheduled to end. Alternatively, if you'd prefer to manually disable maintenance mode when updates are finished, select **Indefinite**.

On the **Dashboard**, the **Application Control Maintenance Mode Status** widget indicates whether the command succeeded.

4. Install or upgrade software.
5. If you chose to disable maintenance mode manually, remember to disable maintenance mode in order to start to detect software changes again.

Application control tips and considerations

- For better performance with application control, use Deep Security anti-malware instead of Windows Defender. See ["Disable Windows Defender after installing Deep Security anti-malware on Windows Server 2016" on page 686](#).
- If you create a block rule for a batch file or PowerShell script, you will not be able to copy, move, or rename the file when using its associated interpreter (powershell.exe for PowerShell scripts or cmd.exe for batch files).
- If you add an allow or block rule, it is normally sent to the agent the next time the agent connects to Deep Security Manager. If you see an error saying that the ruleset upload was not successful, verify that network devices between the agent and the manager or relay allow communications on the [heartbeat port number](#) or [relay port numbers](#).
- To verify that a block rule is working, try to run the software that you just blocked. (For details on how Deep Security Agent detects changes, see ["What does application control detect as a software change?" on page 631](#))
- When blocked software remains installed, application control continues to record logs and show alerts when it blocks the software from running. To reduce the permission error logs on the computer and also reduce your attack surface, uninstall the software that application control is blocking. Once that is done, if you want to dismiss related alerts, either go to **Alerts** or go to **Dashboard**, click the alert, and then click **Dismiss Alert**. Not all alerts can be dismissed. For more information, see ["Predefined alerts" on page 1205](#).
- For performance reasons, if the computer has too much software change, application control will continue to enforce existing rules, but stop detecting and displaying software

changes. To resolve this, see ["Reset application control after too much software change" on page 649](#).


Verify that application control is enabled

For an overview of application control, see ["Lock down software with application control" on page 625](#). For initial configuration instructions, see ["Set up application control" on page 633](#).

When application control is enabled and has finished its initial software inventory scan:

- The **State** field indicates "On" or "On, Blocking unrecognized software".
- On **Computers**, the **Status** field changes from "Application Control Ruleset Build In Progress" to "Managed (Online)".
- **Events & Reports > Events > System Events** will record "Application Control Ruleset Build Started" and "Application Control Ruleset Build Completed". (If you don't see any

logs, see ["Choose which application control events to log" on the next page.](#))



To verify that application control is working:

1. Copy an executable to the computer or add execute permissions to a plain text file. Try to run the executable.

Depending on your enforcement setting for unrecognized software, it should be either blocked or allowed. Once application control has built initial allow rules or downloaded a shared ruleset, if any change is detected, it should appear in the **Actions** tab, which you can use to create allow and block rules (see ["Monitor new and changed software" on page 634](#)). Depending on your alert configuration, you will also see an alert if unrecognized software is detected, or if application control blocks software from launching (see ["Monitor application control events" on the next page](#)). The event should persist until

the software change no longer exists, or until the oldest data has been removed from the database.

2. Add an allow or block rule for your test software and then try again. This time, application control should apply your allow or block rule.

Tip: If software is accidentally blocked because you've selected **Block unrecognized software until it is explicitly allowed** and the software isn't being recognized, the **Reason** column in application control event logs can help you to troubleshoot the cause.

Monitor application control events

For an overview of application control, see ["Lock down software with application control" on page 625](#). For initial configuration instructions, see ["Set up application control" on page 633](#).

By default, when you enable application control it logs events, such as when there are software changes or when it blocks software from executing. Application control events appear on the **Actions** and **Events & Reports** pages. If configured, an alert appears on the **Alerts** page.

You can configure some of which application control event logs are recorded, and which are [forwarded to external SIEM systems, or syslog servers](#).

To monitor for software changes on computers:

1. ["Choose which application control events to log" below](#)
2. ["View application control event logs" on the next page](#)
3. ["Interpret aggregated security events" on the next page](#)
4. ["Monitor application control alerts" on page 644](#)

Choose which application control events to log

1. Go to **Administration > System Settings > System Events**.
2. Scroll down to the application control events such as Event ID 7000 "Application Control Events Exported".
3. If you want to record event logs for that type of event, select **Record**.

When those events occur, they appear on **Events & Reports > Events > System Events**. Logs are kept until they meet maximum log age criteria. For details, see ["Events in Deep Security" on page 1088](#).

Note: Events that appear on **Computers > Details > Application Control > Events** are not configured here. They are always logged.

4. If you want to forward event logs to a SIEM, or syslog server, select **Forward**.
5. If you use an external SIEM, you may need to load the list of possible application control event logs, and indicate what action to take. For a list of application control events, see ["System events" on page 1220](#).

View application control event logs

Application control generates system events and security events:

- **System event:** An audit event that provides a history of configuration changes or software updates. To see system events click **Events & Reports > Events > System Events**. For a list, see ["System events" on page 1220](#).
- **Security event:** An event that occurs on the agent when application control blocks or allows unrecognized software, or blocks software due to a block rule. To see security events, click **Events & Reports > Events > Application Control Events > Security Events**.

Application Control logs the following security events:

- Execution of Unrecognized Software Allowed
- Execution of Unrecognized Software Blocked
- Execution of Software Blocked by Rule

Interpret aggregated security events

When an agent heartbeat includes several instances of the same security event, Deep Security aggregates the events in the Security Events log. Event aggregation reduces the number of items in the log, making it easier to find important events:

Trend Micro Deep Security On-Premise 11.3

- When the event occurs for the same file, which is usually the case, the log includes the file name with the aggregated event. For example, a heartbeat includes 3 instances of the "Execution of Unrecognized Software Allowed" event for the Test_6_file.sh file, and no other instances of that event. Deep Security aggregates these 3 events for the file Test_6_file.sh.
- When the event occurs for many files, the log omits the rules link, path, file name, and user name. For example, a heartbeat includes 21 instances of the "Execution of Unrecognized Software Allowed" event that occurred for several different files. Deep Security aggregates the 21 events in a single event, but does not include a rules link, path, file name, or user name.

When aggregated events apply to multiple files, other occurrences of these events have likely been reported in other heartbeats. After you respond to other events where the file name is known, it is likely that no more aggregated events occur.


In the log, aggregated events use special icons, and the **Repeat Count** column indicates the number of events that are aggregated.

Application Control Events All No Grouping Search this page									
Period: Last 7 Days									
Computers: All Computers									
View Export Auto-Tagging... Columns...									
	TIME	COMPUTER	EVENT	RULES	RULESET	REPEAT COUNT	ACTION	REASON	FILE
	October 6, 2017 10:31:...		Execution of Unrecognized Software Allowed	Change rules...	None	1	Allowed	N/A	Test_4_file.sh
	October 6, 2017 10:30:...		Execution of Unrecognized Software Allowed	Change rules...	None	1	Allowed	N/A	Test_3_file.sh
	October 6, 2017 10:31:...		Execution of Unrecognized Software Allowed	Change rules...	None	2	Allowed	N/A	Test_1_file.sh
	October 6, 2017 10:30:...		Execution of Unrecognized Software Allowed	Change rules...	None	2	Allowed	N/A	Test_9_file.sh
	October 6, 2017 10:31:...		Execution of Unrecognized Software Allowed	Change rules...	None	2	Allowed	N/A	Test_5_file.sh
	October 6, 2017 10:31:...		Execution of Unrecognized Software Allowed	Change rules...	None	3	Allowed	N/A	Test_6_file.sh
	October 6, 2017 10:30:...		Execution of Unrecognized Software Allowed	Change rules...	None	1	Allowed	N/A	heartbeatSyn...
	October 5, 2017 15:04:...		Execution of Unrecognized Software Allowed	Change rules...	None	1	Allowed	N/A	Test_7_file.sh
	October 5, 2017 15:04:...		Execution of Unrecognized Software Allowed	Change rules...	None	1	Allowed	N/A	Test_3_file.sh
	October 5, 2017 15:04:...		Execution of Unrecognized Software Allowed	Change rules...	None	1	Allowed	N/A	Test_5_file.sh
	October 5, 2017 15:04:...		Execution of Unrecognized Software Allowed	Change rules...	None	1	Allowed	N/A	heartbeatSyn...
	October 5, 2017 14:42:...		Execution of Unrecognized Software Allowed	N/A	None	21	Allowed	N/A	N/A

Monitor application control alerts

To configure which application control events or severity levels cause an alert, go to the **Alerts** tab, click the **Configure Alerts** button, and then select an event and double-click **Properties**. For details, see ["Configure alerts" on page 1066](#).

When alerts are enabled for application control events, any software change that the application control engine detects and any software that it blocks from executing appear in the **Alerts** tab. If you have enabled the **Alert Status** widget, application control alerts also appear on the Dashboard.



To monitor which computers are in maintenance mode, you can also click **Add/Remove Widgets** and enable the **Application Control Maintenance Mode** widget, which displays a list of the computers and their scheduled maintenance windows.

View and change application control rulesets

Each computer has its own application control ruleset. You can:

- ["View application control rulesets" below](#) and find out which rules they include.

Tip: When you first enable application control for a computer, the software installed on the computer is added to the computer's inventory and allowed to run. However, you cannot see the rules associated with the inventory from Deep Security Manager unless you use the Deep Security API to do so (see ["Use the API to create shared and global rulesets" on page 650](#)). In Deep Security Manager, a computer's ruleset appears empty until you create some allow/block rules for the computer.

- ["Change the action for an application control rule" on page 647](#) if a software file should no longer be allowed/blocked.
- ["Delete an individual application control rule" on page 649](#) if the software has been removed and isn't likely to return.
- ["Delete an application control ruleset" on page 649](#) if the computer associated with the ruleset has been removed.

Tip: If a user reports that application control is blocking software that they need to run on a particular computer, you can undo the block rule on that computer. Go to **Events & Reports > Application Control Events > Security Events**, find the computer, locate the block event, and then click **View Rules**. In the pop-up that appears, you can change the block rule to an allow rule.

View application control rulesets

To view the list of application control rulesets, go to **Policies > Common Objects > Rules > Application Control Rulesets**.

DashboardActionsAlertsEvents & ReportsComputersPoliciesAdministration

Policies

Common Objects

Rules

Firewall Rules

Intrusion Prevention Rules

Integrity Monitoring Rules

Log Inspection Rules

Application Control Rulesets

Lists

Other

Application Control Rulesets

By Type

Search

Properties...

Delete...


Columns...

NAME	CREATED	LAST UPDATED
Local (2)		
[redacted]	October 18, 2016 15:03	October 18, 2016 15:03
[redacted]	October 18, 2016 13:32	October 18, 2016 14:12
Shared (15)		
ActionableEventsSecurityEvent...	October 18, 2016 14:04	October 18, 2016 14:05
ActionableEventsSecurityEvent...	October 18, 2016 14:06	October 18, 2016 14:07
ActionableEventsSecurityEvent...	October 18, 2016 14:09	October 18, 2016 14:09
ActionableEventsSecurityEvent...	October 18, 2016 14:05	October 18, 2016 14:06
ActionableEventsSecurityEvent...	October 18, 2016 14:08	October 18, 2016 14:08
inventoryName1476811733	October 18, 2016 13:31	October 18, 2016 13:31

To see which rules are part of a ruleset, double-click the ruleset and go to the **Rules** tab. The Rules tab displays the software files that have rules associated with them and enables you to change allow rules to block, and vice versa. (See ["Change the action for an application control rule" on the next page.](#))

645

Security Events



Events & Reports > Events > Application Control Events > Security Events displays all unrecognized software that either has been run on a computer or has been actively blocked from running. You can filter this list by time period and other criteria.

For each event (except aggregated events), you can click **View rules** to change the rule from Allow to Block or vice versa.

Deep Security Agent 10.2 or later includes event aggregation logic to reduce the volume of logs when the same event occurs repeatedly. (See ["Interpret aggregated security events" on page 642.](#))


Change the action for an application control rule

If you want to allow a software that you previously blocked (or the opposite), you can edit the action in the rule. If you need to undo the rule so that the software is not recognized by application control (in other words, delete the rule, not only change its action), see ["Delete an individual application control rule" on page 649](#) instead.

1. Go to **Policies > Common Objects > Rules > Application Control Rulesets**.
2. Double-click to select the ruleset that contains the rule that you want to change.

3. On the pop-up window that appears, go to the **Rules** tab.
4. If you want to focus on software that was blocked (or allowed), then in the menu next to **Application Control Rules**, select **By Action** or **By Path** to group similar rules. Alternatively, you can use the search to filter the list.

If you want to change the action for a software file, but it has multiple different file names or paths, select **By File Name** or **By Path** to group related rules.



5. Find the row for the specific software that you want to allow or block.
6. In the **Action** column, change the setting to allow or block, then click **OK**.

The next time that the agent connects with Deep Security Manager, the rule will be updated, and the version number will increase.

Delete an individual application control rule

If you want to undo a rule that you created, go to **Policies > Common Objects > Rules > Application Control Rulesets**, double-click the ruleset that contains the rule, go to the **Rules** tab, select the rule and then click **Delete**.

Some things to keep in mind:

- When the rules are not needed anymore, you can delete them to reduce the size of the ruleset. This improves performance by reducing RAM and CPU usage.
- If you delete a rule, application control will not recognize the software anymore. If the software is installed again, it will appear again on the **Actions** tab.
- If a software update is unstable and you might need to downgrade, keep rules that allow rollback to the previous software version until you have completed testing.
- To find the oldest rules, go to **Policies > Rules > Application Control Rulesets**, then click **Columns**. Select **Date/Time (Last Change)**, click **OK**, and then click that column's header to sort by date.

Delete an application control ruleset

If an application control ruleset is not being used anymore (for example, if the computer associated with the ruleset no longer exists), you can delete it.

To delete a ruleset, go to **Policies > Rules > Application Control Rulesets**, click a ruleset to select it, and click **Delete**.

Reset application control after too much software change

For an overview of application control, see ["Lock down software with application control" on page 625](#).

Application control is intended for use on stable servers that are not updated frequently, and not for workstations or servers that undergo a lot of software changes.

Too many changes make large rulesets that consume more RAM, unless you remove old rules. If you don't use maintenance mode during authorized software updates, too many changes can

also result in high administrator workload because they must manually create allow rules for each change.

If unrecognized software changes exceed the maximum, application control will stop detecting and displaying all of the computer's software changes. This stoppage is designed to prevent out-of-memory and disk space errors that can occur if the ruleset grows too large.

When a stoppage occurs, Deep Security Manager will notify you through an alert ("Unresolved software change limit") and an event log ("Unresolved software change limit reached"). You must resolve the issue to continue detecting software changes.

1. Examine the computer's processes and security events. Verify that the computer has not been compromised. If you are not sure, or do not have enough time, the safest and fastest way is to restore the system from a backup or VM snapshot.

Warning: If you don't remove any unauthorized software (including zero-day malware), application control will ignore it when you reset application control. It won't appear on the Actions tab anymore and if its process has already executed and it is in RAM, application control won't log any events or alerts about it until you reboot the computer.

2. If the computer was running software updates, including auto-updates (for example, browser, Adobe Reader, or yum auto-updates), disable them or schedule them so that they occur only when you have enabled application control's maintenance mode (see ["Turn on maintenance mode when making planned changes" on page 637](#)).
3. Reset application control. To do this, disable application control in the **Computer editor**¹. Once the agent has acknowledged it and cleared the error status, enable application control again. The agent generates a new software inventory.

Use the API to create shared and global rulesets

For an overview of application control, see ["Lock down software with application control" on page 625](#). For initial configuration instructions, see ["Set up application control" on page 633](#).

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Using the Deep Security Manager interface, you can create a local, individual ruleset for each computer that you are protecting. Using the Deep Security API, you can also create shared rulesets and global rulesets. You can use one type of ruleset, or a combination.

- **Local ruleset:** Rules that are added as part of a computer's software inventory or when in maintenance mode are stored only on the protected computer and are not visible in Deep Security Manager. Allow or block rules that you configure in Deep Security Manager are sent to the agent and stored in both places. Because agents don't transfer their inventory information to the manager, local rulesets offer better performance than shared rulesets.

To determine whether software is new or has changed, Deep Security 10.x agents compare the file with the initially installed software's SHA-256 hash, file size, path, and file name (they have a "file-based" local ruleset). Deep Security 11.x agents compare only the file's SHA-256 hash and file size (they have a "hash-based" local ruleset). Because the rules created by Deep Security 11.x agents compare only the unique hash and file size, a rule will continue to be applied even if the software file is renamed or moved. As a result, using Deep Security 11.x agents reduces the number of software changes that you need to deal with. A Deep Security 10.x agent continues to use a file-based local ruleset until it is upgraded to Deep Security 11.0 or newer. When you upgrade an agent to version 11.0 or newer, its local ruleset is converted to use hash-based rules.

Note: If there are multiple file-based rules for the same hash value, they are consolidated into one hash-based rule. If the rules being consolidated conflict with each other (one rule blocks the file and another allows it), the new hash-based rule will be an "allow" rule.

- **Shared ruleset:** Syncs all of its rule data onto both agents and manager (and also relays, if enabled). This increases network and disk space usage. However, it may be easier if you need to verify the rules from the initial inventory scan or maintenance mode, or if you manage a server farm with many computers that should be identical. For example, if you have a server pool of identical LAMP web servers, or if they are virtual machines (VMs) that are part of an auto-scaling group, shared rulesets can be useful. It can also reduce administrator workload. To create a shared ruleset, see ["Create a shared ruleset" on page 653](#).

Warning: Don't use a shared ruleset if you enabled **Block unrecognized software until it is explicitly allowed**, and if computers are merely similar (but not identical). It will block all software on other computers that isn't in the first computer's ruleset. If those include critical files, it could break the OS. If that happens, you may be required to reinstall, revert to a backup, or use the OS recovery mode.

When you create a new shared ruleset using Deep Security 11.1 or newer, it can only contain hash-based rules (rules that compare only a file's hash and size). If you created a shared ruleset using Deep Security 11.0 or earlier, it contains file-based rules (rules that compare a file's name, path, size, and hash). Older shared rulesets will continue to use file-based rules until all agents using the shared ruleset are upgraded to Deep Security Agent 11.0 or newer. When all agents are version 11.0 or newer, the shared ruleset will be converted to use hash-based rules.

Warning: Don't create a new shared ruleset unless all agents using the ruleset are version 11.0 or newer. New shared rulesets are hash-based and are not compatible with 10.3 or earlier agents, which support only file-based rulesets.

Note: If there are multiple file-based rules for the same hash value, they are consolidated into one hash-based rule. If the rules being consolidated conflict with each other (one rule blocks the file and another allows it), the new hash-based rule will be an "allow" rule.

- **Global ruleset:** Like shared rulesets, global rulesets are distributed to agents by the manager (and also relays, if enabled). This increases network and disk space usage. However, because they are global, you don't need to spend time selecting them in each policy. Global rules aren't part of the rulesets you can see in Deep Security Manager. To view them, use the API. (See ["Use the Deep Security API to automate tasks" on page 417.](#)) Global rulesets can only contain block rules, not allow rules.

Global rulesets require Deep Security Agent 10.2 or newer. The manager will not send the global ruleset to older agents. Global rulesets take precedence over all other application control rules and are enforced on all computers where application control is enabled. The rules in global rulesets are based on a file's SHA-256 hash. Because a software file's hash

is unique, you can block specific software everywhere - regardless of file path, policy, or computer group, and regardless of whether application control has detected the software before.

Note: In a multi-tenant deployment, each tenant has a separate global ruleset. To block software for all tenants, create the same global rules for each tenant.

In this article:

- ["Create a shared ruleset" below](#)
- ["Change from shared to computer-specific allow and block rules" on the next page](#)
- ["Deploy application control shared rulesets via relays" on page 655](#)
- ["Considerations when using relays with share rulesets" on page 656](#)

Create a shared ruleset

You can use the API to create shared allow or block rules and apply the ruleset to other computers. This can be useful if you have many identical computers (such as a load balanced web server farm). **Shared rulesets should be applied only to computers with the exact same inventory.**

1. Use the API to build a computer's shared allow and block rules. For more information, see ["Use the Deep Security API to automate tasks" on page 417](#). If you want to examine the shared ruleset before you deploy it, see ["View and change application control rulesets" on page 644](#).
2. Go to **Computer or Policy editor**¹ > **Application Control**.
3. In the ruleset section, make sure **Inherit settings** is not selected and then select **Use a shared ruleset**. Indicate which shared rules to use.

Note: These settings are hidden until you use the API to create at least one shared

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

ruleset. If you haven't created any shared rulesets, or if you keep the default settings, each computer will keep its own allow and block rules locally. Changes to local rules don't affect other computers.

4. Click **Save**.

The next time that the Deep Security Agent on the computer connects with Deep Security Manager, the agent applies those rules.

If you see an error saying that the ruleset upload was not successful, verify that network devices between the agent and the manager or relay allow communications on the [heartbeat port](#) or [relay port numbers](#).

Change from shared to computer-specific allow and block rules

If the computer is currently using shared allow or block rules created via the [API](#), you can change it to use local rules. Application control will scan the file system for all currently installed software and create an initial ruleset for it, similarly to when you first enabled application control.

Warning: Before you start, verify that only good software is currently installed. Rebuilding the ruleset will allow all currently installed software, even if it is insecure or malware. If you are not sure what is installed, the safest approach is to make a clean install and then enable application control.

The steps below configure a computer's agent to use a local ruleset. If you want all computers to use local rules, edit the setting in the **Policies** tab instead.

1. Go to **Computer editor**¹ > **Application Control**.
2. In the ruleset section, deselect **Inherit settings** (if necessary), and then select **Use local ruleset initially based on installed software**.
3. Click **Save**.

To verify the change, the next time the agent and Deep Security Manager connect, look for [event log messages about building the application control ruleset](#).

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Deploy application control shared rulesets via relays


Each time you create an application control ruleset or change it, it must be distributed to all computers that use it. Shared rulesets are bigger than local rulesets. Shared rulesets are also often applied to many servers. If they all downloaded the ruleset directly from the manager at the same time, high load could cause slower performance. Global rulesets have the same considerations.

Using Deep Security Relays can solve this problem. (For information on configuring relays, see ["Distribute security and software updates with relays" on page 380.](#))

Steps vary depending whether or not you have a multi-tenant deployment.


Single tenant deployments

Go to **Administration > System Settings > Advanced** and then select **Serve application control rulesets from relays**.



Multi-tenant deployments

The primary tenant (t0) can't access other tenants' (tN) configurations, so t0 relays don't have tN application control rulesets. Other tenants (Tn) must create their own [relay group](#), then select **Serve application control rulesets from relays**.



Considerations when using relays with share rulesets

Before using relays, verify that they are compatible with your deployment. If the agent doesn't have any previously downloaded ruleset currently in effect, and **if it doesn't receive new application control rules, then the computer won't be protected by application control**. If application control ruleset download fails, a ruleset download failure event will be recorded on the manager and on the agent.

- If you are using a proxy to connect agents to a manager, you must use a relay.

Note: In Deep Security Agent 10.0 GM and earlier, agents didn't have support for connections through a proxy to relays. If a ruleset download fails due to a proxy, and if your agents require a proxy to access the relay or manager (including Deep Security as a Service), then you must either:

- [update agents' software](#), then [configure the proxy](#)
- bypass the proxy

- add a relay and then select **Serve application control rulesets from relays**

- If you are using shared or global rulesets, a relay can result in faster performance.
- If you are using local rulesets, a relay can cause slower performance,
- Do not use a relay with multi-tenant configurations when non-primary tenants (tN) use the default, primary (t0) relay group.

Protect against malware

The Deep Security anti-malware module provides agent computers with both real-time and on-demand protection against file-based threats, including malware, viruses, Trojans, and spyware. To identify threats, the anti-malware module checks files on the local hard drive against a comprehensive threat database. The anti-malware module also checks files for certain characteristics, such as compression and known exploit code.

Portions of the threat database are hosted on Trend Micro servers or stored locally as patterns. Deep Security Agents periodically download anti-malware patterns and updates to ensure protection against the latest threats.

Note: A newly installed Deep Security Agent cannot provide anti-malware protection until it has contacted an update server to download anti-malware patterns and updates. Ensure that your Deep Security Agents can communicate with a Deep Security Relay or the Trend Micro Update Server after installation.

The anti-malware module eliminates threats while minimizing the impact on system performance. The anti-malware module can clean, delete, or quarantine malicious files. It can also terminate processes and delete other system objects that are associated with identified threats.

To turn on and configure the anti-malware module, see ["Enable and configure anti-malware" on page 665](#).

- ["Types of malware scans" on the next page](#)
- ["Malware scan configurations" on page 660](#)

- ["Malware events" on page 660](#)
- ["SmartScan" on page 661](#)
- ["Predictive Machine Learning" on page 661](#)
- ["Connected Threat Defense" on page 662](#)
- ["Types of malware scans" below](#)

Types of malware scans

The anti-malware module performs several types of scans. See also ["Select the types of scans to perform" on page 666](#).

Real-time scan

Scan immediately each time a file is received, opened, downloaded, copied, or modified, Deep Security scans the file for security risks. If Deep Security detects no security risk, the file remains in its location and users can proceed to access the file. If Deep Security detects a security risk, it displays a notification message that shows the name of the infected file and the specific security risk.

Real-time scans are in effect continuously unless another time period is configured using the Schedule option.

Tip: You can configure real-time scanning to run when it will not have a large impact on performance; for example, when a file server is scheduled to back up files.

This scan can run on all platforms supported by the anti-malware module.

Manual scan

Runs a full system scan on all processes and files on a computer. The time required to complete a scan depends on the number of files to scan and the computer's hardware resources. A manual scan requires more time than a Quick Scan.

A manual scan executes when **Full Scan for Malware** is clicked.

This scan can be run on all platforms supported by the anti-malware module.

Scheduled scan

Runs automatically on the configured date and time. Use scheduled scan to automate routine scans and improve scan management efficiency.

A scheduled scan runs according to the date and time you specify when you create a **Scan computers for Malware task** using scheduled tasks (see ["Schedule Deep Security to perform tasks" on page 418](#)).

This scan can be run on all platforms supported by the anti-malware module.

Quick scan

Only scans a computer's critical system areas for currently active threats. A Quick Scan will look for currently active malware but it will not perform deep file scans to look for dormant or stored infected files. It is significantly faster than a Full Scan on larger drives. Quick scan is not configurable.

A Quick Scan runs when you click **Quick Scan for Malware**.

Note: Quick Scan can run only on Windows computers.

Scan objects and sequence

The following table lists the objects scanned during each type of scan and the sequence in which they are scanned.

Targets	Full Scan (Manual or Scheduled)	Quick Scan
Drivers	1	1
Trojan	2	2
Process Image	3	3
Memory	4	4
Boot Sector	5	-

Targets	Full Scan (Manual or Scheduled)	Quick Scan
Files	6	5
Spyware	7	6

Malware scan configurations

Malware scan configurations are sets of options that control the behavior of malware scans. When you configure anti-malware using a policy or for a specific computer, you select a malware scan configuration to use. You can create several malware scan configurations and use them with different policies when different groups of computers have different scan requirements.

Real-time, manual, and scheduled scans all use malware scan configurations. Deep Security provides a default malware scan configuration for each type of scan. These scan configurations are used in the default security policies. You can use the default scan configurations as-is, modify them, or create your own.

Note: Quick Scans are not configurable, and do not use malware scan configurations.

You can specify which files and directories are included or excluded during a scan and which actions are taken if malware is detected on a computer (for example, clean, quarantine, or delete).

For more information, see ["Configure malware scans" on page 668](#).

Malware events

When Deep Security detects malware it triggers an event that appears in the event log. From there you can see information about the event, or create an exception for the file in case of false positives. You can also restore quarantined files that are actually benign. (See ["Anti-malware events" on page 1251](#) and ["Handle malware" on page 712](#).)

SmartScan

Smart Scan uses threat signatures that are stored on Trend Micro servers and provides several benefits:

- Provides fast, cloud-based, real-time security status lookups
- Reduces the time required to deliver protection against emerging threats
- Reduces network bandwidth consumed during pattern updates (bulk of pattern definition updates only need to be delivered to the cloud, not to many computers)
- Reduces cost and overhead of corporate-wide pattern deployments
- Lowers kernel memory consumption on computers (consumption increases minimally over time)

When Smart Scan is enabled, Deep Security first scans locally for security risks. If Deep Security cannot assess the risk of the file during the scan, it will try to connect to a local Smart Scan server. If no local Smart Scan Server is detected, Deep Security will attempt to connect to the Trend Micro Global Smart Scan server. For more information on this feature, see ["Smart Protection in Deep Security" on page 709](#).

Predictive Machine Learning

Deep Security provides enhanced malware protection for unknown threats and zero-day attacks through Predictive Machine Learning. Trend Micro Predictive Machine Learning uses advanced machine learning technology to correlate threat information and perform in-depth file analysis to detect emerging security risks through digital DNA fingerprinting, API mapping, and other file features.

Predictive Machine Learning is effective in protecting against security breaches that result from targeted attacks using techniques such as phishing and spear phishing. In these cases, malware that is designed specifically to target your environment can bypass traditional malware scanning techniques.

During real-time scans, when Deep Security detects an unknown or low-prevalence file, Deep Security scans the file using the Advanced Threat Scan Engine (ATSE) to extract file features. It then sends the report to the Predictive Machine Learning engine on the Trend Micro Smart

Protection Network. Through the use of malware modeling, Predictive Machine Learning compares the sample to the malware model, assigns a probability score, and determines the probable malware type that the file contains.

If the file is identified as a threat, Deep Security quarantines the file to prevent the threat from continuing to spread across your network.

For information about using Predictive Machine Learning, see ["Detect emerging threats using Predictive Machine Learning" on page 690](#).

Connected Threat Defense

Connected Threat Defense provides enhanced malware protection for new and emerging threats by setting up a connection between Deep Security and Trend Micro's sandboxing technology, Deep Discovery Analyzer. For details, see ["Detect emerging threats using Connected Threat Defense" on page 692](#).

Malware types

The anti-malware module protects against many file-based threats. See also ["Scan for specific types of malware" on page 671](#) and ["Configure how to handle malware" on page 680](#)

Virus

Viruses infect files by inserting malicious code. Typically, when an infected file is opened the malicious code automatically runs and delivers a payload in addition to infecting other files. Below are some of the more common types of viruses:

- **COM and EXE infectors** infect DOS and Windows executable files, which typically have COM and EXE extensions.
- **Macro viruses** infect Microsoft Office files by inserting malicious macros.
- **Boot sector viruses** infect the section of hard disk drives that contain operating system startup instructions

The anti-malware module uses different technologies to identify and clean infected files. The most traditional method is to detect the actual malicious code that is used to infect files and strip

infected files of this code. Other methods include regulating changes to infectable files or backing up such files whenever suspicious modifications are applied to them.

Trojans

Some malware does not spread by injecting code into other files. Instead, it has other methods or effects:

- **Trojans:** Malware files that execute and infect the system when opened (like the mythological Trojan horse).
- **Backdoors:** Malicious applications that open port numbers to allow unauthorized remote users to access infected systems.
- **Worms:** Malware programs that use the network to propagate from system to system. Worms are known to propagate by taking advantage of social engineering through attractively packaged email messages, instant messages, or shared files. They are also known to copy themselves to accessible network shares and spread to other computers by exploiting vulnerabilities.
- **Network viruses:** Worms that are memory-only or packet-only programs (not file-based). Anti-malware is unable to detect or remove network viruses.
- **Rootkits:** File-based malware that manipulate calls to operating system components. Applications, including monitoring and security software, need to make such calls for very basic functions, such as listing files or identifying running processes. By manipulating these calls, rootkits are able to hide their presence or the presence of other malware.

Packer

Packers are compressed and encrypted executable programs. To evade detection, malware authors often pack existing malware under several layers of compression and encryption. Anti-malware checks executable files for compression patterns associated with malware.

Spyware/grayware

Spyware and grayware comprises applications and components that collect information to be transmitted to a separate system or collected by another application. Spyware/grayware

detections, although exhibiting potentially malicious behavior, may include applications used for legitimate purposes such as remote monitoring. Spyware/grayware applications that are inherently malicious, including those that are distributed through known malware channels, are typically detected as other Trojans.

Spyware and grayware applications are typically categorized as:

- **Spyware:** software installed on a computer to collect and transmit personal information.
- **Dialers:** malicious dialers are designed to connect through premium-rate numbers causing unexpected charges. Some dialers also transmit personal information and download malicious software.
- **Hacking tools:** programs or sets of programs designed to assist unauthorized access to computer systems.
- **Adware (advertising-supported software):** any software package that automatically plays, displays, or downloads advertising material.
- **Cookies:** text files stored by a Web browser. Cookies contain website-related data such as authentication information and site preferences. Cookies are not executable and cannot be infected; however, they can be used as spyware. Even cookies sent from legitimate websites can be used for malicious purposes.
- **Keyloggers:** software that logs user keystrokes to steal passwords and other private information. Some keyloggers transmit logs to remote systems.

What is grayware?

Although they exhibit what can be intrusive behavior, some spyware-like applications are considered legitimate. For example, some commercially available remote control and monitoring applications can track and collect system events and then send information about these events to another system. System administrators and other users may find themselves installing these legitimate applications. These applications are called "grayware".

To provide protection against the illegitimate use of grayware, the anti-malware module detects grayware but provides an option to "approve" detected applications and allow them to run.

Cookie

Cookies are text files stored by a web browser, transmitted back to the web server with each HTTP request. Cookies can contain authentication information, preferences, and (in the case of stored attacks from an infected server) SQL injection and XSS exploits.

Other threats

Other threats includes malware not categorized under any of the malware types. This category includes joke programs, which display false notifications or manipulate screen behavior but are generally harmless.

Possible malware

Possible malware is a file that appears suspicious but cannot be classified as a specific malware variant. When possible malware is detected, Trend Micro recommends that you contact your support provider for assistance in further analysis of the file. By default, these detections are logged and files are anonymously sent back to Trend Micro for analysis.

Enable and configure anti-malware

To use anti-malware, perform these basic steps:

1. ["Turn on the anti-malware module" on the next page.](#)
2. ["Select the types of scans to perform" on the next page.](#)
3. ["Configure scan exclusions" on page 667](#)
4. ["Ensure that Deep Security can keep up to date on the latest threats" on page 667.](#)

When you have completed these steps, review ["Configure malware scans" on page 668](#) and refine the anti-malware scan behavior.

Tip: For most anti-malware settings, you can either configure them for each individual computer or in a policy that applies to multiple computers (for example, to all Windows 2008 Servers). To make management easier, configure the settings in the policy (not individual computers) wherever possible. For more information, see ["Policies, inheritance, and overrides" on page 524.](#)

Tip: CPU usage and RAM usage varies by your anti-malware configuration. To optimize anti-malware performance on Deep Security Agent, see ["Performance tips for anti-malware" on page 683](#).

For an overview of the anti-malware feature, see ["Protect against malware" on page 657](#).

Turn on the anti-malware module

1. Go to **Policies**.
2. Double-click the policy for which you want to enable anti-malware.
3. Go to **Anti-Malware > General**.
4. From **Anti-Malware State**, select **On**.
5. Click **Save**.

Select the types of scans to perform

When anti-malware is turned on, Deep Security needs to know what type of scans it should perform (see ["Types of malware scans" on page 658](#)).

1. Go to **Policies**.
2. Double-click the policy to configure.
3. Click **Anti-Malware > General**.
4. Enable or disable each type of scan:
 - a. To perform the scan using default settings, select **Default**.
 - b. To perform the scan using a malware scan configuration that you can customize, select a malware scan configuration.
 - c. To disable the scan, for the malware scan configuration select **No Configuration**.
5. Click **Save**.

Tip: Trend Micro recommends that you configure Deep Security to perform weekly scheduled scans on all protected servers. You can do this using Scheduled Tasks. (See ["Schedule Deep Security to perform tasks" on page 418](#).)

Configure scan exclusions

To reduce scanning time and minimize the use of computing resources, you can configure Deep Security malware scans to exclude specific folders, files, and file types from all types of scans. You can also exclude process image files from real-time malware scans that are run on Windows servers.

All of these exclusions are specified by selecting exclusion lists on the **Exclusions** tab of the Malware Scan Configuration editor. See ["Specify the files to scan" on page 673](#).


Tip: If any performance-related issues are experienced when Deep Security anti-malware protection is enabled, you can use exclusions to help troubleshoot these issues by excluding specific folders or files from scanning.

Ensure that Deep Security can keep up to date on the latest threats

To remain effective against new viruses and exploits, Deep Security Agents need to be able to download the latest software and security update packages from Trend Micro or indirectly, from your own Relay. These packages contain threat definitions and patterns. Relay-enabled agents, organized into relay groups (also managed and configured by the Deep Security Manager) retrieve security updates from Trend Micro, and then distribute them to other agents and appliances.

1. Go to **Administration > System Settings > Updates**.
2. Configure Deep Security's ability to retrieve security updates from Trend Micro. Make sure you have at least one relay-enabled agent, and it is assigned to the appropriate agents and appliances.

To determine if a Deep Security Agent is a relay, next to a computer, click **Preview**.



3. Go to **Administration > Scheduled Tasks**.
4. Verify that there is a scheduled task to regularly download available updates for both security and software updates.

Configure malware scans

Malware scan configurations are reusable saved settings that you can apply when configuring anti-malware in a policy or for a computer. A malware scan configuration specifies what types of malware scanning Deep Security performs and which files it scans. Some policy properties also affect the behavior of malware scans.

- ["Create or edit a malware scan configuration" on the next page](#)
- ["Scan for specific types of malware" on page 671](#)
- ["Specify the files to scan" on page 673](#)
- ["Specify when real-time scans occur" on page 679](#)
- ["Configure how to handle malware" on page 680](#)

- ["Identify malware files by file hash digest" on page 682](#)
- ["Configure notifications on the computer" on page 683](#)

The Deep Security [Best Practice Guide](#) also provides several recommendations for configuration malware scans.

Tip: CPU usage and RAM usage varies by your anti-malware configuration. To optimize anti-malware performance on the Deep Security Agent, see ["Performance tips for anti-malware" on page 683](#).

Create or edit a malware scan configuration

Create or edit a malware scan configuration to control the behavior of a real-time, manual, or scheduled scan. (For more information, see ["Malware scan configurations" on page 660](#).) You can create multiple malware scan configurations as required.

- After you create a malware scan configuration, you can then associate it with a scan in a policy or computer (see ["Select the types of scans to perform" on page 666](#))
- When you edit a malware scan configuration that a policy or computer is using, the changes affect the scans that are associated with the configuration.

Tip: To create a malware scan configuration that is similar to an existing one, duplicate the existing configuration and then edit it.

You can create two types of malware scan configurations according to the type of scan it controls (see ["Types of malware scans" on page 658](#)):

- **Real-time scan configuration:** Controls real-time scans. Some actions such as **Deny Access** are only available to real-time scan configurations
- **Manual/scheduled scan configuration:** Controls either manual or scheduled scans. Some options such as **CPU Usage** are only available to manual/scheduled scan configurations

Deep Security provides a default malware scan configuration for each type of scan.

1. Go to **Policies > Common Objects > Other > Malware Scan Configurations**.
2. To create a scan configuration, click **New** and then click **New Real-Time Scan Configuration** or **New Manual/Scheduled Scan Configuration**.

- a. Type a name to identify the scan configuration. You see the name in a list when configuring malware scans in a policy.
- b. (Optional) Type a description that explains the use case for the configuration.
3. To view and edit an existing scan configuration, select it and click **Properties**.
4. To duplicate a scan configuration, select it and click **Duplicate**.

Tip: To see the policies and computers that are using a malware scan configuration, see the AssignedTo tab of the properties.

Test malware scans

Before continuing with further Anti-Malware configuration steps, test real-time and manual/scheduled scans to ensure they're working correctly.

Test real-time scans:

1. Make sure the real-time scan is enabled and that a configuration is selected.
2. Go to the [EICAR site](#) and download their anti-malware test file. This standardized file will test the real-time scan's anti-virus capabilities. The file should be quarantined.
3. On Deep Security Manager, go to **Events & Reports > Anti-Malware Events** to verify the record of the EICAR file detection. If the detection is recorded, the Anti-Malware real-time scans are working correctly.

Test manual/scheduled scans:

Note: Before you begin, make sure the real-time scan is disabled before testing manual/scheduled scans.

1. Go to **Administration**.
2. Click **Scheduled tasks > New**.
3. Select **Scan Computers for Malware** from the drop-down menu and select a frequency. Complete the scan configuration with your desired specifications.
4. Go to the [EICAR site](#) and download their anti-malware test file. This standardized file will test the manual/scheduled scan's anti-virus capabilities.
5. Select the scheduled scan and click **Run Task Now**. The test file should be quarantined.

6. On Deep Security Manager, go to **Events & Reports > Anti-Malware Events** to verify the record of the EICAR file detection. If the detection is recorded, the Anti-Malware manual/scheduled scans are working correctly.

Scan for specific types of malware

- ["Scan for spyware and grayware" below](#)
- ["Scan for compressed executable files \(real-time scans only\)" below](#)
- ["Scan process memory \(real-time scans only\)" on the next page](#)
- ["Scan compressed files" on the next page](#)
- ["Scan embedded Microsoft Office objects" on page 673](#)

See also:

- ["Enhanced anti-malware and ransomware scanning with behavior monitoring" on page 702](#)
- ["Detect emerging threats using Connected Threat Defense" on page 692](#)

Scan for spyware and grayware

When spyware and grayware protection is enabled, the spyware scan engine quarantines suspicious files when they are detected.

1. Open the properties of the malware scan configuration.
2. On the **General** tab, select **Enable spyware/grayware protection**.
3. Click **OK**.

To identify a specific file that the spyware scan engine should ignore, see ["Create anti-malware exceptions" on page 720](#).

Scan for compressed executable files (real-time scans only)

Viruses often use real-time compression algorithms to attempt to circumvent virus filtering. The IntelliTrap feature blocks real-time compressed executable files and pairing them with other malware characteristics.

Note: Because IntelliTrap identifies such files as security risks and may incorrectly block safe files, consider quarantining (not deleting or cleaning) files when you enable IntelliTrap. (See ["Configure how to handle malware" on page 680](#).) If users regularly exchange real-time compressed executable files, disable IntelliTrap. IntelliTrap uses the virus scan engine, IntelliTrap Pattern, and IntelliTrap Exception Pattern.

1. Open the properties of the malware scan configuration.
2. On the **General** tab, select **Enable IntelliTrap**.
3. Click **OK**.

Scan process memory (real-time scans only)

Monitor process memory in real time and perform additional checks with the Trend Micro Smart Protection network to determine whether a suspicious process is known to be malicious. If the process is malicious, Deep Security terminates the process. For more information, see ["Smart Protection in Deep Security" on page 709](#)

1. Open the properties of the malware scan configuration.
2. On the **General** tab, select **Scan process memory for malware**.
3. Click **OK**.

Scan compressed files

Extract compressed files and scan the contents for malware. When you enable the scan, you specify the maximum size and number of files to extract (large files can affect performance). You also specify the levels of compression to inspect so that you can scan compressed files that reside inside compressed files. Level 1 compression is a single compressed file. Compressed files inside that file are level two. You can scan a maximum of 6 compression levels, however higher levels can affect performance.

1. Open the properties of the malware scan configuration.
2. On the **Advanced** tab, select **Scan compressed files**.
3. Specify the maximum size of content files to extract, in MB, the levels of compression to scan, and the maximum number of files to extract.
4. Click **OK**.

Scan embedded Microsoft Office objects

Certain versions of Microsoft Office use Object Linking and Embedding (OLE) to insert files and other objects into Office files. These embedded objects can contain malicious code.

Specify the number of OLE layers to scan to detect objects that are embedded in other objects. To reduce the impact on performance, you can scan only a few layers of embedded objects within each file.

1. Open the properties of the malware scan configuration.
2. On the **Advanced** tab, select **Scan Embedded Microsoft Office Objects**.
3. Specify the number of OLE layers to scan.
4. Click **OK**.

Specify the files to scan

To specify the files to scan for malware, identify files and directories to include in the scan and then of those files and directories, identify exclusions. You can also scan network directories:

- ["Inclusions" below](#)
- ["Exclusions" on the next page](#)
- ["Scan a network directory \(real-time scan only\)" on page 679](#)

Inclusions

Specify the directories to scan as well as the files inside the directories to scan.

To identify directories to scan, you can specify all directories or a list of directories. The directory list uses patterns with a specific syntax to identify the directories to scan. (See ["Syntax for directory lists" on page 675](#).)

To identify the files to scan, use one of the following options:

- All files
- File types that are identified by IntelliScan. IntelliScan only scans file types that are vulnerable to infection, such as .zip or .exe. IntelliScan does not rely on file extensions to determine file type but instead reads the header and content of a file to determine whether

it should be scanned. Compared to scanning all files, Intelliscan reduces the number of files to scan and improves performance.

- Files that have a file name extension that is included in a specified list: The file extension list uses patterns with a specific syntax. (See ["Syntax of file extension lists" on page 679.](#))
1. Open the properties of the malware scan configuration.
 2. Click the **Inclusions** tab.
 3. To specify the directories to scan, select **All directories** or **Directory List**.
 4. If you selected Directory List, from the drop-down menu either select an existing list or select **New** to create one.
 5. To specify the files to scan, select either **All files**, **File types scanned by IntelliScan**, or **File Extension List**.
 6. If you selected File Extension List, from the drop-down menu either select an existing list or select **New** to create one.
 7. Click **OK**.

Exclusions

Exclude specific directories, files, and file extensions from being scanned. For real-time scans (except when performed by Deep Security Virtual Appliance), you can also exclude specific process image files from being scanned. For example, if you are creating a malware scan configuration for a Microsoft Exchange server, you should exclude the SMEX quarantine folder to avoid re-scanning files that have already been confirmed to be malware.

Note: If you choose to run malware scans on database servers used by Deep Security Manager, exclude the data directory. The Deep Security Manager captures and stores intrusion prevention data that might include viruses, which can trigger a quarantine by the Deep Security Agent, leading to database corruption.

To exclude directories, files, and process image files, you create a list that uses patterns to identify the item to exclude.

1. Open the properties of the malware scan configuration.
2. Click the **Exclusions** tab.

3. Specify the directories to exclude:
 - a. Select **Directory List**.
 - b. Select a directory list or select New to create one. (See ["Syntax for directory lists" below](#).)
 - c. If you created a directory list, select it in the directory list.
4. Similarly, specify the file list, file extension list, and process image file list to exclude. (See ["Syntax of file lists" on page 677](#), ["Syntax of file extension lists" on page 679](#), and ["Syntax of process image file lists \(real-time scans only\):" on page 679](#).)
5. Click **OK**.

Test file exclusions

Before continuing with further Anti-Malware configuration steps, test file exclusions to ensure they're working correctly:

Note: Before you begin, make sure the real-time scan is enabled and a configuration is selected.

1. Go to **Policies > Common Objects > Other > Malware Scan Configurations**.
2. Click **New > New Real-time Scan Configuration**.
3. Go to the **Exclusions** tab, and select **New** from the directory list.
4. Name the directory list.
5. Under **Directory(s)** specify the path of the directory you want to exclude from the scan. For example, `c:\Test Folder\`. Click **OK**.
6. Go to the **General** tab, name the manual scan, and click **OK**.
7. Go to the [EICAR site](#) and download their anti-malware test file. Save the file in the folder specified in the previous step. The file should be saved and undetected by the Anti-Malware module.

Syntax for directory lists

Note: Directory list items accept either forward slash "/" or backslash "\" to support both Windows and Linux conventions.

Exclusion	Format	Description	Examples
Directory	DIRECTORY\	Excludes all files in the specified directory and all files in all subdirectories.	<i>C:\Program Files\</i> Excludes all files in the "Program Files" directory

Exclusion	Format	Description	Examples
			and all subdirectories.
Directory with wildcard (*)	DIRECTORY*	Excludes all subdirectories except for the specified subdirectory and the files that it contains.	<p>C:\abc\1 Excludes all files in all subdirectories of "abc" but does not exclude the files in the "abc" directory.</p> <p>C:\abc\wx*z <i>Matches:</i> C:\abc\wxz\ C:\abc\wx123z\ <i>Does not match:</i> C:\abc\wxz C:\abc\wx123z</p> <p>C:\abc*wx\ <i>Matches:</i> C:\abc\wx\ C:\abc\123wx\ <i>Does not match:</i> C:\abc\wx C:\abc\123wx</p>
Directory with wildcard (*)	DIRECTORY*	Excludes any subdirectories with a matching name, but does not exclude the files in that directory and any subdirectories.	<p>C:\abc* <i>Matches:</i> C:\abc\ C:\abc\1 C:\abc\123 <i>Does not match:</i> C:\abc C:\abc\123\ C:\abc\123\456 C:\abx\ C:\xyz\</p> <p>C:\abc*wx <i>Matches:</i> C:\abc\wx C:\abc\123wx <i>Does not match:</i> C:\abc\wx\ C:\abc\123wx\ C:\abc\wx*z <i>Matches:</i> C:\abc\wxz C:\abc\wx123z</p>

Exclusion	Format	Description	Examples
			<p><i>Does not match:</i> C:\abc\wxz\ C:\abc\wx123z\ C:\abc\wx* <i>Matches:</i> C:\abc\wx C:\abc\wx\ C:\abc\wx12 C:\abc\wx12\345\ C:\abc\wxz\ <i>Does not match:</i> C:\abc\wx123z\</p>
Environment variable	\${ENV VAR}	Excludes all files and subdirectories defined by an environment variable. For a Virtual Appliance, the value pairs for the environment variable must be defined in Policy or Computer Editor > Settings > General > Environment Variable Overrides .	<p>\${windir} If the variable resolves to "c:\windows", excludes all the files in "c:\windows" and all its subdirectories.</p>
Comments	DIRECTORY #Comment	Adds a comment to your exclusion definitions.	c:\abc #Exclude the abc directory

Syntax of file lists

Exclusion	Format	Description	Example
File	FILE	Excludes all files with the specified file name regardless of its location or directory.	abc.doc Excludes all files named "abc.doc" in all directories. Does not exclude "abc.exe".
File path	FILEPATH	Excludes the specific file specified by the file path.	C:\Documents\abc.doc Excludes only the file named "abc.doc" in the "Documents" directory.
File path with wildcard (*)	FILEPATH	Excludes all the specific files specified by the file path.	C:\Documents\abc.co* (For Windows Agent platforms only) Excludes any file that has file name of "abc" and extension beginning with ".co" in the "Documents" directory.
File with wildcard (*)	FILE*	Excludes all files with a matching pattern in the file name.	abc*.exe Excludes any file that has prefix of "abc" and extension of ".exe". *.db <i>Matches:</i> 123.db abc.db <i>Does not match:</i> 123db

Exclusion	Format	Description	Example
			<p>123.abd cbc.dba</p> <p>*db <i>Matches:</i> 123.db 123db ac.db acdb db <i>Does not match:</i> db123</p> <p>wxy*.db <i>Matches:</i> wxy.db wxy123.db <i>Does not match:</i> wxydb</p>
File with wildcard (*)	FILE.EXT*	Excludes all files with a matching pattern in the file extension.	<p>abc.v* Excludes any file that has file name of "abc" and extension beginning with ".v".</p> <p>abc.*pp <i>Matches:</i> abc.pp abc.app <i>Does not match:</i> wxy.app</p> <p>abc.a*p <i>Matches:</i> abc.ap abc.a123p <i>Does not match:</i> abc.pp</p> <p>abc.* <i>Matches:</i> abc.123 abc.xyz <i>Does not match:</i> wxy.123</p>
File with wildcard (*)	FILE*.EXT*	Excludes all files with a matching pattern in the file name and in the extension.	<p>a*c.a*p <i>Matches:</i> ac.ap a123c.ap ac.a456p</p>

Exclusion	Format	Description	Example
			a123c.a456p <i>Does not match:</i> ad.aa
Environment variable	\${ENV VAR}	Excludes files specified by an environment variable with the format \${ENV VAR}. These can be defined or overridden using Policy or Computer Editor > Settings > General > Environment Variable Overrides .	<i>\${myDBFile}</i> Excludes the file "myDBFile".
Comments	FILEPATH #Comment	Adds a comment to your exclusion definitions.	C:\Documents\abc.doc #This is a comment

Syntax of file extension lists

Exclusion	Format	Description	Example
File Extension	EXT	Matches all files with a matching file extension.	<i>doc</i> Matches all files with a ".doc" extension in all directories.
Comments	EXT #Comment	Adds a comment to your exclusion definitions.	doc #This a comment

Syntax of process image file lists (real-time scans only):

Exclusion	Format	Description	Example
File path	FILEPATH	Excludes the specific Process Image file specified by the file path.	<i>C:\abc\file.exe</i> Excludes only the file named "file.exe" in the "abc" directory.

Scan a network directory (real-time scan only)

If you want to scan files and folders in network shares and mapped network drives that reside in a Network File System (NFS), Server Message Block (SMB) or Common Internet File System (CIFS), select **Enable Network Directory Scan**. This option is available only for real-time scans.

Note: Resources accessed in "~/gvfs" via GVFS, a virtual file system available for the GNOME desktop, will be treated as local resources, not network drives.

Specify when real-time scans occur

Choose between scanning files when they are opened for reading, when they are written to, or both.

1. Open the properties of the malware scan configuration.
2. On the **Advanced** tab, select one of the options for the **Real-Time Scan** property.

3. Click **OK**.

Configure how to handle malware

Configure how Deep Security behaves when malware is detected:

- ["Customize malware remedial actions" below](#)
- ["Generate alerts for malware detection" on page 682](#)
- ["Apply NSX security tags" on page 682](#)

Customize malware remedial actions

When Deep Security detects malware, it performs a remedial action to handle the file. There are five possible actions that Deep Security can take when it encounters malware:

- **Pass:** Allows full access to the infected file without doing anything to the file. (An Anti-Malware Event will still be recorded.)

Note: The remedial action **Pass** should never be used for a possible virus.

- **Clean:** Cleans a cleanable file before allowing full access to the file. (Not available for Possible Malware.)
- **Delete:** Deletes the infected file.
- **Deny Access:** This scan action can only be performed during Real-time scans. When Deep Security detects an attempt to open or execute an infected file, it immediately blocks the operation. If a malware scan configuration with the "Deny Access" option selected is applied during a Manual/Scheduled scan, a "Pass" action will be applied and an Anti-Malware Event will be recorded.
- **Quarantine:** Moves the file to the quarantine directory on the computer or Virtual Appliance. (Once quarantined, you can download the file to a location of your choice. See ["View and restore identified malware" on page 713](#) for more information.)

The default remediation actions in the malware scan configurations are appropriate for most circumstances. However, you can customize the actions to take when Deep Security detects malware. You can either use the action that ActiveAction determines, or specify the action for each type of vulnerability.

ActiveAction is a predefined group of cleanup actions that are optimized for each malware category. Trend Micro continually adjusts the actions in ActiveAction to ensure that individual detections are handled properly. (See ["ActiveAction actions" below](#).)

1. Open the properties of the malware scan configuration.
2. On the **Advanced** tab, for **Remediation Actions** select Custom.
3. Specify the action to take:
 - a. To let ActiveAction decide which action to take, select **Use action recommended by ActiveAction**.
 - b. To specify an action for each type of vulnerability, select **Use custom actions**, and then select the actions to use.
4. Specify the action to take for Possible Malware.
5. Click **OK**.

ActiveAction actions

The following table lists the actions that ActiveAction takes:

Malware Type	Action
"Virus" on page 662	Clean
"Trojans" on page 663	Quarantine
"Packer" on page 663	Quarantine
"Spyware/grayware" on page 663	Quarantine
CVE Exploit	Quarantine
Aggressive Detection Rule	Pass (This setting detects more issues but may also result in more false positives, so the default action is to raise an event.)
"Cookie" on page 665	Delete (Does not apply to real-time scans)
"Other threats" on page 665	Clean
"Possible malware" on page 665	ActiveAction

Note: When the agent downloads virus pattern updates from an ActiveUpdate server or relay, it may change its ActiveAction scan actions.

For information about CVE Exploit and Aggressive Detection Rule, see ["Create a malware scan configuration for use with Connected Threat Defense" on page 697](#).

Generate alerts for malware detection

When Deep Security detects malware, you can generate an alert.

1. Open the properties of the malware scan configuration.
2. On the **General** tab, for **Alert** select **Alert when this Malware Scan Configuration logs an event**.
3. Click **OK**.

Apply NSX security tags

Deep Security can apply **NSX Security Tags** to protected VMs upon detecting a malware threat. For details, see ["Configure Anti-Malware to apply NSX security tags" on page 315](#).

Identify malware files by file hash digest

Deep Security can calculate the hash value of a malware file and display it on the **Events & Reports > Events > Anti-Malware Events** page. Because a particular piece of malware can go by several different names, the hash value is useful because it uniquely identifies the malware. You can use the hash value when looking up information about the malware from other sources.

1. Open the policy or computer editor that you want to configure.
2. Click **Anti-Malware > Advanced**.
3. Under **File Hash Calculation**, clear the **Default** or **Inherited** check box. (**Default** is displayed for a root policy and **Inherited** is displayed for child policies).

Note: When **Inherited** is selected, the file hash settings are inherited from the current policy's parent policy.

Note: When **Default** is selected, Deep Security does not calculate any hash values.

4. Select the **Calculate hash values of all anti-malware events**.
5. By default, Deep Security will use produce SHA-1 hash values. If you want to produce additional hash values, you can select one or both of **MD5** and **SHA256**.
6. You can also change the maximum size of malware files that will have hash values calculated. The default is to skip files that are larger than 128MB, but you can change the value to anything between 64 and 512 MB.

Configure notifications on the computer

On Windows-based agents, you might occasionally see onscreen notification messages alerting you of Deep Security actions you must take that are related to the anti-malware and web reputation modules. For example, you might see the message, `A reboot is required for Anti-Malware cleanup task`. You must click OK on the dialog box to dismiss it.

If you don't want these notifications to appear:

1. Go to the **Computer or Policy editor**¹.
2. Click **Settings** on the left.
3. Under the **General** tab, scroll to the **Notifications** section.
4. Set **Suppress all pop-up notifications on host** to **Yes**. The messages still appear as alerts or events in Deep Security Manager. For more information about the notifier, see ["Deep Security Notifier" on page 514](#).

Performance tips for anti-malware

To improve system resources utilization on Deep Security Agent, you can optimize these performance-related settings according to best practices.

See also:

- ["Create anti-malware exceptions" on page 720](#)
- ["Identify malware files by file hash digest" on the previous page](#)
- ["Configure NSX security tags" on page 315](#)

Minimize disk usage

Reserve an appropriate amount of disk space for storing identified malware files. The space that you reserve applies globally to all computers: physical machines, virtual machines, and Deep

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Security Virtual Appliances. The setting can be overridden at the policy level and at the computer level.

Tip: Alerts are raised when there is not enough disk space to store an identified file.

1. Open the policy or computer editor that you want to configure.
2. Click **Anti-Malware > Advanced**.
3. Under **Identified Files**, clear **Default**.
4. Specify the disk space to use in the **Maximum disk space used to store identified files** box.
5. Click **Save**.

If you are using a Deep Security Virtual Appliance to protect virtual machines, all identified files from the protected VMs will be stored on the virtual appliance. As a result, you should increase the amount of disk space for identified files on the virtual appliance.

See also ["Virtual Appliance Scan Caching" on page 885](#)

Optimize CPU usage

- Exclude files from real-time scans if they are normally safe but have high I/O, such as databases, Microsoft Exchange quarantines, and network shares (on Windows, you can use [procmon](#) to find files with high I/O). See ["Exclusions" on page 674](#).
- Do not scan network directories. See ["Scan a network directory \(real-time scan only\)" on page 679](#)
- Do not use Smart Scan if the computer doesn't have reliable network connectivity to the Trend Micro Smart Protection Network or your Smart Protection Server. See ["Smart Protection in Deep Security" on page 709](#).
- Reduce the CPU impact of malware scans by setting CPU Usage to **Medium** (Recommended; pauses when overall CPU usage exceeds 50%,) or **Low** (Pauses when overall CPU usage exceeds 20%).
 - a. Open the properties of the malware scan configuration.
 - b. On the **Advanced** tab, select the **CPU Usage** during which scans run.
 - c. Click **OK**.

- Create a scheduled task to run scans at a time when CPU resources are more readily available. See ["Schedule Deep Security to perform tasks" on page 418](#).
- In VM Scan Cache, select a Real-Time Scan Cache Configuration. If scans are not frequent, increase the Expiry Time (avoid repeated scans). See ["Virtual Appliance Scan Caching" on page 885](#).
- Use agentless deployments so that CPU usage is in one centralized virtual appliance, not on every computer. See ["Choose agentless vs. combined mode protection" on page 133](#)
- Reduce or keep small default values for the maximum file size to scan, maximum levels of compression from which to extract files, maximum size of individual extracted files, maximum number of files to extract, and OLE Layers to scan. See ["Scan for specific types of malware" on page 671](#).

Warning: Most malware is small, and nested compression indicates malware. But if you don't scan large files, there is a small risk that anti-malware won't detect some malware. You can mitigate this risk with other features such as integrity monitoring. See

- Use multi-threaded processing for manual and scheduled scans (real-time scans use multi-threaded processing by default). Multi-threaded processing is effective only on systems that support this capability. To apply the setting, after you have enabled it, restart the computer.

Note: Do not enable multi-threaded processing under the following circumstances:

- Resources are limited (for example, CPU-bound tasks)
- Resources should be held by only one operator at a time (for example, IO-bound tasks)

- a. Click **Policies**.
- b. Double-click to open the policy where you want to enable multi-threaded processing.
- c. Click **Anti-Malware > Advanced**.
- d. In the Resource Allocation for Malware Scans section, select **Yes**.
- e. Restart the computers on which you enabled multi-threaded processing for the setting to take effect.

Note: Multi-threaded processing may reduce the number of CPU cores available at a given time to the computer's other processes.

Optimize RAM usage

- Reduce or keep small default values for the maximum file size to scan, maximum levels of compression from which to extract files, maximum size of individual extracted files, maximum number of files to extract, and OLE Layers to scan. See ["Scan for specific types of malware" on page 671](#).

Warning: Most malware is small, and nested compression indicates malware. But if you don't scan large files, there is a small risk that anti-malware won't detect some malware. You can mitigate this risk with other features such as integrity monitoring. See ["Set up integrity monitoring" on page 824](#)

- Use agentless deployments (RAM usage is in one centralized virtual appliance, not every computer). See ["Choose agentless vs. combined mode protection" on page 133](#).

Disable Windows Defender after installing Deep Security anti-malware on Windows Server 2016

When you install the Anti-Malware module for a Deep Security 10.0 Agent on Windows Server 2016, the agent will automatically disable Windows Defender, but not all of the Windows processes related to the Windows Defender service. To do so, you need to reboot Windows Server 2016 after the Deep Security Anti-Malware module installation finishes. The Deep Security Agent will open a Windows message to let you know when to reboot.

Note: The agent will report a computer warning event ("Computer reboot is required for Anti-Malware protection") to the Deep Security Manager. This event will remain indefinitely, and will need to be manually dismissed by an administrator.

Installing the Anti-Malware module when Windows Defender is already disabled

If you disable Windows Defender before installing the Deep Security Anti-Malware module, the Deep Security Agent will not open a Windows reboot message. However, you still need to reboot Windows Server 2016 to ensure that Deep Security Anti-malware functions correctly.

Virtual Appliance Scan Caching

Scan Caching is used by the Virtual Appliance to maximize the efficiency of Anti-Malware and Integrity Monitoring Scans of virtual machines. Scan Caching improves the efficiency of scans by eliminating the unnecessary scanning of identical content across multiple VMs in large VMware deployments. A Scan Cache contains lists of files and other scan targets that have been scanned by a Deep Security protection module. If a scan target on a virtual machine is determined to be identical to a target that has already been scanned, the Virtual Appliance will not scan the target a second time. Attributes used to determine whether entities are identical are creation time, modification time, file size, and file name. In the case of Real-time Scan Caching, Deep Security will read partial content of files to determine if two files are identical. There is an option setting to use a file's Update Sequence Number (USN, Windows only) but its use should be limited to cloned virtual machines.

Scan Caching benefits **Integrity Monitoring** by sharing Integrity Monitoring scan results among cloned or similar virtual machines.

Scan Caching benefits **Manual Malware Scans** of cloned or similar virtual machines by increasing the speed up subsequent scans.

Scan Caching benefits **Real-Time Malware Scanning** by speeding up boot process scans and application access scans on cloned or similar virtual machines.

Scan Cache Configurations

A Scan Cache Configuration is a collection of settings that determines Expiry Time, the use of Update Sequence Numbers (USNs), files to exclude, and files to include.

Note: Virtual machines that use the same Scan Cache Configuration also share the same Scan Cache.

You can see the list of existing Scan Cache Configurations by going **Administration > System Settings > Advanced>Scan Cache Configurations** and clicking **View Scan Cache Configurations** . Deep Security comes with several preconfigured default Scan Cache Configurations. These are implemented automatically by the Virtual Appliance depending the properties of the virtual machines being protected and the types of scan being performed.

Expiry Time determines the lifetime of individual entries in a Scan Cache. The default recommended settings are one day for Manual (on-demand) or Scheduled Malware Scans, 15 mins for Real-Time Malware Scans, and one day for Integrity Monitoring Scans.

Use USN (Windows only) specifies whether to make use of Windows NTFS Update Sequence Numbers, which is a 64-bit number used to record changes to an individual file. This option should only be set for cloned VMs.

Files Included and **Files Excluded** are regular expression patterns and lists of files to be included in or excluded from the Scan Cache. Files to be scanned are matched against the include list first.

Individual files and folders can be identified by name or you can use wildcards ("*" and "?") to refer to multiple files and locations with a single expression. (Use "*" to represent any zero or more characters, and use question mark "?" to represent any single character.)

Note: The include and exclude lists only determine whether the scan of the file will take advantage of Scan Caching. The lists will not prevent a file from being scanned in the traditional way.

Malware Scan Cache Configuration

To select which Scan Cache Configuration is used by a virtual machine, open the **Computer or Policy editor**¹ and go to **Anti-Malware > Advanced > VM Scan Cache**. You can select which Scan Cache Configuration is used for Real-Time Malware Scans and which Scan Cache Configuration is used for manual and scheduled scans.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Integrity Monitoring Scan Cache Configuration

To select which Scan Cache Configuration is used by a virtual machine, open the **Computer or Policy editor**¹ and go to **Integrity Monitoring > Advanced > VM Scan Cache**.

Scan Cache Settings

Scan Cache Settings are not included in a Scan Cache Configuration because they determine how the Virtual Appliance manages Scan Caches rather than how Scan Caching is carried out. Scan Cache settings are controlled at the Policy level. You can find the Scan cache settings by opening a **Policy editor**² and going to the **Settings > General > Virtual Appliance Scans** area.

Max Concurrent Scans determines the number of scans that the Virtual Appliance performs at the same time. The recommended number is five. If you increase this number beyond 10, scan performance may degrade. Scan requests are queued by the virtual appliance and carried out in the order in which they arrive. This setting applies to manual and scheduled scans.

Max On-Demand Malware Scan Cache Entries determines, for manual or scheduled malware scans, the maximum number of records that identify and describe a file or other type of scannable content to keep. One million entries use approximately 100 MB of memory.

Max Malware Real-Time Scan Cache Entries determines, for real-time malware scans, the maximum number of records that identify and describe a file or other type of scannable content to keep. One million entries use approximately 100MB of memory.

Max Integrity Monitoring Scan Cache Entries determines the maximum number of entities included in the baseline data for integrity monitoring. Two hundred thousand entities use approximately 100MB of memory.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

When to change the default configuration

Scan caching is designed to avoid scanning identical files twice. Deep Security does not examine the entire contents of all files to determine if files are identical. Although when configured to do so, Deep Security can check the USN value of a file, and during Real-time Scans it will read partial content of files, it generally examines file attributes to determine if files are identical. It would be difficult but not impossible for some malware to make changes to a file and then restore those files attributes to what they were before the file was modified.

Deep Security limits this potential vulnerability by establishing short default cache expiry times. To strengthen the security you can use shorter expiry times on cache and you can use USN but doing so may reduce the performance benefit or require a larger cache setting. For the strongest security for VMs that you want to keep separate and never share scan results you can create dedicated policies for these VMs kind of like keeping them in separate zones. This might be appropriate if you have different departments or organizations sharing the same infrastructure. (In a multi-tenant Deep Security Manager, this is automatically enforced for each tenant.)

If you have a very large number of guest VMs per ESXi host (for example, a VDI environment), then you should monitor your disk I/O and CPU usage during scanning. If scanning takes too long, then you may need to increase the size of the cache or adjust the Scan Cache Settings until you get better performance. If you need to increase cache size, then you may need to adjust Deep Security Virtual Appliance system memory too.

Detect emerging threats using Predictive Machine Learning

Use Predictive Machine Learning to detect unknown or low-prevalence malware. (For more information, see ["Predictive Machine Learning" on page 661](#).)

Predictive Machine Learning uses the Advanced Threat Scan Engine (ATSE) to extract file features and sends the report to the Predictive Machine Learning engine on the Trend Micro Smart Protection Network. To enable Predictive Machine Learning, perform the following:

1. ["Ensure Internet connectivity" on the next page](#)
2. ["Enable Predictive Machine Learning" on the next page](#)

As with all detected malware, Predictive Machine Learning logs an event when it detects malware. (See ["Events in Deep Security" on page 1088](#).) You can also create an exception for any false positives. (See ["Create anti-malware exceptions" on page 720](#).)

Ensure Internet connectivity

Predictive Machine Learning requires access to the Global Census Service, Good File Reputation Service, and Predictive Machine Learning Service. These services are hosted in the Trend Micro Smart Protection Network. If your Deep Security Agents or Virtual Appliance cannot access the Internet directly, see ["Configure agents that have no Internet access" on page 354](#) for workarounds.

Enable Predictive Machine Learning

Predictive Machine Learning is configured as part of a real-time scan configuration that is applied to a policy or individual computer. (See ["Configure malware scans" on page 668](#).) After you configure the scan configuration, apply it to a policy or computer.

Note: Predictive Machine Learning protects only the files and directories that real-time scan is configured to scan. See ["Specify the files to scan" on page 673](#).

These settings can only be applied to the real-time scan configuration for Windows computers.

1. Go to **Policies > Common Objects > Other > Malware Scan Configurations**.
2. Select the real-time scan configuration to configure and click **Details**.

You can also create a new real-time scan configuration if desired.

3. On the **General** tab, under **Predictive Machine Learning**, select **Enable Predictive Machine Learning**.
4. Click **OK**.
5. Open the policy or computer editor to which you want to apply the scan configuration and go to **Anti-Malware > General**.
6. Ensure that **Anti-Malware State** is **On** or **Inherited (On)**.
7. In the **Real-Time Scan** section, select the malware scan configuration.
8. Click **Save**.

Detect emerging threats using Connected Threat Defense

In the modern data center, more and more security breaches are a result of targeted attacks using techniques such as phishing and spear-phishing. In these cases, malware writers can bypass traditional malware scanners by creating malware specifically targeted for your environment. Deep Security provides enhanced malware protection for new and emerging threats through its Connected Threat Defense feature.

Note: Connected Threat Defense is not available when FIPS mode is enabled. See ["FIPS 140-2 support" on page 1381](#).

In this article:

- ["How does Connected Threat Defense work?" below](#)
- ["Check the Connected Threat Defense prerequisites" on the next page](#)
- ["Set up the connection to Deep Discovery Analyzer" on page 694](#)
- ["Set up the connection to Trend Micro Control Manager" on page 695](#)
- ["Create a malware scan configuration for use with Connected Threat Defense" on page 697](#)
- ["Enable Connected Threat Defense for your computers" on page 698](#)
- ["Manually submit a file to Deep Discovery for analysis" on page 699](#)
- ["Allow a file that has raised a false alarm" on page 699](#)
- ["Configure the scan action for a suspicious file" on page 699](#)
- ["Update the suspicious objects list in Deep Security" on page 700](#)
- ["Configure Connected Threat Defense in a multi-tenant environment" on page 700](#)
- ["Supported file types" on page 701](#)

For an overview of the anti-malware module, see ["Protect against malware" on page 657](#).

How does Connected Threat Defense work?

1. When all of the components are configured properly, the Deep Security Agent uses heuristic detection to analyze files on the protected computer and determines whether they

are suspicious.

2. Optionally, you can manually or automatically send suspicious files from Deep Security to Deep Discovery Analyzer, which executes and observes the suspicious file in a sandbox (a secure, isolated virtual environment).
3. Deep Security Manager gets the sandbox analysis results from Deep Discovery Analyzer.

Note: The sandbox analysis report doesn't provide protection; it simply provides information on the Deep Discovery analysis. For complete protection, this feature requires a connection to the Trend Micro Control Manager. The report is retrieved from Deep Discovery Analyzer every 15 minutes.

4. Deep Discovery Analyzer pushes the analysis results to Trend Micro Control Manager, where an action can be specified for the file based on the analysis. Once the action is specified, a list of emerging threats called a suspicious object list is created or updated. Other Trend Micro products, such as Deep Discovery Inspector or Deep Discovery Email Inspector, may also be connected to Trend Micro Control Manager and able to update the list.
5. Optionally, you can configure Deep Security Manager to receive the list of suspicious objects from Trend Micro Control Manager and send the list of suspicious objects to Deep Security Agents.

Check the Connected Threat Defense prerequisites

Before connecting Deep Security to Deep Discovery, check that your environment meets these requirements:

- Deep Security Manager is installed and configured with Deep Security Agents, Deep Security Agents protecting computers, or both.

Optional:

- Deep Discovery Analyzer 5.5 is installed and the sandbox virtual machines are provisioned.
- Trend Micro Control Manager 6.0 SP3 Patch 2 or later is installed.
- Deep Discovery Analyzer has been added to the Trend Micro Control Manager Managed Servers. See the Trend Micro Control Manager documentation for details.


Note: To use Connected Threat Defense with the Deep Security Virtual Appliance, you must be using VMware NSX 6.x.

Set up the connection to Deep Discovery Analyzer

If you want Deep Security Manager to send suspicious files to Deep Discovery Analyzer for analysis, you'll need to set up a connection.

If Control Manager is already managing Deep Security:

1. In Deep Security Manager, go to **Administration > System Settings > Connected Threat Defense**.
2. Select **Enable submission of suspicious file to Deep Discovery Analyzer**.




3. If you want Deep Security Manager to automatically submit files to Deep Discovery Analyzer, select **Enable automatic file submission**.

Note: Automatic Submission to Deep Discovery Analyzer occurs every 15 minutes and will submit a maximum of 100 files per submission

4. Select **Use Deep Discovery Analyzer associated with the Control Manager that Deep Security is registered with**.
5. Click **Test Connection**. If you get an error saying that Deep Security is unable to connect due to a missing or invalid certificate, click **Add/Update Certificate** to update to the correct Deep Discovery Analyzer certificate.
6. Click **Save**.

If Control Manager is not yet managing Deep Security:

1. In Deep Discovery Analyzer, go to **Help > About** and note the **Service URL** and **API key**. You will need these values later, so copy them into a text file temporarily.
2. In Deep Security Manager, go to **Administration > System Settings > Connected Threat Defense**.
3. Select **Enable submission of suspicious file to Deep Discovery Analyzer**.



4. If you want Deep Security Manager to automatically submit files to Deep Discovery Analyzer, select **Enable automatic file submission**.

Note: Automatic Submission to Deep Discovery Analyzer occurs every 15 minutes and will submit a maximum of 100 files per submission

5. Select **Manually select a Deep Discovery Analyzer server**, and enter the **Server URL** and **API key** that you found in step 1.
6. Click **Test Connection**. If you get an error saying that Deep Security is unable to connect due to a missing or invalid certificate, click **Add/Update Certificate** to update to the correct Deep Discovery Analyzer certificate.
7. Click **Save**.


Set up the connection to Trend Micro Control Manager

When you configure these settings, Deep Security Manager will be able to retrieve the suspected object list from Trend Micro Control Manager, share it with protected computers, and compare local objects against the Control Manager's Suspicious Object List.

If Control Manager is already managing Deep Security:

Trend Micro Deep Security On-Premise 11.3


1. In Deep Security Manager, go to **Administration > System Settings > Connected Threat Defense**.
2. Select **Compare objects against Suspicious Object List**.



3. If Trend Micro Control Manager is already managing Deep Security, select **Use the Control Manager that Deep Security is registered with**.
4. Click **Test Connection**. If you get an error saying that Deep Security is unable to connect due to a missing or invalid certificate, click **Add/Update Certificate** to update to the correct Trend Micro Control Manager certificate.
5. Click **Save**.

If Control Manager is not yet managing Deep Security:

1. In Trend Micro Control Manager, go to **Administration > Suspicious Objects > Distribution Settings**. Note the **Service URL** and **API key**. You will need these values later, so copy them into a text file temporarily.



2. In Deep Security Manager, go to **Administration > System Settings > Connected Threat Defense**.
3. Select **Compare objects against Suspicious Object List**.
4. Select **Manually select a Control Manager server** and enter the **Server URL** and **API key** that you found in step 1.
5. Click **Test Connection**. If you get an error saying that Deep Security is unable to connect due to a missing or invalid certificate, click **Add/Update Certificate** to update to the correct Trend Micro Control Manager certificate.
6. Click **Save**.

Create a malware scan configuration for use with Connected Threat Defense

The following configuration allows Deep Security to detect suspicious files, back up the suspicious files, and automatically send them to Deep Discovery Analyzer for further analysis.

1. In Deep Security Manager, go to **Policies > Common Objects > Other > Malware Scan Configurations**.
2. Create a new scan configuration or edit an existing configuration.
3. On the **General** tab, under **Document Exploit Protection**, select **Scan documents for exploits** and select one of these options:
 - **Scan for exploits against known critical vulnerabilities only:** Only detects known critical vulnerabilities. The CVE Exploit vulnerability type is associated with this option

(See ["Customize malware remedial actions" on page 680.](#))

- **Scan for exploits against known critical vulnerabilities and aggressive detection of unknown suspicious exploits:** Detects more issues but may also result in more false positives. If you want to detect suspicious files and submit them to Deep Discovery Analyzer, you must select this option. The Aggressive Detection Rule vulnerability type is associated with this option. (See ["Customize malware remedial actions" on page 680.](#))

4. Configure the other malware scan settings as described in ["Configure malware scans" on page 668.](#)

Enable Connected Threat Defense for your computers

You can enable Connected Threat Defense in policies or for individual computers.

1. In the **Computer or Policy editor**¹, go to **Anti-Malware > General**.
2. Ensure that the **Anti-Malware State** is **On** or **Inherited (On)**.
3. The **General** tab contains sections for **Real-Time Scan**, **Manual Scan**, and **Scheduled Scan**. (For information on the different types of scans, see ["Enable and configure anti-malware" on page 665.](#)) In the appropriate sections, use the **Malware Scan Configuration** list to select the scan configuration that you created above.
4. Go to the **Connected Threat Defense** tab and adjust these settings as required:
 - If you want Deep Security to send suspicious files to Deep Discovery Analyzer, set the option under **Sandbox Analysis** to **Yes** or **Inherited (Yes)**.
 - If you have set up a connection between Deep Security and Trend Micro Control Manager and you want to use the suspicious object list from the Control Manager to detect malicious files, set **Use Control Manager's Suspicious Object List** (under **Suspicious Objects List**) to **Yes** or **Inherited (Yes)**.
5. Click **Save**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Manually submit a file to Deep Discovery for analysis

You can manually submit files that appear on the **Events & Reports > Events > Anti-Malware Events > Identified Files** page.

1. Select the file that you want to submit and click the **Analyze** button.
2. Follow the steps in the wizard that appears.
3. After the file is submitted, you can check the progress of its analysis in the **Submission Status** column on the Identified Files page.
4. When the analysis is finished, the **Submission Status** column will display "Results Ready". You can click the **Results Ready** link to see details.

Allow a file that has raised a false alarm

If a file is identified as malware on the **Events & Reports > Events > Anti-Malware Events > Identified Files** page but you know it's not malware, you can add it to the **Document Exploit Protection Rule Exceptions** list on the **Anti-Malware > Advanced** tab of the **Computer or Policy editor**¹.

To allow the file, right-click it, click **Allow**, and follow the steps in the wizard that appears.

Configure the scan action for a suspicious file

You can view the suspicious objects list in the Trend Micro Control Manager console and configure the action (log, block, or quarantine) that should be taken when a suspicious object is found. (See [Suspicious Object Management and Handling Process](#) for details on configuring the actions.) If you have configured Deep Security Manager to obtain the suspicious object list from Control Manager, Deep Security will perform the specified action when it finds the suspected object.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Note: Deep Security supports file suspicious objects. It also supports URL suspicious objects if the web reputation protection module is configured to use the Trend Micro Smart Protection Server. Deep Security does not support IP and domain suspicious objects.

Note: Trend Micro Control Manager 6.0 SP3 User-Defined Objects do not work with Deep Security. Virtual Analyzer objects for files do work with Deep Security.

Update the suspicious objects list in Deep Security

After the analysis of a suspicious object has been completed and the action for the file has been set in Trend Micro Control Manager, Deep Security can use the Suspicious Object list from Trend Micro Control Manager to protect your computers. To manually update the suspicious file list in Deep Security Manager, go to **Administration > Updates > Security** and use the controls in the Suspicious Object List Updates column to get the latest list and send it to your protected computers. You can also create a scheduled task that regularly checks for an updated list (see ["Schedule Deep Security to perform tasks" on page 418](#)).

Note: In Trend Micro Control Manager, the default suspicious object setting is "Log". You may want to consider changing the default setting to "Quarantine" or "Block".

Once the suspicious object list has been updated in Deep Security and the computer policies have been updated with the action specified, the Deep Security Agent will then check the affected computers and use this action any time this file is encountered again on a protected computer.

Configure Connected Threat Defense in a multi-tenant environment

In a multi-tenant environment, the primary tenant (t0) can choose whether to share their Deep Discovery Analyzer and Trend Micro Control Manager settings with their tenants. The setting that controls this behavior is **Administration > System Settings > Tenants > Allow Tenants to use Primary Tenant's Trend Micro Control Manager and Deep Discovery Analyzer Server settings**:

- When the setting is enabled and a tenant goes to **Administration > System Settings > Connected Threat Defense**, they see an additional **Use default server settings** check box.

When this check box is selected, the tenant uses the primary tenant's settings. When **Use default server settings** is not selected, the tenant can configure their own Connected Threat Defense settings.

- When the setting is not enabled, tenants must use their own Trend Micro Control Manager and Deep Discovery Analyzer if they want to use Connected Threat Defense.

Supported file types

Deep Security can send these file types to Deep Discovery Analyzer:

- doc - Microsoft Word document
- docx - Microsoft Office Word 2007 document
- gul - JungUm Global document
- hwp - Hancom Hangul Word Processor (HWP) document
- hwpX - Hancom Hangul Word Processor 2014 (HWPX) document
- jar - Java Applet Java application
- js - JavaScript file
- jse - JavaScript encoded script file
- jtd - JustSystems Ichitaro document
- Ink - Microsoft Windows Shell Binary Link shortcut
- mov - Apple QuickTime media
- pdf - Adobe Portable Document Format (PDF)
- ppt - Microsoft Powerpoint presentation
- pptx - Microsoft Office PowerPoint 2007 Presentation
- ps1 - Microsoft Windows PowerShell script file
- rtf - Microsoft Rich Text Format (RTF) document
- swf - Adobe Shockwave Flash file
- vbe - Visual Basic encoded script file
- vbs - Visual Basic script file
- xls - Microsoft Excel spreadsheet

- [xlsx - Microsoft Office Excel 2007 Spreadsheet](#)
- [xml - Microsoft Office 2003 XML file](#)

Enhanced anti-malware and ransomware scanning with behavior monitoring

Deep Security provides security settings that you can apply to Windows machines that are protected by a Deep Security Agent to enhance your malware and ransomware detection and clean rate. These settings enable you to go beyond malware pattern matching and identify suspicious files that could potentially contain emerging malware that hasn't yet been added to the anti-malware patterns (known as a zero-day attack).

In this article:

- ["How does enhanced scanning protect you?" below](#)
- ["How to enable enhanced scanning" on the next page](#)
- ["What happens when enhanced scanning finds a problem?" on page 704](#)
- ["What if my agents can't connect to the Internet directly?" on page 709](#)

For an overview of the anti-malware module, see ["Protect against malware" on page 657](#).

How does enhanced scanning protect you?

Threat detection: To avoid detection, some types of malware attempt to modify system files or files related to known installed software. These types of changes often go unnoticed because the malware takes the place of legitimate files. Deep Security can monitor system files and installed software for unauthorized changes to detect and prevent these changes from occurring.

Anti-exploit: Malware writers can use malicious code to hook in to user mode processes in order to gain privileged access to trusted processes and to hide the malicious activity. Malware writers inject code into user processes through DLL injection, which calls an API with escalated privilege. They can also trigger an attack on a software exploit by feeding a malicious payload to trigger code execution in memory. In Deep Security, the anti-exploit functionality monitors for processes that may be performing actions that are not typically performed by a given process.

Using a number of mechanisms, including Data Execution Prevention (DEP), Structured Exception Handling Overwrite Protection (SEHOP), and heap spray prevention, Deep Security can determine whether a process has been compromised and then terminate the process to prevent further infection.

Extended ransomware protection: Recently, ransomware has become more sophisticated and targeted. Most organizations have a security policy that includes anti-malware protection on their endpoints, which offers a level of protection against known ransomware variants; however, it may not be sufficient to detect and prevent an outbreak for new variants. The ransomware protection offered by Deep Security can protect documents against unauthorized encryption or modification. Deep Security has also incorporated a data recovery engine that can optionally create copies of files being encrypted to offer users an added chance of recovering files that may have been encrypted by a ransomware process.

How to enable enhanced scanning

Enhanced scanning is configured as part of the anti-malware settings that are applied to a policy or individual computer. For general information on configuring anti-malware protection, see ["Enable and configure anti-malware" on page 665](#).

Note: These settings can only be applied to Windows machines that are protected by a Deep Security Agent.

Warning: Enhanced scanning may have a performance impact on agent computers running applications with heavy loads. We recommend reviewing the ["Performance tips for anti-malware" on page 683](#) before deploying Deep Security Agents with enhanced scanning enabled.

The first step is to enable enhanced scanning in a real-time malware scan configuration:

1. In Deep Security Manager, go to **Policies > Common Objects > Other > Malware Scan Configurations**.
2. Double-click an existing real-time scan configuration to edit it (for details on malware scan configurations, see ["Configure malware scans" on page 668](#)).

3. On the **General** tab, select these options:
 - **Detect suspicious activity and unauthorized changes (incl. ransomware)**: Enables the threat detection, anti-exploit, and ransomware detection features that are described above.
 - **Back up and restore ransomware-encrypted files**: When this option is selected, Deep Security will create backup copies of files that are being encrypted, in case they are being encrypted by a ransomware process.
4. Click **OK**.

Note: By default, real-time scans are set to scan all directories. If you change the scan settings to scan a directory list, the enhanced scanning may not work as expected. For example, if you set **Directories to scan** to scan "Folder1" and ransomware occurs in Folder1, it may not be detected if the encryption associated with the ransomware happens to files outside of Folder1.

Next, apply the malware scan configuration to a policy or an individual computer:

1. In the **Computer or Policy editor**¹, go to **Anti-Malware > General**.
2. Ensure that the **Anti-Malware State** is **On** or **Inherited (On)**.
3. The General tab contains sections for **Real-Time Scan**, **Manual Scan**, and **Scheduled Scan**. In the appropriate sections, use the **Malware Scan Configuration** list to select the scan configuration that you created above.
4. Click **Save**.

What happens when enhanced scanning finds a problem?


When Deep Security discovers activity or files that match the enhanced scan settings you have enabled, it will log an event (go to **Events & Reports > Events > Anti-Malware Events** to see a list of events). The event will be identified as "Suspicious activity" or "Unauthorized change" in the **Major Virus Type** column and details will be displayed in the **Target(s)** and **TargetType** columns.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

Deep Security performs many types of checks related to the enhanced scan settings, and the actions that it takes depend on the type of check that finds an issue. Deep Security may "Deny Access", "Terminate", or "Clean" a suspicious object. These actions are determined by Deep Security and are not configurable, with the exception of the "Clean" action:

- **Deny Access:** When Deep Security detects an attempt to open or execute a suspicious file, it immediately blocks the operation and records an anti-malware event.
- **Terminate:** Deep Security terminates the process that performed the suspicious operation and records an anti-malware event.
- **Clean:** Deep Security checks the Malware Scan Configuration and performs the action specified for Trojans on the Actions tab. One or more additional events will be generated relating to the action performed on the Trojan files.



Double-click an event to see details:

General

Tags

General Information

Computer:

(Win7 x64)

Origin:

Agent

Malware Information

Detection Time:

July 12, 2016 19:02:41

Malware:

TM_MALWARE_BEHAVIOR

Infected File(s):

C:\test\BM_sample.scr

Scan Type:

Real Time

Action Taken:

Terminated

Reason:

Default Real-Time Scan Configuration

Major Virus Type:

Suspicious Activity

Behavior Monitoring Information

Target:

C:\Users\root\AppData\Roaming\Microsoft\Windows\Start Menu\Programs\Startup\StartupFile.exe

TargetType:

File System

< Back

Next >

Close

Events related to ransomware have an additional **Targeted Files** tab:

General

Targeted Files

Tags

General Information

Computer: (Win7 x64)

Origin: Agent

Malware Information

Detection Time: July 12, 2016 19:02:51

Malware: HEU_AEGIS_CRYPT

Infected File(s): c:\test\adc.exe

Scan Type: Real Time

Action Taken: Terminated

Reason: [Default Real-Time Scan Configuration](#)

Major Virus Type: Unauthorized Change

Behavior Monitoring Information

Target: Multiple

TargetType: File System

< Back

Next >

Close

General

Targeted Files

Tags

Targeted Files Information

Export to CSV...

ATTACKING PROGRAM ^	TARGET	RESTORE RESULT
<div><div></div>c:\test\adc.exe</div>	c:\users\ds\documents\outloo...	Success
<div><div></div>c:\test\adc.exe</div>	c:\users\ds\documents\outloo...	Success
<div><div></div>c:\test\adc.exe</div>	c:\users\ds\documents\outloo...	Success

<

>

< Back

Next >

Close

If you investigate and find that an identified file is not harmful, you can right-click the event and click **Allow** to add the file to a scan exclusion list for the computer or policy. You can check the scan exclusion list in the policy or computer editor, under **Anti-Malware > Advanced > Behavior Monitoring Protection Exceptions**.

What if my agents can't connect to the Internet directly?

The enhanced scanning features described in this article require Internet access to check files against the Global Census Server and Good File Reputation Service. If your Deep Security Agents cannot access the Internet directly, see ["Configure agents that have no Internet access" on page 354](#) for workarounds.

Smart Protection in Deep Security

Smart Protection Network integration is available for your computers and workloads through anti-malware and web reputation modules. Smart Feedback, which is set at the system level, allows you to provide continuous feedback to the Smart Protection Network.

For more about Trend Micro's Smart Protection Network, see [Smart Protection Network](#).

In this topic:

- ["Anti-malware and Smart Protection" below](#)
- ["Web Reputation and Smart Protection" on page 711](#)
- ["Smart Feedback" on page 712](#)

See also [Deploy a Smart Protection Server in AWS](#) for AWS deployment instructions, and the [Smart Protection Server documentation](#) for instructions on manually deploying the server.

Anti-malware and Smart Protection

- ["Enable Smart Scan" below](#)
- ["Smart Protection Server for File Reputation Service" on the next page](#)

Enable Smart Scan

Smart Scan is available in the anti-malware module. It leverages Trend Micro's [Smart Protection Network](#) to allow local pattern files to be small and reduces the size and number of updates required by agents and Appliances. When Smart Scan is enabled, the agent downloads a small version of the much larger full malware pattern from a Smart Protection Server. This smaller pattern can quickly identify files as either "confirmed safe", or "possibly dangerous". "Possibly

dangerous" files are compared against the larger complete pattern files stored on Trend Micro Smart Protection Servers to determine with certainty whether they pose a danger or not.

Without Smart Scan enabled, your relay agents must download the full malware pattern from a Smart Protection Server to be used locally on the agent. The pattern will only be updated as scheduled security updates are processed. The pattern is typically updated once per day for your agents to download and is around 120 MB.

Note: Verify that the computer can reliably connect to the global Trend Micro Smart Protection Network URLs (see "[Port numbers, URLs, and IP addresses](#)" on page 111 for a list of URLs). If connectivity is blocked by a firewall, proxy, or AWS security group or if the connection is unreliable, it will reduce anti-malware performance.

1. Go to **Policies**.
2. Double-click a policy.
3. Go to **Anti-Malware > Smart Protection**.
4. In the **Smart Scan** section, either:
 - select **Inherited** (if the parent policy has Smart Scan enabled)
 - deselect **Inherited**, and then select either **On** or **On for Deep Security Agent, Off for Virtual Appliance**.
5. Click **Save**.

Note: A computer that is configured to use Smart Scan will not download full anti-malware patterns locally. Therefore if your anti-malware license expires while a computer is configured to use Smart Scan, switching Smart Scan off will not result in local patterns being used to scan for malware since no anti-malware patterns will be present locally.

Smart Protection Server for File Reputation Service

Smart Protection Server for File Reputation Service is available in the anti-malware module. It supplies file reputation information required by Smart Scan.

To edit Smart Protection Server for File Reputation Service:

1. Go to **Computers** or **Policies > Anti-Malware > Smart Protection**.
2. You can select to connect directly to Trend Micro's Smart Protection Server or to connect to one or more locally installed Smart Protection Servers.
3. If you want to use a proxy for communication between agents and the Smart Protection Network, we recommend that you create a proxy server specifically for the Smart Protection Network. You can view and edit the list of available proxies on the **Proxies** tab on the **Administration > System Settings** page. For information on proxy protocols, see ["Proxy protocols supported by Deep Security" on page 361](#).

Note: After you select a proxy, you will need to restart any agents that will be using it.

4. Select the **When off domain, connect to global Smart Protection Service (Windows only)** option to use the global Smart Protection Service if the computer is off domain. The computer is considered to be off domain if it cannot connect to its domain controller. (This option is for Windows agents only.)

Note: If you have a locally installed Smart Protection Server, this option should be set to **Yes** on at least one computer so that you are notified if there is a problem with the Smart Protection Server itself.

5. Set the **Smart Protection Server Connection Warning** to generate error events and alerts when a computer loses its connection to the Smart Protection Server.

Web Reputation and Smart Protection

Smart Protection Server for Web Reputation supplies web reputation information required by the web reputation module.

To edit Smart Protection Server for Web Reputation Service:

1. Go to **Computers** or **Policies > Web Reputation > Smart Protection**.
2. You can select to connect directly to Trend Micro's Smart Protection Server or to connect to one or more locally installed Smart Protection Servers.
3. If you want to use a proxy for communication between agents and the Smart Protection Network, we recommend that you create a proxy server specifically for the Smart Protection Network. You can view and edit the list of available proxies on the **Proxies** tab on the **Administration > System Settings** page. For information on proxy protocols, see ["Proxy protocols supported by Deep Security" on page 361](#).

Note: After you select a proxy, you will need to restart any agents that will be using it.

4. Select the **When off domain, connect to global Smart Protection Service (Windows only)** option to use the global Smart Protection Service if the computer is off domain. The computer is considered to be off domain if it cannot connect to its domain controller. (This option is for Windows agents only.)

Note: If you have a locally installed Smart Protection Server, this option should be set to **Yes** on at least one computer so that you are notified if there is a problem with the Smart Protection Server itself.

5. Set the **Smart Protection Server Connection Warning** to generate error events and alerts when a computer loses its connection to the Smart Protection Server.

Smart Feedback

Trend Micro Smart Feedback provides continuous communication between Trend Micro products and the company's 24/7 threat research centers and technologies. With Smart Feedback, products become an active part of the Trend Micro Smart Protection Network, where large amounts of threat data is shared and analyzed in real time. This interconnection enables never before possible rates of analysis, identification, and prevention of new threats—a level of responsiveness that addresses the thousands of new threats and threat variants released daily.

Trend Micro Smart Feedback is a system setting in the Deep Security Manager. When enabled, Smart Feedback shares anonymous threat information with the Smart Protection Network, allowing Trend Micro to rapidly identify and address new threats. By default, Smart Feedback is enabled. You can disable it or adjust its settings by going to **Administration > System Settings > Smart Feedback**.

Note: Smart Feedback will use the agents, appliances, and relays (security updates) proxy selected in the Proxy Server Use section on the **Administration > System Settings > Proxies** tab.

Handle malware

You can perform the following tasks to handle malware that the anti-malware module detects:

- ["View and restore identified malware" below](#)
- ["Create anti-malware exceptions" on page 720](#)
- ["Increase debug logging for anti-malware in protected Linux instances" on page 723](#)

See also ["Generate alerts for malware detection" on page 682](#).

For an overview of the anti-malware module, see ["Protect against malware" on page 657](#).

View and restore identified malware

An identified file is a file that has been found to be or to contain malware and has therefore been encrypted and moved to a special folder. (See the "Quarantine" action in ["Customize malware remedial actions" on page 680](#).) Whether or not an infected file is quarantined depends on the anti-malware configuration that was in effect when the file was scanned.

- ["See a list of identified files" below](#)
- ["Working with identified files" on the next page](#)
- ["Search for an identified file" on page 715](#)
- ["Restore quarantined files" on page 717](#)
- ["Manually restore quarantined files" on page 720](#)

For information about events that are generated when malware is encountered, see ["Anti-malware events" on page 1251](#).

See a list of identified files

The Events and Reports page provides a list of identified files. From there you can see the details for any of those files.

1. Click **Events & Reports > Events > Anti-Malware Events > Identified Files**.
2. To see the details of a file, select the file and click **View**.

The list of identified files includes the following columns of information:

- **Infected File:** Shows the name of the infected file and the specific security risk.
- **Malware:** Names the malware infection.





- **Computer:** Indicates the name of the computer with the suspected infection.







The Details window provides the following information:

- **Detection Time:** The date and time on the infected computer that the infection was detected.
- **Infected File(s):** The name of the infected file.
- **File SHA-1:** The SHA-1 hash of the file.
- **Malware:** The name of the malware that was found.
- **Scan Type:** Indicates whether the malware was detected by a Real-time, Scheduled, or Manual scan.
- **Action Taken:** The result of the action taken by Deep Security when the malware was detected.
- **Computer:** The computer on which this file was found. (If the computer has been removed, this entry will read "Unknown Computer".)
- **Container Name:** Name of the Docker container where the malware was found.
- **Container ID:** ID of the Docker container where the malware was found.
- **Container Image Name:** Image name of the Docker container where the malware was found.

Working with identified files

The **Identified Files** page allows you to manage tasks related to identified files. Using the menu bar or the right-click context menu, you can:

-  **Restore** only quarantined files back to their original location and condition.
-  **Download** identified files from the computer or Virtual Appliance to a location of your choice.
-  **Analyze** identified files from the computer or Virtual Appliance.
-  **Delete** one or more identified files from the computer or Virtual Appliance.

-  **Export** information about the identified file(s) (not the file itself) to a CSV file.
-  **View** the details of an identified file.
-  **Computer Details** displays the screen of the computer on which the malware was detected.
-  **View Anti-Malware Event** displays the anti-malware event associated with this identified file.
-  **Add or Remove Columns** by clicking **Add/Remove**.
-  **Search** for a particular identified file.

Note:

Identified files are automatically deleted from a Deep Security Virtual Appliance when a:

- VM is moved to another ESXi host by vMotion. Identified files associated with that VM will be deleted from the virtual appliance.
- VM is deactivated from the Deep Security Manager. Identified files associated with that VM will be deleted from the virtual appliance.
- Deep Security Virtual Appliance is deactivated from the Deep Security Manager. All the identified files stored on that virtual appliance will be deleted.
- Deep Security Virtual Appliance is deleted from the vCenter. All the identified files stored on that virtual appliance will also be deleted.

Search for an identified file

- Use the **Period** drop down menu to see only the files that were identified within a specific time frame.
- Use the **Computers** drop-down menu to organize files by Computer Groups or Computer Policies.
- Click **Search this page > Open Advanced Search** to toggle the display of the advanced search options:

Identified Files

No Grouping ▼

Q Search th

Period: Last Hour ▼

Computers: All Computers ▼

Search: Infected File(s) ▼

Contains ▼

Delete...

View

Export ▼

Restore...

Download...

Columns...

Advanced searches include one or more search criteria for filtering identified files. Each criterion is a logical statement comprised of the following items:

- The characteristic of the identified file to filter on, such as the type of file (infected file or malware) or the computer that was affected.
- An operator:
 - **Contains:** The entry in the selected column contains the search string.
 - **Does Not Contain:** The entry in the selected column does not contain the search string.
 - **Equals:** The entry in the selected column exactly matches the search string.
 - **Does Not Equal:** The entry in the selected column does not exactly match the search string.
 - **In:** The entry in the selected column exactly matches one of the comma-separated search string entries.
 - **Not In:** The entry in the selected column does not exactly match any of the comma-separated search string entries.
- A value.

To add a criterion, click the "plus" button (+) to the right of the topmost criterion. To search, click the Search button (the circular arrow).

Note: Searches are not case-sensitive.

Restore quarantined files

Create a scan exclusion for the file

Before you can restore the file to its original location you have to create a scan exclusion so that Deep Security doesn't immediately re-quarantine the file when it reappears on the computer.

Note: The following instructions describe how to create an exclusion for the file on an individual computer but you can make the same configuration changes at the policy level.

1. Open the Computers page and go to **Anti-Malware > Identified Files** and double click the quarantined file to view its properties.
2. Note the file's exact name and original location.
3. Still in the Computers page, go to **Anti-Malware > General** and click the Edit button next to each Malware Scan that's in effect to open the Malware Scan Configuration properties

window.

Computer: laptop_adaggs (lap)

Overview | **Anti-Malware** | Web Reputation | Firewall | Intrusion Prevention | Integrity Monitoring | Log Inspection | Interfaces | Settings | Updates | Overrides

General | Smart Protection | Advanced | Quarantined Files | Events

Anti-Malware

Configuration: Inherited (On) ▼

State: ● On, matching module plug-in not found, Real Time

Real-Time Scan

☒ Inherited

Malware Scan Configuration: Default Real-Time Scan Configuration ▼ **Edit**

Schedule: Every Day All Day ▼ **Edit**

Manual Scan

☒ Inherited

Malware Scan Configuration: Default Manual Scan Configuration ▼ **Edit**

Scheduled Scan

☒ Inherited

Malware Scan Configuration: Default Scheduled Scan Configuration ▼ **Edit**

Malware scan

Last Manual Scan for Malware: N/A

Last Scheduled Scan for Malware: N/A

Quick Scan for Malware Full Scan for Malware Cancel M

4. In the **Malware Scan Configuration** properties window, click on the **Exclusions** tab.
5. In the **Scan Exclusions** area, select **File List** and then either press edit if a file list is already selected, or select **New** from the menu to create a new File List.

6. In the **File List** properties window, enter the file path and name of the file to be restored. Click **OK** to close the File List properties window.

General **Assigned To**

General Information

Name:

Description:

File(s): (One file per line)

Supported Formats:

NOTE The "Process Image File List" only handles full path, other formats are ignored.

File:

FILE	Example: testfile.doc
FILEPATH	Example: C:\Documents\testfile.doc

File with WildCard (*):

FILE*	Example: MyApp*.vApp
FILE.EXT*	Example: MyApp.v*

Environment Variable:

\${ENV VAR}	Example: \${myDBFile}
-------------	-----------------------

Comments:

FILEPATH #Comment	Example: C:\temp\file.txt #Exclude
-------------------	------------------------------------

7. Close the **Malware Scan Configuration** properties window by clicking **OK**.

8. When you've edited all the **Malware Scan Configurations**, click **Save** in the Computers page to save your changes. You're now ready to restore your file.

Restore the file

1. Still in the Computers page, go to the **Anti-Malware > Identified Files** tab.
2. Right-click the quarantined file and select **Actions > Restore** and follow the steps in the wizard.

Your file will be restored to its original location.

Manually restore quarantined files

To manually restore a quarantined file, download the file to your computer. The **Identified File** wizard will display a link to an **Administration Utility** which you can use to decrypt, examine, or restore the file. Use the quarantined file decryption utility to decrypt the file and then move it back to its original location.

The decryption utility is in a zip file, **QFAdminUtil_win32.zip**, located in the "util" folder under the Deep Security Manager root directory. The zipped file contains two utilities which perform the same function: **QDecrypt.exe** and **QDecrypt.com**. Running **QDecrypt.exe** invokes an open file dialog that lets you select the file for decryption. **QDecrypt.com** is a command-line utility with the following options:

- **/h, --help**: show this help message
- **--verbose**: generate verbose log messages
- **/i, --in=<str>**: quarantined file to be decrypted, where **<str>** is the name of the quarantined file
- **/o, --out=<str>**: decrypted file output, where **<str>** is the name given to the resulting decrypted file

Note: This utility is supported only on Windows 32-bit systems.

Create anti-malware exceptions

Files that are not malicious can be falsely identified as malware if they share certain characteristics with malware. If a file is known to be benign and is identified as malware, you can

create an exception for that file. When an exception is created, the file does not trigger an event when Deep Security scans the file.

For an overview of the anti-malware module, see ["Protect against malware" on page 657](#).

Note: You can also exclude files from real-time, manual, and scheduled scans. See ["Specify the files to scan" on page 673](#).

Exceptions can be created for the following types of malware and malware scans:

- Predictive Machine Learning scans (for information, see ["Detect emerging threats using Predictive Machine Learning" on page 690](#).)
- Document exploit protection scans (for information, see ["Detect emerging threats using Connected Threat Defense" on page 692](#))
- Scans for spyware and grayware (for information, see ["Scan for spyware and grayware" on page 671](#))
- Behavior monitoring protection (for information, see ["Enhanced anti-malware and ransomware scanning with behavior monitoring" on page 702](#))

Deep Security maintains a list of exceptions for each type of malware scan in policy and computer properties.

1. To see the lists of exceptions, open the policy or computer editor.
2. Click **Anti-Malware > Advanced**.

The exceptions are listed in the **Allowed Spyware/Grayware**, **Document Exploit Protection Rule Exceptions**, **Predictive Machine Learning Detection Exceptions**, and **Behavior Monitoring Protection Exceptions** sections.

See also ["Scan exclusion recommendations" on page 723](#).

Create an exception from an anti-malware event

When a file is identified as malware, Deep Security generates an anti-malware event. If you know that the file is benign, you can create an exception for the file from the event report.

1. Click **Events & Reports > Events > Anti-Malware Events** and locate the malware detection event.

2. Right-click the event.
3. Select **Allow**.

Manually create an anti-malware exception

You can manually create anti-malware exceptions for spyware or grayware, document exploit protection rules, predictive machine learning, and behavior monitoring exceptions. To add the exception, you need specific information from the anti-malware event that the scan generated. The type of malware or scan determines the information that you need:

- **Spyware or grayware:** The value in the "MALWARE" field, for example `SPY_CCFR_CPP_TEST.A`
- **Document exploit protection rules:** The value in the "MALWARE" field, for example `HEUR_OLEP.EXE`
- **Predictive machine learning:** The SHA1 digest of the file from the "FILE SHA-1" field, for example `3395856CE81F2B7382DEE72602F798B642F14140`
- **Behavior monitoring:** The process image path, for example `C:\test.exe`

1. Click **Events & Reports > Events > Anti-Malware Events** and copy the field value that is required to identify the malware.
2. Open the policy or computer editor where you want to create the exception.
3. Click **Anti-Malware > Advanced**.
4. In the **Allowed Spyware/Grayware, Document Exploit Protection Rule Exceptions, Predictive Machine Learning Detection Exceptions, or Behavior Monitoring Protection Exceptions** section, enter the information from the event in the text box.
5. Click **Add**.

Exception strategies for spyware and grayware

When spyware is detected the malware can be immediately quarantined, depending on the malware scan configuration that controls the scan. After you create the exception for a spyware or grayware event, you might have to restore the quarantined file. (See ["Restore quarantined files" on page 717](#).)

Alternatively, you can temporarily scan for spyware and grayware with the action set to "Pass" so that all spyware and grayware detections are recorded on the Anti-Malware Events page but neither quarantined nor deleted. You can then create exceptions for the detected spyware and

grayware. When your exception list is robust, you can set the action to "Quarantine" or "Delete" modes.

For information about setting the action, see ["Configure how to handle malware" on page 680](#).

Scan exclusion recommendations

The best and most comprehensive source for scan exclusions is from the software vendor. The following are some high-level scan exclusion recommendations:

- Quarantine folders (such as `SMEX` on Microsoft Windows Exchange Server) should be excluded to avoid rescanning files that have already been confirmed to be malware.
- Large databases and database files (for example, `dsm.mdf` and `dsm.ldf`) should be excluded because scanning could impact database performance. If it is necessary to scan database files, you can create a scheduled task to scan the database during off-peak hours. Since Microsoft SQL Server databases are dynamic, exclude the directory and backup folders from the scan list:

```
{ProgramFiles}\Microsoft SQL Server\MSSQL\Data\  
{Windir}\WINNT\Cluster\ # if using SQL Clustering  
Q:\ # if using SQL Clustering
```

For a list of recommended scan exclusions, see the [Trend Micro recommended scan exclusion list](#). Microsoft also maintains an [Anti-Virus Exclusion List](#) that you can use as a reference for excluding files from scanning on Windows servers.

Increase debug logging for anti-malware in protected Linux instances

You can increase or decrease verbosity of the anti-malware (AM) debug logging used to diagnose any issue related to AM when running on a Linux operating system.

Anti-malware debug logs are automatically included when you create a diagnostic package for technical support.

For information on creating a diagnostic package, see ["Create a diagnostic package and logs" on page 1484](#).

To increase the anti-malware debug log level, enter the following command in a shell on the Linux instance as a superuser:

```
killall -USR1 ds_am
```

This command will increase the level one unit. By default the level is 6 and the maximum is 8.

To decrease the anti-malware debug log level, enter the following command in a shell on the Linux instance as a superuser:

```
killall -USR2 ds_am
```

This command decreases the level by one unit. The minimum level is 0.

Block exploit attempts using intrusion prevention

The intrusion prevention module protects your computers from known and zero-day vulnerability attacks as well as against SQL injections attacks, cross-site scripting attacks, and other web application vulnerabilities.

When patches are not available for known vulnerabilities in applications or operating systems, intrusion prevention rules can intercept traffic that is trying to exploit the vulnerability. It identifies malicious software that is accessing the network and it increases visibility into, or control over, applications that are accessing the network. Therefore your computers are protected until patches that fix the vulnerability are released, tested, and deployed.

Protection is available for file sharing and messaging software such as Skype, but also web applications with vulnerabilities such as SQL injection and cross-site scripting (XSS). In this way, intrusion prevention can also be used as a lightweight web application firewall (WAF).

To enable and configure intrusion prevention, see ["Set up intrusion prevention" on page 728](#).

Intrusion prevention rules

Intrusion prevention rules define a set of conditions that are compared to the payload session and application layers of network packets (such as DNS, HTTP, SSL, and SMTP), as well as the sequence of those packets according to those higher-layer protocols.

Tip: Firewall rules examine the network and transport layers of a packet (IP, TCP, and UDP, for example).

When Deep Security Agents scan network traffic and the traffic meets a rule's match conditions, the agent handles it as a possible or confirmed attack and performs one of the following actions, depending on the rule:

- Replace specifically defined or suspicious byte sequences
- Completely drop packets
- Reset the connection

Intrusion prevention rules are assigned to policies and computers. Therefore you can enforce sets of rules on groups of computers based on the policy that they use, and override policies as required. (See ["Policies, inheritance, and overrides" on page 524.](#))

For information about how you can affect the functionality of rules, see ["Configure intrusion prevention rules" on page 736.](#)

Application types

Application types organize rules by the application that they are associated with. Application types can also store property values that rules can reference as required, such as protocols used for communications, and port numbers. Some application types have configurable properties. For example, the Database Microsoft SQL application type contains rules that are associated with Microsoft SQL Server. You can configure this application type to specify the ports used to connect to the database.

For more information, see ["Application types" on page 758.](#)

Rule updates

Trend Micro creates intrusion prevention rules for application vulnerabilities as they are discovered. Security updates can include new or updated rules and application types. When a rule is already assigned to a policy, and an update includes rules upon which the assigned rule depends, you can choose to automatically assign the updated rules.

Tip: Intrusion prevention rules from Trend Micro include information about the vulnerability against which it protects.

Intrusion prevention rules from Trend Micro are not directly editable through Deep Security Manager. However some rules are configurable, and some rules require configuration. (See ["Setting configuration options \(Trend Micro rules only\)" on page 742.](#))

Recommendation scans

You can use recommendation scans discover the intrusion prevention rules that you should assign to your policies and computers. (See ["Manage and run recommendation scans" on page 529.](#))

Use behavior modes to test rules

Intrusion protection works in either Detect or Prevent mode:

- **Detect:** Intrusion prevention uses rules to detect matching traffic and generate events, but does not block traffic. Detect mode is useful to test that intrusion prevention rules do not interfere with legitimate traffic.
- **Prevent:** Intrusion detention uses rules to detect matching traffic, generate events, and block traffic to prevent attacks.

When you first apply new intrusion prevention rules, use Detect mode to verify that they don't accidentally block normal traffic (false positives). When you are satisfied that no false positives occur, you can use Prevent mode to enforce the rules and block attacks. (See ["Enable intrusion prevention in Detect mode" on page 729](#) and ["Switch to prevent mode" on page 734.](#))

Tip: Similar to using intrusion prevention in Detect mode, the Deep Security network engine can run in tap mode for testing purposes. In tap mode, intrusion prevention detects rule-matching traffic and generates events, but doesn't block traffic. However, tap mode uses a copy of the packet stream, not the actual stream. Also, tap mode affects the firewall and web reputation modules. You can use Detect mode to test intrusion prevention rules separately. You use tap mode with intrusion prevention in the same way that tap mode is used for testing firewall rules. See ["Test Firewall rules before deploying them" on page 772.](#)

Override the behavior mode for rules

You can configure a rule's behavior mode to override the mode that is set for intrusion prevention at the policy or computer level. Overriding is useful for testing new rules that are applied to a policy or computer. For example, when a policy is configured such that intrusion prevention works in Protect mode, you can configure a rule to use Detect mode. For that rule only, intrusion prevention merely logs the traffic, and enforces other rules that do not override the policy's behavior mode. (See ["Override the behavior mode for a rule" on page 744.](#))

Some rules issued by Trend Micro use Detect mode by default. For example, mail client rules generally use Detect mode because in Protect mode they block the downloading of all mail. Some rules trigger an alert only when a condition occurs a large number of times, or a certain number of times within a certain period of time. These types of rules apply to traffic that constitutes suspicious behavior only when a condition recurs, and a single occurrence of the condition is considered normal.

Warning:

To prevent blocking legitimate traffic and interrupting network services, when a rule requires configuration, keep it in Detect mode until you've configured the rule. Switch a rule to Prevent mode only after configuration and testing.

Intrusion prevention events

By default, the Deep Security Manager collects firewall and intrusion prevention event logs from the Deep Security **agents and appliances**¹ at every heartbeat. Once collected by the Deep Security Manager, event logs are kept for a period of time which can be configured. The default setting is one week. (See ["Log and event storage best practices" on page 1094.](#)) You can configure event logging for individual rules as required. (See ["Configure event logging for rules" on page 741.](#))

Event tagging can help you to sort events. You can manually apply tags to events or automatically tag them. You can also use the auto-tagging feature to group and label multiple

¹The Deep Security Agent and Deep Security Virtual Appliance are the components that enforce the Deep Security policies that you have defined. Agents are deployed directly on a computer. Appliances are used in VMware vSphere environments to provide agentless protection. They are not available with Deep Security as a Service.

events. For more information on event tagging, see ["Apply tags to identify and group events" on page 1099](#).

Support for secure connections

The intrusion prevention module supports inspecting packets over secure connections. See ["Inspect SSL or TLS traffic" on page 760](#).

Contexts

Contexts are a powerful way of implementing different security policies depending on the computer's network environment. You typically use contexts to create policies that apply different firewall and intrusion prevention rules to computers (usually mobile laptops) depending on whether that computer is in the office or away.

To determine a computer's location, contexts examine the nature of the computer's connection to its domain controller. For more information, see ["Define contexts for use in policies" on page 618](#).

Interface tagging

You can use interface types when you need to assign firewall or intrusion prevention rules to a specific interface when a machine has multiple network interfaces. By default, firewall and intrusion prevention rules are assigned to all interfaces on a computer. For example, to apply special rules only to the wireless network interface, use interface types to accomplish this. For more information, see ["Configure a policy for multiple interfaces" on page 540](#).

Set up intrusion prevention

Enable the intrusion prevention module and monitor network traffic for exploits using Detect mode. When you are satisfied with how your intrusion prevention rules are assigned, switch to Protect mode.

1. ["Enable intrusion prevention in Detect mode" on the next page](#)
2. ["Test intrusion prevention" on page 731](#)

3. ["Apply recommended rules" on page 732](#)
4. ["Monitor your system" on page 734](#)
5. ["Enable 'fail open' for packet or system failures" on page 734](#)
6. ["Switch to prevent mode" on page 734](#)
7. ["Implement best practices for specific rules" on page 735](#)
8. ["Apply NSX security tags" on page 736](#)

Note: CPU usage and RAM usage varies by your IPS configuration. To optimize IPS performance on Deep Security Agent, see ["Performance tips for intrusion prevention" on page 768](#).

For an overview of the intrusion prevention module, see ["Block exploit attempts using intrusion prevention" on page 724](#).

Enable intrusion prevention in Detect mode

Enable intrusion prevention and use Detect mode for monitoring. Configure intrusion prevention using the appropriate policies to affect the targeted computers. You can also configure individual computers.

1. Go to **Computer or Policy editor**¹ > Intrusion Prevention > General.
2. For Configuration, select either On or Inherited (On).

The screenshot displays the 'Computer: [Name]' configuration window for 'Intrusion Prevention'. The left sidebar shows navigation options: Overview, Anti-Malware, Web Reputation, Firewall, Intrusion Prevention (selected), Integrity Monitoring, Log Inspection, Application Control, Interfaces, Settings, Updates, and Overrides. The main panel has tabs for General, Advanced, and Intrusion Prevention Events. The 'General' tab is active, showing the following settings:

- Intrusion Prevention Configuration:** On
- State:** Intrusion Prevention Engine Offline
- Intrusion Prevention Behavior:** Prevent (selected), Detect
- Container Protection:** Scan container network traffic: Inherited (Yes)
- Assigned Intrusion Prevention Rules:** A table with 4 columns: NAME, DESCRIPTION, APPLICATION TYPE, and PRIORITY. It lists two rules:

NAME	DESCRIPTION	APPLICATION TYPE	PRIORITY
1004715 - HTTP Web Client Decoding	This is a smart filter that decodes the We...	Web Client Common	1 - Low
1009218 - Microsoft Windows VBScript Engine Use-After-Free Vulnerability	Microsoft Windows VBScript Engine is pr...	Web Client Common	2 - Normal
- Recommendations:**
 - Current Status: 2 Intrusion Prevention Rule(s) assigned
 - Last Scan for Recommendations: N/A
 - No Recommendation Scan Results
 - Automatically implement Intrusion Prevention Recommendations (when possible): Default (No)
 - Buttons: Scan For Recommendations, Cancel Recommendation Scan, Clear Recommendations

At the bottom right, there are 'Save' and 'Close' buttons.

3. For Intrusion Prevention Behavior, select Detect.
4. With Deep Security Agent 11.1 and earlier, the Intrusion Prevention module inspects traffic that passes through the host computer's network interface to containers. With Deep

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Security Agent 11.2 or later, it can also inspect traffic between containers. When the **Scan container network traffic** setting is set to **Yes**, Deep Security scans the traffic that goes through both containers and hosts. When it is set to **No**, Deep Security scans only the traffic that goes through the host network interface.

5. Click **Save**.

Tip: If the behavior settings are not available, **Network Engine Mode** may be set to **Tap**. (See ["Test Firewall rules before deploying them" on page 772.](#))

For more fine-grained control, when you assign intrusion prevention rules, you can override the global behavior mode and configure specific rules to either prevent or detect. (See ["Override the behavior mode for a rule" on page 744.](#))

Test intrusion prevention

You should test that the intrusion prevention module is working properly before continuing with further steps.

1. If you have an agent-based deployment, make sure you have a computer that has an agent running. For an agentless deployment, make sure your Deep Security Virtual Appliance is running normally.
2. Turn off the web reputation module. In Deep Security Manager, click **Computers**, then double-click the computer where you'll test intrusion prevention. In the computer's dialog box, click **Web Reputation**, and select **Off**. Web reputation is now disabled and won't interfere with the intrusion prevention functionality.
3. Make sure bad traffic is blocked. Still in the computer's dialog box, click **Intrusion Prevention**, and under the **General** tab, select **Prevent**. (If it is shaded, set the **Configuration** drop-down list to **Inherited (On)**.)
4. Assign the EICAR test policy. Still in the computer's dialog box, click **Intrusion Prevention**. Click **Assign/Unassign**. Search for `1005924`. The **1005924 - Restrict Download of EICAR Test File Over HTTP** policy appears. Select its check box and click **OK**. The policy is now assigned to the computer.
5. Try to download the EICAR file (you can't, if intrusion prevention is running properly). On Windows, go to this link: <http://www.eicar.org/download/eicar.com.txt>. On Linux, enter this command: `curl -O http://www.eicar.org/download/eicar.com`

6. Check the intrusion prevention events for the computer. Still in the computer's dialog box, click **Intrusion Prevention > Intrusion Prevention Events**. Click **Get Events** to see events that have occurred since the last heartbeat. An event appears with a **Reason** of **1005924 - Restrict Download of EICAR Test File Over HTTP**. The presence of this event indicates that intrusion prevention is working.
7. Revert your changes to return your system to its previous state. Turn on the Web Reputation module (if you turned it off), reset the **Prevent** or **Detect** option, and remove the EICAR policy from the computer.

Apply recommended rules

To maximize performance, minimize the number of intrusion prevention rules that are assigned to your policies and computers. Therefore, you should assign only the rules that are required. Use a recommendation scan to obtain a list of rules that are appropriate.


Although recommendation scans are performed for a specific computer, you can assign the recommendations to a policy that the computer uses.

For more information, see ["Manage and run recommendation scans" on page 529](#).

1. Open the properties for the computer to scan. Run the recommendation scan as described in ["Manually run a recommendation scan" on page 534](#).

Note: Do not automatically assign the recommended rules.

2. Open the policy to which you want to assign the rules, and complete the rule assignments as described in ["Check scan results and manually assign rules" on page 536](#).



Tip: To automatically and periodically fine tune your assigned intrusion prevention rules, you can schedule recommendation scans. See ["Schedule Deep Security to perform tasks" on page 418](#).

Monitor your system

After you apply intrusion prevention rules, monitor system performance and intrusion prevention event logs.

Monitor system performance

Monitor CPU, RAM, and network usage to verify that system performance is still acceptable. If not, you can modify some settings and deployment aspects to improve performance. (See ["Performance tips for intrusion prevention" on page 768.](#))

Check intrusion prevention events

Monitor intrusion prevention events to ensure that rules are not matching legitimate network traffic. If a rule is causing false positives you can unassign the rule. (See ["Assign and unassign rules" on page 740.](#))

To see intrusion prevention events, click **Events & Reports > Intrusion Prevention Events**.

Enable 'fail open' for packet or system failures

The intrusion prevention module includes a network engine that might block packets before intrusion prevention rules can be applied. This might lead to downtime or performance issues with your services and applications. You can change this behavior so that packets are allowed through when system or internal packet failures occur. For details, see ["Enable 'fail open' behavior" on page 774.](#)

Switch to prevent mode

When you are satisfied that intrusion prevention is not finding false positives, configure your policy to use intrusion prevention in Prevent mode so that rules are enforced and related events are logged.

1. Go to **Computer or Policy editor**¹ > Intrusion Prevention > General.
2. For **Intrusion Prevention Behavior**, select **Detect**.
3. Click **Save**.

Implement best practices for specific rules

HTTP Protocol Decoding rule

The HTTP Protocol Decoding rule is the most important rule in the "Web Server Common" Application Type. This rule decodes the HTTP traffic before the other rules inspect it. This rule also allows you to control various components of the decoding process.

This rule is required when you use any of the Web Application Common or Web Server Common rules that require it. The Deep Security Manager automatically assigns this rule when it is required by other rules. As each web application is different, the policy that uses this rule should run in Detect mode for a period of time before switching to Prevent mode to determine if any configuration changes are required.

Quite often, changes are required to the list of illegal characters.

Refer to the following Knowledge Base articles for more details on this rule and how to tune it:

- <https://success.trendmicro.com/solution/1098016>
- <https://success.trendmicro.com/solution/1054481>
- <https://success.trendmicro.com/solution/1096566>

Cross-site scripting and generic SQL injection rules

Two of the most common application-layer attacks are SQL injection and cross-site scripting (XSS). Cross-site scripting and SQL injection rules intercept the majority of attacks by default, but you may need to adjust the drop score for specific resources if they cause false positives.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Both rules are smart filters that need custom configuration for web servers. If you have output from a Web Application Vulnerability Scanner, you should leverage that information when applying protection. For example, if the user name field on the login.asp page is vulnerable to SQL injection, ensure that the SQL injection rule is configured to monitor that parameter with a low threshold to drop on.

For more information, see <https://success.trendmicro.com/solution/1098159>

Apply NSX security tags

Apply NSX security tags

Deep Security can apply NSX security tags to protected VMs when Intrusion Prevention rules are triggered. For details, see "Configure Intrusion Prevention to apply NSX security tags" on page 317.

Configure intrusion prevention rules

Perform the following tasks to configure and work with intrusion prevention rules:

- "See the list of intrusion prevention rules" on the next page
- "See information about an intrusion prevention rule" on the next page
- "See information about the associated vulnerability (Trend Micro rules only)" on page 739
- "Assign and unassign rules" on page 740
- "Automatically assign updated required rules" on page 741
- "Configure event logging for rules" on page 741
- "Generate alerts" on page 742
- "Setting configuration options (Trend Micro rules only)" on page 742
- "Schedule active times" on page 743
- "Exclude from recommendations" on page 744
- "Set the context for a rule" on page 744
- "Override the behavior mode for a rule" on page 744
- "Override rule and application type configurations" on page 745

- ["Export and import rules" on page 746](#)
- ["Configure an SQL injection prevention rule" on page 746](#)

For an overview of the intrusion prevention module, see ["Block exploit attempts using intrusion prevention" on page 724](#).

See the list of intrusion prevention rules

The Policies page provides a list of intrusion prevention rules. You can search for intrusion prevention rules, and open and edit rule properties. In the list, rules are grouped by application type, and some rule properties appear in different columns.

Tip: The "TippingPoint" column contains the equivalent Trend Micro TippingPoint rule ID. In the Advanced Search for intrusion prevention, you can search on the TippingPoint rule ID. You can also see the TippingPoint rule ID in the list of assigned intrusion prevention rules in the policy and computer editor.

To see the list, click **Policies**, and then below **Common Objects/Rules** click **Intrusion Prevention Rules**.

See information about an intrusion prevention rule

The properties of intrusion prevention rules include information about the rule and the exploit against which it protects.



1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.

General Information

- **Name:** The name of the intrusion prevention rule.
- **Description:** The description of the intrusion prevention rule.

- **Minimum Agent/Appliance Version:** The minimum version of the Deep Security **Agent or Appliance**¹ required to support this intrusion prevention rule.

Details

Clicking **New** () or **Properties** () displays the **Intrusion Prevention Rule Properties** window.

Note: Note the **Configuration** tab. Intrusion Prevention Rules from Trend Micro are not directly editable through Deep Security Manager. Instead, if the Intrusion Prevention Rule requires (or allows) configuration, those configuration options will be available on the **Configuration** tab. Custom Intrusion Prevention Rules that you write yourself will be editable, in which case the **Rules** tab will be visible.

See the list of intrusion prevention rules

The Policies page provides a list of intrusion prevention rules. You can search for intrusion prevention rules, and open and edit rule properties. In the list, rules are grouped by application type, and some rule properties appear in different columns.

Tip: The "TippingPoint" column contains the equivalent Trend Micro TippingPoint rule ID. In the Advanced Search for intrusion prevention, you can search on the TippingPoint rule ID. You can also see the TippingPoint rule ID in the list of assigned intrusion prevention rules in the policy and computer editor.

To see the list, click **Policies**, and then below **Common Objects/Rules** click **Intrusion Prevention Rules**.

¹The Deep Security Agent and Deep Security Virtual Appliance are the components that enforce the Deep Security policies that you have defined. Agents are deployed directly on a computer. Appliances are used in VMware vSphere environments to provide agentless protection. They are not available with Deep Security as a Service.

General Information

- **Application Type:** The application type under which this intrusion prevention rule is grouped.

Tip: You can edit application types from this panel. When you edit an application type from here, the changes are applied to all security elements that use it.

- **Priority:** The priority level of the rule. Higher priority rules are applied before lower priority rules.
- **Severity:** Setting the severity of a rule has no effect on how the rule is implemented or applied. Severity levels can be useful as sorting criteria when viewing a list of intrusion prevention rules. More importantly, each severity level is associated with a severity value; this value is multiplied by a computer's Asset Value to determine the Ranking of an Event. (See **Administration > System Settings > Ranking**.)
- **CVSS Score:** A measure of the severity of the vulnerability according the [National Vulnerability Database](#).

Identification (Trend Micro rules only)

- **Type:** Can be either Smart (one or more known and unknown (zero day) vulnerabilities), Exploit (a specific exploit, usually signature based), or Vulnerability (a specific vulnerability for which one or more exploits may exist).
- **Issued:** The date the rule was released. This does not indicate when the rule was downloaded.
- **Last Updated:** The last time the rule was modified either locally or during Security Update download.
- **Identifier:** The rule's unique identification tag.

See information about the associated vulnerability (Trend Micro rules only)

Rules that Trend Micro provides can include information about the vulnerability against which the rule protects. When applicable, the Common Vulnerability Scoring System (CVSS) is

displayed. (For information on this scoring system, see the CVSS page at the [National Vulnerability Database](#).)

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the **Vulnerabilities** tab.

Assign and unassign rules

To apply intrusion prevention rules during agent scans, you assign them to the appropriate policies and computers. When the rule is no longer necessary because the vulnerability has been patched you can unassign the rule.

If you cannot unassign intrusion prevention rules from a **Computer editor**¹, it is likely because the rules are currently assigned in a policy. Rules assigned at the policy level must be removed using the **Policy editor**² and cannot be removed at the computer level.

When you make a change to a policy, it affects all computers using the policy. For example, when you unassign a rule from a policy you remove the rule from all computers that are protected by that policy. To continue to apply the rule to other computers, create a new policy for that group of computers. (See "[Policies, inheritance, and overrides](#)" on page 524.)

Tip: To see the policies and computers to which a rule is assigned, see the Assigned To tab of the rule properties.

1. Go to the **Policies** page, right-click the policy to configure and click **Details**.
2. Click **Intrusion Prevention > General**.
The list of rules that are assigned to the policy appear in the **Assigned Intrusion Prevention Rules** list.
3. Under **Assigned Intrusion Prevention Rules**, click **Assign/Unassign**.
4. To assign a rule, select the check box next to the rule.

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

5. To unassign a rule, deselect the check box next to the rule.
6. Click **OK**.

Automatically assign updated required rules

Security updates can include new or updated application types and intrusion prevention rules which require the assignment of secondary intrusion prevention rules. Deep Security can automatically assign these rules if they are required. You enable these automatic assignments in the the policy or computer properties.

1. Go to the **Policies** page, right-click the policy to configure and click **Details**.
2. Click **Intrusion Prevention > Advanced**.
3. To enable the automatic assignments, in the **Rule Updates** area, select **Yes**.
4. Click **OK**.

Configure event logging for rules

Configure whether events are logged for a rule, and whether to include packet data in the log.

Note: Deep Security can display X-Forwarded-For headers in intrusion prevention events when they are available in the packet data. This information can be useful when the Deep Security Agent is behind a load balancer or proxy. The X-Forwarded-For header data appears in the event's Properties window. To include the header data, include packet data in the log. In addition, rule 1006540 "Enable X-Forwarded-For HTTP Header Logging" must be assigned.

Because it would be impractical to record all packet data every time a rule triggers an event, Deep Security records the data only the first time the event occurs within a specified period of time. The default time is five minutes, however you can change the time period using the "Period for Log only one packet within period" property of a policy's Advanced Network Engine settings. (See [Advanced Network Engine Options](#).)

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" on page 745](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.

3. On the General tab, go to the Events area and select the desired options:
 - To disable logging for the rule, select **Disable Event Logging**.
 - To log an event when a packet is dropped or blocked, select **Generate Event on Packet Drop**.
 - To include the packet data in the log entry, select **Always Include Packet Data**.
 - To log several packets that precede and follow the packet that the rule detected, select **Enable Debug Mode**. Use debug mode only when your support provider instructs you to do so.

Additionally, to include packet data in the log, the policy to which the rule is assigned must allow rules to capture packet data:

1. On the Policies page, open the policy that is assigned the rule.
2. Click **Intrusion Prevention > Advanced**.
3. In the **Event Data** area, select **Yes**.

Generate alerts

Generate an alert when an intrusion prevention rule triggers an event.

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" on page 745](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the Options tab, and in the **Alert** area select **On**.
4. Click **OK**.

Setting configuration options (Trend Micro rules only)

Some intrusion prevention rules that Trend Micro provides have one or more configuration options such as header length, allowed extensions for HTTP, or cookie length. Some options require you to configure them. If you assign a rule without setting a required option, an alert is generated that informs you about the required option. (This also applies to any rules that are downloaded and automatically applied by way of a Security Update.)


Intrusion prevention rules that have configuration options appear in the Intrusion Prevention Rules list with a small gear over their icon .

Note: Custom intrusion prevention rules that you write yourself include a **Rules** tab where you can edit the rules.

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" on page 745](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the **Configuration** tab.
4. Configure the properties and then click **OK**.

Schedule active times

Schedule a time during which an intrusion prevention rule is active. Intrusion prevention rules that are active only at scheduled times appear in the Intrusion Prevention Rules page with a small clock over their icon .

Note: With Agent-based protection, schedules use the same time zone as the endpoint operating system. With Agentless protection, schedules use the same time zone as the Deep Security Virtual Appliance. Agentless protection is not available with Deep Security as a Service.

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" on page 745](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the **Options** tab.
4. In the **Schedule** area, select **New** or select a frequency.
5. Edit the schedule as required.
6. Click **OK**.

Exclude from recommendations

Exclude intrusion prevention rules from rule recommendations of recommendation scans.

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" on the next page](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the **Options** tab.
4. In the **Recommendations Options** area, select **Exclude from Recommendations**.
5. Click **OK**.

Set the context for a rule

Set the context in which the rule is applied.

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" on the next page](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Click the **Options** tab.
4. In the **Context** area, select **New** or select a context.
5. Edit the context as required.
6. Click **OK**.

Override the behavior mode for a rule

Set the behavior mode of an intrusion prevention rule to Detect when testing new rules. In Detect mode, the rule creates a log entry prefaced with the words "detect only:" and does not interfere with traffic. Some intrusion prevention rules are designed to operate only in Detect mode. For these rules, you cannot change the behavior mode.

Note: If you disable logging for the rule, the rule activity is not logged regardless of the behavior mode.

For more information about behavior modes, see ["Use behavior modes to test rules" on page 726](#).

The configuration performed in the following procedure affects all policies. For information about configuring a rule for one policy, see ["Override rule and application type configurations" below](#).

1. Click **Policies > Intrusion Prevention Rules**.
2. Select a rule and click **Properties**.
3. Select **Detect Only**.

Override rule and application type configurations

From a **Computer or Policy editor**¹, you can edit an intrusion prevention rule so that your changes apply only in the context of the policy or computer. You can also edit the rule so that the changes apply globally so that the changes affect other policies and computers that are assigned the rule. Similarly, you can configure application types for a single policy or computer, or globally.

1. Go to the **Policies** page, right-click the policy to configure and click **Details**.
2. Click **Intrusion Prevention**.
3. To edit a rule, right-click the rule and select one of the following commands:
 - **Properties**: Edit the rule only for the policy.
 - **Properties (Global)**: Edit the rule globally, for all policies and computers.
4. To edit the application type of a rule, right-click the rule and select one of the following commands:
 - **Application Type Properties**: Edit the application type only for the policy.
 - **Application Type Properties (Global)**: Edit the application type globally, for all policies and computers.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

5. Click **OK**.

Tip: When you select the rule and click Properties, you are editing the rule only for the policy that you are editing.

Note: You cannot assign one port to more than eight application types. If they are, the rules will not function on that port.

Export and import rules

You can export one or more intrusion prevention rules to an XML or CSV file, and import rules from an XML file.

1. Click **Policies > Intrusion Prevention Rules**.
2. To export one or more rules, select them and click **Export > Export Selected to CSV** or **Export > Export Selected to XML**.
3. To export all rules, click **Export > Export to CSV** or **Export > Export to XML**.
4. To import rules, click **New > Import From File** and follow the instructions on the wizard.

Configure an SQL injection prevention rule

Deep Security's intrusion prevention module includes a built-in rule that detects SQL injection attacks and drops the connection or logs it depending on its characteristics. The rule is called **1000608 - Generic SQL Injection Prevention** and can be configured to suit your organization's needs. For example, you can change the sensitivity of the rule by modifying the drop threshold.

The screenshot shows the Trend Micro Deep Security console interface. The left sidebar contains a navigation menu with 'Policies' expanded, showing 'Common Objects' and 'Rules'. Under 'Rules', 'Intrusion Prevention Rules' is selected. The main panel displays the 'IPS Rules' section with a table of rules. The rule '1000608 - Generic SQL Injection Prevention' is highlighted with a red box. The table columns are NAME, PRIORI..., SEVERI..., MODE, TYPE, CATEGORY, and CVE. The rule details show it is a 'Critical' severity rule with a 'Prevent' mode, 'Smart' type, and 'Web Application Prot...' category.

NAME	PRIORI...	SEVERI...	MODE	TYPE	CATEGORY	CVE
1000608 - Generic SQL Injection Prevention	1 - Low	Critical	Prevent	Smart	Web Application Prot...	CVE-2

Topics in this article:

- ["What is an SQL injection attack?" below](#)
- ["What are common characters and strings used in SQL injection attacks?" below](#)
- ["How does the Generic SQL Injection Prevention rule work?" on page 749](#)
- ["Examples of the rule and scoring system in action" on page 751](#)
- ["Configure the Generic SQL Injection Prevention rule" on page 753](#)
- ["Character encoding guidelines" on page 756](#)

What is an SQL injection attack?

An SQL injection attack, or SQL phishing attack, is a method of attacking data-driven applications wherein an attacker includes portions of SQL statements in an entry field. The newly-formed rogue SQL command is passed by the website to your database where it is executed. The command can result in the attacker being able to read, add, delete, or change information in the database.

What are common characters and strings used in SQL injection attacks?

Here are some commonly used characters and strings. The list is not exhaustive.

- (
- %27
- \x22
- %22
- char
- ;
- ascii
- %3B
- %2B
- --
- %2D%2D

- /*
- %2F%2A
- */
- %2A%2F
- substring
- drop table
- drop+table
- insert into
- insert+into
- version(
- values
- group by
- group+by
- create table
- create+table
- delete
- update
- bulk insert
- bulk+insert
- load_file
- shutdown
- union
- having
- select
- declare
- exec
- and

- or
- like
- @@hostname
- @@tmpdir
- is null
- is+null
- is not null
- is+not+null
- %3D
- CONCAT
- %40%40basedir
- version%28,user(
- user%28,system_user(
- (,%28,)
- %29
- @
- %40
- cast

How does the Generic SQL Injection Prevention rule work?

To detect SQL injection attacks, the Generic SQL Injection Prevention rule uses a scoring system. It works like this:

1. Packets from your application arrive at the Deep Security Agent for analysis.
2. The Generic SQL Injection Prevention rule looks at the packets and determines whether any of the strings shown in the table below are present. Notice that the strings are separated by commas and divided into ten groups.
3. If strings are found, a score is calculated as follows:
 - If a single string is found, then the score associated with its group constitutes the total score.

Trend Micro Deep Security On-Premise 11.3

- If multiple strings are found in *different* groups, then the scores of those groups are added together.
- If multiple strings are found in the *same* group, then the score of that group is counted only once.

See ["Examples of the rule and scoring system in action" on the next page](#) for clarification.

4. Using the total score, Deep Security determines whether to drop the connection or log it. If the total score exceeds the **Drop Threshold** score, then the connection is dropped, and if it exceeds the **Log Threshold** score, then it is logged.

Note: Trend Micro frequently updates its rules, so the strings in the table below might not match exactly the ones in Deep Security Manager.

Note: The use of '\W' in the lines below means 'followed by a non-alphanumeric character'.

Group	Score
drop table,drop+table,insert into,insert+into,values\W,create table,create+table,delete\W,update\W,bulk insert,bulk+insert,shutdown\W,from\W	2
declare\W,select\W	2
cast\W,exec\W,load_file	2
union\W,group by,group+by,order by,order+by,having\W	2
and\W,or\W,like\W,is null,is+null,is not null,is+not+null,where\W	1
--,%2D%2D,/*,%2F%2A,*/,%2A%2F	1
',%27,\x22,%22,char\W	1
;;,%3B	1
%2B,CONCAT\W	1
%3D	1
(,%28,),%29,@,%40	1

Group	Score
ascii,substring	1
version(,version%28,user(,user%28,system_user(,system_user%28,database(,database%28,@@hostname,%40%40hostname,@@basedir,%40%40basedir,@@tmpdir,%40%40tmpdir,@@datadir,%40%40datadir	2

Examples of the rule and scoring system in action

Below are some examples of how the scores are tallied and what actions are undertaken in each scenario.

Example 1: Logged and dropped traffic

Let's assume you are using this rule configuration (where the score for the group comes after the colon (":")):

```
drop table,drop+table,insert into,insert+into,values\W,create
table,create+table,delete\W,update\W,bulk insert,bulk+insert,shutdown\W,from\W:2
declare\W,select\W:2
cast\W,exec\W,load_file:2
union\W,group by,group+by,order by,order+by,having\W:2
and\W,or\W,like\W,is null,is+null,is not null,is+not+null,where\W:1
--, %2D%2D, /*, %2F%2A, */%, %2A%2F:1
', %27, \x22, %22, char\W:1
;, %3B:1
%2B, CONCAT\W:1
%3D:1
(, %28, ), %29, @, %40:1
ascii, substring:1
version(, version%28, user(, user%28, system_user(, system_user%28, databas
(, database%28, @@hostname, %40%40hostname, @@basedir, %40%40basedir, @@tmpdir, %40%40tmpd
ir, @@datadir,
%40%40datadir:2

Log Threshold: 3
Drop Threshold: 4
```

Trend Micro Deep Security On-Premise 11.3

And this attack string is encountered:

```
productID=BB10735166+UNION/**/+SELECT+FROM+user
```

Then the total score is 5 (2+1+0+2) because:

- The string `UNION/` matches the fourth group for a score of 2.
- The string `/*` matches the sixth group for a score of 1.
- The string `*/` matches the sixth group for a score of 0 (because the score of the sixth group has already been counted).
- The string `SELECT+` matches the second group for a score of 2.

With a total score of 5, a log is generated and the traffic is dropped.

Example 2: No logged or dropped traffic

Let's assume you are using this rule configuration (where the `select\W` string has been moved to the same line as `union\W`):

```
drop table,drop+table,insert into,insert+into,values\W,create
table,create+table,delete\W,update\W,bulk insert,bulk+insert,shutdown\W,from\W:2
declare\W:2
cast\W,exec\W,load_file:2
union\W,select\W,group by,group+by,order by,order+by,having\W:2
and\W,or\W,like\W,is null,is+null,is not null,is+not+null,where\W:1
--, %2D%2D, /*, %2F%2A, */, %2A%2F:1
', %27, \x22, %22, char\W:1
;, %3B:1
%2B, CONCAT\W:1
%3D:1
(, %28, ), %29, @, %40:1
ascii, substring:1
version(, version%28, user(, user%28, system_user(, system_user%28, databas
(, database%28, @@hostname, %40%40hostname, @@basedir, %40%40basedir, @@tmpdir,
%40%40tmpdir, @@datadir, %40%40datadir:2

Log Threshold: 3
Drop Threshold: 4
```

And this attack string is encountered:

```
productID=BB10735166+UNION/**/+SELECT+FROM+user
```

Then the total score is 3 (2+1+0+0) because:

- The string `UNION/` matches the fourth group for a score of 2.
- The string `/**` matches the sixth group for a score of 1.
- The string `*/` matches the sixth group for a score of 0 (because the score of the sixth group has already been counted).
- The string `SELECT+` matches the fourth group for a score of 0 (because the score of the fourth group has already been counted).

With a total score of 3, no log is generated and no traffic is dropped. The score must *exceed* the thresholds for them to take effect.

Configure the Generic SQL Injection Prevention rule

You can configure the Generic SQL Injection Prevention rule to suit your organization's needs. The configurable options are shown in the image below.

Generic SQL Injection Prevention Properties - Microsoft Edge

app.deepsecurity.trendmicro.com/com.trendmicro.ds.network--PayloadFilter2Pro

General

Vulnerability

Details

Configuration

Options

Assigned To

Configuration Options

SQL Injection Patterns. One group per line separated by ','. The score for the group is at the end of the line after ':'. For ',' use '\x2c' and for '"' use '\x22'. The Maximum number of groups is 32.
eg. script, object, embed:2

drop table,drop+table,insert
into,insert+into,values\W,create
table,create+table,delete\W,update\W,bulk
insert,bulk+insert,shutdown\W,from\W:2
declare\W,select\W:2

Drop Threshold (if the score exceeds this value, the connection will be dropped):

4

Log Threshold (if the score exceeds this value, a log will be generated):

4

Max distance between matches (if this many characters go by without seeing a pattern in any group, the score is reset to 0):

35

Note: If Log Threshold is greater or equal to Drop Threshold then only Drop events will be generated. In the default configuration both are equal.

Pages (resource) with a non-default score to drop on. The score for each resource is at the end of the line after ':'. eg. /index.html:5 : (One per line)

/example/questionnaire.html:8

Form parameters with a non-default score to drop on. Each line begins with the resource name followed by the resource parameters separated by a ':'. The score for each parameter is set at the end of the parameter after '='.
eg. /index.html:userid=5,passwd=7 (One per line).

/example/login.html:username=10

View Rules...

OKCancelApply

To configure the rule:

1. Log in to Deep Security Manager.
2. At the top, click **Policies**.
3. In the search box on the right, enter `1000608` which is the Generic SQL Injection Prevention rule's numeric identifier. Press Enter. The rule appears in the main pane.
4. Double-click the rule.
5. Click the **Configuration** tab. You see the SQL injection pattern in the text box at the top.
6. Update the SQL injection pattern with the latest version, if you haven't customized it yet. To update to the latest pattern, go to the **Details** tab, copy the text under the **Default SQL Pattern** heading and paste it into the **SQL Injection Patterns** text box on the **Configuration** tab. You are now working with the most up-to-date pattern from Trend Micro.
7. Edit the fields as follows:
 - **SQL Injection Patterns:** This is where you to specify the list of characters and strings used in SQL injection attacks. Characters and strings are grouped and assigned a score. If you want to add or change the strings, make sure to use the proper encoding. See ["Character encoding guidelines" on the next page](#) below for details.
 - **Drop Threshold:** This is where you specify the drop score. The connection is dropped when the score exceeds this threshold. (If the score equals the drop threshold, the connection is maintained.) The default is `4`.
 - **Log Threshold:** This is where you specify the log score. The connection is logged when the score exceeds this threshold. (If the score equals the log threshold, nothing is logged.) The default is `4`.
 - **Max distance between matches:** This is where you specify the number of bytes that can pass without a match to reset the score to `0`. The default is `35`.
 - **Note:** Consider using the next two options to create overrides for pages and fields that might cause the normal thresholds to be exceeded.
 - **Pages (resource) with a non-default score to drop on:** This is where you can override the **Drop Threshold** for specific resources. For example, if your **Drop Threshold** is `4`, but you want a drop score of `8` for a questionnaire page, specify `/example/questionnaire.html:8`. With this configuration, `/example/questionnaire.html` needs to have a score *higher than* `8` in order for the

connection to be dropped, while all other resources only need a score higher than 4. Specify each resource on a separate line.

- **Form parameters with a non-default score to drop on:** This is where you can override the thresholds defined in **Drop Threshold** or the **Pages (resources) with a non-default score to drop on** fields for specific form fields. For example, if your **Drop Threshold** score is 4, but you want a higher drop score of 10 for a username field, specify `/example/login.html:username=10`, where `/example/login.html` is replaced with the path and name of the page where the username field appears, and `username` is replaced with the username field used by your application. With this configuration, the username field needs to have a score *higher than* 10 for the connection to be dropped, while the page itself only needs a score higher than 4. Specify each form field on a separate line.

Note: The **Log Threshold** does not take effect when connections are dropped due to a match on the **Pages (resources) with a non-default score to drop on** or **Form parameters with a non-default score to drop on** fields. For example, if you set the form parameter field to `/example/login.html:username=10`, and the username field scores 11, the connection is dropped but there is no log of this event.

8. Click **OK**.

You have now configured the Generic SQL Injection Prevention rule.

Character encoding guidelines

If you want to change or add strings to the Generic SQL Injection Prevention rule, you must encode them properly. For example, if you want to use the quote character `'` in your pattern, you must enter `\x22`.

The table below shows characters and their encoded equivalents, as well as character classes that you can use to denote extended patterns.

Enter this string...	To denote...
<code>\a</code>	alphanumeric characters, a-z A-Z

Enter this string...	To denote...
\A	<p>non-alphabetic characters</p> <p>example: <code>delete\A</code> means "the word 'delete' followed by alphabetical characters"</p>
\w \W	<p>alphanumeric characters, a-z A-Z 0-9</p> <p>non-alphanumeric characters</p> <p>example: <code>delete\W</code> means "the word 'delete' followed by non-alphanumeric characters"</p>
\d \D	<p>digits 0-9</p> <p>non-digit characters</p> <p>example: <code>delete\d</code> means "the word 'delete' followed by digits between zero and nine"</p>
\s \S	<p>whitespace</p> <p>not whitespace [r,n,t,0x32]</p> <p>example: <code>delete\S</code> means "the word 'delete' followed by non-whitespace"</p>
\p \P	<p>punctuation character, printable ascii other than above</p> <p>non-punctuation character</p> <p>example: <code>delete\p</code> means "the word 'delete' followed by a punctuation character or printable ascii"</p>
\c \C	<p>control character, below 32, or greater than or equal to 127, not including whitespace</p> <p>non-control character</p>

Enter this string...	To denote...
	You can find details on control characters here .
\.	any
\xDD	hex byte 0xDD
\x2c	comma character (,)
\x22	double-quotes character (")
\\	escaped backslash (\)
\	escaped pipe ()
xx xx xx...	hex pipe (byte sequence)


Application types

The applications defined by Application Types are identified by the direction of traffic, the protocol being used, and the port number through which the traffic passes. Application Types are useful for grouping intrusion prevention rules that have a common purpose. Rule groups simplify the process of selecting a set of intrusion prevention rules to assign to a computer. For example, consider the set of rules required to protect HTTP traffic to an Oracle Report Server. Simply select the rules in the "Web Server Common" and "Web Server Oracle Report Server" application types and then exclude unneeded rules, such as the rules that are specific to IIS servers.

See a list of application types

Open the list of application types where you can see the properties of existing application types, as well as configure, export, and duplicate them. You can export to XML or CSV files. You can import XML files. You can also create and delete application types.

1. Click **Policies > Intrusion Prevention Rules**.
2. Click **Application Types**.
3. To apply a command to an application type, select the type and click the appropriate button.

Tip: Application types that have configurable properties have an icon with a gear. 

See also ["Override rule and application type configurations" on page 745](#).

General Information

The name and description of the Application Type. "Minimum Agent/Appliance Version" tells you what version of the Deep Security **agent or appliance**¹ is required to support this Application Type.

Connection

- **Direction:** The direction of the initiating communication. That is, the direction of the first packet that establishes a connection between two computers. For example, if you wanted to define an Application Type for Web browsers, you would select "Outgoing" because it is the Web browser that sends the first packet to a server to establish a connection (even though you may only want to examine traffic traveling from the server to the browser). The Intrusion Prevention Rules associated with a particular Application Type can be written to examine individual packets traveling in either direction.
- **Protocol:** The protocol this Application Type applies to.
- **Port:** The port(s) this Application Type monitors. (*Not* the port(s) over which traffic is exclusively allowed.)

¹The Deep Security Agent and Deep Security Virtual Appliance are the components that enforce the Deep Security policies that you have defined. Agents are deployed directly on a computer. Appliances are used in VMware vSphere environments to provide agentless protection. They are not available with Deep Security as a Service.

Configuration

The **Configuration** tab displays options that control how Intrusion Prevention Rules associated with this Application Type behave. For example, the "Web Server Common" Application Type has an option to "Monitor responses from Web Server". If this option is deselected, Intrusion Prevention Rules associated with this Application Type will not inspect response traffic.

Options

Items in the **Options** tab control how the Deep Security Manager uses and applies the Application Type. For example, most Application Types have an option to exclude them from Recommendation Scans. This means that if the "Exclude from Recommendations" options is selected, a Recommendation Scan will not recommend this Application Type and its associated Intrusion Prevention Rules for a computer even if the application in question is detected.

Assigned To

The **Assigned To** tab lists the Intrusion Prevention Rules associated with this Application Type.

Inspect SSL or TLS traffic

For the intrusion prevention module, you can configure SSL inspection for a given credential-port pair on one or more interfaces of your protected computer.

Note: Compressed traffic does not support SSL inspection.

Credentials can be imported in PKCS#12 or PEM format. The credential file must include the private key. Windows computers can use CryptoAPI directly.

For an overview of the intrusion prevention module, see ["Block exploit attempts using intrusion prevention" on page 724](#).

In this topic:

- ["Configure SSL inspection" on the next page](#)
- ["Change port settings" on page 762](#)

- ["Use Intrusion Prevention when traffic is encrypted with Perfect Forward Secrecy \(PFS\)" on the next page](#)
- ["Supported ciphers" on page 764](#)
- ["Supported protocols" on page 765](#)

Configure SSL inspection

1. In Deep Security Manager, select the computer to configure and click **Details** to open the computer editor.
2. In the left pane of the computer editor, click **Intrusion Prevention > Advanced > View SSL Configurations**, and click **View SSL Configurations** to open the SSL computer Configurations window.
3. Click **New** to open the SSL Configuration wizard.
4. Specify the interface to which to apply the configuration on this computer:
 - To apply to all interfaces on this computer, select **All Interface(s)**.
 - To apply to specific interfaces, select **Specific Interface(s)**.
5. Select **Port(s)** or **Ports List** and select a list, then click **Next**.
6. On the IP Selection screen, select **All IPs** or provide a **Specific IP** on which to perform SSL inspection, then click **Next**.
7. On the Credentials screen, select how to provide the credentials:
 - **I will upload credentials now**
 - **The credentials are on the computer**

Note: The credential file must include the private key.

8. If you chose the option to upload credentials now, enter their type, location, and pass phrase (if required).

If the credentials are on the computer, provide Credential Details.

- If you are using PEM or PKCS#12 credential formats stored on the computer, identify the location of the credential file and the file's pass phrase (if required).
- If you are using Windows CryptoAPI credentials, choose the credentials from the list of credentials found on the computer.

9. Provide a name and description for this configuration.
10. Review the summary and close the SSL Configuration Wizard. Read the summary of the configuration operation and click **Finish** to close the wizard.

Change port settings

Change the port settings for the computer to ensure that the agent is performing the appropriate intrusion prevention filtering on the SSL-enabled ports. The changes you make are applied to a specific application type, such as Web Server Common, on the agent computer. The changes do not affect the application type on other computers.

1. Go to **Intrusion Prevention Rules** in the computer's Details window to see the list of intrusion prevention rules being applied on this computer.
2. Sort the rules by **Application Type** and locate the "Web Server Common" application type. (You can perform these changes to similar application types as well.)
3. Right-click a rule in the application type and click **Application Type Properties**.
4. Override the inherited "HTTP" Port List so that you include the port you defined during the SSL Configuration setup as well as port 80. Enter the ports as comma-separated values. For example, if you use port 9090 in the SSL configuration, enter 9090, 80.
5. To improve performance, on the **Configuration** tab, deselect **Inherited and Monitor responses from Web Server**.
6. Click **OK** to close the dialog.

Use Intrusion Prevention when traffic is encrypted with Perfect Forward Secrecy (PFS)

[Perfect Forward Secrecy \(PFS\)](#) can be used to create a communication channel that cannot be decrypted if, at a later time, the server's private key is compromised. It relies on the Diffie-Hellman key exchange algorithm which uses ephemeral keys to establish a TLS session. You can identify a server that uses Diffie-Hellman Exchange if its cipher suite contains the string `DHE` (for example, `TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA384`) or `EDH` in some OpenSSL configurations.

Since the intent of Perfect Forward Secrecy is to prevent decryption after the session is over, it also prevents SSL inspection through the Deep Security intrusion prevention module.

To work around this issue, we recommend you do the following:

1. Use Perfect Forward Secrecy for TLS traffic between the Internet and your load balancer (or reverse proxy).
2. Terminate the Perfect Forward Secrecy session at your load balancer (or reverse proxy).
3. Use a non-PFS cipher suite (see "[Supported ciphers](#)" on the next page below) for traffic between the load balancer (or reverse proxy) and the web server or application server, so that the intrusion prevention module on the server can decrypt the TLS sessions and inspect them.
4. Restrict traffic to the web server for application server ports that do not use Perfect Forward Secrecy.

Special considerations for Diffie-Hellman ciphers

On some web servers, Diffie-Hellman ciphers might be the default, so it is important to check the server's configuration file and disable it for TLS traffic between the web server and load balancer (or reverse proxy). For example, to disable Diffie-Hellman on an Apache server:

1. Open the server's configuration file. The file name and location of web server configuration files vary by operating system (OS) and distribution. For example, the path could be:
 - **Default installation on RHEL4:** `/etc/httpd/conf.d/ssl.conf`
 - **Apache 2.2.2 on Red Hat Linux:** `/apache2/conf/extra/httpd-ssl.conf`
2. In the configuration file, find the "`SSLCipherSuite`" variable.
3. Add `!DH:!EDH:!ADH:` to these fields, if this string does not already appear. (The "!" tells Apache to "not" use this cipher.)
4. For example, you might edit the Apache configuration file's cipher suite to look like this:

```
SSLCipherSuite !DH:!EDH:!ADH:!EXPORT56:RC4+RSA:+HIGH:+MEDIUM:+LOW:+SSLv2:+EXP:+eNULL
```

For more information, see the Apache Documentation for `SSLCipherSuite` :

http://httpd.apache.org/docs/2.0/mod/mod_ssl.html#sslcipher suite.

Supported ciphers

Hex Value	OpenSSL Name	IANA Name	NSS Name
0x00,0x04	RC4-MD5	TLS_RSA_WITH_RC4_128_MD5	SSL_RSA_WITH_RC4_128_MD5
0x00,0x05	RC4-SHA	TLS_RSA_WITH_RC4_128_SHA	SSL_RSA_WITH_RC4_128_SHA
0x00,0x09	DES-CBC-SHA	TLS_RSA_WITH_DES_CBC_SHA	SSL_RSA_WITH_DES_CBC_SHA
0x00,0x0A	DES-CBC3-SHA	TLS_RSA_WITH_3DES_EDE_CBC_SHA	SSL_RSA_WITH_3DES_EDE_CBC_SHA
0x00,0x2F	AES128-SHA	TLS_RSA_WITH_AES_128_CBC_SHA	TLS_RSA_WITH_AES_128_CBC_SHA
0x00,0x35	AES256-SHA	TLS_RSA_WITH_AES_256_CBC_SHA	TLS_RSA_WITH_AES_256_CBC_SHA
0x00,0x3C	AES128-SHA256	TLS_RSA_WITH_AES_128_CBC_SHA256	TLS_RSA_WITH_AES_128_CBC_SHA256
0x00,0x3D	AES256-SHA256	TLS_RSA_WITH_AES_256_CBC_SHA256	TLS_RSA_WITH_AES_256_CBC_SHA256
0x00,0x41	CAMELLIA128-SHA	TLS_RSA_WITH_CAMELLIA_128_CBC_SHA	TLS_RSA_WITH_CAMELLIA_128_CBC_SHA
0x00,0x84	CAMELLIA256-SHA	TLS_RSA_WITH_CAMELLIA_256_CBC_SHA	TLS_RSA_WITH_CAMELLIA_256_CBC_SHA

Hex Value	OpenSSL Name	IANA Name	NSS Name
0x00,0xBA	CAMELLIA128-SHA256	TLS_RSA_WITH_CAMELLIA_128_CBC_SHA256	TLS_RSA_WITH_CAMELLIA_128_CBC_SHA256
0x00,0xC0	not implemented	TLS_RSA_WITH_CAMELLIA_256_CBC_SHA256	TLS_RSA_WITH_CAMELLIA_256_CBC_SHA256

Supported protocols

The following protocols are supported:

- SSL 3.0
- TLS 1.0
- TLS 1.1
- TLS 1.2

Configure anti-evasion settings

Anti-evasion settings control the network engine handling of abnormal packets that may be attempting to evade analysis. Anti evasion settings are configured in a policy or an individual computer. The Security Posture setting controls how rigorous intrusion prevention analyzes packets, and can be set to one of the following values:

- **Normal:** Prevents the evasion of intrusion prevention rules without false positives. This is the default value.
- **Strict:** Performs more stringent checking than Normal mode but can produce some false-positive results. Strict mode is useful for penetration testing but should not be enabled under normal circumstances.
- **Custom:** If you select **Custom**, additional settings are available that enable you to specify how Deep Security will handle issues with packets. For these settings (with the exception

of **TCP Timestamp PAWS Window**), the options are **Allow** (Deep Security sends the packet through to the system), **Log Only** (same behavior as Allow, but an event is logged), **Deny** (Deep Security drops the packet and logs an event), or **Deny Silent** (same behavior as Deny, but no event is logged):

Note: If you changed the posture to "Custom" in Deep Security 10.1 or earlier, all default values for the anti-evasion settings were set to "Deny". This led to a dramatic increase in block events. The default custom values have changed in Deep Security 10.2, as indicated in the table below.

Setting	Description	Normal value	Strict value	Default custom value (pre-10.2)	Default custom value (10.2 or later)
Invalid TCP Timestamps	Action to take when a TCP timestamp is too old	Ignore and Log (same function as Log Only)	Deny	Deny	Ignore and Log (same function as Log Only)
TCP Timestamp PAWS Window	Packets can have timestamps. When a timestamp has an earlier timestamp than the one that came before it, it can be suspicious. The tolerance for the difference in timestamps depends on the operating system. For Windows systems, select 0 (the system will only accept packets with a timestamp that is equal to or newer than the previous packet). For Linux systems, select 1 (the system will accept packets with a timestamp that is a maximum of one second earlier than the previous packet).	1 for Linux agents, otherwise 0	1 for Linux agents, otherwise 0	0	1 for Linux agents, otherwise 0
Timestamp PAWS Zero Allowed	Action to take when a TCP timestamp is zero	Deny for Linux agents or NDIS5, otherwise Allow	Deny for Linux agents or NDIS5, otherwise Allow	Deny	Deny for Linux agents or NDIS5, otherwise Allow

Setting	Description	Normal value	Strict value	Default custom value (pre-10.2)	Default custom value (10.2 or later)
Fragmented Packets	Action to take when a packet is fragmented	Allow	Allow	Deny	Allow
TCP Zero Flags	Action to take when a packet has zero flags set	Deny	Deny	Deny	Deny
TCP Congestion Flags	Action to take when a packet has congestion flags set	Allow	Allow	Deny	Allow
TCP Urgent Flags	Action to take when a packet has urgent flags set	Allow	Deny	Deny	Allow
TCP Syn Fin Flags	Action to take when a packet has both SYN and FIN flags set	Deny	Deny	Deny	Deny
TCP Syn Rst Flags	Action to take when a packet has both SYN and RST flags set	Deny	Deny	Deny	Deny
TCP Rst Fin Flags	Action to take when a packet has both RST and FIN flags set	Deny	Deny	Deny	Deny
TCP Syn with Data	Action to take when a packet has a SYN flag set and also contains data	Deny	Deny	Deny	Deny
TCP Split Handshake	Action to take when a SYN is received instead of SYNACK, as a reply to a SYN.	Deny	Deny	Deny	Deny
RST Packet Out of Connection	Action to take for a RST packet without a known connection	Allow	Deny	Deny	Allow
FIN Packet Out of Connection	Action to take for a FIN packet without a known connection	Allow	Deny	Deny	Allow
OUT Packet Out of Connection	Action to take for an outgoing packet without a known connection	Allow	Deny	Deny	Allow

Setting	Description	Normal value	Strict value	Default custom value (pre-10.2)	Default custom value (10.2 or later)
Evasive Retransmit	Action to take for a packet with duplicated or overlapping data	Allow	Deny	Deny	Allow
TCP Checksum	Action to take for a packet with an invalid checksum	Allow	Deny	Deny	Allow

Performance tips for intrusion prevention

To improve system resources utilization on Deep Security Agent, optimize certain performance-related settings.

For an overview of the intrusion prevention module, see ["Block exploit attempts using intrusion prevention" on page 724](#).

System resource	Settings that impact performance
CPU usage	<ul style="list-style-type: none"> Log an event when a packet is dropped or blocked. Logging packet modifications may result in a lot of log entries. (See "Configure event logging for rules" on page 741) Include packet data in the event log only during troubleshooting. (See "Configure event logging for rules" on page 741) Assign only intrusion prevention rules that apply to the computer's OS and applications. See "Manage and run recommendation scans" on page 529 for information about using recommendation scans to discover applicable vulnerabilities and rules. Don't assign more than 300 rules.
Network usage or throughput	<ul style="list-style-type: none"> Log an event when a packet is dropped or blocked. Logging packet modifications may result in a lot of log entries. (See "Configure event

System resource	Settings that impact performance
	<p>logging for rules" on page 741)</p> <ul style="list-style-type: none"> • Include packet data in the event log only during troubleshooting. (See "Configure event logging for rules" on page 741) • Do not monitor HTTP responses from the web server, especially if the policy has many signatures applied: <ul style="list-style-type: none"> a. Click Policies > Intrusion Prevention Rules. b. Right-click a rule in the Web Server Common application type and click Application Type Properties. c. On the Configuration tab, deselect Inherited and Monitor responses from Web Server.
Disk usage	<ul style="list-style-type: none"> • Include packet data in the event log only during troubleshooting. (See "Configure event logging for rules" on page 741)

Maximum size for configuration packages

When an agent is assigned a large number of intrusion prevention rules, the size of the configuration package can exceed the maximum allowed size. When the allowed size is exceeded, the status of the agent changes to "Agent configuration package too large" and the event message "Configuration package too large" appears.

Note: There is a configuration limit of 20 MB in Windows 32-bit platform because it has smaller kernel memory available. For other platforms, the limit is 32 MB.

For performance reasons, you should have less than 350 intrusion prevention rules assigned to a computer. To minimize the number of required rules, ensure all available patches are applied to the computer operation system and any third-party software that is installed.

1. Apply available patches to the computer operating system.
2. Apply available patches to any third-party software that is installed.

3. Apply only the intrusion prevention rules that a recommendation scan recommends. Remove any rules from the computer or the assigned policy that are recommended for unassignment. (See ["Manage and run recommendation scans" on page 529.](#))
4. If you are managing intrusion prevention at the policy level and the configuration package is still too large, configure intrusion prevention in one of the following ways:
 - Make the policy more granular, so that all servers in that policy have the same operating system and applications.
 - Manage intrusion prevention at the server level so that rules are added and removed automatically for the computer.

Use the following procedure to manage intrusion prevention at the server level.

1. Open the editor for the policy that is assigned to the computer.
2. Click **Intrusion Prevention > General**.
3. In the **Recommendations** section, set **Automatically implement Intrusion Prevention Recommendations (when possible)** to **Yes**.
4. Remove any intrusion prevention rules from the policy.
5. Run a recommendation scan on the computer.

Control endpoint traffic using the firewall

The firewall module provides bidirectional stateful inspection of incoming and outgoing traffic. Firewall rules define what actions to take on individual packets in that traffic. Packets can be filtered by IP and MAC address, port and packet flag across all IP-based protocols and frame types. The firewall module can also help prevent denial of service attacks and detect and prevent reconnaissance scans.

To enable and configure the firewall, see ["Set up the Deep Security firewall" on the next page.](#)

Firewall rules

Firewall rules can process traffic using one of the following actions, listed in order of precedence:

- Bypass
- Log Only
- Force Allow
- Deny
- Allow

Rules also have a priority level between 4 (highest priority) to 0 (lowest priority). Within a specific priority level rules are processed in order based on the precedence of the action type of the rule as listed above. This means that unlike what you may have experienced when configuring other firewalls, the Deep Security firewall processes rules independently of their assignment order.

For more information on how rule priorities and actions determine processing order, see ["Firewall rule actions and priorities" on page 794](#).

For more detailed information on how to create firewall rules, see ["Create a firewall rule" on page 786](#).

Note: When creating your rules, make sure to test them using the Tap and Inline modes of the firewall module before deploying them. For information on how to do so, see the "Test firewall rules before deploying them" section of ["Set up the Deep Security firewall" below](#).

Set up the Deep Security firewall

The Deep Security Firewall is a highly flexible Firewall that you can configure to be restrictive or permissive. Like the intrusion prevention and web reputation modules, the Firewall module can also be run in two modes: inline or tap. It is recommended that you test your Firewall rules in tap mode and then switch to inline mode when everything is working correctly.

The configuration and administration of your Firewall must be performed carefully and there is no one set of rules that fits all environments. Make sure you understand the Firewall rule actions and rule priorities before creating your rules and proceed with extra caution when creating Allow rules because they implicitly deny everything else not defined.

In this article:

- ["Test Firewall rules before deploying them" below](#)
- ["Enable 'fail open' behavior" on page 774](#)
- ["Turn on Firewall " on page 775](#)
- ["Default Firewall rules" on page 776](#)
- ["Restrictive or permissive Firewall design" on page 778](#)
- ["Firewall rule actions" on page 778](#)
- ["Firewall rule priorities" on page 779](#)
- ["Recommended Firewall policy rules" on page 780](#)
- ["Test Firewall rules" on page 781](#)
- ["Reconnaissance scans" on page 782](#)
- ["Stateful inspection" on page 783](#)
- ["Example" on page 784](#)
- ["Important things to remember" on page 785](#)

Test Firewall rules before deploying them

The Firewall module (as well as the intrusion prevention and web reputation modules) includes a Deep Security network engine that decides whether to block or allow packets. For the Firewall and intrusion prevention modules, the network engine performs a packet sanity check and also makes sure each packet passes the Firewall and intrusion prevention rules. The network engine operates in one of two modes:

- **Tap mode:** Packet streams are not modified. The traffic is still processed by the Firewall and/or intrusion prevention modules, if they are enabled. However any issues detected do not result in packet or connection drops. When in Tap mode, Deep Security offers no protection beyond providing a record of events.
- **Inline mode:** Packet streams pass directly through the Deep Security network engine. All rules are applied to the network traffic before they proceed up the protocol stack.

It's important to test your Firewall rules in either Tap mode or Inline mode with the action for the rules set to Log Only before deploying them. This allows you to preview the effect of the rules on

traffic, without any action being taken. If rules aren't properly tested before deployment, all traffic could become blocked and your computer could become inaccessible.

Test in Tap mode

Tap mode allows you to test your Firewall rules, without disturbing the flow of traffic.

1. Go to **Computers** or **Policies** in the Deep Security Manager.
2. Right-click a computer (or policy) and select **Details** to open the **Computer or Policy editor**¹.
3. Go to **Settings > Advanced > Network Engine Mode**.
4. Select **Tap** from the list and click **Save**.
5. Create your rules and click **OK**. To check your rules, go to **Events & Reports > Events > Firewall Events**.

Note: It is not necessary to set the action of the rule to Log Only in Tap mode.

Once you are satisfied with your Firewall rules, go back to the **Computer or Policy editor**², select **Inline** from the drop-down list, and click **Save**.

Test in Inline mode

In most situations, Tap mode is a good way to test your Firewall rules without disturbing traffic. However, you can also test your rules in Inline mode, if the action of the rule is set to Log Only. This way, the real world process of analyzing the traffic takes place without having to perform any action, such as blocking or denying packets.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

1. Go to **Computers** or **Policies** in the Deep Security Manager.
2. Right-click a computer (or policy) and select **Details** to open the **Computer or Policy editor**¹.
3. Go to **Settings > Advanced > Network Engine Mode**.
4. Select **Inline** from the drop down menu and click **Save**.
5. While you're creating your rule, ensure the action is set to **Log Only**.
6. To check your rules, go to **Events & Reports > Events > Firewall Events**.

Once you are satisfied with your Firewall rules, change the action from Log Only to your desired action and click **OK**.

Enable 'fail open' behavior

In some cases, the network engine blocks packets before the Firewall rules (or intrusion prevention rules) can be applied. By default, the network engine blocks packets if the:

- agent or virtual appliance has a system problem, such as if it's out of memory
- packet sanity check fails

This 'fail closed' behavior offers a high level of security: it ensures that cyber attacks cannot penetrate your network when an agent or virtual appliance is not functioning properly, and safeguards against potentially malicious packets. The disadvantage to 'fail closed' is that your services and applications might become unavailable because of problems on the agent or virtual appliance. You might also experience performance issues if a large number of packets are being dropped unnecessarily as a result of the packet sanity check (too many false-positives).

If you have concerns about service availability, consider changing the default behavior to allow packets through (or 'fail open') for system and packet check failures, as explained below.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

1. Go to **Computers** or **Policies** in the Deep Security Manager.
2. Right-click a computer (or policy) and select **Details** to open the **Computer or Policy editor**¹.
3. Click **Settings** on the left.
4. Click the **Advanced** tab.
5. Under **Network Engine Settings**, set the **Failure Response** settings as follows:
6. Set **Network Engine System Failure** to **Fail open** to allow packets through if the Deep Security network engine experiences problems, such as out-of-memory failures, allocated memory failures, and network engine deep packet inspection (DPI) decoding failures. Consider using fail open here if your agent or virtual appliance frequently encounters network exceptions because of heavy loads or a lack of resources. With fail open, the network engine allows the packet through, does not perform rules checking, and logs an event. Your services and applications remain available despite the problems on the agent or virtual appliance.
7. Set **Network Packet Sanity Check Failure** to **Fail open** to allow packets through that fail the network engine's packet sanity checks. Examples of packet sanity checks: Firewall sanity checks, network layer 2, 3, or 4 attribute checks, and TCP state checks. Consider using fail open here if you want to do rules checking only on 'good' packets that pass the sanity check. With fail open, the network engine allows the failed packet through, does not perform rules checking on it, and logs an event.
8. Click **Save**.

You have now enabled fail open behavior for system or packet check failures.

Turn on Firewall

To enable Firewall functionality on a computer:

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).


1. In the **Computer or Policy editor**¹, go to **Firewall > General**.
2. With Deep Security Agent 11.1 and earlier, the Firewall module inspects traffic that passes through the host computer's network interface to containers. With Deep Security Agent 11.2 or later, it can also inspect traffic between containers. When the **Scan container network traffic** setting is set to **Yes**, Deep Security scans the traffic that goes through both containers and hosts. When it is set to **No**, Deep Security scans only the traffic that goes through the host network interface.
3. Select **On** and then click **Save**.

Default Firewall rules

No outbound rules are assigned to the policies that come with Deep Security by default but several recommended inbound rules are. You can view the default inbound rules assigned to each policy by going to the **Firewall** tab in the relevant operating system policy. The example below shows the default assigned Firewall rules for the Windows 10 Desktop policy. You can configure these Firewall rules to meet the needs of your environment, but we have provided several default rules for you to get you started.

Tip: To minimize the impact on system performance, try not to assign more than 300 Firewall rules. It is also good practice to document all Firewall rule changes in the "Description" field of the Firewall rule. Make a note of when and why rules were created or deleted for easier Firewall maintenance.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).



Default Bypass rule for Deep Security Manager Traffic

The Deep Security Manager automatically implements a **Priority 4 Bypass Rule** that opens the listening port number of the agent for heartbeats on computers running Deep Security Agent. A priority of 4 ensures that this rule is applied before any Deny rule, and Bypass guarantees that the traffic is never impaired. The Bypass rule is not explicitly shown in the Firewall rule list because the rule is created internally.

This rule, however, accepts traffic from any IP address and any MAC address. To harden the Deep Security Agent's listening ports, you can create an alternative, more restrictive, Bypass rule for this port. The agent will override the default Deep Security Manager traffic rule with the new custom rule if it has these settings:

- **Priority:** 4 - Highest
- **Packet direction:** Incoming
- **Frame type:** IP

- **Protocol:** TCP
- **Packet Destination Port:** [Agent's listening port for heartbeats](#)

The custom rule must use the above parameters to replace the default rule. Ideally, the IP address or MAC address of the actual Deep Security Manager should be used as the packet source for the rule.

Restrictive or permissive Firewall design

Typically, Firewall policies are based on one of two design strategies. Either they permit any service unless it is expressly denied or they deny all services unless expressly allowed. It is best practice to decide what type of Firewall you would like to implement. This helps reduce administrative overhead in terms of creating and maintaining the rules.

Restrictive Firewall

A restrictive Firewall is the recommended best practice from a security perspective. All traffic is stopped by default and only traffic that has been explicitly allowed is permitted. If the primary goal of your planned Firewall is to block unauthorized access, the emphasis needs to be on restricting rather than enabling connectivity. A restrictive Firewall is easier to maintain and more secured. Allow rules are used only to permit certain traffic across the Firewall and deny everything else.

Note: As soon as you assign a single outgoing Allow rule, the outgoing Firewall will operate in restrictive mode. This is also true for the inbound Firewall: as soon as you assign a single incoming Allow rule, the inbound Firewall will operate in restrictive mode.

Permissive Firewall

A permissive Firewall permits all traffic by default and only blocks traffic believed to be malicious based on signatures or other information. A permissive Firewall is easy to implement but it provides minimal security and requires complex rules. Deny rules are used to explicitly block traffic.

Firewall rule actions

You can configure the Firewall to take the following actions:

Warning: If you assign only incoming rules, all outgoing traffic will be allowed. If you assign a single outgoing Allow rule, the outgoing Firewall will operate in restrictive mode. There is one exception to this: ICMPv6 traffic is always permitted unless it is specifically blocked by a Deny rule.

Allow	<p>Explicitly allows traffic that matches the rule to pass and then implicitly denies everything else.</p> <p>Note: You should use an Allow action with caution because it implicitly denies everything else not defined. Be careful when creating Allow rules without defining the related rules correctly because doing so can cause all traffic to be blocked except for the traffic that the Allow rule is created for. Traffic that is not explicitly allowed by an Allow rule is dropped and gets recorded as a 'Out of "allowed" Policy' Firewall event.</p>
Bypass	<p>Allows traffic to bypass both Firewall and intrusion prevention analysis. Bypass rules should always be created in pairs (for both incoming and outgoing traffic). A Bypass rule can be based on IP, port, traffic direction, and protocol.</p> <p>The Bypass rule is designed for media-intensive protocols or traffic originating from trusted sources.</p>
Deny	Explicitly blocks traffic that matches the rule.
Force Allow	<p>If a packet matches a force allow rule, it is passed but still filtered by intrusion prevention. No events are logged.</p> <p>This type of Firewall rule action must be used for UDP and ICMP traffic.</p>
Log only	Traffic will only be logged. No other action will be taken.

For more information on how to create a Firewall rule, see ["Create a firewall rule" on page 786](#).

Firewall rule priorities

Rule priority determines the order in which filters are applied. This means that high priority rules get applied before low priority rules. When actions share the same priority, the orders of precedence for rules are: Bypass, Force Allow, and then Deny. However, a Deny action with a

higher priority will take precedence over a Bypass action with a lower priority. For more information on how rule priorities and actions determine processing order, see ["Firewall rule actions and priorities" on page 794](#).

To simplify the administration of Firewall rules, consider reserving certain priority levels for specific actions. For example, apply a default of priority 3 to rules that use Bypass, priority 2 for Force Allow rules, and priority 1 for Deny rules. This reduces the potential for rule conflicts.

Allow rules

Allow rules can only have a priority of 0. This is to ensure it is processed after all Force Allow and Deny rules at higher priorities. Keep this in mind when using Allow rules to implicitly deny traffic (any traffic not matching the Allow rules are denied). This means that when a Deny rule is assigned, it will take precedence over all of the existing assigned Allow rules.

Force Allow rules

Force Allow rules are recommended for traffic that must always be allowed, such as Address Resolution Protocol (ARP). The Force Allow action only acts as a trump card to a deny rule at the same or higher priority. For example, if you have a Deny rule at priority 3 that prevents access to an allowed port number from the 10.0.0.0/8 subnet, and you want to allow host 10.102.12.56 to access that, you must create a Force Allow rule at priority 3 or 4 to trump the Deny rule at priority 3. Once a packet triggers this rule, it is immediately allowed and the lower priority rules will not process it anymore.

Bypass rules

The Bypass rule is a special type of rule that allows a packet to bypass both the Firewall and Deep Packet Inspection (DPI) engines. This rule must be priority 4 and created in pairs, one rule for each traffic direction.

Recommended Firewall policy rules

We recommend that you make the following rules mandatory for all of your Firewall policies:

- **ARP:** Allows incoming ARP requests so that the computer can reply to queries for its MAC address. If you do not assign this rule, no devices on the network can query the host for its

MAC address and it will be inaccessible from the network.

- **Allow solicited TCP/UDP replies:** Allows the computer to receive replies to its own TCP connections and UDP messages. This works in conjunction with TCP and UDP stateful Firewall configuration.
- **Allow solicited ICMP replies:** Allows the computer to receive replies to its own ICMP messages. This works in conjunction with ICMP stateful Firewall configuration.
- **DNS Server:** Allows DNS servers to receive inbound DNS queries.
- **Remote Access RDP:** Allows the computer to accept Remote Desktop connections.
- **Remote Access SSH:** Allows the computer to accept SSH connections.

Test Firewall rules

Before continuing with further Firewall configuration steps, test the recommended Firewall rules to ensure they're working correctly.

Test the remote access SSH rule:

1. Try to establish a SSH connection to the computer. If the Firewall is enabled and the Remote Access SSH rule is not enabled, the connection will be denied. Go to **Events & Reports > Firewall Events** to view the denied event.
2. Go to the **Computer or Policy editor**¹ > **Firewall**. Under **Assigned Firewall Rules**, click **Assign/Unassign**.
3. Search for Remote Access SSH and enable the rule. Click **OK** and **Save**.
4. Try to establish a SSH connection to the computer. The connection should be allowed.

Test the remote access RDP rule:

1. Try to establish a RDP connection to the computer. If the Firewall is enabled and the Remote Access RDP rule is not enabled, the connection will be denied. Go to **Events & Reports > Firewall** events to view the denied event.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

2. Go to the **Computer or Policy editor**¹ > **Firewall**. Under **Assigned Firewall Rules**, click **Assign/Unassign**.
3. Search for Remote Access RDP and enable the rule. Click **OK** and **Save**.
4. Try to establish a RDP connection to the computer. The connection should be allowed.

Reconnaissance scans

You can configure the Firewall to detect possible reconnaissance scans and help prevent attacks by blocking traffic from the source IPs for a period of time. Once an attack has been detected, you can instruct agents and appliances to block traffic from the source IPs for a period of time. Use the Block Traffic lists on the **Policy or Computer Editor > Firewall > Reconnaissance** tab to set the number of minutes.

- **Computer OS Fingerprint Probe:** The agent or appliance detects an attempt to discover the computer's OS.
- **Network or Port Scan:** The agent or appliance reports a network or port scan if it detects that a remote IP is visiting an abnormal ratio of IPs to ports. Normally, an agent or appliance computer will only see traffic destined for itself, so a port scan is the most common type of probe that will be detected. The statistical analysis method used in computer or port scan detection is derived from the "TAPS" algorithm proposed in the paper "Connectionless Port Scan Detection on the Backbone" presented at IPCCC in 2006.
- **TCP Null Scan:** The agent or appliance detects packages with no flags set.
- **TCP SYNFIN Scan:** The agent or appliance detects packets with only the SYN and FIN flags set.
- **TCP Xmas Scan:** The agent or appliance detects packets with only the FIN, URG, and PSH flags set or a value of 0xFF (every possible flag set).

For each type of attack, the agent or appliance can be instructed to send the information to the Deep Security Manager where an alert will be triggered by selecting the option **Notify DSM**

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Immediately. For this option to work, the agents and appliances must be configured for agent or appliance-initiated or bidirectional communication in **Policy / Computer Editor > Settings > Computer.**) If enabled, the agent or appliance will initiate a heartbeat to the Deep Security Manager immediately upon detecting the attack or probe.

Note: If you want to enable reconnaissance protection, you must also enable the Firewall and stateful inspection on the **Policy or Computer Editor > Firewall > General** tab. You should also go to the **Policy or Computer Editor > Firewall > Advanced** tab and enable the **Generate Firewall Events** for packets that are 'Out of Allowed Policy' setting. This will generate Firewall events that are required for reconnaissance.

Note: The reconnaissance scans detection requires there to be at least one active Firewall rule assigned to the policy of the agent.

For information on how to handle reconnaissance warnings, see ["Warning: Reconnaissance Detected" on page 1304](#).

Stateful inspection

Deep Security Firewall stateful configuration mechanism should be enabled when the Firewall is on. This mechanism analyzes each packet in the context of traffic history, correctness of TCP and IP header values, and TCP connection state transitions. In the case of stateless protocols like UDP and ICMP, a pseudo-stateful mechanism is implemented based on historical traffic analysis.

Packets are handled by the stateful mechanism as follows:

1. A packet is passed to the stateful routine if it has been allowed through by the static Firewall rule conditions.
2. The packet is examined to determine whether it belongs to an existing connection.
3. The TCP header is examined for correctness (for example, sequence numbers, flag combinations, and so on).

The Deep Security Firewall stateful configuration enables protection against attacks such as denial of service, provided that a default configuration with stateful TCP, ICMP, or UDP protocol is enabled and only solicited replies are allowed. If the UDP stateful option is enabled, Force

Allow must be used when running UDP servers (for example, DHCP). If there is no DNS or WINS server configured for the Deep Security Agents, a Force Allow Incoming UDP Ports 137 rule might be required for NetBIOS.

Stateful logging should be disabled unless required for ICMP or UDP protocols.

Example

This is an example of how a simple Firewall policy can be created for a web server:

1. Enable stateful inspection for TCP, UDP, and ICMP using a global Firewall stateful configuration with these options enabled.
2. Add a Firewall rule to allow TCP and UDP replies to requests originated on the workstation. To do this create an incoming Allow rule with the protocol set to **TCP + UDP** and select **Not** and **Syn** under **Specific Flags**. At this point the policy only allows TCP and UDP packets that are replies to requests initiated by a user on the workstation. For example, in conjunction with the stateful analysis options enabled in step 1, this rule allows a user on this computer to perform DNS lookups (via UDP) and to browse the Web via HTTP (TCP).
3. Add a Firewall rule to allow ICMP replies to requests originated on the workstation. To do this, create an incoming Allow rule with the protocol set to **ICMP** and select the **Any Flags** check box. This means that a user on this computer can ping other workstations and receive a reply but other users will not be able to ping this computer.
4. Add a Firewall rule to allow incoming TCP traffic to port 80 and 443 with the **Syn** check box checked in the **Specific Flags** section. This means that external users can access a Web server on this computer.

At this point we have a basic Firewall policy that allows solicited TCP, UDP and ICMP replies and external access to the Web server on this computer all other incoming traffic is denied.

For an example of how Deny and Force Allow rule actions can be used to further refine this policy consider how we may want to restrict traffic from other computers in the network. For example, we may want to allow access to the Web server on this computer to internal

users but deny access from any computers that are in the DMZ. This can be done by adding a Deny rule to prohibit access from servers in the DMZ IP range.

5. Add a Deny rule for incoming TCP traffic with source IP 10.0.0.0/24 which is the IP range assigned to computers in the DMZ. This rule denies any traffic from computers in the DMZ to this computer.

We may, however, want to refine this policy further to allow incoming traffic from the mail server which resides in the DMZ.

6. Use a Force Allow for incoming TCP traffic from source IP 10.0.0.100. This Force Allow overrides the Deny rule we created in the previous step to permit traffic from this one computer in the DMZ.

Important things to remember

- All traffic is first checked against Firewall rules before being analyzed by the stateful inspection engine. If the traffic clears the Firewall rules, the traffic is then analyzed by the stateful inspection engine (provided stateful inspection is enabled in the Firewall Stateful Configuration).
- Allow rules are prohibitive. Anything not specified in the Allow rules is automatically dropped. This includes traffic of other frame types so you need to remember to include rules to allow other types of required traffic. For example, don't forget to include a rule to allow ARP traffic if static ARP tables are not in use.
- If UDP stateful inspection is enabled a Force Allow rule must be used to allow unsolicited UDP traffic. For example, if UDP stateful inspection is enabled on a DNS server then a Force Allow for port 53 is required to allow the server to accept incoming DNS requests.
- If ICMP stateful inspection is enabled a Force Allow rule must be used to allow unsolicited ICMP traffic. For example, if you wish to allow outside ping requests a Force Allow rule for ICMP type 3 (Echo Request) is required.
- A Force Allow acts as a trump card only within the same priority context.
- If you do not have a DNS or WINS server configured (which is common in test environments) a "Force Allow incoming UDP port 137" rule may be required for NetBIOS (Windows shares).

Note: When troubleshooting a new Firewall policy the first thing you should do is check the Firewall rule logs on the **agent or appliance**¹. The Firewall rule logs contain all the information you need to determine what traffic is being denied so that you can further refine your policy as required.

Create a firewall rule

Firewall rules examine the control information in individual packets, and either block or allow them according to the criteria that you define. Firewall rules can be assigned to a policy or directly to a computer.

Note: This article specifically covers how to create a firewall rule. For information on how to configure the firewall module, see ["Set up the Deep Security firewall" on page 771](#).

To create a new firewall rule, you need to:

1. ["Add a new rule" below](#).
2. ["Select the behavior and protocol of the rule" on the next page](#).
3. ["Select a Packet Source and Packet Destination" on page 789](#).

When you're done with your firewall rule, you can also learn how to:

- ["Configure rule events and alerts" on page 791](#)
- ["Set a schedule for the rule" on page 791](#)
- ["See policies and computers a rule is assigned to" on page 792](#)
- ["Assign a context to the rule " on page 791](#)

Add a new rule

There are three ways to add a new firewall rule on the **Policies > Common Objects > Rules > Firewall Rules** page. You can:

¹The Deep Security Agent and Deep Security Virtual Appliance are the components that enforce the Deep Security policies that you have defined. Agents are deployed directly on a computer. Appliances are used in VMware vSphere environments to provide agentless protection. They are not available with Deep Security as a Service.

- Create a new rule. Click **New > New Firewall Rule**.
- Import a rule from an XML file. Click **New > Import From File**.
- Copy and then modify an existing rule. Right-click the rule in the Firewall Rules list and then click **Duplicate**. To edit the new rule, select it and then click **Properties**.

Select the behavior and protocol of the rule

1. Enter a **Name** and **Description** for the rule.

Tip: It is good practice to document all firewall rule changes in the Description field of the firewall rule. Make a note of when and why rules were created or deleted for easier firewall maintenance.

2. Select the **Action** that the rule should perform on packets. You can select from one of the following five actions:

Note: Only one rule action is applied to a packet, and rules (of the same priority) are applied in the order of precedence listed below.

- The rule can allow traffic to **bypass** the firewall. A bypass rule allows traffic to pass through the firewall and intrusion prevention engine at the fastest possible rate. Bypass rules are meant for traffic using media intensive protocols where filtering may not be desired or for traffic originating from trusted sources.

Tip: For an example of how to create and use a bypass rule for trusted sources in a policy, see "[Allow trusted traffic to bypass the firewall](#)" on page 792.

Note: Bypass rules are unidirectional. Explicit rules are required for each direction of traffic.

Tip: You can achieve maximum throughput performance on a bypass rule with the following settings:

- **Priority:** Highest
- **Frame Type:** IP

- **Protocol:** TCP, UDP, or other IP protocol. (Do not use the "Any" option.)
- **Source and Destination IP and MAC:** all "Any"
- If the protocol is TCP or UDP and the traffic direction is "incoming", the destination ports must be one or more specified ports (not "Any"), and the source ports must be "Any".
- If the protocol is TCP or UDP and the traffic direction is "outgoing", the source ports must be one or more specified ports (Not "Any"), and the destination ports must be "Any".
- **Schedule:** None.

- The rule can **log only**. This action will make entries in the logs but will not process traffic.
- The rule can **force allow** defined traffic (it will allow traffic defined by this rule without excluding any other traffic.)
- The rule can **deny** traffic (it will deny traffic defined by this rule.)
- The rule can **allow** traffic (it will exclusively allow traffic defined by this rule.)

Note: If you have no allow rules in effect on a computer, all traffic is permitted unless it is specifically blocked by a deny rule. Once you create a single allow rule, all other traffic is blocked unless it meets the requirements of the allow rule. There is one exception to this: ICMPv6 traffic is always permitted unless it is specifically blocked by a deny rule.

3. Select the **Priority** of the rule. The priority determines the order in which rules are applied. If you have selected "force allow", "deny", or "bypass" as your rule action, you can set a priority of 0 (low) to 4 (highest). Setting a priority allows you to combine the actions of rules to achieve a cascading rule effect.

Note: Log only rules can only have a priority of 4, and Allow rules can only have a priority of 0.

Note: High priority rules get applied before low priority rules. For example, a port 80 incoming deny rule with a priority of 3 will drop a packet before a port 80 incoming force allow rule with a priority of 2 gets applied to it.

For detailed information on how actions and priority work together, see ["Firewall rule actions and priorities" on page 794](#).

4. Select a **Packet Direction**. Select whether this rule will be applied to **incoming** (from the network to the computer) or **outgoing** (from the computer to the network) traffic.

Note: An individual firewall rule only apply to a single direction of traffic. You may need to create incoming and outgoing firewall rules in pairs for specific types of traffic.

5. Select an Ethernet **Frame Type**. The term "frame" refers to Ethernet frames, and the available protocols specify the data that the frame carries. If you select "Other" as the frame type, you need to specify a [frame number](#).

6. **Note:** IP covers both IPv4 and IPv6. You can also select **IPv4** or **IPv6** individually

Note: Linux Agents will only examine packets with IP or ARP frame types. Packets with other frame types will be allowed through. Note that the Virtual Appliance does not have these restrictions and can examine all frame types, regardless of the operating system of the virtual machine it is protecting.

If you select the Internet Protocol (IP) frame type, you need to select the transport **Protocol**. If you select "Other" as the protocol, you also need to enter a [protocol number](#).

Select a Packet Source and Packet Destination

Select a combination of **IP** and **MAC** addresses, and if available for the frame type, **Port** and **Specific Flags** for the Packet Source and Packet Destination.

Tip: You can use a previously created [IP](#), [MAC](#) or [port](#) list.

Support for IP-based frame types is as follows:

	IP	MAC	Port	Flags
Any	✓	✓		
ICMP	✓	✓		✓
ICMPV6	✓	✓		✓
IGMP	✓	✓		
GGP	✓	✓		
TCP	✓	✓	✓	✓
PUP	✓	✓		
UDP	✓	✓	✓	
IDP	✓	✓		
ND	✓	✓		
RAW	✓	✓		
TCP+UDP	✓	✓	✓	✓

Note: ARP and REVARP frame types only support using MAC addresses as packet sources and destinations.

You can select **Any Flags** or individually select the following flags:

- URG
- ACK
- PSH
- RST
- SYN
- FIN

Configure rule events and alerts

When a firewall rule is triggered, it logs an event in the Deep Security Manager and records the packet data.

Note: Note that rules using the "Allow", "Force Allow" and "Bypass" actions will not log any events.

Alerts

You can configure rules to also trigger an alert if they log an event. To do so, open the properties for a rule, click on **Options**, and then select **Alert when this rule logs an event**.

Note: Only firewall rules with an action set to "Deny" or "Log Only" can be configured to trigger an alert.

Set a schedule for the rule

Select whether the firewall rule should only be active during a scheduled time.

For more information on how to do so, see ["Define a schedule that you can apply to rules" on page 625](#).

Assign a context to the rule

Rule contexts allow you to set firewall rules uniquely for different network environments. Contexts are commonly used to allow for different rules to be in effect for laptops when they are on and off-site.

For more information on how to create a context, see ["Define contexts for use in policies" on page 618](#).

Tip: For an example of a policy that implements firewall rules using contexts, look at the properties of the "Windows Mobile Laptop" Policy.

See policies and computers a rule is assigned to

You can see which policies and computers are assigned to a firewall rule on the **Assigned To** tab. Click on a policy or computer in the list to see their properties.

Export a rule

You can export all firewall rules to a .csv or .xml file by clicking **Export** and selecting the corresponding export action from the list. You can also export specific rules by first selecting them, clicking **Export** and then selecting the corresponding export action from the list.

Delete a rule

To delete a rule, right-click the rule in the Firewall Rules list, click **Delete** and then click **OK**.

Note: Firewall Rules that are assigned to one or more computers or that are part of a policy cannot be deleted.

Allow trusted traffic to bypass the firewall

You can set up Deep Security to allow trusted traffic to bypass the firewall.

To configure this, the basic steps are as follows:

1. ["Create a new IP list of trusted traffic sources" below](#)
2. ["Create incoming and outbound firewall rules for trusted traffic using the IP list" on the next page](#)
3. ["Assign the firewall rules to a policy used by computers that trusted traffic flows through" on the next page](#)

After the firewall rules have been assigned to a policy, Deep Security will allow traffic from trusted sources in the IP list and will not scan the traffic for stateful issues or vulnerabilities.

Create a new IP list of trusted traffic sources

1. Click **Policies**.
2. In the left pane, click **Lists > IP Lists**.

3. Click **New > New IP List**.
4. Enter a name for the IP list.
5. Paste the IP addresses for your trusted sources into the **IP(s)** box, one per line.
6. Click **OK**.

Create incoming and outbound firewall rules for trusted traffic using the IP list

1. Click **Policies**.
2. In the left pane, click **Rules**.
3. Click **Firewall Rules > New > New Firewall Rule**.
4. Create a firewall rule for incoming trusted traffic using the values in the below:

Name:	<i>source name</i> Traffic - Incoming
Action:	Bypass
Protocol:	Any
Packet Source:	IP List (select the IP list created above)

5. Create a firewall rule for outgoing trusted traffic using the values in the below:

Name:	<i>source name</i> Traffic - Outgoing
Action:	Bypass
Protocol:	Any
Packet Destination:	IP List (select the IP list created above)

Assign the firewall rules to a policy used by computers that trusted traffic flows through

1. Click **Policies**.
2. In the left pane, click **Policies**.
3. Double-click a policy to open its properties window.
4. In the left pane of the policy's properties window, click **Firewall**.
5. Click **Assign/Unassign**.
6. Ensure your view at the top left shows **All** firewall rules.
7. Use the search window to find the rules you created and select them.
8. Click **OK**.
9. Repeat the steps above for each computer that trusted traffic flows through.

Firewall rule actions and priorities

In this article:

- ["Firewall rule actions" below](#)
- ["Firewall rule sequence" on page 797](#)
- ["How firewall rules work together" on page 798](#)
- ["Rule priority" on page 800](#)
- ["Putting rule action and priority together" on page 800](#)

Firewall rule actions

Firewall rules can take the following actions:

- **Allow:** Explicitly allows traffic that matches the rule to pass, and then implicitly denies everything else.
- **Bypass:** Allows traffic to bypass both firewall and intrusion prevention analysis. Use this setting for media-intensive protocols or for traffic originating from trusted sources. A bypass rule can be based on IP, port, traffic direction, and protocol.
- **Deny:** Explicitly blocks traffic that matches the rule.
- **Force Allow:** Forcibly allows traffic that would otherwise be denied by other rules.

Note: Traffic permitted by a Force Allow rule will still be subject to analysis by the intrusion prevention module.

- **Log only:** Traffic will only be logged. No other action will be taken.

More about Allow rules

Allow rules have two functions:

1. Permit traffic that is explicitly allowed.
2. Implicitly deny all other traffic.

Note: Traffic that is not explicitly allowed by an Allow rule is dropped, and gets recorded as an 'Out of "Allowed" Policy' firewall event.

Commonly applied Allow rules include:

- **ARP:** Permits incoming Address Resolution Protocol (ARP) traffic .
- **Allow solicited TCP/UDP replies:** Allow the computer to receive replies to its own TCP and UDP messages. This works in conjunction with TCP and UDP stateful configuration.
- **Allow solicited ICMP replies:** Allow the computer to receive replies to its own ICMP messages. This works in conjunction with ICMP stateful configuration.

More about Bypass rules

The Bypass rule is designed for media-intensive protocols or for traffic originating from trusted sources where filtering by the firewall or intrusion prevention modules is neither required nor desired.

A packet that matches the conditions of a Bypass rule:

- Is not subject to conditions of stateful configuration settings.
- Bypasses both firewall and Intrusion prevention analysis.

Since stateful inspection is not applied to bypassed traffic, bypassing traffic in one direction does not automatically bypass the response in the other direction. Bypass rules should always be created and applied in pairs, one rule for incoming traffic and another for outgoing.

Note: Bypass rule events are not recorded. This is not a configurable behavior.

Tip: If the Deep Security Manager uses a remote database that is protected by a Deep Security Agent, intrusion prevention-related false alarms may occur when the Deep Security Manager saves intrusion prevention rules to the database. The contents of the rules themselves could be misidentified as an attack. One of the workarounds for this is to create a bypass rule for traffic from the Deep Security Manager to the database.

Default Bypass rule for Deep Security Manager traffic

The Deep Security Manager automatically implements a priority 4 Bypass rule that opens incoming TCP traffic on the agent's listening port for heartbeats (see ["Configure the heartbeat" on page 344](#)) on computers running Deep Security Agent. Priority 4 ensures that this rule is

applied before any Deny rules, and Bypass guarantees that the traffic is never impaired. The Bypass rule is not explicitly shown in the firewall rule list because the rule is created internally.

This rule, however, accepts traffic from any IP address and any MAC address. To harden the agent's security on this port, you can create an alternative, more restrictive bypass rule for this port. The agent will actually disable the default Deep Security Manager traffic rule in favor of the new custom rule provided it has these characteristics:

- **Priority:** 4 - Highest
- **Packet direction:** Incoming
- **Frame type:** IP
- **Protocol:** TCP
- **Packet Destination Port:** agent's listening port number for heartbeats from the Manager

The custom rule must use the above parameters to replace the default rule. Ideally, the IP address or MAC address of the actual Deep Security Manager should be used as the packet source for the rule.

More about Force Allow rules

The Force Allow option excludes a sub-set of traffic that could otherwise have been covered by a Deny action. Its relationship to other actions is illustrated below. Force Allow has the same effect as a Bypass rule. However, unlike Bypass, traffic that passes the firewall because of this action is still subject to inspection by the intrusion prevention module. The Force Allow action is particularly useful for making sure that essential network services are able to communicate with the DSA computer. Generally, Force Allow rules should only be used in conjunction with Allow and rules to Allow a subset of traffic that has been prohibited by the Allow and Deny rules. Force Allow rules are also required to Allow unsolicited ICMP and UDP traffic when ICMP and UDP stateful are enabled.

Note: When using multiple Deep Security Managers in a multi-node arrangement, it may be useful to define an IP list for these servers, and then create a custom Deep Security Manager traffic rule with that list.

Firewall rule sequence

Packets arriving at a computer get processed first by firewall rules, then the firewall stateful configuration conditions, and finally by the intrusion prevention rules.

This is the order in which firewall rules are applied (incoming and outgoing):

1. Firewall rules with priority **4 (highest)**
 - a. **Bypass**
 - b. **Log Only** (Log Only rules can only be assigned a priority of **4 (highest)**)
 - c. **Force Allow**
 - d. **Deny**
2. Firewall rules with priority **3 (high)**
 - a. **Bypass**
 - b. **Force Allow**
 - c. **Deny**
3. Firewall rules with priority **2 (normal)**
 - a. **Bypass**
 - b. **Force Allow**
 - c. **Deny**
4. Firewall rules with priority **1 (low)**
 - a. **Bypass**
 - b. **Force Allow**
 - c. **Deny**
5. Firewall rules with priority **0 (lowest)**
 - a. **Bypass**
 - b. **Force Allow**
 - c. **Deny**
 - d. **Allow**(Note that an Allow rule can only be assigned a priority of **0 (lowest)**)

Note: If you have no Allow rules in effect on a computer, all traffic is permitted unless it is specifically blocked by a Deny rule. Once you create a single Allow rule, all other traffic is blocked unless it meets the conditions of the Allow rule. There is one exception to this: ICMPv6 traffic is always permitted unless it is specifically blocked by a Deny rule.

Within the same priority context, a Deny rule will override an Allow rule, and a Force Allow rule will override a Deny rule. By using the rule priorities system, a higher priority Deny rule can be made to override a lower priority Force Allow rule.

Consider the example of a DNS server policy that makes use of a Force Allow rule to Allow all [incoming DNS queries](#). Creating a Deny rule with a higher priority than the Force Allow rule lets you specify a particular range of IP addresses that must be prohibited from accessing the same public server.

Priority-based rule sets allow you set the order in which the rules are applied. If a Deny rule is set with the highest priority, and there are no Force Allow rules with the same priority, then any packet matching the Deny rule is automatically dropped and the remaining rules are ignored. Conversely, if a Force Allow rule with the highest priority flag set exists, any incoming packets matching the Force Allow rule will be automatically allowed through without being checked against any other rules.

A note on logging

Bypass rules will never generate an event. This is not configurable.

Log Only rules will only generate an event if the packet in question is not subsequently stopped by either:

- a Deny rule, or
- an Allow rule that excludes it.

If the packet is stopped by one of those two rules, those rules will generate the Event and not the Log Only rule. If no subsequent rules stop the packet, the Log Only rule will generate an event.

How firewall rules work together


Deep Security firewall rules have both a rule action and a rule priority. Used in conjunction, these two properties allow you to create very flexible and powerful rule-sets. Unlike rule-sets used by other firewalls, which may require that the rules be defined in the order in which they should be run, Deep Security Firewall rules are run in a deterministic order based on the rule action and the rule priority, which is independent of the order in which they are defined or assigned.

Rule Action


Each rule can have one of four actions.

1. **Bypass:** if a packet matches a Bypass rule, it is passed through both the firewall *and the Intrusion Prevention Engine* regardless of any other rule (at the same priority level).
2. **Log Only:** if a packet matches a Log Only rule it is passed and the event is logged.
3. **Force Allow:** if a packet matches a Force Allow rule it is passed regardless of any other rules (at the same priority level).
4. **Deny:** if a packet matches a Deny rule it is dropped.
5. **Allow:** if a packet matches an Allow rule, it is passed. Any traffic not matching one of the Allow rules is denied.


Implementing an Allow rule will cause all other traffic not specifically covered by the Allow rule to be denied:



A Deny rule can be implemented over an Allow to block specific types of traffic:



A Force Allow rule can be placed over the denied traffic to Allow certain exceptions to pass through:



Rule priority

Rule actions of type Deny and Force Allow can be defined at any one of 5 priorities to allow further refinement of the permitted traffic defined by the set of Allow rules. Rules are run in priority order from highest (Priority 4) to lowest (Priority 0). Within a specific priority level the rules are processed in order based on the rule action (Force Allow, Deny, Allow, log only).

The priority context Allows a User to successively refine traffic controls using Deny and Force Allow rule combinations. Within the same priority context, an Allow rule can be negated with a Deny rule, and a Deny rule can be negated by a Force Allow rule.

Note: Rule actions of type Allow run only at priority 0 while rule actions of type Log Only run only at priority 4.

Putting rule action and priority together

Rules are run in priority order from highest (Priority 4) to lowest (Priority 0). Within a specific priority level the rules are processed in order based on the rule action. The order in which rules of equal priority are processed is as follows:

- Bypass
- Log Only
- Force Allow
- Deny
- Allow

Note: Remember that rule actions of type Allow run only at priority 0 while rule actions of type Log Only run only at priority 4.

Note: It is important to remember that if you have a Force Allow rule and a Deny rule at the same priority the Force Allow rule takes precedence over the Deny rule and therefore traffic matching the Force Allow rule will be permitted.

Firewall settings

The **Firewall** module provides bidirectional stateful firewall protection. It prevents denial of service attacks and provides coverage for all IP-based protocols and frame types as well as filtering for ports and IP and MAC addresses.

The Firewall section of the **Computer or Policy editor**¹ has the following tabbed sections:

- ["General" below](#)
- ["Interface Isolation" on page 803](#)
- ["Reconnaissance" on page 804](#)
- ["Advanced" on page 806](#)
- ["Events" on page 807](#)

Note: This article includes references to the Deep Security Virtual Appliance, which is not available with Deep Security as a Service.

General

Firewall

You can configure this policy or computer to inherit its firewall On/Off state from its parent policy or you can lock the setting locally.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Firewall Stateful Configurations

Select which firewall stateful configuration to apply to this policy. If you have defined multiple Interfaces for this policy (above), you can specify independent configurations for each interface. For more information on creating a stateful configuration see ["Define stateful firewall configurations" on page 814](#).

Port Scan (Computer Editor only)

Last Port Scan: The last time that the Deep Security manager ran a port scan on this computer.

Scanned Ports: The ports that were scanned during the most recent port scan.

Open Ports: Listed beneath the IP address of the local computer will be a list of ports that were found to be open.

The **Scan For Open Ports** and the **Cancel Port Scan** buttons let you initiate or cancel a port scan on this computer. Deep Security Manager will scan the range of ports defined in **Computer or Policy editor**¹ > Settings > General > Open Ports > Ports to Scan.

Note: Regardless of the ports configured to be scanned, Deep Security Manager will always scan the [agent or appliance's listening port number for heartbeat connections from the Manager](#).

Assigned Firewall Rules

Displays the firewall rules that are in effect for this policy or computer. To add or remove firewall rules, click **Assign/Unassign** This will display a window showing all available firewall rules from which you can select or deselect rules.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

From a **Computer or Policy editor**¹ window, you can edit a firewall rule so that your changes apply only locally in the context of your editor, or you can edit the rule so that the changes apply globally to all other policies and computers that are using the rule.

To edit the Rule locally, right-click the rule and click **Properties**.

To edit the Rule globally, right-click the rule and click **Properties (Global)**.

For more information on creating firewall rules, see "[Create a firewall rule](#)" on page 786.

Interface Isolation

Interface Isolation

You can configure this policy or computer to inherit its Interface Isolation enabled or disabled state from its parent policy or you can lock the setting locally.

Warning: Before you enable Interface Isolation make sure that you have configured the interface patterns in the proper order and that you have removed or added all necessary string patterns. Only interfaces matching the highest priority pattern will be permitted to transmit traffic. Other interfaces (which match any of the remaining patterns on the list) will be "restricted". Restricted Interfaces will block all traffic unless an Allow Firewall Rule is used to allow specific traffic to pass through.

Interface Patterns

When Interface Isolation is enabled, the firewall will try to match the regular expression patterns to interface names on the local computer.

Note: Deep Security uses POSIX basic regular expressions to match interface names. For information on basic POSIX regular expressions, see http://pubs.opengroup.org/onlinepubs/009695399/basedefs/xbd_chap09.html#tag_09_03

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Only interfaces matching the highest priority pattern will be permitted to transmit traffic. Other interfaces (which match any of the remaining patterns on the list) will be "restricted". Restricted Interfaces will block all traffic unless an **Allow** firewall rule is used to allow specific traffic to pass through.

Selecting **Limit to one active interface** will restrict traffic to only a single interface (even if more than one interface matches the highest priority pattern).

Reconnaissance

Reconnaissance Scans

The **Reconnaissance** page allows you to enable and configure traffic analysis settings on your computers. This feature can detect possible reconnaissance scans that attackers often use to discover weaknesses before beginning a targeted attack.

- **Reconnaissance Scan Detection Enabled:** Turn the ability to detect reconnaissance scans on or off.
- **Computers/Networks on which to perform detection:** Choose from the list the IPs to protect. Choose from existing IP Lists. (You can use the **Policies > Common Objects > Lists > IP Lists** page to create an IP List specifically for this purpose.)
- **Do not perform detection on traffic coming from:** Select from a set of IP Lists which computers and networks to ignore. (As above, you can use the **Policies > Common Objects > Lists > IP Lists** page to create an IP List specifically for this purpose.)

Note: If you want to enable reconnaissance protection, you must also enable the Firewall and Stateful Inspection on the **Computer or Policy editor**¹ > **Firewall > General** tab. You should also go to the **Computer or Policy editor**² > **Firewall > Advanced** tab and enable the **Generate**

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Firewall Events for packets that are 'Out of Allowed Policy' setting. This will generate firewall events that are required for reconnaissance.

For each type of attack, the **agent or appliance**¹ can be instructed to send the information to the Deep Security Manager where an alert will be triggered. You can configure the Deep Security Manager to send an email notification when the alerts are triggered. (See **Administration > System Settings > Alerts**. The alerts are: "Network or Port Scan Detected", "Computer OS Fingerprint Probe Detected", "TCP Null Scan Detected", "TCP FIN Scan Detected", and "TCP Xmas Scan Detected.") Select **Notify DSM Immediately** for this option.

Note: For the "Notify DSM Immediately" option to work, the agents and appliances must be configured for **agent or appliance-initiated** or **bidirectional** communication in **Computer or Policy editor**² > **Settings > General**.) If enabled, the agent or appliance will initiate a heartbeat to the Deep Security Manager immediately upon detecting the attack or probe.

Once an attack has been detected, you can instruct the agents and appliances to block traffic from the source IPs for a period of time. Use the **Block Traffic** lists to set the number of minutes.

- **Computer OS Fingerprint Probe:** The agent or appliance detects an attempt to discover the computers OS.
- **Network or Port Scan:** The agent or appliance reports a network or port scan if it detects that a remote IP is visiting an abnormal ratio of IPs to ports. Normally, an agent or appliance computer will only see traffic destined for itself, so a port scan is the most common type of probe that will be detected. The statistical analysis method used in computer or port scan detection is derived from the "TAPS" algorithm proposed in the paper "Connectionless Port Scan Detection on the Backbone" presented at IPCCC in 2006.

¹ The Deep Security Agent and Deep Security Virtual Appliance are the components that enforce the Deep Security policies that you have defined. Agents are deployed directly on a computer. Appliances are used in VMware vSphere environments to provide agentless protection. They are not available with Deep Security as a Service.

² You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

- **TCP Null Scan:** The agent or appliance detects packages with no flags set.
- **TCP SYNFIN Scan:** The agent or appliance detects packets with only the SYN and FIN flags set.
- **TCP Xmas Scan:** The agent or appliance detects packets with only the FIN, URG, and PSH flags set or a value of 0xFF (every possible flag set).

Note: "Network or Port Scans" differs from the other types of reconnaissance in that it cannot be recognized by a single packet and requires Deep Security to watch traffic for a period of time.

The agent or appliance reports a computer or port scan if it detects that a remote IP is visiting an abnormal ratio of IPs to ports. Normally an agent or appliance computer will only see traffic destined for itself, so a port scan is by far the most common type of probe that will be detected. However, if a computer is acting as a router or bridge it could see traffic destined for a number of other computers, making it possible for the agent or appliance to detect a computer scan (ex. scanning a whole subnet for computers with port 80 open).

Detecting these scans can take several seconds since the agent or appliance needs to be able to track failed connections and decide that there are an abnormal number of failed connections coming from a single computer in a relatively short period of time.

Note: Deep Security Agents running on Windows computers with browser applications may occasionally report false-positive reconnaissance scans due to residual traffic arriving from closed connections.

For information on how to handle reconnaissance warnings, see ["Warning: Reconnaissance Detected" on page 1304](#).

Advanced

Events

Set whether to generate events for packets that are "Out of Allowed Policy". These are packets that have been blocked because they have not been specifically allowed by an **Allow** firewall rule. Setting this option to **Yes** may generate a large number of events depending on the firewall rules you have in effect.

Events

Firewall events are displayed the same way as they are in the main Deep Security Manager window except that only events relating to this policy or specific computer are displayed.

Firewall settings with Oracle RAC

Deep Security supports:

- SUSE Linux Enterprise Server 11 SP3 with Oracle RAC 12c Release 1 (v12.1.0.2.0)
- Red Hat Linux Enterprise Server 6.6 with Oracle RAC 12c Release 1 (v12.1.0.2.0)
- Red Hat Linux Enterprise Server 7.0 with Oracle RAC 12c Release 1 (v12.1.0.2)

The default Linux Server Deep Security policy is compatible with the Oracle RAC environment, with the exception of firewall settings. Because there are complex communication channels between RAC nodes, the RAC nodes will fail to create a virtual NIC and scan the NIC, due to firewall interference. As a result, Oracle Clusterware would fail to start on some nodes. You can disable the firewall or customize the firewall settings.

Add a rule to allow communication between nodes

1. In the Deep Security Manager, go to the **Policies** tab.
2. Right-click the **Linux Server** policy and click **Duplicate**.
3. Click the new **Linux Server_2** policy and click **Details**.
4. Give the policy a new name, for example, "Oracle RAC" and click **Save**.
5. Click **Firewall**.
6. Click **Assign/Unassign**.
7. Click **New > New Firewall Rule**.
8. Under **General Information**, set the **Name** to something descriptive, like "Allow communication with Oracle nodes". Set **Action** to "Force Allow" and set **Protocol** to "Any".
9. Under **Packet Source**, set **MAC** to "MAC List". In the **Select MAC List** that appears, select "New". A "New MAC List Properties" dialog box appears.
10. Give the MAC list a name, like "Oracle RAC MAC list". Under **MAC(s): (One MAC per line)**, add all of the MAC addresses used by all Oracle nodes (including MACs from both private and public NICs). Click **OK** when finished.

11. Under **Packet Destination**, set **MAC** to "MAC List". In the **Select MAC List** that appears, select the MAC list you created in step 10 and then click **OK**.
12. In the Firewall Rules list for the policy, ensure that this new rule is selected and click **OK** and then click **Save**.

Add a rule to allow UDP port 42424

Follow the steps described in the procedure above to add a new rule that allows UDP port 42424. This [port number](#) is used by the Cluster Synchronization Service daemon (CSSD), Oracle Grid Interprocess Communication (GIPCD) and Oracle HA Services daemon (OHASD).

Note: Please note that the MAC list that you created above may not be able to cover this rule. This rule is essential for Oracle RAC.

GeneralOptionsAssigned To

General Information

Name:

New Firewall Rule

Description:

Action:

Force Allow

Priority:

0 - Lowest

Packet direction:

Incoming

Frame Type:

IP

☐ Not

Protocol:

UDP

☐ Not

Packet Source

IP:

Any

☐ Not

MAC:

Any

☐ Not

Port:

Any

☐ Not

Packet Destination

IP:

Any

☐ Not

MAC:

Any

☐ Not

Port:

Port(s):

42424

☐ Not

OK

Cancel

Allow other RAC-related packets

Oracle RAC will send a very large number of packets with Frame Type C08A and 0ACB.

Blocking them may cause some unpredictable behavior.

- **Allow TCP port 6200:** Add the public IP addresses of the RAC nodes in the **IP** fields under **Packet Source** and **Packet Destination** and set destination port to 6200. This [port number](#) is used by Oracle Notification Services (ONS). This port is configurable, so check the value on your system set the correct port number if it is something other than 6200.

General Options Assigned To

General Information

Name: RAC_TCP 6200_suse

Description:

Action: Allow

Priority: 0 - Lowest

Packet direction: Incoming

Frame Type: IP ☐ Not

Protocol: TCP ☐ Not

Packet Source

IP: Any ☐ Not

MAC: Any ☐ Not

Port: Port(s): 6200 ☐ Not

OK Cancel

- **Allow Frame Type C0A8:** Add a rule with the **Frame Type** set to "Other" and the **Frame no** set to "C0A8".

General Options Assigned To

General Information

Name: RAC_C0A8

Description:

Action: Allow

Priority: 0 - Lowest

Packet direction: Incoming

Frame Type: Other: Frame no: CA08

Protocol: Any

Not

Not

OK Cancel

- **Allow Frame Type 0ACB:** Add a rule with the **Frame Type** set to "Other" and the **Frame no** set to "0ACB".
- **Allow Frame Type 0AC9:** Add a rule with the **Frame Type** set to "Other" and the **Frame no** set to "0AC9".

- **Allow IGMP protocol:** Add a rule with the **Protocol** set to "IGMP".

The screenshot shows the 'General' tab of a rule configuration window. The rule name is 'RAC_allow_IGMP'. The description field is empty. The action is set to 'Allow', priority is '0 - Lowest', and packet direction is 'Incoming'. The frame type is 'IP' and the protocol is 'IGMP'. There are two checkboxes labeled 'Not' on the right side of the frame type and protocol fields. The window has 'OK' and 'Cancel' buttons at the bottom right.

General	Options	Assigned To
General Information		
Name:	RAC_allow_IGMP	
Description:		
Action:	Allow	
Priority:	0 - Lowest	
Packet direction:	Incoming	
Frame Type:	IP	<input type="checkbox"/> Not
Protocol:	IGMP	<input type="checkbox"/> Not

OK Cancel

Please refer to the following link to check whether there are additional RAC-related components in your system that need extra firewall rules to allow certain ports:

<https://docs.oracle.com/database/121/RILIN/ports.htm#RILIN1178>


Ensure that the Oracle SQL Server rule is assigned

Check that the "Oracle SQL Server" Firewall rule is assigned to the Linux Server policy. This is a pre-defined Deep Security Firewall rule that allows port 1521.

Ensure that anti-evasion settings are set to "Normal"

In the properties for the Linux Server policy, **Settings > Network Engine > Anti-Evasion Settings** are set to "Normal" by default. If this setting is set to "Strict", the RAC database response will be

extremely slow.



Define stateful firewall configurations

Deep Security's stateful firewall configuration mechanism analyzes each packet in the context of traffic history, correctness of TCP and IP header values, and TCP connection state transitions. In the case of stateless protocols like UDP and ICMP, a pseudo-stateful mechanism is implemented based on historical traffic analysis. Packets are handled by the stateful mechanism as follows:

1. A packet is passed to the stateful routine if it has been allowed through by the static firewall rule conditions,
2. The packet is examined to determine whether it belongs to an existing connection, and
3. The TCP header is examined for correctness (e.g. sequence numbers, flag combinations, etc.).

To create a new stateful configuration, you need to:

1. "Add a stateful configuration " on the next page.
2. "Enter stateful configuration information" on the next page.
3. "Select packet inspection options" on the next page.

When you're done with your stateful configuration, you can also learn how to

- ["See policies and computers a stateful configuration is assigned to" on page 819](#)
- ["Export a stateful configuration " on page 819](#)
- ["Delete a stateful configuration " on page 819](#)

Add a stateful configuration

There are three ways to define a stateful configuration on the **Policies > Common Objects > Other > Firewall Stateful Configurations** page:

- Create a new configuration. Click **New > New Firewall Stateful Configuration**.
- Import a configuration from an XML file. Click **New > Import From File**.
- Copy and then modify an existing configuration. Right-click the configuration in the Firewall Stateful Configurations list and then click **Duplicate**. To edit the new configuration, select it and then click **Properties**.

Enter stateful configuration information

Enter a **Name** and **Description** for the configuration.

Select packet inspection options

You can define options for IP, TCP, UDP and ICMP packet inspection, and enable Active or Passive FTP.

IP packet inspection

Under the **General** tab, select the **Deny all incoming fragmented packets** to drop any fragmented packets. Dropped packets will bypass fragmentation analysis and generate an "IP fragmented packet" log entry. Packets with a total length smaller than the IP header length are dropped silently.

Warning: Attackers sometimes create and send fragmented packets in an attempt to bypass Firewall Rules.

Note: The Firewall Engine, by default, performs a series of checks on fragmented packets. This is default behavior and cannot be reconfigured. Packets with the following characteristics are dropped:

- **Invalid fragmentation flags/offset:** A packet is dropped when either the **DF** and **MF** flags in the IP header are set to 1, or the header contains the **DF** flag set to 1 and an **Offset** value different than 0.
- **First fragment too small:** A packet is dropped if its **MF** flag is set to 1, its **Offset** value is at 0, and it has total length of less than 120 bytes (the maximum combined header length).
- **IP fragment out of boundary:** A packet is dropped if its **Offset** flag value combined with the total packet length exceeds the maximum datagram length of 65535 bytes.
- **IP fragment offset too small:** A packet is dropped if it has a non-zero **Offset** flag with a value that is smaller than 60 bytes.

TCP packet inspection

Under the **TCP** tab, select which of the following options you would like to enable:

- **Deny TCP packets containing CWR, ECE flags:** These flags are set when there is network congestion.

Note: RFC 3168 defines two of the six bits from the Reserved field to be used for ECN (Explicit Congestion Notification), as follows:

- Bits 8 to 15: CWR-ECE-URG-ACK-PSH-RST-SYN-FIN
- TCP Header Flags Bit Name Reference:
 - Bit 8: CWR (Congestion Window Reduced) [RFC3168]
 - Bit 9: ECE (ECN-Echo) [RFC3168]

Warning: Automated packet transmission (such as that generated by a denial of service attack, among other things) will often produce packets in which these flags are set.

- **Enable TCP stateful inspection:** Enable stateful inspection at the TCP level. If you enable stateful TCP inspection, the following options become available:
 - **Enable TCP stateful logging:** TCP stateful inspection events will be logged.
 - **Limit the number of incoming connections from a single computer to:** Limiting the number of connections from a single computer can lessen the effect of a denial of service attack.
 - **Limit the number of outgoing connections to a single computer to:** Limiting the number of outgoing connections to a single computer can significantly reduce the effects of Nimda-like worms.
 - **Limit the number of half-open connections from a single computer to:** Setting a limit here can protect you from DoS attacks like SYN Flood. Although most servers have timeout settings for closing half-open connections, setting a value here can prevent half-open connections from becoming a significant problem. If the specified limit for SYN-SENT (remote) entries is reached, subsequent TCP packets from that specific computer will be dropped.
- Note:** When deciding on how many open connections from a single computer to allow, choose your number from somewhere between what you would consider a reasonable number of half-open connections from a single computer for the type of protocol being used, and how many half-open connections from a single computer your system can maintain without getting congested.
- **Enable ACK Storm protection when the number of already acknowledged packets exceeds:** Set this option to log an event that an ACK Storm attack has occurred.
 - **Drop Connection when ACK Storm detected:** Set this option to drop the connection if such an attack is detected.

Note: ACK Storm protection options are only available on Deep Security Agent 8.0 and earlier.

FTP Options

Under the **FTP Options** tab, you can enable the following options:

Note: The following FTP options are available in Deep Security Agent version 8.0 and earlier.

- **Active FTP**
 - **Allow Incoming:** Allow Active FTP when this computer is acting as a server.
 - **Allow Outgoing:** Allow Active FTP when this computer is acting as client.
- **Passive FTP**
 - **Allow Incoming:** Allow Passive FTP when this computer is acting as a server.
 - **Allow Outgoing:** Allow Passive FTP when this computer is acting as a client.

UDP packet inspection

Under the **UDP** tab, you can enable the following options:

- **Enable UDP stateful inspection:** Select to enable stateful inspection of UDP traffic.

Note: The UDP stateful mechanism drops unsolicited incoming UDP packets. For every outgoing UDP packet, the rule will update its UDP "stateful" table and will then only allow a UDP response if it occurs within 60 seconds of the request. If you wish to allow specific incoming UDP traffic, you will have to create a **Force Allow** rule. For example, if you are running a DNS server, you will have to create a **Force Allow** rule to allow incoming UDP packets to destination port 53.

Warning: Without stateful inspection of UDP traffic, an attacker can masquerade as a DNS server and send unsolicited UDP "replies" from source port 53 to computers behind a firewall.

- **Enable UDP stateful logging:** Selecting this option will enable the logging of UDP stateful inspection events.

ICMP packet inspection

Under the **ICMP** tab, you can enable the following options:

Note: ICMP stateful inspection is available in Deep Security Agent version 8.0 or earlier.

- **Enable ICMP stateful inspection:** Select to enable stateful inspection of ICMP traffic.

Note: The ICMP (pseudo-)stateful mechanism drops incoming unsolicited ICMP packets. For every outgoing ICMP packet, the rule will create or update its ICMP "stateful" table and will then only allow a ICMP response if it occurs within 60 seconds of the request. (ICMP pair types supported: Type 0 & 8, 13 & 14, 15 & 16, 17 & 18.)

Warning: With stateful ICMP inspection enabled, you can, for example, only allow an ICMP echo-reply in if an echo-request has been sent out. Unrequested echo-replies could be a sign of several kinds of attack including a Smurf amplification attack, a Tribe Flood Network communication between master and daemon, or a Loki 2 back-door.

- **Enable ICMP stateful logging:** Selecting this option will enable the logging of ICMP stateful inspection events.

Export a stateful configuration

You can export all stateful configurations to a .csv or .xml file by clicking **Export** and selecting the corresponding export action from the list. You can also export specific stateful configurations by first selecting them, clicking **Export** and then selecting the corresponding export action from the list.

Delete a stateful configuration

To delete a stateful configuration, right-click the configuration in the Firewall Stateful Configurations list, click **Delete** and then click **OK**.

Note: Stateful configurations that are assigned to one or more computers or that are part of a policy cannot be deleted.

See policies and computers a stateful configuration is assigned to

You can see which policies and computers are assigned to a stateful inspection configuration on the **Assigned To** tab. Click on a policy or computer in the list to see their properties.

Scan for open ports

The Deep Security Manager can be instructed to scan a computer for open ports by right-clicking the computer and selecting **Actions > Scan for Open ports**, or by clicking the **Scan for Open Ports** button in the **Firewall** page of the **Computer editor**¹ window (where the results of the latest scan are displayed).

(Port scans can also be initiated by right-clicking an existing computer on the Manager's **Computers** page and choosing "Scan for Open Ports". Another way to initiate port scans is to create a **Scheduled Task** to regularly carry out port scans on a list of computers.)

By default, the range of ports that are scanned is the range known as the "Common Ports", 1-1024, but you can define a different set of ports to scan.

Note: [The agent's port number for incoming heartbeat connections from the Manager](#) is always scanned regardless of port range settings. It is the port on the computer to which communications initiated by the Manager are sent. If communication direction is set to "Agent/Appliance Initiated" for a computer (**Computer or Policy editor**² > **Settings > General**), however, that port number will be closed.

1. Go to **Policies > Common Objects > Lists > Port Lists** and click **New** in the menu bar. The **New Port List** window will appear.
2. Type a name and description for the new port list and then define the ports in the **Port(s)** text box using the accepted formats. (For example, to scan ports 100, 105, and 110 through 120, you would type "100" on the first line "105" on the second, and "110-120" on the third.) Click **OK**.

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

3. Go to **Computer or Policy editor**¹ > **Settings** > **General** and click the "Ports to Scan" menu. Your newly defined Port List will be one of the choices.

Container Firewall rules

If you are using Deep Security Agent 11.2 or higher to protect containers that use an overlay network, you may need to add some Firewall rules to allow network traffic for the Swarm or Kubernetes services because the default Firewall rules block that traffic.

Kubernetes Firewall rules

If you are using Kubernetes, add the following rules to bypass the k8s communication traffic and export service traffic:

Name	Action Type	Priority	Direction	Frame Type	Protocol	Source IP	Source Port	Destination IP	Destination Port
HTTP incoming TCP 80 destination port	Force Allow	0 - Lowest	Incoming	IP	TCP	Any	N/A	Any	80
HTTP outgoing TCP 80 source port	Force Allow	0 - Lowest	Outgoing	IP	TCP	Any	80	Any	Any
K8s incoming TCP 10054 port	Force Allow	0 - Lowest	Incoming	IP	TCP	Any	Any	Any	10054
K8s outgoing TCP 10054 port	Force Allow	0 - Lowest	Outgoing	IP	TCP	Any	Any	Any	10054
K8s outgoing	Force Allow	0 - Lowest	Outgoing	IP	TCP	Any	Any	Any	443

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Name	Action Type	Priority	Direction	Frame Type	Protocol	Source IP	Source Port	Destination IP	Destination Port
TCP 443 port									
K8s outgoing TCP 6443 port	Force Allow	0 - Lowest	Incoming	IP	TCP	Any	Any	Any	6443
K8s outgoing TCP 6443 port	Force Allow	0 - Lowest	Outgoing	IP	TCP	Any	Any	Any	6443
K8s outgoing TCP 8081 port	Force Allow	0 - Lowest	Incoming	IP	TCP	Any	Any	Any	8081
K8s outgoing TCP 8081 port	Force Allow	0 - Lowest	Outgoing	IP	TCP	Any	Any	Any	8081
K8s outgoing UDP 8472 port	Force Allow	0 - Lowest	Outgoing	IP	UDP	Any	Any	Any	8472
K8s outgoing UDP 8285 port	Force Allow	0 - Lowest	Outgoing	IP	UDP	Any	Any	Any	8285
K8s outgoing UDP 8285 port	Force Allow	0 - Lowest	Incoming	IP	UDP	Any	Any	Any	8285

Swarm Firewall rules

If you are using Swarm, add the following rules to bypass the k8s communication traffic and export service traffic:

Name	Action Type	Priority	Direction	Frame Type	Protocol	Source IP	Source Port	Destination IP	Destination Port
HTTP incoming TCP 80	Force Allow	0 - Lowest	Incoming	IP	TCP	Any	N/A	Any	80

Name	Action Type	Priority	Direction	Frame Type	Protocol	Source IP	Source Port	Destination IP	Destination Port
destination port									
HTTP outgoing TCP 80 source port	Force Allow	0 - Lowest	Outgoing	IP	TCP	Any	80	Any	Any
Swarm outgoing TCP 443 port	Force Allow	0 - Lowest	Outgoing	IP	TCP	Any	Any	Any	443
Swarm incoming TCP 2377, 4789, 7946, 60012 port	Force Allow	0 - Lowest	Incoming	IP	TCP+UDP	Any	Any	Any	2377, 4789, 7946, 60012
Swarm outgoing TCP 2377, 4789, 7946, 60012 port	Force Allow	0 - Lowest	Outgoing	IP	TCP+UDP	Any	2377, 4789, 7946, 60012	Any	Any

Monitor for system changes with integrity monitoring

The integrity monitoring module scans for unexpected changes to registry values, registry keys, services, processes, installed software, ports and files on Deep Security Agents. Using a baseline secure state as a reference, the integrity monitoring module performs scans on the above and logs an event (and an optional alert) if it detects any unexpected changes.

To enable and configure integrity monitoring, see ["Set up integrity monitoring" on the next page](#).

To more information on creating integrity monitoring rules, see ["Create an integrity monitoring rule" on page 832](#). You can create a rule from a file or registry monitoring template, or by using the Deep Security XML-based ["Integrity monitoring rules language" on page 837](#).

Set up integrity monitoring

The Integrity Monitoring protection module detects changes to files and critical system areas like the Windows registry that could indicate suspicious activity. It does this by comparing current conditions to a baseline reading it has previously recorded. Deep Security ships with predefined Integrity Monitoring rules and new Integrity Monitoring rules are provided in security updates.

Note: Integrity Monitoring detects changes made to the system, but will not prevent or undo the change.

How to enable Integrity Monitoring

You can enable Integrity Monitoring in policies or at the computer level. To do so, you will need to:

1. ["Turn on Integrity Monitoring" below.](#)
2. ["Run a Recommendation scan" on the next page.](#)
3. ["Apply the Integrity Monitoring rules" on page 826.](#)
4. ["Build a baseline for the computer" on page 828.](#)
5. ["Periodically scan for changes" on page 828.](#)
6. ["Test Integrity Monitoring" on page 828.](#)


Once you've enabled integrity monitoring, you can also learn more about

- ["When Integrity Monitoring scans are performed" on page 829](#)
- ["Integrity Monitoring scan performance settings" on page 830](#)
- ["Integrity Monitoring event tagging" on page 832](#)

Following is a typical procedure for enabling Integrity Monitoring:

Turn on Integrity Monitoring

You can enable Integrity Monitoring in the settings for a computer or in policies. To do this, open the Policy or Computer editor and go to **Integrity Monitoring > General**. Set the Configuration to "On" or "Inherited (On)" and then click **Save**.



Run a Recommendation scan

Run a Recommendation scan on the computer to get recommendations about which rules would be appropriate. To do this, open the Computer editor and go to **Integrity Monitoring > General**. In the Recommendations section, click **Scan for Recommendations**. You can optionally specify that Deep Security should implement the rule recommendations that it finds.

Recommended Integrity Monitoring rules may result in too many monitored entities and attributes. The best practice is to decide what is critical and should be monitored, then create custom rules or tune the predefined rules. Pay extra attention to rules that monitor frequently-

changed properties such as process IDs and source port numbers because they can be noisy and may need some tuning.


If you have enabled real-time integrity monitoring scans and find that some recommended rules produce too many events because they are monitoring directories that change frequently, you can disable real-time scanning for those rules. Go to **Policies > Common Objects > Rules > Integrity Monitoring Rules** and double-click the rule. On the **Options** tab, clear the **Allow Real Time Monitoring** checkbox.

Apply the Integrity Monitoring rules

As described above, when you run a Recommendation scan, you can have Deep Security implement the recommended rules automatically. You can also manually assign rules.

In the Computer or Policy editor, go to **Integrity Monitoring > General**. The "Assigned Integrity Monitoring Rules" section displays the rules that are in effect for this policy or computer. To add or remove Integrity Monitoring Rules, click **Assign/Unassign**. This will display a window showing all available Integrity Monitoring Rules, from which you can select or deselect rules.

Trend Micro Deep Security On-Premise 11.3



Some Integrity Monitoring rules written by Trend Micro require local configuration to function properly. If you assign one of these rules to your computers or one of these rules gets assigned automatically, an alert will be raised to notify you that configuration is required.

You can edit an Integrity Monitoring rule locally so that the changes apply only to the computer or policy being edited, or globally so that the changes apply to all other policies or computers that are using the rule. To edit a rule locally, right-click it and click **Properties**. To edit a rule globally, right-click it and click **Properties (Global)**.

You can also create custom rules to monitor for specific changes that concern your organization, such as a new user being added or new software being installed. For information on how to create a custom rule, see ["Integrity monitoring rules language" on page 837](#).

Tip: Integrity Monitoring rules should be as specific as possible to improve performance and to avoid conflicts and false positives. For example, do not create a rule that monitors the entire hard drive.

Build a baseline for the computer

The baseline is the original secure state that an Integrity Scan's results will be compared against. To create a new baseline for Integrity Scans on a computer, open the Computer editor, go to **Integrity Monitoring > General** and click **Rebuild Baseline**.

To view the current baseline data, click **View Baseline**.

Tip: It's a best practice to run a new baseline scan after applying patches.

Periodically scan for changes

Periodically scan for changes. To perform an on-demand scan, open the Computer editor, go to **Integrity Monitoring > General** and click **Scan for Integrity**. You can also create a [scheduled task](#) that performs scans on a regular basis.

Test Integrity Monitoring

Before continuing with further Integrity Monitoring configuration steps, test that the rules and baseline are working correctly:

1. Ensure Integrity Monitoring is enabled.
2. Go to the **Computer or Policy editor**¹ > **Integrity Monitoring > Assigned Integrity Monitoring Rules**. Click **Assign/Unassign**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the **Polices** page and double-click the policy that you want to edit (or select the policy and click **Details**). To change the settings for a computer, go to the **Computers** page and double-click the computer that you want to edit (or select the computer and click **Details**).

3. If you're a Windows user:

- Search for **1002773 - Microsoft Windows - 'Hosts' file modified** and enable the rule. This rule raises an alert when changes are made to `C:\windows\system32\drivers\etc\hosts`.

If you're a Linux user

- Search for **1003513 - Unix - File attributes changes in /etc location** and enable the rule. This rule raises an alert when changes are made to the `/etc/hosts` file.
4. Modify the above file and save the changes.
 5. Go to **Computer editor**¹ > **Integrity Monitoring > General** and click **Scan for Integrity**.
 6. Go to **Events & Reports > Integrity Monitoring Events** to verify the record of the modified host file. If the detection is recorded, the Integrity Monitoring module is working correctly.

When Integrity Monitoring scans are performed

There are three options for performing Integrity Monitoring scans:

- **On-demand scans:** You can initiate an on-demand integrity monitoring scan as needed by opening the **Computer editor**², and going to **Integrity Monitoring > General**. In the Integrity Scan section, click **Scan for Integrity**.
- **Scheduled scans:** You can schedule integrity monitoring scans just like other Deep Security operations. Deep Security checks the entities that are being monitored and identifies and records an event for any changes since the last time it performed a scan. Multiple changes to monitored entities between scans will not be tracked; only the last change will be detected. To detect and report multiple changes to an entity's state, consider increasing the frequency of scheduled scans (for example, daily instead of weekly) or enable real-time scanning for entities that change frequently. To enable scheduled integrity monitoring scans, go to **Administration > Scheduled Tasks > New**. In the New Scheduled Task Wizard, select **Scan Computers for Integrity Changes** and the

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

frequency for the scheduled scan. Fill in the information requested by the New Scheduled Task Wizard with your desired specifications. For more information on scheduled tasks, see ["Schedule Deep Security to perform tasks" on page 418](#).

- **Real-time scans:** You can enable real-time scanning. When this option is selected, Deep Security monitors entities for changes in real time and raises integrity monitoring events when it detects changes. Events are forwarded in real time via syslog to the SIEM or when the next heartbeat communication to the Deep Security Manager occurs. To enable real-time scans, go to the **Computer or Policy Editor**¹ > **Integrity Monitoring** > **General** and select **Real Time**. With Deep Security Agent 11.0 or higher on 64-bit Linux platforms and with Deep Security Agent 11.2 or higher on 64-bit Windows servers, the real-time scan results indicate the user and process that changed the file. For details about which platforms support this feature, see ["Supported features by platform" on page 85](#).

Note: Real-time monitoring of an entire disk for changes to any file would affect performance and result in too many integrity monitoring events. As a safeguard, if you choose to monitor the root drive (C:\) in real time, Deep Security will only monitor executable files and scripts. If you want to perform real-time monitoring of all files, specify a folder other than the root drive.

Integrity Monitoring scan performance settings

Changing the following settings may help to improve the performance of Integrity Monitoring scans:

Limit CPU usage

Integrity Monitoring uses local CPU resources during the system scan that leads to the creation of the initial baseline and during the system scan that compares a later state of the system to the previously created baseline. If you are finding that Integrity Monitoring is consuming more resources than you want it to, you can restrict the CPU usage to the following levels:

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

- **High:** Unlimited CPU usage
- **Medium:** The Integrity Monitoring process will not consume more than 50% of CPU resources
- **Low:** The Integrity Monitoring process will not consume more than 25% of CPU resources

To change the **Integrity Monitoring CPU Usage Level** setting, open the **Computer or Policy editor**¹ and go to **Integrity Monitoring > Advanced**.

Change the content hash algorithm

You can select the hash algorithm(s) that will be used by the Integrity Monitoring module to store baseline information. You can select more than one algorithm, but this is not recommended because of the detrimental effect on performance.

You can change the content hash algorithm

Enable a VM Scan Cache configuration

Using scan caching for Integrity Monitoring improves the efficiency of scans by eliminating the unnecessary scanning of identical content across multiple VMs in large VMware deployments. To select which scan cache configuration is used by a virtual machine, open the **Computer or Policy editor**² and go to **Integrity Monitoring > Advanced > VM Scan Cache**.

For information on Integrity Monitoring scan cache configurations, see "[Virtual Appliance Scan Caching](#)" on page 885.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Integrity Monitoring event tagging

The events generated by the Integrity Monitoring module are displayed in Deep Security Manager, under **Events & Reports > Integrity Monitoring Events**. Event tagging can help you to sort events and determine which ones are legitimate and which ones need to be investigated further.

You can manually apply tags to events by right-clicking the event and then clicking **Add Tag(s)**. You can choose to apply the tag to only the selected event or to any similar Integrity Monitoring events.

You can also use the auto-tagging feature to group and label multiple events. To configure this feature in the Deep Security Manager, go to **Events and Reports > Integrity Monitoring Events > Auto-Tagging > New Trusted Source**. There are three sources that you can use to perform the tagging:

- A Local Trusted Computer.
- The Trend Micro Certified Safe Software Service.
- A Trusted Common Baseline, which is a set of file states collected from a group of computers.

For more information on event tagging, see ["Apply tags to identify and group events" on page 1099](#).

Create an integrity monitoring rule

Integrity Monitoring rules describe how Deep Security Agents should scan for and detect changes to a computer's files, directories, and registry keys and values, as well as changes in installed software, processes, listening ports, and running services. Integrity Monitoring rules can be assigned directly to computers or can be made part of a policy.

Note: This article specifically covers how to create an Integrity Monitoring rule. For information on how to configure the Integrity Monitoring module, see ["Set up integrity monitoring" on page 824](#).

There are two types of Integrity Monitoring rules: those that you have created, and those that are issued by Trend Micro. For more information on how to configure rules issued by Trend Micro, see the ["Configure Trend Micro Integrity Monitoring rules" on page 835](#) section.

To create a new Integrity Monitoring rule, you need to:

1. ["Add a new rule" below](#).
2. ["Enter Integrity Monitoring rule information " below](#).
3. ["Select a rule template and define rule attributes" on the next page](#).

When you're done with your rule, you can also learn how to

- ["Configure rule events and alerts" on page 836](#)
- ["See policies and computers a rule is assigned to" on page 836](#)
- ["Export a rule" on page 836](#)
- ["Delete a rule" on page 837](#)

Add a new rule

There are three ways to add an Integrity Monitoring rule on the **Policies > Common Objects > Rules > Integrity Monitoring Rules** page. You can:

- Create a new rule. Click **New > New Integrity Monitoring Rule**.
- Import a rule from an XML file. Click **New > Import From File**.
- Copy and then modify an existing rule. Right-click the rule in the Integrity Monitoring Rules list and then click **Duplicate**. To edit the new rule, select it and then click **Properties**.

Enter Integrity Monitoring rule information

1. Enter a **Name** and **Description** for the rule.

Tip: It is good practice to document all Integrity Monitoring rule changes in the Description field of the firewall rule. Make a note of when and why rules were created or deleted for easier maintenance.

2. Set the **Severity** of the rule.

Note: Setting the severity of a rule has no effect on how the rule is implemented or applied. Severity levels can be useful as sorting criteria when viewing a list of Integrity Monitoring rules. More importantly, each severity level is associated with a severity value; this value is multiplied by a computer's Asset Value to determine the ranking of an event. (See **Administration > System Settings > Ranking**.)

Select a rule template and define rule attributes

Go to the **Content** tab and select from one of the following three templates:

Registry Value template

Create an Integrity Monitoring rule to specifically monitor changes to registry values.

Note: The Registry Value template is only for Windows-based computers .

1. Select the **Base Key** to monitor and whether or not to monitor contents of sub keys.
2. List **Value Names** to be included or excluded. You can use "?" and "*" as wildcard characters.
3. Enter **Attributes** to monitor. Entering "STANDARD" will monitor changes in registry size, content and type. For more information on Registry Value template attributes see the ["RegistryValueSet" on page 871](#) documentation.

File template

Create an Integrity Monitoring rule to specifically monitor changes to files.

1. Enter a **Base Directory** for the rule (for example, `C:\Program Files\MySQL .`) Select **Include Sub Directories** to include the contents of all subdirectories relative to the base directory.
2. Use the **File Names** fields to include or exclude specific files. You can use wildcards (" ? " for a single character and " * " for zero or more characters.

Note: Leaving the **File Names** fields blank will cause the rule to monitor all files in the base directory. This can use significant system resources if the base directory contains numerous or large files.

3. Enter **Attributes** to monitor. Entering "STANDARD" will monitor changes in file creation date, last modified date, permissions, owner, group, size, content, flags (Windows), and SymLinkPath (Linux). For more information on File template attributes see the ["FileSet" on page 854](#) documentation.









Custom (XML) template

Create a custom Integrity Monitoring rule template to monitor [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) using the Deep Security XML-based ["Integrity monitoring rules language" on page 837](#).

Tip: You can create your rule in your preferred text editor and paste it to the **Content** field when you are done.

Configure Trend Micro Integrity Monitoring rules

Integrity Monitoring rules issued by Trend Micro cannot be edited in the same way as the custom rules you create. Some Trend Micro rules cannot be modified at all, while other rules may offer limited configuration options. Both of these rule types will show as "Defined" under the "Type" column, but rules that can be configured will display a gear in the Integrity Monitoring icon (⚙️).

Integrity Monitoring Rules				No Grouping ▼	Search this page
<div> New ▼ Delete... Properties... Duplicate Export ▼ </div>					
NAME	SEVERITY	TYPE	LAST UPDATED ▲		
 New Integrity Monitoring Rule	 Medium	Custom	N/A		
 1002784 - Microsoft Windows - IE A...	 Medium	Defined	June 23, 2009		
 1002781 - Microsoft Windows - Attri...	 Medium	Defined	June 23, 2009		
 1002778 - Microsoft Windows - Syst...	 High	Defined	June 23, 2009		

You can access the configuration options for a rule by opening the properties for the rule and clicking on the **Configuration** tab.

Rules issued by Trend Micro also show the following additional information under the **General** tab:

- When the rule was first issued and last updated, as well as a unique identifier for the rule.
- The minimum versions of the Agent and the Deep Security Manager that are required for the rule to function.

Although you cannot edit rules issued by Trend Micro directly, you can duplicate them and then edit the copy.

Configure rule events and alerts

Any changes detected by an Integrity Monitoring rule is logged as an event in the Deep Security Manager.

Real-time event monitoring

By default, events are logged at the time they occur. If you only want events to be logged when you manually perform a scan for changes, deselect **Allow Real Time Monitoring**.

Alerts

You can also configure the rules to trigger an alert when they log an event. To do so, open the properties for a rule, click on **Options**, and then select **Alert when this rule logs an event**.

See policies and computers a rule is assigned to

You can see which policies and computers are assigned to an Integrity Monitoring rule on the **Assigned To** tab. Click on a policy or computer in the list to see their properties.

Export a rule

You can export all Integrity Monitoring rules to a .csv or .xml file by clicking **Export** and selecting the corresponding export action from the list. You can also export specific rules by first selecting them, clicking **Export** and then selecting the corresponding export action from the list.

Delete a rule

To delete a rule, right-click the rule in the Integrity Monitoring Rules list, click **Delete** and then click **OK**.

Note: Integrity Monitoring rules that are assigned to one or more computers or that are part of a policy cannot be deleted.

Integrity monitoring rules language

The Integrity Monitoring rules language is a declarative XML-based language that describes the system components and associated attributes that should be monitored by Deep Security. It also provides a means to specify what components within a larger set of components should be excluded from monitoring.

Tip: If you only need to monitor for unauthorized changes to files or the Windows registry, you can use File and Registry rule templates instead of creating a custom one. For more information on using these templates, see ["Create an integrity monitoring rule" on page 832](#).

To create a new custom Integrity Monitoring rule, start with the procedure in ["Create an integrity monitoring rule" on page 832](#) (selecting **Custom (XML)** as the template type), then create your custom rule according to the Integrity Monitoring rules language, as covered in the following sections:

- ["Entity Sets" on the next page](#)
- ["Hierarchies and wildcards" on page 839](#)
- ["Syntax and concepts" on page 840](#)
- ["Include tag" on page 841](#)
- ["Exclude tag" on page 842](#)
- ["Case sensitivity" on page 842](#)
- ["Entity features" on page 843](#)
- ["ANDs and ORs" on page 845](#)

- ["Order of evaluation" on page 846](#)
- ["Entity attributes" on page 846](#)
- ["Shorthand attributes" on page 847](#)
- ["onChange attribute" on page 848](#)
- ["Environment variables" on page 848](#)
- ["Registry values" on page 849](#)
- ["Use of ".." on page 850](#)
- ["Best practices" on page 850](#)

Entity Sets

System components included in an Integrity Monitoring rule are referred to as "Entities". Each type of component is a class of Entity. For example, files, registry keys, and processes are each a class of Entity. The Integrity Monitoring Rules language provides a tag for describing a set of Entities (an Entity Set) for each class of Entity. The following **Entity Set** types are available to be used in a rule:

- ["DirectorySet" on page 851](#): rules will scan the integrity of directories
- ["FileSet" on page 854](#): rules will scan the integrity of files
- ["GroupSet" on page 858](#): rules will scan the integrity of groups
- ["InstalledSoftwareSet" on page 860](#): rules will scan the integrity of installed software
- ["PortSet" on page 862](#): rules will scan the integrity of listening ports
- ["ProcessSet" on page 866](#): rules will scan the integrity of processes
- ["RegistryKeySet" on page 869](#): rules will scan registry keys
- ["RegistryValueSet" on page 871](#): rules will scan registry values
- ["ServiceSet" on page 873](#): rules will scan the integrity of services
- ["UserSet" on page 876](#): rules will scan the integrity of users
- ["WQLSet" on page 881](#): rules will monitor the integrity of the results of a [Windows Management Instrumentation WQL](#) query statement

A single Integrity Rule can contain multiple Entity Sets. This allows you to, for example, secure an application with a single rule that monitors multiple files and registry entries.

Hierarchies and wildcards

For Entity Sets that represent a hierarchical data type such as FileSet and RegistryKeySet, section-based pattern matching is supported:

- `/` (forward slash) : demarcates sections of the pattern to be applied to levels of the hierarchy
- `**` (two stars) : matches zero or more sections

The following wildcards are supported:

- `?` (question mark) : matches one character
- `*` (one star) : matches zero or more characters

"Escaping" characters is also supported:

- `\` (back slash) : escapes the next character

The pattern is divided into sections using the "`/`" character, with each section of the pattern being applied to successive levels of the hierarchy as long as it continues to match. For example, if the pattern:

```
/a?c/123/*.java
```

is applied to the path:

```
/abc/123/test.java
```

Then:

- `"a?c"` matches `"abc"`
- `"123"` matches `"123"`
- `"*.java"` matches `"test.java"`

When the pattern is applied to the path:

Trend Micro Deep Security On-Premise 11.3

```
/abc/123456/test.java
```

Then:

- "a?c " matches "abc"
- " 123 " does *not* match "123456", and so no more matching is performed

The " ** " notation pattern matches zero or more sections, and so:

```
/abc/**/*.java
```

matches both "abc/123/test.java" and "abc/123456/test.java". It would also match "abc/test.java" and "abc/123/456/test.java".

Syntax and concepts

This section will present some example Integrity Monitoring rules. The examples will use the **FileSet** Entity Set but the topics and components described are common to all Entity Sets. A minimal Integrity Monitoring rule could look like this:

```
<FileSet base="C:\Program Files\MySQL">  
</FileSet>
```

The "base" attribute specifies the base directory for the FileSet. Everything else about the rule will be relative to this directory. If nothing further is added to the rule, everything (including subdirectories) below the "base" will be monitored for changes.

Note: The " * " and " ? " wildcards can be used in a "base" attribute string, but only in the last path component of the base. So this is valid:

```
base="C:\program files\CompanyName * Web Server"
```

but this is not:

```
base="C:\* files\Microsoft Office"
```

Within an Entity Set, "include" and "exclude" tags can be used to control pattern matching. These tags have a "key" attribute that specifies the pattern to match against. The source of the

key varies by Entity Set. For example, for Files and Directories it is their path, while for Ports it is the unique protocol/IP/portNumber tuple.

Note: If a path supplied in an include or exclude rule is syntactically invalid, the Agent will generate an "Integrity Monitoring Rule Compile Issue" Agent Event and supply the rule ID and the path (after expansion) as parameters. An example of an invalid path would be `C:\test1\D:\test2` since a file name may not contain two volume identifiers.

Include tag

The include tag is essentially an allow list. Using it means that only those Entities matched by it (or other include tags) will be included. By adding an include tag, the following rule now only monitors changes to files with the name "*.exe" in the "C:\Program Files\MySQL" folder and sub folders:

```
<FileSet base="C:\Program Files\MySQL">
  <include key="**/*.exe"/>
</FileSet>
```

"Includes" can be combined. The following rule will monitor changes to files with the names "*.exe" and "*.dll" in the "C:\Program Files\MySQL" folder and sub folders:

```
<FileSet base="C:\Program Files\MySQL">
  <include key="**/*.exe"/>
  <include key="**/*.dll"/>
</FileSet>
```

It is also possible to combine multiple criteria in a single include block, in which case **all** criteria must be true for a given Entity to be included. The following "include" tag requires that an Entity both end in ".exe" and start with "sample" to be included. Although this requirement could be represented more succinctly, the usefulness of this becomes more apparent as key patterns are combined with other features of the Entity, as described in the "Features" section below.

```
<include>
  <key pattern="**/*.exe"/>
  <key pattern="**/sample*"/>
</include>
```

The following is another way to express the same requirements:

```
<include key="**/*.exe">
  <key pattern="**/sample*" />
</include>
```

Exclude tag

The exclude tag functions as a block list, removing files from the set that would otherwise be returned. The following (unlikely) example would place everything but temp files under watch.

```
<FileSet base="C:\Program Files\MySQL">
  <include key="**"/>
  <exclude key="**/*.tmp" />
</FileSet>
```

The following rule excludes the "MySQLInstanceConfig.exe" from the set of EXEs and DLLs:

```
<FileSet base="C:\Program Files\MySQL">
  <include key="**/*.exe" />
  <include key="**/*.dll" />
  <exclude key="**/MySQLInstanceConfig.exe" />
</FileSet>
```

Like the "include" tag, the "exclude" tag can be written to require multiple criteria. The following example shows a multi-criteria "exclude" tag.

```
<exclude>
  <key pattern="**/MySQLInstanceConfig*" />
  <key pattern="**/*.exe" />
</exclude>
```

Case sensitivity

The case sensitivity of pattern matching for an include or exclude tag may be controlled by the "casesensitive" attribute. The attribute has three allowed values:

- **true**
- **false**
- **platform**

The default value for this attribute is "platform", which means that the case sensitivity of the pattern will match the platform on which it is running. In the following example, both "Sample.txt" and "sample.txt" would be returned on a Windows system, but only "Sample.txt" would be returned on a Unix system:

```
<FileSet base="C:\Program Files\MySQL">
  <include key="**/*Sample*" />
</FileSet>
```

In this example, only "Sample.txt" would be returned on Windows and Unix:

```
<FileSet base="C:\Program Files\MySQL">
  <include key="**/*Sample*" casesensitive="true" />
</FileSet>
```

Note: A case sensitive setting of "true" is of limited use on a platform such as Windows which is case insensitive when it comes to most object names.

Entity features

The inclusion and exclusion of Entities based on features other than their "key" is also supported for some Entity types. The set of features differs by Entity type. The following example will include all executable files. It does not depend on the file extension as previous examples using file extensions did, but instead will check the first few hundred bytes of the file to determine if it is executable on the given OS.

```
<FileSet base="C:\Program Files\MySQL">
  <include key="**" executable="true" />
</FileSet>
```

Feature attributes must appear in an "include" or "exclude" tag. To use them as part of a multi-criteria include or exclude, they must be specified as attributes of the enclosing include or exclude tag. The following example includes all files that contain the string "MySQL" in their name and are also executable:

```
<include executable="true">
  <key pattern="**/*MySQL*" />
</include>
```

The previous example can be more succinctly expressed as:

```
<include key="**/*MySQL*" executable="true"/>
```

Some feature attributes are simply matches against the value of one of the Entity's attributes. In such cases, wildcard matches using " `*` " and " `?` " are sometimes supported. The help pages for the individual Entity Sets indicate which attributes can be used in include or exclude rules in this way, and whether they support wildcard matching or simple string matching.

Note: Where wildcard matches *are* supported, it is important to note that the match is against the string value of the attribute and that no normalization takes place. Constructs available for Entity key matches such as " `**` " and the use of " `/` " to separate hierarchical components don't apply. Matching a path name on Windows requires the use of " `\` " since that is the character which appears in the value of the attribute being tested, whereas Unix systems will use " `/` " in path values so matches against Unix paths need to use " `/` ".

The following is an example of a feature match using the "state" attribute:

```
<ServiceSet>
  <include state="running"/>
</ServiceSet>
```

Note: Wildcards are not supported in state matches.

The following example matches any processes where the path of the binary ends in "`\notepad.exe`":

```
<ProcessSet>
  <include path="*\notepad.exe"/>
</ProcessSet>
```

The following example matches any processes where the command-line begins with "`/sbin/`":

```
<ProcessSet>
  <include commandLine="/sbin/*"/>
</ProcessSet>
```

Note: Be careful when using wildcards. A wildcard expression like " ** " will look at every file in every sub directory beneath "base". Creating a baseline for such an expression can take a lot of time and resources.

ANDs and ORs

It is possible to express logical ANDs and ORs through the use of multi-criteria includes and excludes and multiple includes and excludes.

There are several ways that a multi criteria include or exclude can be used to express an AND. The most straightforward is to include multiple criteria within a single enclosing tag. The following example shows a simple multi-criteria AND-ing:

```
<include>
  <key pattern="**/*MySQL*" />
  <key pattern="**/*.exe"/>
</include>
```

As well, any criteria expressed as an attribute of the including tag will be grouped with the enclosed criteria as part of the multi-criteria requirement. The following example shows the previous multi-criteria "include" re-written in this way:

```
<include key="**/*.exe">
  <key pattern="**/*MySQL*" />
</include>
```

Finally, if multiple criteria are expressed as attributes of an include or exclude they are treated as an AND:

```
<include executable="true" key="**/*MySQL*" />
```

ORs are expressed simply by the inclusion of multiple include or exclude tags. The following code includes files if their extensions are ".exe" OR ".dll":

```
<include key="**/*.dll" />
<include key="**/*.exe" />
```


Order of evaluation

All "includes" are processed first, regardless of order of appearance in the rule. If an object name matches at least one "include" tag, it is then tested against the "exclude" tags. It is removed from the set of monitored objects if it matches at least one "exclude" tag.

Entity attributes

A given Entity has a set of attributes that can be monitored. If no attributes are specified for an Entity Set (i.e. the attributes wrapper tag is not present) then the STANDARD set of attributes for that Entity is assumed. (See the *Shorthand Attributes* sections for the individual Entity Sets.)

However, for a given Entity Set only certain attributes of the Entity may be of interest for Integrity Monitoring. For example, changes to the contents of a log file are most likely expected and allowed. However changes to the permissions or ownership should be reported.

The "attributes" tag of the Entity Sets allows this to be expressed. The "attributes" tag contains a set of tags enumerating the attributes of interest. The set of allowed "attribute" tags varies depending on the Entity Set for which they are being supplied.

Note: If the "attributes" tag is present, but contains no entries, then the Entities defined by the rule are monitored for existence only.

The following example monitors executable files in "C:\Program Files\MySQL" whose name includes "SQL" for changes to their "last modified", "permissions", and "owner" attributes:

```
<FileSet base="C:\Program Files\MySQL" >
  <include key="**/*SQL*" executable="true"/>
  <attributes>
    <lastModified/>
    <permissions/>
    <owner/>
  </attributes>
</FileSet>
```

The following example monitors the "permissions", and "owner" attributes of log files in "C:\Program Files\MySQL":

```
<FileSet base="C:\Program Files\MySQL" >
  <attributes>
    <permissions/>
    <owner/>
  </attributes>
  <include key="**/*.log" />
</FileSet>
```

In the following example, the STANDARD set of attributes will be monitored. (See Shorthand Attributes, below)

```
<FileSet base="C:\Program Files\MySQL" >
  <include key="**/*.log" />
</FileSet>
```

In the following example, no attributes will be monitored. Only the existence of the Entities will be tracked for change.

```
<FileSet base="C:\Program Files\MySQL" >
  <attributes/>
  <include key="**/*.log" />
</FileSet>
```

Shorthand attributes

Shorthand attributes provide a way to specify a group of attributes using a single higher level attribute. Like regular attributes the set of allowed values differs based on the Entity Set for which they are being supplied.

Shorthand Attributes are useful in cases where a set of attributes naturally group together, in cases where exhaustively listing the set of attributes would be tedious, and in cases where the set of attributes represented by the high level attribute may change with time or system configuration. An example of each case follows:

Attribute	Description
STANDARD	The set of attributes to monitor for the Entity Set. This is different than "every possible attribute" for the Entity Set. For example, it would not include every possible hash algorithm, just the ones deemed sufficient. For the list of "standard" attributes for each Entity Set, see sections for the individual Entity Sets.
CONTENTS	This is Shorthand for the hash, or set of hashes, of the contents of the file. Defaults to SHA-1.

onChange attribute

An EntitySet may be set to monitor changes in real time. If the onChange attribute of an EntitySet is set to true (the default value) then the entities returned by the EntitySet will be monitored for changes in real time. When a change is detected the Entity is immediately compared against its baseline for variation. If the onChange attribute of an EntitySet is set to false, it will be run only when a baseline is built or when it is triggered via a scheduled task or on demand by the Deep Security Manager.

The following sample monitors the MySQL binaries in real time:

```
<FileSet base="C:\Program Files\MySQL" onChange="true">
  <include key="**/*.exe"/>
  <include key="**/*.dll" />
</FileSet>
```

Environment variables

Environment variables can be included in the base value used in Entity Sets. They are enclosed in "\${}". The variable name itself is prefaced with "env.".

The following example sets the base directory of the FileSet to the path stored in the PROGRAMFILES environment variable:

```
<FileSet base="${env.PROGRAMFILES}"/>
```

Note: The values of referenced environment variables are read and stored by the Deep Security Agent on Agent startup. If the value of an environment variable changes, the Agent must be restarted to register the change.

If a referenced environment variable is not found, the Entity Sets referencing it are not scanned or monitored, but the rest of the configuration is used. An alert is triggered indicating that the variable is not present. The Agent reports an invalid environment variable using Agent event "Integrity Monitoring Rule Compile Issue". The ID of the Integrity Monitoring rule and the environment variable name are supplied as parameters to the event.

The following are the default environment variables that Integrity Monitoring uses:

Name	Value
ALLUSERSPROFILE	C:\ProgramData
COMMONPROGRAMFILES	C:\Program Files\Common Files
PROGRAMFILES	C:\Program Files
SYSTEMDRIVE	C:
SYSTEMROOT	C:\Windows
WINDIR	C:\Windows

Environment variable overrides

Override environment variables when non-standard locations are used in the Windows operating system. For example, the **Microsoft Windows - 'Hosts' file modified** Integrity Monitoring rule, which monitors changes to the Windows `hosts` file, looks for that file in the `C:\WINDOWS\system32\drivers\etc` folder. However not all Windows installations use the `C:\WINDOWS\` directory, so the Integrity Monitoring rule uses the `WINDIR` environment variable and represents the directory as `%WINDIR%\system32\drivers\etc`.

Note: Environment variables are used primarily by the virtual appliance when performing agentless Integrity Monitoring on a virtual machine. This is because the virtual appliance has no way of knowing if the operating system on a particular virtual machine is using standard directory locations.

1. Open the **Computer or Policy editor**¹ where you want to override an environment variable.
2. Click **Settings > Advanced**.
3. In the **Environment Variable Overrides** section, click **View Environment Variables** to display the **Environment Variable Overrides** page.
4. Click **New** in the menu bar and enter a new name-value pair (for example, `WINDIR` and `D:\Windows`) and click **OK**.

Registry values

Registry values can be included in the base value used in Entity Sets. They are enclosed in `{}`. The path to the registry value itself is prefaced with "reg.". The following example sets the base

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

directory of the FileSet to the path stored in the "HKLM\Software\Trend Micro\Deep Security Agent\InstallationFolder" registry value:

```
<FileSet base="${reg.HKLM\Software\Trend Micro\Deep Security Agent\InstallationFolder}"/>
```

The values of referenced registry values are read when a new or changed rule is received by the Agent. The Agent also checks all rules at startup time and will rebuild the baseline for affected Rules if any referenced registry values change.

If a referenced registry value is not found, the EntitySets referencing it are not scanned or monitored, but the rest of the configuration is used. An alert notifying that the variable is not present is raised. The Agent reports an invalid environment variable expansion using Agent Event 8012. The ID of the Integrity Monitoring rule and the registry value path are supplied as parameters to the event.

Note: A wildcard is allowed only in the last hierarchical component of a base name. For example, `base="HKLM\Software\ATI*"` is valid and will find both "HKLM\Software\ATI" and "HKLM\Software\ATI Technologies"; however, `base="HKLM*\Software\ATI"` is invalid.

Use of ".."

The ".." convention for referencing a parent directory is supported in all current versions of the Agent. The Agent will attempt to normalize base directory names for FileSet and DirectorySet elements by resolving ".." references and converting Windows short names to long names. For example, on some newer versions of Windows the following FileSet would have a base directory of `C:\Users`. On earlier versions of Windows it would be `C:\Documents and Settings`.

```
<FileSet base="${env.USERPROFILE}\..">
  <include key="*/Start Menu/Programs/Startup/*"/>
</FileSet>
```

Best practices

Rules should be written to only include objects and attributes that are of significance. This will ensure that no events are reported if other attributes of the object change. For example, your change monitoring policy may place restrictions on permission and ownership of files in `/bin`.

Your Integrity Monitoring rule should monitor owner, group, and permissions, but not other attributes like lastModified or hash values.

When using Integrity Monitoring rules to detect malware and suspicious activity, monitor services, watch for use of NTFS data streams, and watch for executable files in unusual places such as " /tmp " or " \${env.windir}\temp ".

Always be as specific as possible when specifying what objects to include in a rule. The fewer objects you include, the less time it will take to create your baseline and the less time it will take to scan for changes. Exclude objects which are expected to change and only monitor the attributes you are concerned about.

When creating a rule, do not:

- Use " */... " from a top-level of the hierarchy such as " / ", "C:\", or " HKLM\Software ".
- Use more than one content hash type unless absolutely necessary.
- Reference user-specific locations such as `HKEY_CURRENT_USER` , `${env.USERPROFILE}` , or `${env.HOME}` .

Any of these statements in your integrity monitoring rules will cause performance issues as the Deep Security Agent searches through many items in order to match the specified patterns.

DirectorySet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

The DirectorySet tag describes a set of Directories.

Tag Attributes

These are XML attributes of the tag itself, as opposed to the attributes of the Entity monitored by Integrity Monitoring Rules.

Attribute	Description	Required	Default Value	Allowed Values
base	Sets the base directory of the DirectorySet. Everything else in the tag is relative to this directory	Yes	N/A	String values resolving to syntactically valid path (Path is not required to exist) Note: UNC paths are allowed by Windows Agents, but require that the remote system allow access by the "LocalSystem" account of the Agent computer. The Agent is a Windows service and runs as LocalSystem, aka NT AUTHORITY\SYSTEM. When accessing a network resource, the LocalSystem uses the computer's credentials, which is an account named <i>DOMAINMACHINE\$</i> . The access token presented to the remote computer also contains the "Administrators" group for the computer, so remote shares must grant read privileges to either the Agent computer's account, the Agent computer's Administrators group, or "Everyone". If the base value is not syntactically valid, the FileSet will not be processed. The rest of the config will be evaluated.
onChange	Whether the directories returned should be monitored in real time.	No	false	true, false
followLinks	Will this DirectorySet follow symbolic links.	No	false	true, false

Entity Set Attributes

These are the attributes of the Entity that may be monitored by Integrity Monitoring Rules.

- **Created:** Timestamp when the directory was created
- **LastModified:** Timestamp when the directory was last modified
- **LastAccessed:** Timestamp when the directory was last accessed. On Windows this value does not get updated immediately, and recording of the last accessed timestamp can be disabled as a performance enhancement. See [File Times](#) for details. The other problem with this attribute is that the act of scanning a directory requires that the Agent open the directory, which will change its last accessed timestamp.
- **Permissions:** The directory's security descriptor (in [SDDL](#) format) on Windows or Posix-style ACLs on Unix systems that support ACLs, otherwise the Unix style `rwxrwxrwx` file permissions in numeric (octal) format.

- **Owner:** User ID of the directory owner (commonly referred to as the "UID" on Unix)
- **Group:** Group ID of the directory owner (commonly referred to as the "GID" on Unix)
- **Flags:** Windows-only. Flags returned by the [GetFileAttributes\(\)](#) Win32 API. Windows Explorer calls these the "Attributes" of the file: Read-only, Archived, Compressed, etc.
- **SymLinkPath:** If the directory is a symbolic link, the path of the link is stored here. On Windows, use the SysInternals "junction" utility to create the Windows equivalent of symbolic links.
- **InodeNumber** (Unix and Linux only): Inode number of the disk on which the inode associated with the file is stored
- **DeviceNumber** (Unix and Linux only): Device number of the disk on which the inode associated with the directory is stored

Short Hand Attributes

The following are the Short Hand Attributes, and the attributes to which they map.

- **STANDARD:**
 - Created
 - LastModified
 - Permissions
 - Owner
 - Group
 - Flags (Windows only)
 - SymLinkPath

Meaning of "Key"

Key is a pattern to match against the path of the directory relative to the directory specified by "dir". This is a hierarchical pattern, with sections of the pattern separated by "/" matched against sections of the path separated by the file separator of the given OS.

Sub Elements

- Include
- Exclude

See ["Integrity monitoring rules language" on page 837](#) for a general description of Include and Exclude for their allowed attributes and sub elements. Only information specific to includes and excludes relating to this EntitySet class are included here.

FileSet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

The FileSet tag describes a set of Files.

Tag Attributes

These are XML attributes of the tag itself, as opposed to the attributes of the Entity monitored by Integrity Monitoring Rules.

Attribute	Description	Required	Default Value	Allowed Values
base	Sets the base directory of the FileSet. Everything else in the tag is relative to this directory.	Yes	N/A	String values resolving to syntactically valid path (Path is not required to exist). Note: UNC paths are allowed by Windows Agents, but require that the remote system allow access by the "LocalSystem" account of the Agent computer. The Agent is a Windows service and runs as LocalSystem, aka NT AUTHORITY\SYSTEM. When accessing a network resource, the LocalSystem uses the computer's credentials, which is an account named <i>DOMAINMACHINE\$</i> . The access token presented to the remote computer also contains the "Administrators" group for the computer, so remote shares must grant read privileges to either the Agent computer's account, the Agent computer's Administrators group, or "Everyone". If the base value is not syntactically valid, the FileSet will not be processed. The rest of the config will be evaluated.
onChange	Whether the	No	false	true, false

Attribute	Description	Required	Default Value	Allowed Values
	files returned should be monitored in real time.			
followLinks	Will this FileSet follow symbolic links.	No	false	true, false

Entity Set Attributes

These are the attributes of the FileSet that can be monitored by Integrity Monitoring Rules.

- **Created:** Timestamp when the file was created
- **LastModified:** Timestamp when the file was last modified
- **LastAccessed:** Timestamp when the file was last accessed. On Windows this value does not get updated immediately, and recording of the last accessed timestamp can be disabled as a performance enhancement. See [File Times](#) for details. The other problem with this attribute is that the act of scanning a file requires that the Agent open the file, which will change its last accessed timestamp. On Unix, the Agent will use the O_NOATIME flag if it is available when opening the file, which prevents the OS from updating the last accessed timestamp and speeds up scanning.
- **Permissions:** The file's security descriptor (in [SDDL](#) format) on Windows or Posix-style ACLs on Unix systems that support ACLs, otherwise the Unix style rwxrwxrwx file permissions in numeric (octal) format.
- **Owner:** User ID of the file owner (commonly referred to as the "UID" on Unix)
- **Group:** Group ID of the file owner (commonly referred to as the "GID" on Unix)
- **Size:** size of the file
- **Sha1:** SHA-1 hash
- **Sha256:** SHA-256 hash
- **Md5:** MD5 hash (deprecated)
- **Flags:** Windows-only. Flags returned by the [GetFileAttributes\(\)](#) Win32 API. Windows Explorer calls these the "Attributes" of the file: Read-only, Archived, Compressed, etc.

- **SymLinkPath** (Unix and Linux only): If the file is a symbolic link, the path of the link is stored here. Windows NTFS supports Unix-like symlinks, but only for directories, not files. Windows shortcut objects are not true symlinks since they are not handled by the OS; the Windows Explorer handles shortcut files (*.lnk) but other applications that open a *.lnk file will see the contents of the lnk file.
- **InodeNumber** (Unix and Linux only): Inode number of the disk on which the inode associated with the file is stored
- **DeviceNumber** (Unix and Linux only): Device number of the disk on which the inode associated with the file is stored
- **BlocksAllocated** (Linux and Unix only): The number of blocks allocated to store the file.
- **Growing**: (DSA 7.5+) contains the value "true" if the size of the file stays the same or increases between scans, otherwise "false". This is mainly useful for log files that have data appended to them. Note that rolling over a log file will trigger a change in this attribute.
- **Shrinking**: (DSA 7.5+) contains the value "true" if the size of the file stays the same or decreases between scans, otherwise "false".

Short Hand Attributes

The following are the Short Hand Attributes, and the attributes to which they map.

- **CONTENTS**: Resolves to the content hash algorithm set in **Computer or Policy editor**¹ > **Integrity Monitoring > Advanced**.
- **STANDARD**: Created, LastModified, Permissions, Owner, Group, Size, Contents, Flags (Windows only), SymLinkPath (Unix only)

Drives Mounted as Directories

Drives mounted as directories are treated as any other directory, unless they are a network drive in which case they are ignored.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Alternate Data Streams

NTFS based file systems support the concept of alternate data streams. When this feature is used it behaves conceptually like files within the file.

Note: To demonstrate this, type the following at the command prompt:

```
echo plain > sample.txt
echo alternate > sample.txt:s
more < sample.txt
more < sample.txt:s
```

The first "more" will show only the text "plain", the same text that will be displayed if the file is opened with a standard text editor, such as notepad. The second "more", which accesses the "s" stream of sample.txt will display the string "alternate".

For FileSets, if no stream is specified, then all streams are included. Each stream is a separate Entity entry in the baseline. The available attributes for streams are:

- **size**
- **Sha1**
- **Sha256**
- **Md5** (deprecated)
- **Contents**

The following example would include both streams from the demonstration above:

```
<include key="**/sample.txt" />
```

To include or exclude specific streams, the ":" notation is used. The following example matches only the "s" stream on sample.txt and not the main sample.txt stream:

```
<include key="**/sample.txt:s" />
```

Pattern matching is supported for the stream notation. The following example would include sample.txt, but exclude all of its alternate streams:

```
<include key="**/sample.txt" />
<exclude key="**/sample.txt:*" />
```

Meaning of "Key"

Key is a pattern to match against the path of the file relative to the directory specified by "base". This is a hierarchical pattern, with sections of the pattern separated by "/" matched against sections of the path separated by the file separator of the given OS

Sub Elements

- **Include**
- **Exclude**

See ["Integrity monitoring rules language" on page 837](#) for a general description of Include and Exclude for their allowed attributes and sub elements. Only information specific to includes and excludes relating to the FileSet Entity Set class are included here.

Special attributes of Include and Exclude for FileSets:

executable

Determines if the file is executable. This does not mean that its permissions allow it to be executed. Instead the contents of the file are checked, as appropriate for platform, to determine if the file is an executable file.

Note: This is a relatively expensive operation since it requires the Agent to open the file and examine the first kilobyte or two of its content looking for a valid executable image header. Opening and reading every file is much more expensive than simply scanning directories and matching file names based on wild card patterns, so any include and exclude rules using "executable" will result in slower scan times than those that do not use it.

GroupSet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

GroupSet represents a set of groups. Note these are local groups only.

Tag Attributes

These are XML attributes of the tag itself, as opposed to the attributes of the Entity monitored by Integrity Monitoring Rules.

Attribute	Description	Required	Default Value	Allowed Values
onChange	Will be monitored in real time	No	false	true, false

Entity Set Attributes

These are the attributes of the entity that can be monitored:

- **Description:** (Windows only) The textual description of the group.
- **Group:** The group ID and name. The group name is part of the entity key, but it's still important to be able to monitor the group ID-name pairing in case groups are renamed and given new IDs. Operating systems generally enforce security based on its ID.
- **Members:** A comma separated list of the members of the group.
- **SubGroups:** (Windows only) A comma separated list of sub-groups of the group.

Short Hand Attributes

- **Standard:** Group Members SubGroups

Meaning of "Key"

The key is the group's name. This is not a hierarchical Entity Set. Patterns are applied only to the group name. As a result the "*" pattern is not applicable. The following example monitors the "Administrators" group for additions and deletions. (The "Member" attribute is included implicitly because it is a part of the STANDARD set, and no attributes are explicitly listed.)

```
<GroupSet>
  <include key="Administrators" />
</GroupSet>
```

Include and Exclude

See ["Integrity monitoring rules language" on page 837](#) for a general description of Include and Exclude and their allowed attributes and sub elements.

InstalledSoftwareSet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

Represents a set of installed software. The "key" used to uniquely identify an installed application is platform-specific, but it is often a shorthand version of the application name or a unique numeric value.

On Windows, the key can be something readable like "FogBugz Screenshot_is1" or it can be a GUID like "{90110409-6000-11D3-8CFE-0150048383C9}". You can examine these by looking at the sub-keys of HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall

On Linux the key is the RPM package name, as shown by the command:

```
rpm -qa --qf "%{NAME}\n"
```

On Solaris the key is the package name as shown by the **pkginfo** command.

On HP-UX the key is the application name as shown by the command:

```
/usr/sbin/swlist -a name
```

Tag Attributes

These are XML attributes of the tag itself, as opposed to the attributes of the computer where Integrity Monitoring is enabled.

Attribute	Description	Required	Default Value	Allowed Values
onChange	Will be monitored in real time	No	false	true, false

Entity Set Attributes

These are the attributes of the Entity that can be monitored by Integrity Monitoring Rules. Presence of the attributes is dependent on both the platform and the application itself - installation programs do not necessarily populate all of the attributes.

- **Manufacturer:** The publisher or manufacturer of the application
- **Name:** The friendly name or display name of the application. (Not available on Linux.)
- **InstalledDate:** Date of installation. This is normally returned as YYYY-MM-DD [HH:MM:SS], but many installers on Windows format the date string in a different manner so this format is not guaranteed.
- **InstallLocation:** The directory where the application is installed. (Only available on Windows)
- **Parent:** For patches and updates, this gives the key name of this item's parent. Only available on Windows.
- **Size:** The estimated size of the application, if available. On Windows this attribute is read from the "EstimatedSize" registry value under HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Uninstall*. The value in that location is expressed in KB, so the Agent multiplies it by 1024 before returning the value. Note that not all Windows applications populate the EstimatedSize field in the registry.
- **Version:** The version of the installed application. On Windows this comes from the "DisplayVersion" registry value.

Short Hand Attributes

These are the short hand attributes of the Entity and the attributes to which they resolve

- **STANDARD:** InstalledDate, Name, Version

Meaning of "Key"

The key is the name of the installed software. This is not a hierarchical key, so the ** pattern does not apply. On Windows the key is often a GUID, especially for anything installed via the Windows Installer (aka MSI). Use the name="XXX" feature if you need to include or exclude based on the display name rather than the GUID.

The following example would monitor for the addition and deletion of new software.

```
<InstalledSoftwareSet>
  <include key="*" />
  <attributes />
</InstalledSoftwareSet>
```


Sub Elements

- Include
- Exclude

See ["Integrity monitoring rules language" on page 837](#) for a general description of Include and Exclude for their allowed attributes and sub elements. Only information specific to includes and excludes relating to this EntitySet class are included here.

Special attributes of Include and Exclude for InstalledSoftwareSets:

name (Windows only)

Allows wildcard matching using ? and * on the display name of the application (the "name" attribute of the Entity). For example:

```
<InstalledSoftwareSet>  
  <include name="Microsoft*" />  
</InstalledSoftwareSet>
```

will match all installed applications whose display name (as shown by the Control Panel) starts with "Microsoft".

manufacturer

Allows wildcard matching using ? and * on the publisher or manufacturer of the application. For example:

```
<InstalledSoftwareSet>  
  <include manufacturer="* Company " />  
</InstalledSoftwareSet>
```

will match all installed applications whose manufacturer ends with " Company ".

PortSet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and

the [WQL](#) query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

Represents a set of listening ports.

Tag Attributes

These are XML attributes of the tag itself, as opposed to the attributes of the Entity monitored by Integrity Monitoring Rules.

Attribute	Description	Required	Default Value	Allowed Values
onChange	Will be monitored in real time	No	false	true, false

Entity Set Attributes

These are the attributes of the Entity that can be monitored by Integrity Monitoring Rules.

- **Created:** Windows only - XP SP2+ and Server 2003 SP1+ required. Returned by the GetExtendedTcpTable() or GetExtendedUdpTable() API. Indicates when the bind operation that created this TCP or UDP link occurred.
- **Listeners:** The number of active listeners on this protocol, IP address, and port number combination. This reflects the number of sockets bound-to and listening-on the given port, and may be greater than the number of processes listening on the port if processes bind multiple sockets to the port. This attribute has no value if only one socket is bound to the given port.
- **Path:** Windows only - XP SP2+ and Server 2003 SP1+ required. Gives the short name, if available, of the module that owns the port. On Windows this comes from the GetOwnerModuleFromXxxEntry() APIs. According to Microsoft documentation, the resolution of connection table entries to owner modules is a best practice. In a few cases, the owner module name returned can be a process name, such as "svchost.exe", a service name (such as "RPC"), or a component name, such as "timer.dll".
- **Process:** (Windows only - XP SP2+ and Server 2003 SP1+ required.) Gives the full path, if available, of the module that owns the port. On Windows this comes from the GetOwnerModuleFromXxxEntry() APIs. According to Microsoft documentation, the resolution of connection table entries to owner modules is a best practice.

- **ProcessId:** (Windows only - XP SP2+ and Server 2003 SP1+ required.) Gives the PID of the process that issued the bind for this port.
- **User:** (Linux only). Gives the user that owns the port.

Meaning of "Key"

The key is in the following format:

<PROTOCOL>/<IP ADDRESS>/<PORT>

For example:

```
tcp/172.14.207.94/80
udp/172.14.207.94/68
```

IPV6

If the IP address is IPv6 the key is in the same format, but the protocol is TCP6 or UDP6 and the IP address is an IPv6 address as returned by the getnameinfo API:

```
tcp6/3ffe:1900:4545:3:200:f8ff:fe21:67cf/80
udp6/3ffe:1900:4545:3:200:f8ff:fe21:67cf/68
```

Matching of the Key

This is not a hierarchical key, so ** is not applicable. Unix-style glob matching is possible using * and ?. The following pattern matches port 80 on the IP addresses 72.14.207.90 through 72.14.207.99:

```
*/72.14.207.9?/80
```

The following pattern matches port 80 on the IP addresses 72.14.207.2, 72.14.207.20 through 72.14.207.29 as well as 72.14.207.200 through 72.14.207.255:

```
*/72.14.207.2*/80
```

The following pattern matches port 80 on any IP.

```
*/80
```

The following example would monitor for any change in the listening ports but ignore port 80 for TCP in IPv4 and IPv6:

```
<PortSet>
  <include key="*" />
  <exclude key="tcp*/*/80" />
</PortSet>
```

Sub Elements

- **Include**
- **Exclude**

See ["Integrity monitoring rules language" on page 837](#) for a general description of Include and Exclude and their allowed attributes and sub elements. Only information specific to includes and excludes relating to this EntitySet class are included here.

Special attributes of Include and Exclude for PortSets:

Various other attributes of the port may be used in include and exclude feature tests. These tests compare a value against the value of an attribute of the port; take note of the platform support for various attributes - not all attributes are available across platforms or even platform revisions, hence the use of these tests in include and exclude tags is of limited use. The feature tests support Unix glob-style wildcarding with * and ?, and there is no normalization of path separators or other characters - it is a simple match against the value of the attribute.

Path

Checks for a wildcard match against the path attribute of the port. The following example would monitor ports owned by processes running the main IIS binary:

```
<PortSet>
  <include path="*\system32\inetsrv\inetinfo.exe" />
</PortSet>
```

Process

Checks for a wildcard match against the process attribute of the port. The following example would monitor ports owned by anything running in a svchost.exe or outlook.* binary:

```
<PortSet>
  <include process="svchost.exe" />
  <include process="outlook.*" />
</PortSet>
```

User

Checks for a wildcard match against the user attribute of the port. The following example would monitor ports on a Unix system that were owned by the super-user (root):

```
<PortSet>
  <include user="root"/>
</PortSet>
```

ProcessSet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

Represents a set of processes.

Tag Attributes

These are XML attributes of the tag itself, as opposed to the attributes of the Entity monitored by Integrity Monitoring Rules.

Attribute	Description	Required	Default Value	Allowed Values
onChange	Will be monitored in real time	No	false	true, false

Entity Set Attributes

These are the attributes of the Entity that can be monitored by Integrity Monitoring Rules.

- **CommandLine:** The full command-line as shown by "ps -f" (Unix), "ps w" (Linux), or Process Explorer (Windows).
- **Group:** The group under which the process is running. Under Unix this is the "effective" group ID of the process, which can change over time if the process drops privileges or otherwise switches its effective group credentials. On Windows this is the current Primary Group of the process as returned by the Win32 API GetTokenInformation with a TokenInformationClass of TokenPrimaryGroup. This is the default Primary Group SID for newly created objects. In addition to a Primary Group, processes typically have one or

more group credentials associated with them. Those additional group credentials are not monitored by the Agent - they can be viewed on the "Security" tab of the process properties in Process Explorer.

- **Parent:** The PID of the process that created this process.
- **Path:** The full path to the binary of the process. On Windows, this comes from the `GetModuleFileNameEx()` API. On Linux it comes from reading the symlink `/proc/{pid}/exe`.
- **Process:** The short name of the process binary (no path). For example, for `"c:\windows\notepad.exe"` it would be `"notepad.exe"` and for `"/usr/local/bin/httpd"` it would be `"httpd"`.
- **Threads:** The number of threads currently executing in the process.
- **User:** The user under which the process is running. Under Unix this is the "effective" user ID of the process, which can change over time if the process drops privileges or otherwise switches its effective user credentials.

Short Hand Attributes

- **STANDARD:** `CommandLine`, `Group`, `Parent`, `Path` (where available), `Process User`

Meaning of "Key"

The key is a combination of the "Process" attribute (the short name of the executable) and the PID. The PID is appended to the name with a path separator in between, ex. `notepad.exe\1234` on Windows and `httpd/1234` on Unix. The use of the path separator is to allow include or exclude matching of `key="abc/*"` to work as expected.

Sub Elements

- **Include**
- **Exclude**

See ["Integrity monitoring rules language" on page 837](#) for a general description of include for their allowed attributes and sub elements. Only information specific to includes and excludes relating to this EntitySet class are included here.

Special attributes of Include and Exclude for ProcessSets:

The following example would monitor the set of running processes for notepad.exe regardless of the PID.

```
<ProcessSet>
  <include key="notepad.exe\*" />
</ProcessSet>
```

Various other attributes of a process can be used in include and exclude feature tests. The feature tests support Unix glob-style wildcarding with * and ?, and there is no normalization of path separators or other characters - it is a simple glob-style match against the value of the attribute.

CommandLine

Checks for a wildcard match against the commandLine attribute of the process. The following example would monitor any process whose command-line matches "*httpd *":

```
<ProcessSet>
  <include commandLine="*httpd *" />
</ProcessSet>
```

Group

Checks for a wildcard match against the group attribute of the process. The text version of the group name is used rather than the numeric form: use "daemon" rather than "2" to test for the daemon group on Linux. The following example would monitor any process running as one of the groups root, daemon, or lp:

```
<ProcessSet>
  <include group="root" />
  <include group="daemon" />
  <include group="lp" />
</ProcessSet>
```

Path

Checks for a wildcard match against the path attribute of the process. The path attribute is not available on some platforms. The following example would monitor any process whose binary resides under System32:

```
<ProcessSet>
  <include path="*\System32\*" />
</ProcessSet>
```

User

Checks for a wildcard match against the user attribute of the process. The text version of the user name is used rather than the numeric form: use "root" rather than "0" (zero) to test for the superuser on Unix. The following example would monitor any process running as one of the built in system users (ex. NT AUTHORITY\SYSTEM, NT AUTHORITY\LOCAL SERVICE, NT AUTHORITY\NETWORK SERVICE):

```
<ProcessSet>
  <include user="NT AUTHORITY\*" />
</ProcessSet>
```

RegistryKeySet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

The RegistryKeySet tag describes a set keys in the registry (Windows only).

Tag Attributes

These are XML attributes of the tag itself, as opposed to the attributes of the Entity monitored by Integrity Monitoring Rules.

Attribute	Description	Required	Default Value	Allowed Values
base	Sets the base key of the RegistryKeySet. Everything else in the tag is relative to this key. The base must begin with one of the following registry branch names:	Yes	N/A	String values resolving to syntactically valid

Attribute	Description	Required	Default Value	Allowed Values
	HKEY_CLASSES_ROOT (or HKCR), HKEY_LOCAL_MACHINE (or HKLM), HKEY_USERS (or HKU), HKEY_CURRENT_CONFIG (or HKCC)			registry key path

Entity Set Attributes

These are the attributes of the Entity that can be monitored by Integrity Monitoring Rules.

- **Owner**
- **Group**
- **Permissions**
- **LastModified** ("LastWriteTime" in Windows registry terminology)
- **Class**
- **SecurityDescriptorSize**

Short Hand Attributes

- **STANDARD:** Group, Owner, Permissions, LastModified

Meaning of "Key"

Registry Keys are stored hierarchically in the registry, much like directories in a file system. For the purpose of this language the "key path" to a key is considered to look like the path to a directory. For example the "key path" to the "Deep Security Agent" key of the Agent would be:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Trend Micro\Deep Security Agent
```

The "key" value for includes and excludes for the RegistryValueSet is matched against the key path. This is a hierarchical pattern, with sections of the pattern separated by "/" matched against sections of the key path separated by "\".

Sub Elements

- **Include**
- **Exclude**

See ["Integrity monitoring rules language" on page 837](#) for a general description of include for their allowed attributes and sub elements.

RegistryValueSet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

A set of Registry values (Windows only).

Tag Attributes

These are XML attributes of the tag itself as opposed to the attributes of the entity monitored by Integrity Monitoring Rules.

Attribute	Description	Required	Default Value	Allowed Values
base	Sets the base key of the RegistryValueSet. Everything else in the tag is relative to this key. The base must begin with one of the registry branch names: HKEY_CLASSES_ROOT (or HKCR), HKEY_LOCAL_MACHINE (or HKLM), HKEY_USERS (or HKU), HKEY_CURRENT_CONFIG (or HKCC)	Yes	N/A	String values resolving to syntactically valid registry key

Entity Set Attributes

These are the attributes of the Entity that can be monitored by Integrity Monitoring Rules:

- Size
- Type
- Sha1
- Sha256
- Md5 (deprecated)

Short Hand Attributes

- **CONTENTS:** Resolves to the content hash algorithm set in **Computer or Policy editor**¹ > **Integrity Monitoring > Advanced**.
- **STANDARD:** Size, Type, Contents

Meaning of "Key"

Registry Values are name-value pairs stored under a key in the registry. The key under which they are stored may in turn be stored under another key, very much like files and directories on a file system. For the purpose of this language the "key path" to a value is considered to look like the path to a file. For example, the "key path" to the InstallationFolder value of the Agent would be:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Trend Micro\Deep Security Agent\InstallationFolder
```

The "key" value for includes and excludes for the RegistryValueSet is matched against the key path. This is a hierarchical pattern, with sections of the pattern separated by "/" matched against sections of the key path separated by "\"

Default Value

Each registry key has an unnamed or default value.

This value can be explicitly specified for inclusion and exclusion by using a trailing "/" in patterns. For example, "***/" will match all subordinate unnamed values, and "**Agent/**/" will match all unnamed values below a key matching "**Agent".

Note: Registry value names can contain any printable character, including quotes, backslash, the "@" symbol, etc.

The Agent deals with this in Entity key names by using backslash as an escape character, but only backslashes themselves are escaped. It does this so that it can tell the difference between a

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

value name containing a backslash and a backslash that occurs as part of the registry path. This means that value names which end with a backslash character will match rules designed to match the default or unnamed value.

See the table below for example registry value names and the resulting Entity key.

Value	Escaped Form	Example
Hello	Hello	HKLM\Software\Sample\Hello
"Quotes"	"Quotes"	HKLM\Software\Sample\"Quotes"
back\slash	back\\slash	HKLM\Software\Sample\back\\slash
trailing\	trailing\\	HKLM\Software\Sample\trailing\\
		HKLM\Software\Sample\
@	@	HKLM\Software\Sample\@

Sub Elements

- **Include**
- **Exclude**

See ["Integrity monitoring rules language" on page 837](#) for a general description of Include and Exclude for their allowed attributes and sub elements.

ServiceSet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

The ServiceSet element represents a set of services (Windows only). Services are identified by the "service name", which is not the same as the "name" column shown in the Services administrative tool. The service name can be seen in the service properties and is often shorter than the value shown in the "name" column, which is actually the "Display Name" of the service. For example, the Agent has a service name of "ds_agent" and a display name of "Trend Micro Deep Security Agent".

Tag Attributes

These are XML attributes of the tag itself, as opposed to the attributes of the Entity monitored by Integrity Monitoring Rules.

Attribute	Description	Required	Default Value	Allowed Values
onChange	Will be monitored in real time	No	false	true, false

Entity Set Attributes

These are the attributes of the Entity that can be monitored by Integrity Monitoring Rules.

- **Permissions:** The service's security descriptor in [SDDL](#) format.
- **Owner:** User ID of the service owner
- **Group:** Group ID of the service owner
- **BinaryPathName:** The path plus optional command-line arguments that Windows uses to start the service.
- **DisplayName:** The "display name" of the service as shown in the properties panel of the service.
- **Description:** Description as it appears in the Services panel
- **State:** The current state of the service. One of: stopped, starting, stopping, running, continuePending, pausePending, paused
- **StartType:** How is the service started? One of: automatic, disabled, manual.
- **LogOnAs:** The name of the account that the service process will be logged on as when it runs.
- **FirstFailure:** Action to take the first time the service fails. Format is "delayInMsec,action", where action is one of None, Restart, Reboot, RunCommand.
- **SecondFailure:** Action to take the second time the service fails. Format is "delayInMsec,action", where action is one of None, Restart, Reboot, RunCommand.
- **SubsequentFailures:** Action to take if the service fails for a third or subsequent time. Format is "delayInMsec,action", where action is one of None, Restart, Reboot, RunCommand.

- **ResetFailCountAfter:** Time after which to reset the failure count to zero if there are no failures, in seconds.
- **RebootMessage:** Message to broadcast to server users before rebooting in response to the "Reboot" service controller action.
- **RunProgram:** Full command line of the process to execute in response to the RunCommand service controller action.
- **DependsOn:** Comma separated list of components that the service depends on
- **LoadOrderGroup:** The load ordering group to which this service belongs. The system startup program uses load ordering groups to load groups of services in a specified order with respect to the other groups. The list of load ordering groups is contained in the following registry value: HKEY_LOCAL_MACHINE\System\CurrentControlSet\Control\ServiceGroupOrder
- **ProcessId:** This is the numeric ID of the process that hosts the service. Many services may exist in a single Windows process, but for those that run in their own process, the monitoring of this attribute will allow the system to log service restarts.

Short Hand Attributes

These are the short hand attributes of the Entity and the attributes to which they resolve

- **STANDARD:** Permissions, Owner, Group, BinaryPathName, Description, State, StartType, LogOnAs, FirstFailure, SecondFailure, SubsequentFailures, ResetFailCountAfter, RunProgram, DependsOn, LoadOrderGroup, ProcessId

Meaning of "Key"

The key is the Service's name, which is not necessarily the same as the "name" column shown in the Services administrative tool (that tool shows the "display name" of the service). The service name can be seen in the service properties and is often shorter than the value shown in the "name" column.

Note: This is not a hierarchical Entity Set. Patterns are applied only to the service name. As a result the ** pattern is not applicable.

Sub Elements

- Include
- Exclude

See ["Integrity monitoring rules language" on page 837](#) for a general description of include for their allowed attributes and sub elements. Only information specific to includes and excludes relating to this Entity Set class are included here.

Special attributes of Include and Exclude for ServiceSets:

state

Include or exclude based on whether the state of the service (stopped, starting, stopping, running, continuePending, pausePending, paused). The following example would monitor the set of running services for change:

```
<ServiceSet>
  <include state="running"/>
</ServiceSet>
```

UserSet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the [WQL](#) query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

The UserSet element represents a set of users. On a Windows system it operates on users local to the system - the same users displayed by the "Local Users and Groups" MMC snap-in. Note that these are *local* users only if the DSA is running on something other than a domain controller. On a domain controller a UserSet element will enumerate all of the domain users, which may not be advisable for extremely large domains.

On Unix systems, the users monitored are whatever the "getpwent_r()" and "getspnam_r()" APIs have been configured to return.

Tag Attributes

These are XML attributes of the tag itself, as opposed to the attributes of the Entity monitored by Integrity Monitoring Rules.

Attribute	Description	Required	Default Value	Allowed Values
onChange	Will be monitored in real time	No	false	true, false

Entity Set Attributes

These are the attributes of the entity that can be monitored:

Common Attributes

- **cannotChangePassword:** True or false indicating if the user is permitted to change their password.
- **disabled:** True or false indicating if the account has been disabled. On Windows systems this reflects the "disabled" checkbox for the user. On Unix systems this will be true if the user's account has expired or if their password has expired and they've exceeded the inactivity grace period for changing it.
- **fullName:** The display name of the user.
- **groups:** A comma-separated list of the groups to which the user belongs.
- **homeFolder:** The path to the home folder or directory.
- **lockedOut:** True or false indicating if the user has been locked out, either explicitly or due to excessive failed password attempts.
- **passwordHasExpired:** True or false indicating if the user's password has expired. Note that on Windows this attribute is only available on Windows XP and newer operating systems.
- **passwordLastChanged:** The timestamp of the last time the user's password was changed. This is recorded by the DSA as the number of milliseconds since Jan 1 1970 UTC - Deep Security Manager renders the timestamp in local time based on this value. Note that on Unix platforms the resolution of this attribute is one day, so the time component of the rendered timestamp is meaningless.
- **passwordNeverExpires:** True or false indicating if the password does not expire.

- **user:** The name of the user as known to the operating system. For example, "Administrator" or "root".

Windows-only Attributes

- **description:** The primary group the user belongs to.
- **homeDriveLetter:** The drive letter to which a network share is mapped as the user's home folder.
- **logonScript:** The path to a script that executes every time the user logs in.
- **profilePath:** A network path if roaming or mandatory Windows user profiles are being used.

Linux-only Attributes

- **group:** The primary group the user belongs to.
- **logonShell:** The path to the shell process for the user.
- **passwordExpiredDaysBeforeDisabled:** The number of days after the user's password expires that the account is disabled.
- **passwordExpiry:** The date on which the user's account expires and is disabled.
- **passwordExpiryInDays:** The number of days after which the user's password must be changed.
- **passwordMinDaysBetweenChanges:** The minimum number of days permitted between password changes.
- **passwordWarningDays:** The number of days before the user's password is to expire that user is warned.

Short Hand Attributes

- **Standard:**
 - cannotChangePassword
 - disabled
 - groups
 - homeFolder

- passwordHasExpired
- passwordLastChanged
- passwordNeverExpires
- user
- logonScript (Windows-only)
- profilePath (Windows-only)
- group (Linux-only)
- logonShell (Linux-only)
- passwordExpiryInDays (Linux-only)
- passwordMinDaysBetweenChanges (Linux-only)

Meaning of "Key"

The key is the username. This is not a hierarchical EntitySet. Patterns are applied only to the user name. As a result the "*" pattern is not applicable.

The following example monitors for any user creations or deletions. (Note that attributes are explicitly excluded so group membership would not be tracked):

```
<UserSet>
  <Attributes/>
  <include key="*" />
</UserSet>
```

The following example would track the creation and deletion of the "jsmith" account, along with any changes to the STANDARD attributes of the account (since the STANDARD set for this EntitySet is automatically included if no specific attribute list is included):

```
<UserSet>
  <include key="jsmith" />
</UserSet>
```

Sub Elements

Include and Exclude

See ["Integrity monitoring rules language" on page 837](#) for a general description of include for their allowed attributes and sub elements.

Special attributes of Include and Exclude for UserSets

Various other attributes of the user may be used in include and exclude feature tests. These tests compare a value against the value of an attribute of the user; take note of the platform support for various attributes - not all attributes are available across platforms or even platform revisions, hence the use of these tests in include and exclude elements is of limited use. The feature tests support Unix glob-style wildcarding with * and ?, and there is no normalization of path separators or other characters - it is a simple match against the value of the attribute.

- **Disabled:** Does true or false match the disabled attribute of the user. The following example monitors users with a primary group of either "users" or "daemon":

```
<UserSet>
  <include disabled="true"/>
</UserSet>
```

- **Group:** Does a wildcard match against the primary group of the user. This test is only applicable on Unix systems. The following example would monitor users with a primary group of either "users" or "daemon".

```
<UserSet>
  <include group="users"/>
  <include group="daemon"/>
</UserSet>
```

- **LockedOut:** Does a true or false match against the lockedOut attribute of the user.
- **PasswordHasExpired:** Does a true or false match against the passwordHasExpired attribute of the user.
- **PasswordNeverExpires:** Does a true or false match against the passwordNeverExpires attribute of the user.

WQLSet

Note: The Integrity Monitoring module scans for unexpected changes to [directories](#), [registry values](#), [registry keys](#), [services](#), [processes](#), [installed software](#), [ports](#), [groups](#), [users](#), [files](#), and the WQL query statement on Deep Security Agents. To enable and configure Integrity Monitoring, see ["Set up integrity monitoring" on page 824](#).

The WQLSet element describes a result set from a [Windows Management Instrumentation](#) WQL query statement. [WQL](#) allows SQL-like queries to be made against many different object classes, with the results forming a table of rows where each row represents an object and each column represents the value of a specific attribute of the object.

Note: Many WMI queries consume a large amount of time and computer resources. It is easy to inadvertently issue a query that takes several minutes to complete and returns thousands of rows. It is highly recommended that all queries be tested before use in a WQLSet using a program like Powershell or [WMI Explorer](#).

Attribute	Description	Required	Default Value	Allowed Values
namespace	Sets the namespace of the WMI query.	Yes	N/A	String values representing a valid WMI namespace. The "root\cimv2" namespace is the one most commonly used when querying Windows operating system objects, but others such as "root\directory\LDAP" and "root\Microsoft\SqlServer\ComputerManagement" can be used. See here for a small script called GetNamespaces.vbs that enumerates the available WMI namespaces on a given computer.
wql	A WQL query string.	Yes	N/A	A valid WQL string. The query must include the __Path attribute for each returned object; the Agent uses the __Path attribute as the entity key when storing and reporting results, so each returned WMI object must include a __Path. If using a query string such as "SELECT * FROM ..." the __Path attribute will be available, but if using a more selective query such as "SELECT Name FROM ..." you must explicitly include __Path by writing the query as "SELECT __Path, Name FROM ...".
onChange	Whether the files returned should be monitored in real time.	No	false	true, false

Attribute	Description	Required	Default Value	Allowed Values
provider	Optionally specifies an alternative WMI namespace provider to use.	No	none	<p>RsopLoggingModeProvider</p> <p>At present this is only required/supported for group policy queries, and "RsopLoggingModeProvider" is the only supported value. Group policy queries are special since it's recommended that the RsopLoggingModeProvider be used to create a snapshot of the policy data that is present on a computer. If you create a snapshot of the policy data, the query can be performed against a consistent set of data before the system overwrites or deletes it during a refresh of policy. Creating a snapshot actually creates a new WMI namespace, so when using provider="RsopLoggingModeProvider" in a WQLSet, the namespace attribute should specify the suffix to be added to the created namespace. For example, a typical temporary namespace created by the RsopLoggingModeProvider would be "\\.\Root\Rsop\NS71EF4AA3_FB96_465F_AC1C_DF9A3E9010". Specify namespace="Computer" to query "\\.\Root\Rsop\NS71EF4AA3_FB96_465F_AC1C_DF9A3E9010\Computer".</p> <p>Since the temporary namespace is a one-time value, it hampers the ability of the Agent to detect changes since the value appears in the entity key. To avoid this, the Agent will remove the portion of the returned __Path value after \Rsop\ and up to the next backslash when the RsopLoggingModeProvider is used. Entity keys will therefore have prefixes like "\\.\Root\Rsop\Computer" rather than "\\.\Root\Rsop\NS71EF4AA3_FB96_465F_AC1C_DF9A3E9010\Computer".</p>
timeout	Specifies a per-row timeout in milliseconds.	No	5000	<p>1-60000</p> <p>The WMI query is performed in semisynchronous mode, where result rows are fetched one at a time and there is a timeout on the fetching of a single row. If this parameter is not specified, 5000 (5 seconds) is used as the timeout value.</p>

Entity Set Attributes

Each "row" returned by the WQL query is treated as a single Entity for Integrity Monitoring purposes, with the returned columns representing the attributes of the entity. Since WMI/WQL is an open-ended specification, there is no set list of available or supported attributes. The query and the schema of the WMI object being queried will determine the attributes being monitored.

For example, the WQLSet:

Trend Micro Deep Security On-Premise 11.3

```
<WQLSet namespace="Computer" wql="select * from RSOP_SecuritySettings where  
precedence=1" provider="RsopLoggingModeProvider" />
```

will return attributes of:

```
ErrorCode, GPOID, KeyName, SOMID, Setting, Status, id, precedence
```

whereas a WQLSet that queries network adapters such as:

```
<WQLSet namespace="root\cimv2" wql="select * from Win32_NetworkAdapter where  
AdapterTypeId = 0" />
```

will return attributes such as:

```
AdapterType, AdapterTypeId, Availability, Caption, ConfigManagerErrorCode,  
ConfigManagerUserConfig, CreationClassName Description, DeviceID, Index, Installed,  
MACAddress, Manufacturer, MaxNumberControlled, Name, PNPDeviceID,  
PowerManagementSupported, ProductName, ServiceName, SystemCreationClassName,  
SystemName, TimeOfLastReset
```

In order to reduce the load on the Agent, it is advisable to explicitly include only the attributes that require monitoring rather than use "select * ..." in queries. This also has the benefit that changes to the WMI schema to add or remove attributes will not be reported as changes to the object unless the attributes are part of the set being monitored. With "select * from Win32_Foobar", a patch to Windows that adds a new attribute to the Win32_Foobar object class would result in the next integrity scan reporting a change for every object of that class since a new attribute has appeared.

The following are some example WMI queries which return desirable Windows system entities.

Query for Windows mounted storage devices: (selecting for * will typically result in 80% returned attributes being null or duplicate values)

```
<WQLSet namespace="root\cimv2" wql="SELECT ____  
Path, DeviceID, VolumeName, VolumeSerialNumber, DriveType, FileSystem, Access, MediaType, S  
ize, FreeSpace FROM Win32_LogicalDisk" />
```

To further the preceding query, the DriveType can be specified to isolate only certain types of mounted logical storage devices, such as type 2 which is a "Removable Disk": (like a removable USB storage drive)

Trend Micro Deep Security On-Premise 11.3

```
<WQLSet namespace="root\cimv2" wql="SELECT __
Path, DeviceID, VolumeName, VolumeSerialNumber, DriveType, FileSystem, Access, MediaType, S
ize, FreeSpace FROM Win32_LogicalDisk WHERE DriveType=2" />
```

(See [here](#) for details on the Win32_LogicalDisk class)

USB Storage Device notes: U3 USB devices will mount both a type 2 "Removable Disk" device and a type 3 "Compact Disc" device. Also, the above query is for storage devices only. USB non-storage devices will not be included. USB memory card adapters may appear as a type 1 "No Root Directory" device. A badly or Windows incompatible USB storage device may appear as a type 1 "Unknown" device.

Query for all known System Directories where the Drive is "F:" for relevant attributes:

```
<WQLSet namespace="root\cimv2" wql="SELECT __
Path, CreationDate, LastAccessed, LastModified, Drive, Path, FileName, Caption, FileType, Re
adable, Writeable FROM Win32_Directory WHERE Drive='F:'" />
```

Query for all known System Files where the Drive is "F:" for relevant attributes:

```
<WQLSet namespace="root\cimv2" wql="SELECT __
Path, CreationDate, LastAccessed, LastModified, Drive, Path, FileName, Name, FileType, Readable, Writeable FROM CIM_DataFile WHERE Drive='F:'" />
```

Meaning of Key

The key is the "__Path" attribute of the returned WMI object, which is generally of the form:

```
SystemName\Namespace:WmiObjectClass.KeyAttribute=Value[,KeyAttribute=Value...]
```

Some examples:

```
\\TEST-DESK\root\cimv2:Win32_QuickFixEngineering.HotFixID="KB958215-
IE7",ServicePackInEffect="SP0"
\\TEST-DESK\ROOT\RsoP\NSF49B36AD_10A3_4F20_9541_B4C471907CE7\Computer:RSOP_
RegistryValue.

Path="MACHINE\\Software\\Microsoft\\Windows\\CurrentVersion\\Policies\\System\\Lega
lNoticeText",precedence=1
\\TEST-DESK\root\cimv2:BRM_NetworkAdapter.DeviceID="8"
```

Include Exclude

See ["Integrity monitoring rules language" on page 837](#) for a general description of "include" and "exclude" for their allowed attributes and sub elements.

For WQLSet, "include" and "exclude" sub elements should typically not be required. It is preferable to use WQL to specify the exact set of objects to be monitored since that limits the amount of work done by both the agent and the computer's WMI implementation.

The use of any include or exclude sub elements can only reduce the set of objects returned by the query; the WQL must be changed in order to return additional objects. If it is necessary to use include or exclude elements to further restrict the WQL results, "*" and "?" characters can be used as simple wildcards to match against values of the entity key.

Virtual Appliance Scan Caching

Scan Caching is used by the Virtual Appliance to maximize the efficiency of Anti-Malware and Integrity Monitoring Scans of virtual machines. Scan Caching improves the efficiency of scans by eliminating the unnecessary scanning of identical content across multiple VMs in large VMware deployments. A Scan Cache contains lists of files and other scan targets that have been scanned by a Deep Security protection module. If a scan target on a virtual machine is determined to be identical to a target that has already been scanned, the Virtual Appliance will not scan the target a second time. Attributes used to determine whether entities are identical are creation time, modification time, file size, and file name. In the case of Real-time Scan Caching, Deep Security will read partial content of files to determine if two files are identical. There is an option setting to use a file's Update Sequence Number (USN, Windows only) but its use should be limited to cloned virtual machines.

Scan Caching benefits **Integrity Monitoring** by sharing Integrity Monitoring scan results among cloned or similar virtual machines.

Scan Caching benefits **Manual Malware Scans** of cloned or similar virtual machines by increasing the speed up subsequent scans.

Scan Caching benefits **Real-Time Malware Scanning** by speeding up boot process scans and application access scans on cloned or similar virtual machines.

Scan Cache Configurations

A Scan Cache Configuration is a collection of settings that determines Expiry Time, the use of Update Sequence Numbers (USNs), files to exclude, and files to include.

Note: Virtual machines that use the same Scan Cache Configuration also share the same Scan Cache.

You can see the list of existing Scan Cache Configurations by going **Administration > System Settings > Advanced > Scan Cache Configurations** and clicking **View Scan Cache Configurations**. Deep Security comes with several preconfigured default Scan Cache Configurations. These are implemented automatically by the Virtual Appliance depending the properties of the virtual machines being protected and the types of scan being performed.

Expiry Time determines the lifetime of individual entries in a Scan Cache. The default recommended settings are one day for Manual (on-demand) or Scheduled Malware Scans, 15 mins for Real-Time Malware Scans, and one day for Integrity Monitoring Scans.

Use USN (Windows only) specifies whether to make use of Windows NTFS Update Sequence Numbers, which is a 64-bit number used to record changes to an individual file. This option should only be set for cloned VMs.

Files Included and **Files Excluded** are regular expression patterns and lists of files to be included in or excluded from the Scan Cache. Files to be scanned are matched against the include list first.

Individual files and folders can be identified by name or you can use wildcards ("*" and "?") to refer to multiple files and locations with a single expression. (Use "*" to represent any zero or more characters, and use question mark "?" to represent any single character.)

Note: The include and exclude lists only determine whether the scan of the file will take advantage of Scan Caching. The lists will not prevent a file from being scanned in the traditional way.

Malware Scan Cache Configuration

To select which Scan Cache Configuration is used by a virtual machine, open the **Computer or Policy editor**¹ and go to **Anti-Malware > Advanced > VM Scan Cache**. You can select which Scan Cache Configuration is used for Real-Time Malware Scans and which Scan Cache Configuration is used for manual and scheduled scans.

Integrity Monitoring Scan Cache Configuration

To select which Scan Cache Configuration is used by a virtual machine, open the **Computer or Policy editor**² and go to **Integrity Monitoring > Advanced > VM Scan Cache**.

Scan Cache Settings

Scan Cache Settings are not included in a Scan Cache Configuration because they determine how the Virtual Appliance manages Scan Caches rather than how Scan Caching is carried out. Scan Cache settings are controlled at the Policy level. You can find the Scan cache settings by opening a **Policy editor**³ and going to the **Settings > General > Virtual Appliance Scans** area.

Max Concurrent Scans determines the number of scans that the Virtual Appliance performs at the same time. The recommended number is five. If you increase this number beyond 10, scan performance may degrade. Scan requests are queued by the virtual appliance and carried out in the order in which they arrive. This setting applies to manual and scheduled scans.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

³To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

Max On-Demand Malware Scan Cache Entries determines, for manual or scheduled malware scans, the maximum number of records that identify and describe a file or other type of scannable content to keep. One million entries use approximately 100 MB of memory.

Max Malware Real-Time Scan Cache Entries determines, for real-time malware scans, the maximum number of records that identify and describe a file or other type of scannable content to keep. One million entries use approximately 100MB of memory.

Max Integrity Monitoring Scan Cache Entries determines the maximum number of entities included in the baseline data for integrity monitoring. Two hundred thousand entities use approximately 100MB of memory.

When to change the default configuration

Scan caching is designed to avoid scanning identical files twice. Deep Security does not examine the entire contents of all files to determine if files are identical. Although when configured to do so, Deep Security can check the USN value of a file, and during Real-time Scans it will read partial content of files, it generally examines file attributes to determine if files are identical. It would be difficult but not impossible for some malware to make changes to a file and then restore those files attributes to what they were before the file was modified.

Deep Security limits this potential vulnerability by establishing short default cache expiry times. To strengthen the security you can use shorter expiry times on cache and you can use USN but doing so may reduce the performance benefit or require a larger cache setting. For the strongest security for VMs that you want to keep separate and never share scan results you can create dedicated policies for these VMs kind of like keeping them in separate zones. This might be appropriate if you have different departments or organizations sharing the same infrastructure. (In a multi-tenant Deep Security Manager, this is automatically enforced for each tenant.)

If you have a very large number of guest VMs per ESXi host (for example, a VDI environment), then you should monitor your disk I/O and CPU usage during scanning. If scanning takes too long, then you may need to increase the size of the cache or adjust the Scan Cache Settings until you get better performance. If you need to increase cache size, then you may need to adjust Deep Security Virtual Appliance system memory too.

Analyze logs with log inspection

Note: For a list of operating systems where log inspection is supported, see ["Supported features by platform" on page 85](#).

The log inspection protection module helps you identify important events that might be buried in your operating system and application logs. These events can be sent to a security information and event management (SIEM) system or centralized logging server for correlation, reporting, and archiving. All events are also securely collected in the Deep Security Manager. For more information about logging and forwarding events, see ["Configure log inspection event forwarding and storage" on page 892](#).

The log inspection module lets you:

- Meet PCI DSS log monitoring requirements.
- Detect suspicious behavior.
- Collect events across heterogeneous environments containing different operating systems and diverse applications.
- View events such as error and informational events (disk full, service start, service shutdown, etc.).
- Create and maintain audit trails of administrator activity (administrator login or logout, account lockout, policy change, etc.).

To enable and configure log inspection, see ["Set up log inspection" on the next page](#).

The log inspection feature in Deep Security enables real-time analysis of third party log files. The log inspection rules and decoders provide a framework to parse, analyze, rank and correlate events across a wide variety of systems. As with intrusion prevention and integrity monitoring, log inspection content is delivered in the form of rules included in a security update. These rules provide a high level means of selecting the applications and logs to be analyzed. To configure and examine log inspection rules, see ["Define a log inspection rule for use in policies" on page 893](#).

Set up log inspection

To use log inspection, perform these basic steps:

1. ["Turn on the log inspection module" below](#)
2. ["Run a recommendation scan" below](#)
3. ["Apply the recommended log inspection rules" on the next page](#)
4. ["Test Log Inspection" on page 892](#)
5. ["Configure log inspection event forwarding and storage" on page 892](#)

For an overview of the log inspection module, see ["Analyze logs with log inspection" on the previous page](#).

Turn on the log inspection module

1. Go to **Policies**.
2. Double-click the policy for which you want to enable log inspection.
3. Click **Log Inspection > General**.
4. For **Log Inspection State**, select **On**.
5. Click **Save**.

Run a recommendation scan

Rules should be set to gather security events relevant to your requirements. When improperly set, events for this feature can overwhelm the Deep Security database if too many log entries are triggered and stored. Run a recommendation scan on the computer for recommendations about which rules are appropriate to apply.

1. Go to **Computers** and double-click the appropriate computer.
2. Click **Log Inspection > General**.
3. For **Automatically implement Log Inspection Rule Recommendations (when possible)**, you can decide whether Deep Security should implement the rules it finds by selecting **Yes** or **No**.
4. In the **Recommendations** section, click **Scan For Recommendations**. Some log inspection rules written by Trend Micro require local configuration to function properly. If you assign


one of these rules to your computers or one of these rules gets assigned automatically, an alert will be raised to notify you that configuration is required.

For more information about recommendation scans, see ["Manage and run recommendation scans" on page 529](#).

Apply the recommended log inspection rules

Deep Security ships with many pre-defined rules covering a wide variety of operating systems and applications. When you run a recommendation scan, you can choose to have Deep Security [automatically implement the recommended rules](#), or you can choose to manually select and assign the rules by following the steps below:

1. Go to **Policies**.
2. Double-click the policy that you want to configure.
3. Click **Log Inspection > General**.
4. In the **Assigned Log Inspection Rules** section, the rules in effect for the policy are displayed. To add or remove log inspection rules, click **Assign/Unassign**.



5. Select or deselect the checkboxes for the rules you want to assign or unassign. You can edit the log inspection rule by right-clicking the rule and selecting **Properties** to edit the rule locally or **Properties (Global)** to apply the changes to all other policies that are using the rule. For more information, see ["Examine a log inspection rule" on page 916](#).
6. Click **OK**.

Although Deep Security ships with log inspection rules for many common operating systems and applications, you also have the option to create your own custom rules. To create a custom rule, you can either use the "Basic Rule" template, or you can write your new rule in XML. For information on how to create a custom rule, see ["Define a log inspection rule for use in policies" on the next page](#).

Test Log Inspection

Before continuing with further Log Inspection configuration steps, test that the rules are working correctly:

1. Ensure Log Inspection is enabled.
2. Go to **Computer or Policies editor > Log Inspection > Advanced**. Change **Store events at the Agent/Appliance for later retrieval by DSM when they equal or exceed the following severity level to Low (3)** and click **Save**.
3. Go to the **General** tab, and click **Assign/Unassign**. Search for and enable:
 - 1002792 - Default Rules Configuration - This is required for all other Log Inspection rules to work.

If you're a Windows user, enable:

- 1002795 - Microsoft Windows Events - This logs events every time the Windows auditing functionality registers an event.

If you're a Linux user, enable:

- 1002831 - Unix - Syslog - This inspects the syslog for events.
4. Click **OK**, and then click **Save** to apply the rules to the policy.
 5. Attempt to log in to the server with an account that does not exist.
 6. Go to **Events & Reports > Log Inspection Events** to verify the record of the failed login attempt. If the detection is recorded, the Log Inspection module is working correctly.

Configure log inspection event forwarding and storage

When a log inspection rule is triggered, an event is logged. To view these events, go to **Events & Reports > Log Inspection Events** or **Policy editor > Log Inspection > Log Inspection Events**.

For more information on working with log inspection events, see ["Log inspection events" on page 1272](#).

Depending on the severity of the event, you can choose to send them to a syslog server (For information on enabling this feature, see ["Forward Deep Security events to an external syslog or SIEM server" on page 1111](#).) or to store events in the database by using the severity clipping feature.

There are two "severity clipping" settings available:

- **Send Agent events to syslog when they equal or exceed the following severity level:** This setting determines which events triggered by those rules get sent to the syslog server, if syslog is enabled.
- **Store events at the Agent for later retrieval by Deep Security Manager when they equal or exceed the following severity level:** This setting determines which log inspection events are kept in the database and displayed in the **Log Inspection Events** page.

To configure severity clipping:

1. Go to **Policies**.
2. Double-click the policy you want to configure.
3. Click **Log Inspection > Advanced**.
4. For **Send Agent/Appliance events to syslog when they equal or exceed the following severity level**, choose a severity level between **Low (0)** and **Critical (15)**.
5. For **Store events at the Agent/Appliance for later retrieval by DSM when they equal or exceed the following severity level**, choose a severity level between **Low (0)** and **Critical (15)**.
6. Click **Save**.

Define a log inspection rule for use in policies

The OSSEC log inspection engine is integrated into Deep Security Agents and gives Deep Security the ability to inspect the logs and events generated by the operating system and applications running on the computer. Deep Security Manager ships with a standard set of

OSSEC log inspection rules that you can assign to computers or policies. You can also create custom rules if there is no existing rule that fits your requirements.

Log Inspection Rules issued by Trend Micro are not editable (although you can duplicate them and then edit them.)

Note: Log Inspection Rules that are assigned to one or more computers or that are part of a policy cannot be deleted.

To create log inspection rules, perform these basic steps:

- ["Create a new log inspection rule" below](#)
- ["Decoders" on page 896](#)
- ["Subrules" on page 897](#)
- ["Real world examples" on page 905](#)
- ["Log inspection rule severity levels and their recommended use" on page 914](#)
- ["strftime\(\) conversion specifiers " on page 915](#)
- ["Examine a log inspection rule" on page 916](#)

For an overview of the log inspection module, see ["Analyze logs with log inspection" on page 889](#).

Create a new log inspection rule

1. In the Deep Security Manager, go to **Policies > Common Objects > Rules > Log Inspection Rules**.
2. Click **New > New Log Inspection Rule**.
3. On the **General** tab, enter a name and an optional description for the rule.
4. The **Content** tab is where you define the rule. The easiest way to define a rule is to select **Basic Rule** and use the options provided to define the rule. If you need further customization, you can select **Custom (XML)** to switch to an XML view of the rule that you are defining.

Note: Any changes you make in the Custom (XML) view will be lost if you switch back to the Basic Rule view.

For further assistance in writing your own log inspection rules using the XML-based language, consult the [OSSEC](#) documentation or contact your support provider.

These options are available for the Basic Rule template:

- **Rule ID:** The Rule ID is a unique identifier for the rule. OSSEC defines 100000 - 109999 as the space for user-defined rules. Deep Security Manager will pre-populate the field with a new unique Rule ID.
- **Level:** Assign a level to the rule. Zero (0) means the rule never logs an event, although other rules that watch for this rule may fire.
- **Groups:** Assign the rule to one or more comma-separated groups. This can be useful when dependency is used because you can create rules that fire on the firing of a rule, or a rule that belongs to a specific group.
- **Rule Description:** Description of the rule.
- **Pattern Matching:** This is the pattern the rule will look for in the logs. The rule will be triggered on a match. Pattern matching supports Regular Expressions or simpler String Patterns. The "String Pattern" pattern type is faster than RegEx but it only supports three special operations:
 - **^ (caret):** specifies the beginning of text
 - **\$ (dollar sign):** specifies the end of text
 - **| (pipe):** to create a "OR" between multiple patterns

For information on the regular expression syntax used by the Log Inspection module, see <https://www.ossec.net/docs/syntax/regex.html>.

- **Dependency:** Setting a dependency on another rule will cause your rule to only log an event if the rule specified in this area has also triggered.
- **Frequency** is the number of times the rule has to match within a specific time frame before the rule is triggered.

- **Time Frame** is the period of time in seconds within which the rule has to trigger a certain number of times (the frequency, above) to log an event.

Note: The **Content** tab only appears for log inspection rules that you create yourself. Log inspection rules issued by Trend Micro have a **Configuration** tab instead that displays the log inspection rule's configuration options (if any).

1. On the **Files** tab, type the full path to the file(s) you want your rule to monitor and specify the type of file it is.
2. On the **Options** tab, in the **Alert** section, select whether this rule triggers an alert in the Deep Security Manager.

The **Alert Minimum Severity** setting is only used if you have written "multiple rules" within your rule - something that cannot be done using the Basic template. However, if after creating your rule using the Basic template, you edit the XML of the rule and add additional rules to the XML that have different severity levels, you can use the **Alert Minimum Severity Level** setting to set the minimum severity from the multiple rules that will trigger an Alert.

3. The **Assigned To** tab lists the policies and computers that are using this log inspection rule. Because you are creating a new rule, it has not been assigned yet.
4. Click **OK**. The rule is ready to be assigned to policies and computers.

Decoders

A log inspection rule consists of a list of files to monitor for changes and a set of conditions to be met for the rule to trigger. When the log inspection engine detects a change in a monitored log file, the change is parsed by a decoder. Decoders parse the raw log entry into the following fields:

- **log**: the message section of the event
- **full_log**: the entire event
- **location**: where the log came from
- **hostname**: hostname of the event source
- **program_name**: program name from the syslog header of the event

- **srcip**: the source IP address within the event
- **dstip**: the destination IP address within the event
- **srcport**: the source port number within the event
- **dstport**: the destination port number within the event
- **protocol**: the protocol within the event
- **action**: the action taken within the event
- **srcuser**: the originating user within the event
- **dstuser**: the destination user within the event
- **id**: any ID decoded as the ID from the event
- **status**: the decoded status within the event
- **command**: the command being called within the event
- **url**: the URL within the event
- **data**: any additional data extracted from the event
- **systemname**: the system name within the event

Rules examine this decoded data looking for information that matches the conditions defined in the rule.

If the matches are at a sufficiently high severity level, any of the following actions can be taken:

- An alert can be raised. (Configurable on the **Options** tab of the Log Inspection Rule's **Properties** window.)
- The event can be written to syslog. (Configurable in the **SIEM** area on **Administration > System Settings > Event Forwarding** tab.)
- The event can be sent to the Deep Security Manager. (Configurable in the **Log Inspection Syslog Configuration** setting on the **Policy or Computer Editor > Settings > Event Forwarding** tab.)

Subrules

A single log inspection rule can contain multiple subrules. These subrules can be of two types: atomic or composite. An atomic rule evaluates a single event and a composite rule examines

multiple events and can evaluate frequency, repetition, and correlation between events.

Groups

Each rule, or grouping of rules, must be defined within a `<group></group>` element. The attribute name must contain the rules you want to be a part of this group. In the following example we have indicated that our group contains the syslog and sshd rules:

```
<group name="syslog,sshd,">
</group>
```

Note: Notice the trailing comma in the group name. Trailing commas are required if you intend to use the `<if_group></if_group>` tag to conditionally append another sub-rule to this one.

Note: When a set of log inspection rules are sent to an agent, the log inspection engine on the agent takes the XML data from each assigned rule and assembles it into what becomes essentially a single long log inspection rule. Some group definitions are common to all log inspection rules written by Trend Micro. For this reason Trend Micro has included a rule called "Default Rules Configuration" which defines these groups and which always gets assigned along with any other Trend Micro rules. (If you select a rule for assignment and haven't also selected the "Default Rules Configuration" rule, a notice will appear informing you that the rule will be assigned automatically.) *If you create your own log inspection rule and assign it to a Computer without assigning any Trend Micro-written rules, you must either copy the content of the "Default Rules Configuration" rule into your new rule, or also select the "Default Rules Configuration" rule for assignment to the Computer.*

Rules, ID, and Level

A group can contain as many rules as you require. The rules are defined using the `<rule></rule>` element and must have at least two attributes, the **id** and the **level**. The **id** is a unique identifier for that signature and the **level** is the severity of the alert. In the following example, we have created two rules, each with a different rule ID and level:

```
<group name="syslog,sshd,">
  <rule id="100120" level="5">
  </rule>
  <rule id="100121" level="6">
  </rule>
</group>
```

Note: Custom rules must have ID values of 100,000 or greater.

You can define additional subgroups within the parent group using the `<group></group>` tag. This subgroup can reference any of the groups listed in the following table:

Group Type	Group Name	Description
Reconnaissance	connection_attempt web_scan recon	Connection attempt Web scan Generic scan
Authentication Control	authentication_success authentication_failed invalid_login login_denied authentication_failures adduser account_changed	Success Failure Invalid Login Denied Multiple Failures User account added User Account changed or removed
Attack/Misuse	automatic_attack exploit_attempt invalid_access spam multiple_spam sql_injection attack virus	Worm (nontargeted attack) Exploit pattern Invalid access Spam Multiple spam messages SQL injection Generic attack Virus detected
Access Control	access_denied access_allowed unknown_resource firewall_drop multiple_drops client_misconfig client_error	Access denied Access allowed Access to nonexistent resource Firewall drop Multiple firewall drops Client misconfiguration Client error
Network Control	new_host ip_spoof	New computer detected Possible ARP spoofing
System Monitor	service_start system_error system_shutdown logs_cleared invalid_request promisc policy_changed config_changed low_diskspace time_changed	Service start System error Shutdown Logs cleared Invalid request Interface switched to promiscuous mode Policy changed Configuration changed Low disk space Time changed

Note: If event auto-tagging is enabled, the event will be labeled with the group name. Log inspection rules provided by Trend Micro make use of a translation table that changes the

group to a more user-friendly version. So, for example, "login_denied" would appear as "Login Denied". Custom rules will be listed by their group name as it appears in the rule.

Description

Include a `<description></description>` tag. The description text will appear in the event if the rule is triggered.

```
<group name="syslog,sshd,">
  <rule id="100120" level="5">
    <group>authentication_success</group>
    <description>SSHD testing authentication success</description>
  </rule>
  <rule id="100121" level="6">
    <description>SSHD rule testing 2</description>
  </rule>
</group>
```

Decoded As

The `<decoded_as></decoded_as>` tag instructs the log inspection engine to only apply the rule if the specified decoder has decoded the log.

```
<rule id="100123" level="5">
  <decoded_as>sshd</decoded_as>
  <description>Logging every decoded sshd message</description>
</rule>
```

Note: To view the available decoders, go to the **Log Inspection Rule** page and click **Decoders**. Right-click on **1002791-Default Log Decoders** and select **Properties**. Go the **Configuration** tab and click **View Decoders**.

Match

To look for a specific string in a log, use the `<match></match>`. Here is a Linux sshd failed password log:

```
Jan 1 12:34:56 linux_server sshd[1231]: Failed password for invalid
user jsmith from 192.168.1.123 port 1799 ssh2
```

Use the `<match></match>` tag to search for the "password failed" string.

```
<rule id="100124" level="5">
  <decoded_as>sshd</decoded_as>
  <match>^Failed password</match>
  <description>Failed SSHD password attempt</description>
</rule>
```

Note: Notice the regex caret ("^") indicating the beginning of a string. Although "Failed password" does not appear at the beginning of the log, the log inspection decoder will have broken up the log into sections. See ["Decoders" on page 896](#) for more information. One of those sections is "log" which is the message part of the log as opposed to "full_log" which is the log in its entirety.

The following table lists supported regex syntax:

Regex Syntax	Description
\w	A-Z, a-z, 0-9 single letters and numerals
\d	0-9 single numerals
\s	single space
\t	single tab
\p	()*+,-.::;<=>?[]
\W	not \w
\D	not \d
\S	not \s
\.	anything
+	match one or more of any of the above (for example, \w+, \d+)
*	match zero or more of any of the above (for example, \w*, \d*)
^	indicates the beginning of a string (^somestring)
\$	specify the end of a string (somestring\$)
	indicate an "OR" between multiple strings

Conditional Statements

Rule evaluation can be conditional upon other rules having been evaluated as true. The **<if_sid></if_sid>** tag instructs the log inspection engine to only evaluate this subrule if the rule identified in the tag has been evaluated as true. The following example shows three rules: 100123, 100124, and 100125. Rules 100124 and 100125 have been modified to be children of the 100123 rule using the **<if_sid></if_sid>** tag:

```
<group name="syslog,sshd,">
  <rule id="100123" level="2">
    <decoded_as>sshd</decoded_as>
```



```

        <description>Logging every decoded sshd message</description>
    </rule>
    <rule id="100124" level="7">
        <if_sid>100123</if_sid>
        <match>^Failed password</match>
        <group>authentication_failure</group>
        <description>Failed SSHD password attempt</description>
    </rule>
    <rule id="100125" level="3">
        <if_sid>100123</if_sid>
        <match>^Accepted password</match>
        <group>authentication_success</group>
        <description>Successful SSHD password attempt</description>
    </rule>
</group>

```

Hierarchy of Evaluation

The `<if_sid></if_sid>` tag essentially creates a hierarchical set of rules. That is, by including an `<if_sid></if_sid>` tag in a rule, the rule becomes a child of the rule referenced by the `<if_sid></if_sid>` tag. Before applying any rules to a log, the log inspection engine assesses the `<if_sid></if_sid>` tags and builds a hierarchy of parent and child rules.

Note: The hierarchical parent-child structure can be used to improve the efficiency of your rules. If a parent rule does not evaluate as true, the log inspection engine will ignore the children of that parent.

Note: Although the `<if_sid></if_sid>` tag can be used to refer to subrules within an entirely different log inspection rule, you should avoid doing this because it makes the rule very difficult to review later on.

The list of available atomic rule conditional options is shown in the following table:

Tag	Description	Notes
match	A pattern	Any string to match against the event (log).
regex	A regular expression	Any regular expression to match against the event(log).
decoded_ as	A string	Any prematched string.
srcip	A source IP address	Any IP address that is decoded as the source IP address. Use "!" to negate the IP address.

Trend Micro Deep Security On-Premise 11.3

Tag	Description	Notes
dstip	A destination IP address	Any IP address that is decoded as the destination IP address. Use "!" to negate the IP address.
srcport	A source port number	Any source port (match format).
dstport	A destination port number	Any destination port (match format).
user	A username	Any username that is decoded as a username.
program_name	A program name	Any program name that is decoded from the syslog process name.
hostname	A system hostname	Any hostname that is decoded as a syslog hostname.
time	A time range in the format hh:mm - hh:mm or hh:mm am - hh:mm pm	The time range that the event must fall within for the rule to trigger.
weekday	A weekday (sunday, monday, tuesday, etc.)	Day of the week that the event must fall on for the rule to trigger.
id	An ID	Any ID that is decoded from the event.
url	A URL	Any URL that is decoded from the event.

Use the `<if_sid>100125</if_sid>` tag to make this rule depend on the 100125 rule. This rule will be checked only for sshd messages that already matched the successful login rule.

```
<rule id="100127" level="10">
  <if_sid>100125</if_sid>
  <time>6 pm - 8:30 am</time>
  <description>Login outside business hours.</description>
  <group>policy_violation</group>
</rule>
```

Restrictions on the Size of the Log Entry

The following example takes the previous example and adds the **maxsize** attribute which tells the log inspection engine to only evaluate rules that are less than the maxsize number of characters:

```
<rule id="100127" level="10" maxsize="2000">
  <if_sid>100125</if_sid>
  <time>6 pm - 8:30 am</time>
  <description>Login outside business hours.</description>
  <group>policy_violation</group>
</rule>
```

The following table lists possible atomic rule tree-based options:

Tag	Description	Notes
if_sid	A rule ID	Adds this rule as a child rule of the rules that match the specified signature ID.
if_group	A group ID	Adds this rule as a child rule of the rules that match the specified group.
if_level	A rule level	Adds this rule as a child rule of the rules that match the specified severity level.
description	A string	A description of the rule.
info	A string	Extra information about the rule.
cve	A CVE number	Any Common Vulnerabilities and Exposures (CVE) number that you would like associated with the rule.
options	alert_by_email no_email_alert no_log	Additional rule options to indicate if the Alert should generate an e-mail, alert_by_email, should not generate an email, no_email_alert, or should not log anything at all, no_log.

Composite Rules

Atomic rules examine single log entries. To correlate multiple entries, you must use composite rules. Composite rules are supposed to match the current log with those already received.

Composite rules require two additional options: the **frequency** option specifies how many times an event or pattern must occur before the rule generates an alert, and the **timeframe** option tells the log inspection engine how far back, in seconds, it should look for previous logs. All composite rules have the following structure:

```
<rule id="100130" level="10" frequency="x" timeframe="y">
</rule>
```

For example, you could create a composite rule that creates a higher severity alert after five failed passwords within a period of 10 minutes. Using the `<if_matched_sid></if_matched_sid>` tag you can indicate which rule needs to be seen within the desired frequency and timeframe for your new rule to create an alert. In the following example, the **frequency** attribute is set to trigger when five instances of the event are seen and the **timeframe** attribute is set to specify the time window as 600 seconds.

The `<if_matched_sid></if_matched_sid>` tag is used to define which other rule the composite rule will watch:

```
<rule id="100130" level="10" frequency="5" timeframe="600">
  <if_matched_sid>100124</if_matched_sid>
  <description>5 Failed passwords within 10 minutes</description>
</rule>
```

Trend Micro Deep Security On-Premise 11.3

There are several additional tags that you can use to create more granular composite rules. These rules, as shown in the following table, allow you to specify that certain parts of the event must be the same. This allows you to tune your composite rules and reduce false positives:

Tag	Description
same_source_ip	Specifies that the source IP address must be the same.
same_dest_ip	Specifies that the destination IP address must be the same.
same_dst_port	Specifies that the destination port must be the same.
same_location	Specifies that the location (hostname or agent name) must be the same.
same_user	Specifies that the decoded username must be the same.
same_id	Specifies that the decoded id must be the same.

If you wanted your composite rule to alert on every authentication failure, instead of a specific rule ID, you could replace the `<if_matched_sid></if_matched_sid>` tag with the `<if_matched_group></if_matched_group>` tag. This allows you to specify a category, such as `authentication_failure`, to search for authentication failures across your entire infrastructure.

```
<rule id="100130" level="10" frequency="5" timeframe="600">
  <if_matched_group>authentication_failure</if_matched_group>
  <same_source_ip />
  <description>5 Failed passwords within 10 minutes</description>
</rule>
```

In addition to `<if_matched_sid></if_matched_sid>` and `<if_matched_group></if_matched_group>` tags, you can also use the `<if_matched_regex></if_matched_regex>` tag to specify a regular expression to search through logs as they are received.

```
<rule id="100130" level="10" frequency="5" timeframe="600">
  <if_matched_regex>^Failed password</if_matched_regex>
  <same_source_ip />
  <description>5 Failed passwords within 10 minutes</description>
</rule>
```

Real world examples

Deep Security includes many default log inspection rules for dozens of common and popular applications. Through Security Updates, new rules are added regularly. In spite of the growing list of applications supported by log inspection rules, you may find the need to create a custom rule for an unsupported or custom application.

Trend Micro Deep Security On-Premise 11.3

In this section we will walk through the creation of a custom CMS (content management system) hosted on Microsoft Windows Server with IIS and .Net platform, with a Microsoft SQL Server database as the data repository.

The first step is to identify the following application logging attributes:

1. Where does the application log to?
2. Which log inspection decoder can be used to decode the log file?
3. What is the general format of a log file message?

For our custom CMS example the answers are as follows:

1. Windows Event Viewer
2. Windows Event Log (eventlog)
3. Windows Event Log Format with the following core attributes:
 - Source: CMS
 - Category: None
 - Event: <Application Event ID>

The second step is to identify the categories of log events by application feature, and then organize the categories into a hierarchy of cascading groups for inspection. Not all inspected groups need to raise events; a match can be used as a conditional statement. For each group, identify the log format attributes which the rule can use as matching criteria. This can also be performed by inspecting all application logs for patterns and logical groupings of log events.

For example, the CMS application supports the following functional features which we will create log inspection rules for:

- CMS Application Log (Source: CMS)
 - Authentication (Event: 100 to 119)
 - User Login successful (Event: 100)
 - User Login unsuccessful (Event: 101)
 - Administrator Login successful (Event: 105)
 - Administrator Login unsuccessful (Event: 106)

- General Errors (Type: Error)
 - Database error (Event: 200 to 205)
 - Runtime error (Event: 206-249)
- Application Audit (Type: Information)
 - Content
 - New content added (Event: 450 to 459)
 - Existing content modified (Event: 460 to 469)
 - Existing content deleted (Event: 470 to 479)
 - Administration
 - User
 - New User created (Event: 445 to 446)
 - Existing User deleted (Event: 447 to 449)

This structure will provide you with a good basis for rule creation. Now to create a new log inspection rule in Deep Security Manager.

To create the new CMS Log Inspection Rule:

1. In the Deep Security Manager, go to **Policies > Common Objects > Rules > Log Inspection Rules** and click **New** to display the **New Log Inspection Rule Properties** window.
2. Give the new rule a name and a description, and then click the **Content** tab.
3. The quickest way to create a new custom rule is to start with a basic rule template. Select the **Basic Rule** radio button.
4. The **Rule ID** field will be automatically populated with an unused ID number of 100,000 or greater, the IDs reserved for custom rules.
5. Set the **Level** setting to **Low (0)**.
6. Give the rule an appropriate Group name. In this case, "cms".

7. Provide a short rule description.

General	Content	Files	Options	Assigned To
Template <input checked="" type="radio"/> Basic Rule <input type="radio"/> Custom (XML)				
General Information Rule ID: <input type="text" value="100000"/> Level: <input type="text" value="Low (0)"/> Groups (comma separated): <input type="text" value="cms"/> Rule Description: <input type="text" value="windows events for 'cms' group"/>				
Pattern Matching Pattern to Match: <input type="text"/> Pattern Type: <input type="text" value="String Pattern"/>				
Dependency <input checked="" type="radio"/> None <input type="radio"/> Trigger event on the triggering of another rule: <input type="radio"/> Trigger event on the triggering of any rule belonging to a specific group:				
Composite (optional) Only trigger if this rule matches its dependent rule the specified frequency of times in the specified time frame (in seconds). Frequency (1 to 128): <input type="text"/> Time Frame (1 to 86400): <input type="text"/>				
<div>OK</div> <div>Cancel</div>				

8. Now select the **Custom (XML)** option. The options you selected for your "Basic" rule will be converted to XML.

The screenshot shows the 'Content' tab of a configuration window. At the top, there are five tabs: 'General', 'Content' (selected), 'Files', 'Options', and 'Assigned To'. Below the tabs, the 'Template' section has two radio buttons: 'Basic Rule' and 'Custom (XML)', with 'Custom (XML)' selected. The 'Content:' section contains a text area with the following XML code:

```
<group name="cms">
  <rule id="100000" level="0">
    <description>windows events for 'cms' groups</description>
  </rule>
</group>
```

At the bottom right of the window are 'OK' and 'Cancel' buttons.

9. Click the **Files** tab and click the **Add File** button to add any application log files and log types which the rule will be applied to. In this case, "Application", and "eventlog" as the file type.

The screenshot shows the 'Files' tab of the same configuration window. The 'Files:' section contains a list of file types. The first entry is 'Application' in a text box, followed by 'eventlog' in a dropdown menu, and a 'Remove' button to its right. Below this list is an 'Add File' button. At the bottom right of the window are 'OK' and 'Cancel' buttons.

Note: Eventlog is a unique file type in Deep Security because the location and filename of the log files don't have to be specified. Instead, it is sufficient to type the log name as it

is displayed in the Windows Event Viewer. Other log names for the eventlog file type might be "Security", "System", "Internet Explorer", or any other section listed in the Windows Event Viewer. Other file types will require the log file's location and filename. (C/C++ *strftime()* conversion specifiers are available for matching on filenames. See the table below for a list of some of the more useful ones.)

10. Click **OK** to save the basic rule.
11. Working with the basic rule Custom (XML) created, we can begin adding new rules to the group based on the log groupings identified previously. We will set the base rule criteria to the initial rule. In the following example, the CMS base rule has identified Windows Event Logs with a Source attribute of "CMS":

```
<group name="cms">
  <rule id="100000" level="0">
    <category>windows</category>
    <extra_data>^CMS</extra_data>
    <description>Windows events from source 'CMS' group messages.</description>
  </rule>
```

12. Now we build up subsequent rules from the identified log groups. The following example identifies the authentication and login success and failure and logs by Event IDs.

```
<rule id="100001" level="0">
  <if_sid>100000</if_sid>
  <id>^100|^101|^102|^103|^104|^105|^106|^107|^108|^109|^110</id>
  <group>authentication</group>
  <description>CMS Authentication event.</description>
</rule>

<rule id="100002" level="0">
  <if_group>authentication</if_group>
  <id>100</id>
  <description>CMS User Login success event.</description>
</rule>

<rule id="100003" level="4">
  <if_group>authentication</if_group>
  <id>101</id>
  <group>authentication_failure</group>
  <description>CMS User Login failure event.</description>
```

```
</rule>
<rule id="100004" level="0">
  <if_group>authentication</if_group>
  <id>105</id>
  <description>CMS Administrator Login success event.</description>
</rule>
<rule id="100005" level="4">
  <if_group>authentication</if_group>
  <id>106</id>
  <group>authentication_failure</group>
  <description>CMS Administrator Login failure event.</description>
</rule>
```

13. Now we add any composite or correlation rules using the established rules. The following example shows a high severity composite rule that is applied to instances where the repeated login failures have occurred 5 times within a 10 second time period:

```
<rule id="100006" level="10" frequency="5" timeframe="10">
  <if_matched_group>authentication_failure</if_matched_group>
  <description>CMS Repeated Authentication Login failure event.</description>
</rule>
```

14. Review all rules for appropriate severity levels. For example, error logs should have a severity of level 5 or higher. Informational rules would have a lower severity.
15. Finally, open the newly created rule, click the **Configuration** tab and copy your custom rule XML into the rule field. Click **Apply** or **OK** to save the change.

Once the rule is assigned to a policy or computer, the log inspection engine should begin inspecting the designated log file immediately.

The complete Custom CMS Log Inspection Rule:

```
<group name="cms">
  <rule id="100000" level="0">
    <category>windows</category>
    <extra_data>^CMS</extra_data>
    <description>Windows events from source 'CMS' group messages.</description>
  </rule>
  <rule id="100001" level="0">
    <if_sid>100000</if_sid>
    <id>^100|^101|^102|^103|^104|^105|^106|^107|^108|^109|^110</id>
```

```
<group>authentication</group>
<description>CMS Authentication event.</description>
</rule>

<rule id="100002" level="0">
  <if_group>authentication</if_group>
  <id>100</id>
  <description>CMS User Login success event.</description>
</rule>

<rule id="100003" level="4">
  <if_group>authentication</if_group>
  <id>101</id>
  <group>authentication_failure</group>
  <description>CMS User Login failure event.</description>
</rule>

<rule id="100004" level="0">
  <if_group>authentication</if_group>
  <id>105</id>
  <description>CMS Administrator Login success event.</description>
</rule>

<rule id="100005" level="4">
  <if_group>authentication</if_group>
  <id>106</id>
  <group>authentication_failure</group>
  <description>CMS Administrator Login failure event.</description>
</rule>

<rule id="100006" level="10" frequency="5" timeframe="10">
  <if_matched_group>authentication_failure</if_matched_group>
  <description>CMS Repeated Authentication Login failure event.</description>
</rule>

<rule id="100007" level="5">
  <if_sid>100000</if_sid>
  <status>^ERROR</status>
  <description>CMS General error event.</description>
  <group>cms_error</group>
```

```
</rule>

<rule id="100008" level="10">
  <if_group>cms_error</if_group>
  <id>^200|^201|^202|^203|^204|^205</id>
  <description>CMS Database error event.</description>
</rule>

<rule id="100009" level="10">
  <if_group>cms_error</if_group>
  <id>^206|^207|^208|^209|^230|^231|^232|^233|^234|^235|^236|^237|^238|^239|^240|^241|^242|^243|^244|^245|^246|^247|^248|^249</id>
  <description>CMS Runtime error event.</description>
</rule>

<rule id="100010" level="0">
  <if_sid>100000</if_sid>
  <status>^INFORMATION</status>
  <description>CMS General informational event.</description>
  <group>cms_information</group>
</rule>

<rule id="100011" level="5">
  <if_group>cms_information</if_group>
  <id>^450|^451|^452|^453|^454|^455|^456|^457|^458|^459</id>
  <description>CMS New Content added event.</description>
</rule>

<rule id="100012" level="5">
  <if_group>cms_information</if_group>
  <id>^460|^461|^462|^463|^464|^465|^466|^467|^468|^469</id>
  <description>CMS Existing Content modified event.</description>
</rule>

<rule id="100013" level="5">
  <if_group>cms_information</if_group>
  <id>^470|^471|^472|^473|^474|^475|^476|^477|^478|^479</id>
  <description>CMS Existing Content deleted event.</description>
</rule>
```

Trend Micro Deep Security On-Premise 11.3

```
<rule id="100014" level="5">
  <if_group>cms_information</if_group>
  <id>^445|^446</id>
  <description>CMS User created event.</description>
</rule>

<rule id="100015" level="5">
  <if_group>cms_information</if_group>
  <id>^447|^449</id>
  <description>CMS User deleted event.</description>
</rule>

</group>
```

Log inspection rule severity levels and their recommended use

Level	Description	Notes
Level 0	Ignored, no action taken	Primarily used to avoid false positives. These rules are scanned before all the others and include events with no security relevance.
Level 1	no predefined use	
Level 2	System low priority notification	System notification or status messages that have no security relevance.
Level 3	Successful or authorized events	Successful login attempts, firewall allow events, etc.
Level 4	System low priority errors	Errors related to bad configurations or unused devices or applications. They have no security relevance and are usually caused by default installations or software testing.
Level 5	User-generated errors	Missed passwords, denied actions, etc. These messages typically have no security relevance.
Level 6	Low relevance attacks	Indicate a worm or a virus that provide no threat to the system such as a Windows worm attacking a Linux server. They also include frequently triggered IDS events and common error events.
Level 7	no predefined use	
Level 8	no predefined use	
Level 9	Error from invalid source	Include attempts to login as an unknown user or from an invalid source. The message might have security relevance especially if repeated. They also include errors regarding the admin or root account.
Level 10	Multiple user generated	Include multiple bad passwords, multiple failed logins, etc. They might indicate an attack, or it might be just that a user forgot his or her credentials.

Trend Micro Deep Security On-Premise 11.3

Level	Description	Notes
	errors	
Level 11	no predefined use	
Level 12	High-importance event	Include error or warning messages from the system, kernel, etc. They might indicate an attack against a specific application.
Level 13	Unusual error (high importance)	Common attack patterns such as a buffer overflow attempt, a larger than normal syslog message, or a larger than normal URL string.
Level 14	High importance security event	Typically the result of the correlation of multiple attack rules and indicative of an attack.
Level 15	Attack Successful	Very small chance of false positive. Immediate attention is necessary.

strftime() conversion specifiers

Specifier	Description
%a	Abbreviated weekday name (e.g., Thu)
%A	Full weekday name (e.g., Thursday)
%b	Abbreviated month name (e.g., Aug)
%B	Full month name (e.g., August)
%c	Date and time representation (e.g., Thu Sep 22 12:23:45 2007)
%d	Day of the month (01 - 31) (e.g., 20)
%H	Hour in 24 h format (00 - 23) (e.g., 13)
%I	Hour in 12 h format (01 - 12) (e.g., 02)
%j	Day of the year (001 - 366) (e.g., 235)
%m	Month as a decimal number (01 - 12) (e.g., 02)
%M	Minute (00 - 59) (e.g., 12)
%p	AM or PM designation (e.g., AM)
%S	Second (00 - 61) (e.g., 55)
%U	Week number with the first Sunday as the first day of week one (00 - 53) (e.g., 52)
%w	Weekday as a decimal number with Sunday as 0 (0 - 6) (e.g., 2)
%W	Week number with the first Monday as the first day of week one (00 - 53) (e.g., 21)
%x	Date representation (e.g., 02/24/79)
%X	Time representation (e.g., 04:12:51)
%y	Year, last two digits (00 - 99) (e.g., 76)
%Y	Year (e.g., 2008)
%Z	Time zone name or abbreviation (e.g., EST)
%%	A % sign (e.g., %)

More information can be found at the following websites:

<https://secure.php.net/manual/en/function.strftime.php>
www.cplusplus.com/reference/clibrary/ctime/strftime.html

Examine a log inspection rule

Log inspection rules are found in the Deep Security Manager at **Policies > Common Objects > Rules > Log Inspection Rules**.

Log inspection rule structure and the event matching process

This screen shot displays the contents of the **Configuration** tab of the Properties window of the "Microsoft Exchange" log inspection rule:

General Configuration Options Assigned To

Configuration Options

Log Files to monitor:

Add

Remove

C:\Windows\system32\LogFiles\SMTPSVC1\ex%y%m%d.l

Type of Log File(s): syslog

This rule matches events decoded as: msexchange

3800 - Grouping of Exchange rules

Default - Ignore

3801 - E-mail RCPT is not valid (invalid account)

Default - Medium (5)

3851 - Multiple e-mail attempts to an invalid account

Default - High (10)

Frequency (1 to 128): 10

Time Frame (1 to 86400): 120 secs

Time to ignore this rule after triggering it once - to avoid excessive logs (1 to 86400): 120 secs

3802 - E-mail 500 error code

Default - Medium (4)

3852 - Multiple e-mail 500 error code (spam)

Default - High (9)

Frequency (1 to 128): 12

Time Frame (1 to 86400): 120 secs

Time to ignore this rule after triggering it once - to avoid excessive logs (1 to 86400): 240 secs

View Rules...

OK Cancel Apply

Here is the structure of the rule:

- 3800 - Grouping of Exchange Rules - Ignore
 - 3801 - Email rcpt is not valid (invalid account) - Medium (4)
 - 3851 - Multiple email attempts to an invalid account - High (9)
 - Frequency - 10
 - Time Frame - 120
 - Ignore - 120
 - 3802 - Email 500 error code - Medium (4)
 - 3852 - Email 500 error code (spam) - High (9)
 - Frequency - 12
 - Time Frame - 120
 - Ignore - 240

The log inspection engine will apply log events to this structure and see if a match occurs. For example, if an Exchange event occurs, and this event is an email receipt to an invalid account, the event will match line 3800 (because it is an Exchange event). The event will then be applied to line 3800's sub-rules: 3801 and 3802.

If there is no further match, this "cascade" of matches will stop at 3800. Because 3800 has a severity level of "Ignore", no log inspection event would be recorded.

However, an email receipt to an invalid account does match one of 3800's sub-rules: sub-rule 3801. Sub-rule 3801 has a severity level of "Medium(4)". If the matching stopped here, a log inspection event with a severity level of "Medium(4)" would be recorded.

But there is still another sub-rule to be applied to the event: sub-rule 3851. Sub-rule 3851 with its three attributes will match if the same event has occurred 10 times within the last 120 seconds. If so, a log inspection event with a severity "High(9)" is recorded. (The "Ignore" attribute tells sub-rule 3851 to ignore individual events that match sub-rule 3801 for the next 120 seconds. This is useful for reducing "noise".)


Assuming the parameters of sub-rule 3851 have been matched, a log inspection event with Severity "High(9)" is now recorded.

Looking at the Options tab of the Microsoft Exchange Rule, we see that Deep Security Manager will raise an alert if any sub-rules with a severity level of "Medium(4)" have been matched. Since this is the case in our example, the alert will be raised (if "Alert when this rule logs an event" is selected).

Duplicate Sub-rules

Some log inspection rules have duplicate sub-rules. To see an example, open the "Microsoft Windows Events" rule and click on the **Configuration** tab. Note that sub-rule 18125 (Remote access login failure) appears under sub-rules 18102 and 18103. Also note that in both cases sub-rule 18125 does not have a severity value, it only says "See Below".

Instead of being listed twice, Rule 18125 is listed once at the bottom of the **Configuration** page:



Block access to malicious URLs with web reputation

Note: For a list of operating systems where web reputation is supported, see ["Supported features by platform"](#) on page 85.

The web reputation module protects against web threats by blocking access to malicious URLs. Deep Security uses Trend Micro's Web security databases from [Smart Protection Network](#) sources to check the reputation of websites that users are attempting to access. The website's reputation is correlated with the specific web reputation policy enforced on the computer.

Depending on the [security level](#) being enforced, Deep Security will either block or allow access to the URL.

Note: The web reputation module does not block HTTPS traffic.

To enable and configure web reputation, perform the basic steps below:

1. ["Turn on the web reputation module" below](#)
2. ["Switch between inline and tap mode" below](#)
3. ["Enforce the security level" on the next page](#)
4. ["Create exceptions" on page 923](#)
5. ["Configure the Smart Protection Server" on page 924](#)
6. ["Edit advanced settings" on page 925](#)
7. ["Test Web Reputation" on page 926](#)

To suppress messages that appear to users of agent computers, see ["Configure notifications on the computer" on page 683](#)

Turn on the web reputation module

1. Go to **Policies**.
2. Double-click the policy for which you want to enable web reputation.
3. Click **Web Reputation > General**.
4. For **Web Reputation State**, select **On**.
5. Click **Save**.

Switch between inline and tap mode

Web reputation uses the Deep Security Network Engine which can operate in one of two modes:

- **Inline:** Packet streams pass directly through the Deep Security network engine. All rules, therefore are applied to the network traffic before they proceed up the protocol stack
- **Tap mode:** Packet streams are replicated and diverted from the main stream.

In tap mode, the live stream is not modified. All operations are performed on the replicated stream. When in tap mode, Deep Security offers no protection beyond providing a record of events.

To switch between inline and tap mode, open the **Computer or Policy editor**¹ and go to **Settings > Advanced > Network Engine Mode**.

For more on the network engine, see ["Test Firewall rules before deploying them" on page 772](#).

Enforce the security level

Web addresses that are known to be or are suspected of being malicious are assigned a **risk level** of:

- **Dangerous:** Verified to be fraudulent or known sources of threats
- **Highly suspicious:** Suspected to be fraudulent or possible sources of threats
- **Suspicious:** Associated with spam or possibly compromised

Security levels determine whether Deep Security will allow or block access to a URL, based on the associated risk level. For example, if you set the security level to low, Deep Security will only block URLs that are known to be web threats. As you set the security level higher, the web threat detection rate improves but the possibility of false positives also increases.

To configure the security level:

1. Go to **Policies**.
2. Double-click the policy that you want to edit.
3. Click **Web Reputation > General**.
4. Select one of the following security levels:
 - **High:** Blocks pages that are:
 - Dangerous
 - Highly suspicious
 - Suspicious

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

- **Medium:** Blocks pages that are:
 - Dangerous
 - Highly Suspicious
- **Low:** Blocks pages that are:
 - Dangerous

5. Click **Save**.

Create exceptions

You can override the block and allow behavior dictated by the Smart Protection Network's assessments with your lists of URLs that you want to block or allow.

Note: The **Allowed** list takes precedence over the **Blocked** list. URLs that match entries in the **Allowed** list are not checked against the **Blocked** list.

To create URL exceptions:

1. Go to **Policies**.
2. Double-click the policy that you want to edit.
3. Click **Web Reputation > Exceptions**.
4. To allow URLs:
 - a. Go to the **Allowed** section.
 - b. In the blank under **URLs to be added to the Allowed list (one per line)**, enter your desired URL. Multiple URLs can be added at once but they must be separated by a line break.
 - c. Select either:
 - **Allow URLs from the domain:** Allow all pages from the domain. Sub-domains are supported. Only include the domain (and optionally sub-domain) in the entry. For example, "example.com" and "another.example.com" are valid entries.
 - **Allow the URL::** The URL as entered will be allowed. Wildcards are supported. For example, "example.com/shopping/coats.html", and "example.com/shopping/*" are valid entries.
 - d. Click **Add**.

To block URLs:

- a. Go to the **Blocked** section
 - b. In the blank under **URLs to be added to the Blocked list (one per line)**, enter your desired URL. Multiple URLs or keywords can be added at once but they must be separated by a line break.
 - c. Select either:
 - **Block URLs from the domain:** Block all pages from the domain. Sub-domains are supported. Only include the domain (and optionally sub-domain) in the entry. For example, "example.com" and "another.example.com" are valid entries.
 - **Block the URL:** The URL as entered will be blocked. Wildcards are supported. For example, "example.com/shopping/coats.html", and "example.com/shopping/*" are valid entries.
 - **Block URLs containing this keyword:** Any URL containing the keyword will be blocked.
 - d. Click **Add**.
5. Click **Save**.

Configure the Smart Protection Server

Smart Protection Service for web reputation supplies web information required by the web reputation module. For more information, see [Smart Protection Network - Global Threat Intelligence](#).

To configure Smart Protection Server:

1. Go to **Policies**.
2. Double-click the policy you'd like to edit.
3. Click **Web Reputation > Smart Protection**.
4. Select whether to connect directly to Trend Micro's Smart Protection service:
 - a. Select **Connect directly to Global Smart Protection Service**.
 - b. Optionally select **When accessing Global Smart Protection Service, use proxy**. Select **New** from the drop down menu and enter your desired proxy.

Or to connect to one or more locally installed Smart Protection Servers:

- a. Select **Use locally installed Smart Protection Server (ex: "http://[server]:5274")**.
- b. Enter the Smart Protection Server URL into the field and click **Add**. To find the Smart Protection Server URL, do one of the following:
 - Log in to the Smart Protection Server, and in the main pane, look under **Real Time Status**. The Smart Protection Server's HTTP and HTTPS URLs are listed in the **Web Reputation** row. The HTTPS URL is only supported with 11.0 Deep Security Agents and up. If you have 10.3 or earlier agents, use the HTTP URL.

Or

- If you [deployed the Smart Protection Server in AWS](#), go to the AWS **CloudFormation** service, select the check box next to the Smart Protection Server stack, and in the bottom pane, click the **Outputs** tab. The Smart Protection Server's HTTP and HTTPS URLs appear in the **WRSurl** and **WRSHTTPSurl** fields. The WRSHTTPSurl is only supported with 11.0 Deep Security Agents and up. If you have 10.3 or earlier agents, use the WRSurl URL.
- c. Optionally select **When off domain, connect to global Smart Protection Service. (Windows only)**.
5. Click **Save**.

Smart Protection Server Connection Warning

This option determines whether error events are generated and alerts are raised if a computer loses its connection to the Smart Protection Server. Select either **Yes** or **No** and click **Save**.

Note: If you have a locally installed Smart Protection Server, this option should be set to **Yes** on at least one computer so that you are notified if there is a problem with the Smart Protection Server itself.

Edit advanced settings

Blocking Page

When users attempt to access a blocked URL, they will be redirected to a blocking page. In the blank for **Link**, provide a link that users can use to request access to the blocked URL.

Alert

Decide to raise an alert when a web reputation event is logged by selecting either **Yes** or **No**.

Ports

Select specific ports to monitor for potentially harmful web pages from the drop down list next to **Ports to monitor for potentially harmful web pages**.

Test Web Reputation

Before continuing, test that the Web Reputation is working correctly:

1. Ensure Web Reputation is enabled.
2. Go to the **Computer or Policy editor > Web Reputation > Exceptions**.
3. Under **Blocked**, enter *http://www.speedtest.net* and click **Add**. Click **Save**.
4. Open a browser and attempt to access the website. A message denying the access should appear.
5. Go to **Events & Reports > Web Reputation** to verify the record of the denied web access. If the detection is recorded, the Web Reputation module is working correctly.

Deep Security Scanner

Deep Security Scanner provides integration with the SAP NetWeaver platform.

Note: Deep Security Scanner is not supported on computers where the Deep Security Agent is enabled as a Relay.

Note: Deep Security Scanner is not supported when FIPS mode is enabled. See ["FIPS 140-2 support" on page 1381](#).

Activate the Deep Security Scanner feature

1. In the Deep Security Manager, go to **Administration > Licenses**.
2. Click **Enter New Activation Code**.
3. In the **Deep Security Scanner** area (under **Additional Features**), enter your Deep Security Scanner activation code, then click **Next** and follow the prompts.

The Settings > Scanner tab will now be available in the **Computer or Policy editor**¹, where you can enable the SAP feature for individual computers or policies.

Note: In order to use the Deep Security Scanner feature, the Anti-Malware module must also be activated and only available with the Deep Security Agent.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Add the SAP Server

In Deep Security Manager, open the **Computers** page and click **New**. There are several ways to add the SAP server to the Computers list. For details, see ["Add computers and other resources to Deep Security Manager" on page 446](#).

Enable the SAP integration feature in a computer or policy

The **Settings > Scanner** page in the **Computer or Policy editor**¹ allows you to enable the SAP integration module for individual computers or policies. To enable these features, set the **Configuration** to **On** or **Inherited (On)**.

Set up SAP integration

The Trend Micro Deep Security Agent can be called by a library that is automatically deployed on Windows Server 2008 R2 64-bit, Windows Server 2012 R2 64-bit, SUSE Linux Enterprise Server 11 or 12 (SLES) 64-bit, or Red Hat Enterprise Linux 6 or 7 (RHEL) 64-bit operating systems.

This is an overview of the integration steps:

1. Install the Deep Security Agent on a Windows Server 2008 R2 64-bit, Windows Server 2012 R2 64-bit, SLES 11 or 12, or RHEL 6 or 7-based SAP application server. See ["Install the agent" on page 931](#).
2. Add the SAP server to Deep Security Manager and activate the agent on the SAP server. See ["Add the SAP server to the manager" on page 932](#).


¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

3. Apply a security profile that has anti-malware active to provide the agent with the latest pattern and scan engine. See ["Assign a security profile" on page 936](#).
4. Configure the SAP Virus Scan Interface (VSI) by calling the following transactions. See ["Configure SAP to use the agent" on page 942](#):
 - VSCANGROUP
 - VSCAN
 - VSCANPROFILE
 - VSCANTEST

Note: Depending on your operating system and environment, the output that you see may differ slightly from what is shown in this article.

Deep Security and SAP components



Deep Security Manager connects with the Deep Security Agent located on the SAP NetWeaver server. The agent connects with libsapvsa or dsvsa.dll, which are the virus adapters provided by Trend Micro for scanning purposes.

The components involved in this solution are:

- **Deep Security Manager:** The centralized web-based management console that administrators use to configure security policy and deploy protection to the Deep Security Agent.

Trend Micro Deep Security On-Premise 11.3

- **Deep Security Agent:** A security agent deployed directly on a computer. The nature of that protection depends on the rules and security settings that each Deep Security Agent receives from the Deep Security Manager.
- **SAP NetWeaver:** SAP integrated technology computing platform. The SAP NetWeaver Virus Scan Interface (NW-VSI) provides virus scanning capabilities for third-party products that perform the actual scan. The NW-VSI interface must be activated.
- **SAP NetWeaver ABAP WinGUI:** A Windows management console used for SAP NetWeaver. In this document, it is used for the configuration of the Deep Security Agent and the SAP NetWeaver Virus Scan Interface.

Install the agent


The Deep Security Agent is installed with core agent functionality only. After the agent is installed on SUSE Linux Enterprise Server or Red Hat Enterprise Linux, you can enable protection modules on the agent. At that point, the plug-ins required for the protection modules will be downloaded and installed.

1. Go to the Trend Micro Download Center (<http://downloadcenter.trendmicro.com>) and download the Deep Security Agent package for your OS.
2. Install the agent on the target system. You can use rpm or zypper, depending on the OS. In this example, rpm is used by typing:

```
rpm -ihv Agent-Core-SuSE_<version>.x86_64.rpm
```

Trend Micro Deep Security On-Premise 11.3

3. You should see output similar to what's shown in this example, which indicates that the agent installation is complete:



```
ec2-52-28-57-164.eu-central-1.compute.amazonaws.com - PuTTY
ip-172-21-0-50:/home/ec2-user # rpm -ihv Agent-Core-SuSE_11-9.5.3-2774.x86_64.rpm
Preparing...                               ##### [100%]
 1:ds_agent                               ##### [100%]
Starting ds_agent:                          done
ip-172-21-0-50:/home/ec2-user #
```

Note: You can also deploy the agent using a deployment script generated from the Deep Security Manager.

Add the SAP server to the manager

The agent is now installed on the SAP server but no protection modules are active. To enable protection, you need to add the SAP server to the Deep Security Manager console.

Activate SAP in the manager

1. In the Deep Security Manager, go to **Administration > Licenses**.
2. Click **Enter New Activation Code**.
3. In the **Deep Security Scanner** area (under **Additional Features**), enter your SAP activation code, then click **Next** and follow the prompts.

Note: In order to use the SAP integration feature, the anti-malware and web reputation modules must also be activated.

Add the SAP server

To add the SAP server, open the Deep Security Manager console and on the **Computers** tab, click **New**. There are several ways to add the server, including synchronization with Microsoft Active Directory, VMware vCenter, Amazon Web Services, or Microsoft Azure. You can also add the computer using an FQDN or IP address. For detailed instructions, see ["Add computers and other resources to Deep Security Manager" on page 446](#).

Activate the agent

The status of your instance will be either **Unmanaged (Activation Required)** or **Unmanged (Unknown)**. Next, you will need to activate the agent before the manager can assign rules and policies to protect the computer. The activation process includes the exchange of unique fingerprints between the agent and the manager. This ensure that only one Deep Security Manager can communicate with the agent. There are two ways to activate the agent: agent-initiated or manager-initiated.

Manager-initiated activation: The manager-initiated method requires that the Deep Security Manager can connect to the FQDN or the IP of the agent via the [agent's listening port number for heartbeats](#). This can sometimes be difficult due to NAT port forwarding, firewall, or AWS security groups. To perform manager-initiated activation, go to the **Computers** tab in the Deep Security Manager console, right-click the instance where the agent is installed and click **Actions > Activate**. If you use manager-initiated activation, we strongly recommend you also ["Protect Deep Security Agent" on page 1033](#) from unauthorized Deep Security Managers.

Agent-initiated activation: The agent-initiated method requires that the Deep Security Agent can connect to the configured Deep Security Manager address via the manager's listening port number for heartbeats.

You can find the Deep Security Manager address (FQDN or IP) in the Deep Security Manager console, under **Administration > Manager Nodes**.

You will also need to enable agent-initiated activation from the Deep Security Manager console, by clicking **Administration > System Settings > Agents** and selecting **Allow Agent-Initiated Activation**.

Trend Micro Deep Security On-Premise 11.3

Next, use a locally-run command-line tool on the Deep Security Agent to initiate the activation process. The minimum activation instruction contains the activation command and the manager's URL (including the port number):

```
dsa_control -a dsm://[managerurl]:[port]/
```


where:

- `-a` is the command to activate the agent , and
- `dsm://managerurl:4120/` is the parameter that points the agent to the Deep Security Manager. ("managerurl" is the URL of the Deep Security Manager, and "4120" is the default agent-to-manager communication port.)

The manager URL is the only required parameter for the activation command. Additional parameters are also available. (For a list of available parameters, see ["Command-line basics" on page 390.](#))

In the following example, we use the agent-initiated activation by typing:

```
/opt/ds_agent/dsa_control -a dsm://cetl-dsm.ceur-testlab.trendmicro.de:4120/
```



```

ec2-52-28-57-164.eu-central-1.compute.amazonaws.com - PuTTY
ip-172-21-0-50:/home/ec2-user # rpm -ihv Agent-Core-SuSE_11-9.5.3-2774.x86_64.rpm
Preparing... ##### [100%]
 1:ds_agent ##### [100%]
Starting ds_agent: done
ip-172-21-0-50:/home/ec2-user # /opt/ds_agent/dsa_control -a dsm://cetl-dsm.ceur-testlab.trendmicro.de:4120/
Starting thread 'CScriptThread' with stack size of 1048576
HTTP Status: 200 - OK
Response:
Attempting to connect to https://cetl-dsm.ceur-testlab.trendmicro.de:4120/
SSL handshake completed successfully - initiating command session.
Connected with AES256-SHA to peer at cetl-dsm.ceur-testlab.trendmicro.de
Received a 'GetHostInfo' command from the manager.
Received a 'GetHostInfo' command from the manager.
Received a 'SetDSMCert' command from the manager.
Received a 'SetAgentCredentials' command from the manager.
Received a 'GetAgentEvents' command from the manager.
Received a 'GetInterfaces' command from the manager.
Received a 'GetAgentEvents' command from the manager.
Received a 'GetAgentStatus' command from the manager.
Received a 'GetAgentEvents' command from the manager.
Received a 'SetSecurityConfiguration' command from the manager.
Received a 'GetAgentEvents' command from the manager.
Received a 'GetAgentStatus' command from the manager.
Command session completed.
ip-172-21-0-50:/home/ec2-user #

```

This output indicates that the agent activation is complete.

To confirm the activation:

Trend Micro Deep Security On-Premise 11.3

1. In the Deep Security Manager console, go to the **Computers** tab.
2. Click the computer name and then click **Details** and check that the computer's status is "Managed".

Assign a security profile

At this point, the status of the agent is **Managed (Online)** but there is no protection module installed. This means that the agent and the manager are communicating but the agent is not using any configuration.

There are several ways to apply protection. In this example, the configuration is done directly on the SAP instance by activating anti-malware and SAP and assigning the default **Scan Configurations**.

Trend Micro Deep Security On-Premise 11.3

1. In the **Computer editor**¹, go to **Anti-Malware > General**.

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

2. In the **Anti-Malware** section, set **Configuration** to **On** (or **Inherited On**) and then click **Save**.

Computer:

Help

Overview

Anti-Malware

Web Reputation

Firewall

Intrusion Prevention

Integrity Monitoring

Log Inspection

Application Control

Interfaces

Settings

Updates

Overrides

General

Smart Protection

Advanced

Quarantined Files

Events

Anti-Malware

Configuration:

Inherited (Off)
Inherited (Off)
On
Off

State:

not found, no configuration

Real-Time Scan

☒ Inherited

Malware Scan Configuration:

No Configuration

Edit

Schedule:

Select Schedule

Edit

Manual Scan

☒ Inherited

Malware Scan Configuration:

No Configuration

Edit

Scheduled Scan

☒ Inherited

Save

Close

938

Trend Micro Deep Security On-Premise 11.3

3. In the **Real-Time Scan**, **Manual Scan**, or **Scheduled Scan** sections, set the **Malware Scan Configuration** and **Schedule**, or allow those settings to be inherited from the parent policy.
4. Click **Save**. The status of the anti-malware module changes to **Off, installation pending**. This means that the agent is retrieving the required module from the Deep Security Manager. For this to work, the client needs to access the Deep Security Relay on the [relay's listening port number](#). A few moments later, the agent should start downloading security updates such as anti-malware patterns and scan engines.
5. In the Computer editor, go to **Settings > Scanner**.
6. In the **SAP** section, set **Configuration** to **On** (or **Inherited On**) and then click **Save**.

After status of the agent changes to **Managed (Online)** again and the anti-malware and Scanner (SAP) modules are **On**, you can proceed with the SAP configuration.

Computer: [REDACTED]

Overview

- Anti-Malware
- Web Reputation
- Firewall
- Intrusion Prevention
- Integrity Monitoring
- Log Inspection
- Application Control

Interfaces

- Settings
- Updates
- Overrides

General | **Actions** | **System Events**

Hostname: [REDACTED] (Last IP Used: [REDACTED])

Display Name: [REDACTED]

Description: [REDACTED]

Platform: Microsoft Windows Server 2012 (64 bit) Build 9200

Group: Computers

Policy: None [Edit](#)

Asset Importance: None [Edit](#)

Download Security Updates From: Default Relay Group [Edit](#)

Agent

	Agent
Anti-Malware	Managed (Online)
Web Reputation	On, no configuration
Firewall	Off, not installed
Intrusion Prevention	Not Licensed
Integrity Monitoring	Not Licensed
Log Inspection	Not Licensed
Application Control	Not Licensed
Online	Yes
Last Communication	February 10, 2017 14:26

Scanner(SAP): On

Configure SAP to use the agent

The Deep Security Agent is now up and running and is able to scan the file system of its operating system. Next, we need to make the agent aware of the SAP application server. To use this, we must create a virus scan adapter inside the application server. The virus scan adapter must be part of a group. After the virus scan adapter and virus scan group are created, we can use virus scan profiles to configure what to scan and how to behave.

These are the required steps:

1. ["Configure the Trend Micro scanner group" on the next page](#)
2. ["Configure the Trend Micro virus scan provider" on page 949](#)
3. ["Configure the Trend Micro virus scan profile" on page 955](#)
4. ["Test the virus scan interface" on page 964](#)

Note: The virus scan group and the virus scan adapter are both global configurations (client 00). The virus scan profile must be configured in each tenant (client 01, 02, etc.).

Trend Micro Deep Security On-Premise 11.3

Configure the Trend Micro scanner group

Trend Micro Deep Security On-Premise 11.3


1. In the SAP WinGUI, run the **VSCANGROUP** transaction.

Trend Micro Deep Security On-Premise 11.3

2. In Edit mode, click **New Entries**. Create a new scanner group, specifying a group name in the **Scanner Group** area and a description of the scanner group in the **Group Text** area.

Trend Micro Deep Security On-Premise 11.3

3. Clicking **Save** or leaving the edit mode will prompt you to commit a "workbench request". In this example, a new workbench request is created to keep track of all the VSI-related changes:



The next step is the actual configuration of the VSI integration. It is called a **Virus Scan Adapter**.

Trend Micro Deep Security On-Premise 11.3

Configure the Trend Micro virus scan provider

Trend Micro Deep Security On-Premise 11.3

1. In the SAP WinGUI, run the **VSCAN** transaction.

Trend Micro Deep Security On-Premise 11.3

2. In Edit mode, click **New Entries**. Creating a new entry displays a prompt in which the configuration of the VSI- certified solution takes place. In this example, the following configuration parameters are set:

New Entries: Details of Added Entries

Provider Type: ADAPTER (Virus Scan Adapter)

Provider Name: VSA_NPLHOST

Status: Start Stop

Virus Scan Provider Definition

Scanner Group: Z_TMGROUP

Status: Active (Application Server)

Server: nplhost_NPL_42

Reinit. Interv.: 8 Hours

Adapter Path: /opt/ds_agent/lib/libds_sap_vsa.so

Setting	Value	Description
Provider Type	ADAPTER (Virus Scan Adapter)	Automatically set (default)

Trend Micro Deep Security On-Premise 11.3

Setting	Value	Description
Provider Name	VSA_<host name>	Automatically set, serves as alias
Scanner Group	Select the group that you configured earlier	All previously created scanner groups, which you can display using the input help
Status	Active (Application Server)	Automatically set (default)
Server	nplhost_NPL_42	Automatically set, hostname
Reinit. Interv.	8 Hours	Specifies the number of hours after which the Virus Scan Adapter will be reinitialized and load new virus definitions.
Adapter Path (Linux)	/lib64/libsapvsa.so	Default path
Adapter Path (Windows)	C:\Program Files\Trend Micro\Deep Security Agent\lib\dsvsa.dll	Default path

- When you click **Save** or leave the edit mode, there is another prompt to pack this into a workbench request. After confirming, click the **Start** button. The Status light will turn green, which means the adapter is loaded and active:

Table View Edit Goto Selection Utilities(M) System Help

New Entries: Details of Added Entries

Provider Type: ADAPTER (Virus Scan Adapter)

Provider Name: VSA_NPLHOST

Status:

Start Stop

Virus Scan Provider Definition

Scanner Group: Z_IMGROUP

Status: Active (Application Server)

Server: nplhost_NPL_42

Trace Level: Errors Only

Reinit. Interv.: 8 Hours Last Initialization: 13.04.2015 17:09:48

Adapter Path: /lib64/libsapvsa.so

Configuration:

Engine Data

Version	9.8
Version Text	VSAPI-9.8.1009
Date	Mon Apr 13 15:09:47 2015
Known Viruses	

Loaded Drivers

Version	Driver Name	Date	Known Viruses
11.601	Smart Scan Agent Pattern	Mon Apr 13 14:23:22 2015	
1.175	IntelliTran Exception Pattern	Mon Apr 13 14:23:22 2015	

Data was saved


SAP

Trend Micro Deep Security On-Premise 11.3

At this point, the VSI configuration is nearly finished. The application server is now ready to process file transactions using a virus scan provided by Trend Micro Deep Security.

Configure the Trend Micro virus scan profile

1. In the SAP WinGUI, run the **VSCANPROFILE** transaction, then select the SAP operation that requires virus scan. For example, check the "Active" checkbox for **/SCET/GUI_UPLOAD** or **/SCET/GUI_DOWNLOAD** and then click **Save**.



Trend Micro Deep Security On-Premise 11.3

2. In Edit mode, click **New Entries**. The virus scan profiles will define how specific transactions (file uploads, file downloads, etc.) are handled corresponding to the virus scan interface. To have the previously configured virus scan adapter used in the application server, a new virus scan profile needs to be created:

Table View Edit Goto Selection Utilities(M) System Help

✓ [Dropdown]

New Entries: Details of Added Entries

[Icons]

Dialog Structure

- ▼ Virus Scan Profile
 - Steps
 - Step Configurati
 - Profile Configuration
 - MIME Types

Scan Profile: Z_TMProfile

Virus Scan Profile

Profile Text: VSCANPROFILE for Trend Micro Deep Security

☒ Active ☒ Evaluate Profile Configuration Param.

☒ Default Profile

☐ Use Reference

Link: All steps successful

Trend Micro Deep Security On-Premise 11.3


3. In the **Scan Profile** box, enter "Z_TMProfile" and select the **Active**, **Default Profile**, and **Evaluate Profile Configuration Param** check boxes.

Trend Micro Deep Security On-Premise 11.3

4. While still in edit mode, double-click **Steps** to configure the steps:



5. Click **New Entries**.
6. The steps define what to do when the profile is called by a transaction. Set the **Position** to "0", **Type** to "Group" and the **Scanner Group** to the name of the group that you configured earlier.
7. After clicking **Save** or leaving the edit mode, you will eventually receive a notification about an existing virus scan profile, **/SCET/DP_VS_ENABLED**. you can ignore this notification because the profile is not active and is not used. After confirming this notification, you will be asked to pack this configuration in a "customization request". Creating a new request will help keep track of the changes that have been made:



8. To create configuration parameters for a step, double-click the **Profile Configuration Parameters** node. Click **New Entries** and set the parameters:

Parameter	Type	Description
CUST_ACTIVE_CONTENT	BOOL	Check whether a file contains script (JavaScript, PHP, or ASP script) and block
CUST_CHECK_MIME_TYPE	BOOL	Check whether the file extension name matches its MIME type. If they do not match, the file will be blocked. All MIME types and extension names can be exactly matched. For example: <ul style="list-style-type: none"> • Word files must to be .doc or .dot • JPEG files must to be .jpg • Text and binary files could be any extension (won't block)

Parameter	Type	Description
		See "Supported MIME types" on page 970 .

9. Double-click the **Step Configuration Parameters** node. Click **New Entries** and set the parameters:

Parameter	Type	Description
SCANBESTEFFORT	BOOL	The scan should be performed on the "best effort" basis; that is, all (security critical) flags that allow a VSA to scan an object should be activated, such as SCANALLFILES and SCANEXTRACT, but also internal flags. Details about exactly which flags these are can be stored in the certification.
SCANALLFILES	BOOL	Scans for all files regardless of their file extension.
SCANEXTENSIONS	CHAR	List of the file extensions for which the VSA should scan. Only files with the configured extensions will be checked. Other extensions are blocked. Wildcards can also be used here in order to search for patterns. * stands for this location and following and ? stands for for only this character. The syntax is: exe;com;do?;ht* => `**` therefore means to scan all files.
SCANLIMIT	INT	This settings applies to compressed files. It specifies the maximum number of files that will be unpacked and scanned.
SCANEXTRACT	BOOL	Archives or compressed objects are to be unpacked
SCANEXTRACT_SIZE	SIZE_T	Maximum unpack size
SCANEXTRACT_DEPTH	INT	Maximum depth to which an object is to be unpacked.
SCANMIMETYPES	CHAR	List of the MIME types to be scanned for. Only files with configured MIME types will be checked. Other MIME types are blocked. This parameter works only if CUST_CHECK_MIME_TYPE is enabled.
BLOCKMIMETYPES	CHAR	List of MIME types to be blocked. This parameter works only if CUST_CHECK_MIME_TYPE is enabled.
BLOCKEXTENSIONS	CHAR	List of file extensions to be blocked

This configuration is per-client, so it must be done in each tenant of the SAP application server.

Trend Micro Deep Security On-Premise 11.3


Test the virus scan interface

Trend Micro Deep Security On-Premise 11.3


1. In the SAP WinGUI, run the **VSCANTEST** transaction.

ProgramEditGotoSystemHelp

vsctest



Test for Virus Scan Interface



Object to Be Checked

☒ Test Data

EICAR Anti-Virus Test File

☐ Local File

☐ File on the Application Server

Scanner Selection

☒ Virus Scan Profile

(Defaultprofil)

☐ Scanner Group

☐ Virus Scan Provider

General Settings

☒ Display Scan Details

Action

Check Only

Trend Micro Deep Security On-Premise 11.3

2. Every VSI-aware SAP application server also has a built-in test to check whether the configuration steps were done correctly. For this, an EICAR test virus (www.eicar.org) is packed in a transaction that can call a specific scanner. Not filling in anything will call the default profile, which was configured in the last step.

Trend Micro Deep Security On-Premise 11.3

3. Clicking **Execute** prompts a notification that explains what an EICAR test virus is. After confirming this, you will see how the transaction is intercepted:

The screenshot displays the SAP Trend Micro Deep Security On-Premise 11.3 interface. The top menu bar includes 'Goto', 'System', and 'Help'. Below the menu is a toolbar with various icons for navigation and actions. The main content area is titled 'SAP' and contains a 'Result' section. The 'Result' section shows a red 'X' icon and the text 'Return Value: 2- (At least one virus found)'. Below this is an 'Infections' section with a table listing the detected virus. The table has columns for 'ID', 'Virus Name', and 'Object'. The first row shows 'Eicar_test_1' as the virus name and '/tmp/zUeEbZZ_TMPPROFILE' as the object. Below the 'Infections' section is a 'Content Information' section with a table listing file details. The table has columns for 'File Name', 'Extension', 'MIME Type', and 'Object'. The first row shows 'text/plain' as the MIME type and '/tmp/zUeEbZZ_TMPPROFILE' as the object. At the bottom of the interface is a log window with a toolbar and a list of messages. The messages include: 'Start the processing of virus scan profile Z_TMPPROFILE', 'Virus scan profile Z_TMPPROFILE, step 00: scanner group Z_TMGROUP', 'Virus scan adapter VSA_NPLHOST was selected from scanner group Z_TMGROUP', 'Virus scan profile Z_TMPPROFILE, step 00: scan instance returns 2- (At least one virus fo...', 'Virus "Eicar_test_1" found in object "/tmp/zUeEbZZ_TMPPROFILE"', and 'Profile Z_TMPPROFILE failed, since step 00 failed (AND linkage)'. The log window also shows a status bar with icons for 'STOP', '1', '0', and '5'.

SAP

Result

✖ Return Value: 2- (At least one virus found)

Infections

ID	Virus Name	Object
	Eicar_test_1	/tmp/zUeEbZZ_TMPPROFILE

Content Information

File Name	Extension	MIME Type	Object
		text/plain	/tmp/zUeEbZZ_TMPPROFILE

Log messages:

- Start the processing of virus scan profile Z_TMPPROFILE
- Virus scan profile Z_TMPPROFILE, step 00: scanner group Z_TMGROUP
- Virus scan adapter VSA_NPLHOST was selected from scanner group Z_TMGROUP
- Virus scan profile Z_TMPPROFILE, step 00: scan instance returns 2- (At least one virus fo...
- Virus "Eicar_test_1" found in object "/tmp/zUeEbZZ_TMPPROFILE"
- Profile Z_TMPPROFILE failed, since step 00 failed (AND linkage)

Trend Micro Deep Security On-Premise 11.3

Infections shows information about the detected malware.

Content Information shows the correct MIME-type of the file.

The file name is always a randomly generated 7-letter alphabetic string followed by the virus scan profile name.

After this, there is an output about each step of the transaction:

1. The transaction called the default virus scan profile, which is the virus scan profile Z_TMPROFILE.
2. The virus scan profile Z_TMPROFILE is configured to call an adapter from the virus scan group Z_TMGROUP.
3. The virus scan group Z_TMGROUP has multiple adapters configured and calls one of them (in this case, VSA_NPLHOST).
4. The virus scan adapter returns value 2-, which means a virus was found.
5. Information about the detected malware is displayed by showing Eicar_test_1 and the file object /tmp/ zUeEbZZ_TMPROFILE.
6. The called default virus scan profile Z_TMPROFILE fails because step 00 (the virus scan group) was not successful and therefore the file transaction is stopped from further processing.

For a cross-check, there is also information about this "malware" event in the Deep Security Manager console. To see the event, open the **Computer editor**¹ and click **Anti-Malware > Events**.

Supported MIME types

The MIME types supported by Deep Security Scanner vary depending on which version of the Deep Security Agent you are using.

- Deep Security Agent 9.6 uses VSAPI 9.85
- Deep Security Agent 10.0 uses ATSE 9.861

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

- Deep Security Agent 10.1 uses ATSE 9.862
- Deep Security Agent 10.2, 10.3, 11.0, 11.1, and 11.2 uses ATSE 10.000
- Deep Security Agent 11.3 and higher uses ATSE 11.0.000

MIME Type	Description	Extension	Supported in 9.6 Agent	Supported in 10.0 Agent	Supported in 10.1 Agent or higher
application/octet-stream		*	Yes	Yes	Yes
application/com	COM File	com	Yes	Yes	Yes
application/ecmascript	EMCScript File	es	Yes	Yes	Yes
application/hta	HTA File	hta	Yes	Yes	Yes
application/java-archive	Java Archive (JAR) file	jar	Yes	Yes	Yes
application/javascript	Javascript File	js, jsxinc, jsx	Yes	Yes	Yes
application/msword	Word for Windows	doc, dot	Yes	Yes	Yes
application/vnd.ms-access	MS Access	mdb	No	No	No
application/vnd.ms-project	MS Project	mpp	No	No	No
application/msword	MS Word	doc, dot	Yes	Yes	Yes
application/octet-stream	COM File	com	Yes	Yes	Yes
application/octet-stream	EXE File	exe	Yes	Yes	Yes
application/pdf	Adobe Portable Document Format file	pdf	Yes	Yes	Yes
application/postscript	Postscript	ai	Yes	Yes	Yes
application/postscript	Postscript	ps	Yes	Yes	Yes
application/postscript	Postscript	ps	Yes	Yes	Yes
application/rar	RAR File	rar	Yes	Yes	Yes
application/rtf	Microsoft RTF	rtf	Yes	Yes	Yes
application/sar	Sar File	sar	Yes	Yes	Yes
application/vnd.ms-excel	Excel for Windows	xls, xlt, xla	Yes	Yes	Yes
application/vnd.ms-outlook	Outlook for Windows	msg	No	Yes	Yes

Trend Micro Deep Security On-Premise 11.3

MIME Type	Description	Extension	Supported in 9.6 Agent	Supported in 10.0 Agent	Supported in 10.1 Agent or higher
application/vnd.ms-powerpoint	Windows PowerPoint	ppt, pot, pps, ppa	Yes	Yes	Yes
application/vnd.ms-publisher	MS Publisher	pub	No	No	Yes
application/vnd.oasis.opendocument	Open Document	odf	Yes	Yes	Yes
application/vnd.openxmlformats-officedocument.presentationml.presentation	MS Office File	pptx, potx, ppsx, ppam, pptm, potm, ppsm	Yes	Yes	Yes
application/vnd.openxmlformats-officedocument.spreadsheetml.sheet	MS Office File	xlsx, xltx, xlsx, xltm, xlam, xlsb	Yes	Yes	Yes
application/vnd.openxmlformats-officedocument.wordprocessingml.document	MS Office File	docx, dotx, docm, dotm	Yes	Yes	Yes
application/vnd.rn-realmedia	Real Media	rm	Yes	Yes	Yes
application/wordperfect	WOrdPerfect	wp, wp5, wp6, wpd, w60, w61	Yes	Yes	Yes
application/x-alf		alf	Yes	Yes	Yes
application/x-arc-compressed	ARC File	arc	Yes	Yes	Yes
application/x-bzip2	bZIP File	*	Yes	Yes	Yes
application/x-cpio	CPIO File	*	Yes	Yes	Yes
application/x-director	Macromedia Director Shockwave Movie	dcr	Yes	Yes	Yes
application/x-gzip	Gzip	*	Yes	Yes	Yes
application/xhtml+xml	XHTML	dhtml, dhtml, htm, html, htx, sht, shtm, shtml, stml, xht, xhtm, xhtml, xml, txt	Yes	Yes	Yes
application/x-java-class	JAVA Applet	class	Yes	Yes	Yes
application/x-kep		kep	Yes	Yes	Yes
application/x-otf		otf	Yes	Yes	Yes
application/x-sapshortcut		sap, sapc	Yes	Yes	Yes
application/x-shockwave-flash	Macromedia Flash	swf	Yes	Yes	Yes
application/x-silverlight-app	PKZIP	xap	Yes	Yes	Yes
application/x-sim		sim	Yes	Yes	Yes
application/x-tar	TAR File	tar	Yes	Yes	Yes
application/x-vbs		*	Yes	Yes	Yes
application/zip	ZIP File	zip, zipx	Yes	Yes	Yes

Trend Micro Deep Security On-Premise 11.3

MIME Type	Description	Extension	Supported in 9.6 Agent	Supported in 10.0 Agent	Supported in 10.1 Agent or higher
audio/basic	Audio	snd, au	Yes	Yes	Yes
audio/midi	MIDI	mid, midi, rmi, mdi, kar	Yes	Yes	Yes
audio/x-aiff	Audio InterChange File Format from Apple/SGI	aiff, aif, aifc	Yes	Yes	Yes
audio/x-mpeg-3	MP3	mp3	Yes	Yes	Yes
audio/x-realaudio	Real Audio	ra	Yes	Yes	Yes
audio/x-voc	Creative Voice Format (VOC)	voc	Yes	Yes	Yes
image/bmp	Windows BMP	bmp	Yes	Yes	Yes
image/gif	GIF	gif	Yes	Yes	Yes
image/ico	Windows Icon	ico	Yes	Yes	Yes
image/jpeg	JPEG	jpg, jpeg, jpe, jif, jfif, jfi	Yes	Yes	Yes
image/msp	Microsoft Paint	msp	Yes	Yes	Yes
image/png	Portable Network Graphics	png	Yes	Yes	Yes
image/ppm	PPM image	ppm	Yes	Yes	Yes
image/svg+xml		svg	Yes	Yes	Yes
image/tiff	TIFF	tif, tiff	Yes	Yes	Yes
image/vnd.ms-modi	Microsoft Document Imaging	mdi	Yes	Yes	Yes
image/x-cpt	Corel PhotoPaint	cpt	Yes	Yes	Yes
image/x-pcx	PCX	pcx	Yes	Yes	Yes
image/x-pict	Macintosh Bitmap	pct	Yes	Yes	Yes
image/x-ras	Sun Raster(RAS)	ras	Yes	Yes	Yes
image/x-wmf	Windows Metafile	wmf	Yes	Yes	Yes
text/csv	CSV	csv, txt	Yes	Yes	Yes
text/html	HTML	dhtm, dhtml, htm, html, htx, sht, shtm, shtml, stml, xht, xhtm, xhtml, xml, txt	Yes	Yes	Yes
text/plain		*	Yes	Yes	Yes
text/plain	Text File	txt	Yes	Yes	Yes

Trend Micro Deep Security On-Premise 11.3

MIME Type	Description	Extension	Supported in 9.6 Agent	Supported in 10.0 Agent	Supported in 10.1 Agent or higher
text/xml	XML	dhtm, dhtml, htm, html, htx, sht, shtm, shtml, stml, xht, xhtm, xhtml, xml, txt	Yes	Yes	Yes
text/xsl	XSL	xsl	Yes	Yes	Yes
unknown/unknown		*	Yes	Yes	Yes
video/mpeg		*	Yes	Yes	Yes
video/quicktime	Quick Time Media	qt	Yes	Yes	Yes
video/x-fli	AutoDesk Animator	fli	Yes	Yes	Yes
video/x-flv	Macromedia Flash FLV Video	flv	Yes	Yes	Yes
video/x-ms-asf	Advanced Streaming Format	asf	Yes	Yes	Yes
video/x-scm	Lotus ScreenCam Movie	scm	Yes	Yes	Yes

Deep Security Best Practice Guide

The Deep Security 10.0 Best Practice Guide is intended to help you get the best productivity out of the product. It contains a collection of best practices that are based on knowledge gathered from previous enterprise deployments, lab validations, and lessons learned in the field. Examples and considerations in this document serve only as a guide and not a representation of strict design requirements. These guidelines do not apply in every environment but will help guide you through the decisions that you need in configuring Deep Security for optimum performance.

The Deep Security 11.0 Best Practice Guide is currently [available in PDF format](#) and includes the following:

Trend Micro Deep Security On-Premise 11.3

- Deployment considerations and recommendations
- Upgrade guidelines and scenarios
- Sizing considerations and recommendations
- Recommended configurations to maximize system performance and reduce administrative overhead
- Best practice tips for VDI, private, and public cloud environments

Maintain

Check your license information

Note: Does not apply to a multi-tenant configuration that inherits licensing from the parent tenant.

Displays details about your Trend Micro Deep Security product licenses. Deep Security consists of six module packages:

- Anti-Malware and Web Reputation
- Firewall and Intrusion Prevention
- Integrity Monitoring
- Log Inspection
- Multi-Tenancy
- Deep Security Scanner

Trend Micro Deep Security On-Premise 11.3

Each module package can be licensed fully or for a trial basis. You can see an individual package's license status by clicking **View Details**. Contact Trend Micro if you wish to upgrade your license. If Trend Micro has provided you with a new activation code, click **Enter New Activation Code** and enter it there. Newly licensed features are immediately available.

When a license expires, existing functionality persists but updates are no longer delivered.

Alerts are raised if any module is about to expire or has expired.

Back up and restore your database

If you have a database backup, you can restore your Deep Security deployment if there is a catastrophic failure or if you move Deep Security Manager to another computer.

Back up your database

Consult your database vendor's documentation for instructions on how to back up your database.

Tip: For RDS, follow the instructions provided by AWS for backing up your database to an S3 bucket. For example, see [Amazon RDS for SQL Server - Support for Native Backup/Restore to Amazon S3](#).

Restore the database only

1. Stop the Deep Security Manager service.
2. Restore the database.

This must be a database from the same version number of the Deep Security Manager.

3. Start the Deep Security Manager service.

Trend Micro Deep Security On-Premise 11.3

4. Verify contents restored.
5. Update all of the computers to ensure they have the proper configuration.

Restore both the Deep Security Manager and the database

1. Remove any remnants of the lost or corrupted Deep Security Manager and database.
2. Install a fresh Deep Security Manager using a fresh or empty database.
3. Stop the Deep Security Manager service.
4. Restore the database over the freshly installed one, must be the same database name (Must be a database from the same version number of the Manager).
5. Start the Deep Security Manager service.
6. Verify contents restored.
7. Update all of the computers to ensure they have the proper configuration.

Export objects in XML or CSV format

- **Events:** Go to one of the Events pages and use the Advanced Search options to filter the event data. For example, you could search for all firewall events for computers in the Computers > Laptops computer group that were logged within the last hour whose reason column contains the word spoofed.

The screenshot shows the 'Firewall Events' search interface. At the top, there are filters for 'All' and 'No Grouping'. A search bar with a magnifying glass icon and the text 'Search' is on the right. Below this, the 'Period' is set to 'Last Hour'. The 'Computers' section shows 'In Group' and 'Computers > Laptops'. The 'Search' section shows 'Reason' with a dropdown arrow, 'Contains' with a dropdown arrow, and the text 'spoofed'. A blue vertical bar on the right contains a circular refresh icon and a plus sign.

Click the submit button (with the right-facing arrow) to execute the "query". Then click **Export** to export the filtered data in CSV format. You can export all the displayed entries or just selected data. The exporting of logs in this format is primarily for integration with third-party reporting tools.

- **Computer Lists:** Computers lists can be exported in XML or CSV format from the **Computers** page. You might want to do this if you find you are managing too many computers from a single Deep Security Manager and are planning to set up a second Deep Security Manager to manage a collection of computers. Exporting a list of selected computers will save you the trouble of rediscovering all of the computers again and arranging them into groups.

Note: Policy, firewall rule, and intrusion prevention rule settings will *not* be included. You will have to export your firewall rules, intrusion prevention rules, firewall stateful configurations, and policies as well and then reapply them to your computers.

- **Policies:** To export these in XML format, go to **Policies**.

Note: When you export a selected policy to XML, any child policies the policy might have are included in the exported package. The export package contains all of the actual objects associated with the policy except: intrusion prevention rules, log inspection rules, integrity monitoring rules, and application types.

- **Firewall Rules:** Firewall rules can be exported to an XML or CSV file using the same searching and filtering techniques as above.
- **Firewall Stateful Configurations:** Firewall stateful configurations can be exported to an XML or CSV file using the same searching and filtering techniques as above.
- **Intrusion Prevention Rules:** Intrusion prevention rules can be exported to an XML or CSV file using the same searching and filtering techniques as above.

Trend Micro Deep Security On-Premise 11.3

- **Integrity Monitoring Rules:** Integrity monitoring rules can be exported to an XML or CSV file using the same searching and filtering techniques as above.
- **Log Inspection Rules:** Log inspection rules can be exported to an XML or CSV file using the same searching and filtering techniques as above.
- **Other Common Objects :** All the reusable components common objects can be exported to an XML or CSV file the same way.

When exporting to CSV, only displayed column data is included. Use the Columns tool to change which data is displayed. Grouping is ignored so the data might not be in same order as on the screen.

Import objects

To import each of the individual objects into Deep Security, next to **New** in the object page's toolbar, select **Import From File** .

Restart the Deep Security Manager

Linux

To restart the Deep Security Manager, open a CLI and run the following command:

```
sudo systemctl restart dsm_s
```

Windows

To restart the Deep Security Manager, first log in to the Windows instance on which the Deep Security Manager is running and then follow the steps below for the ["Windows desktop" below](#), the ["Command prompt" below](#) or ["PowerShell" below](#):

Windows desktop

1. Open the Windows Task Manager.
2. Click the **Services** tab.
3. Right click the **Trend Micro Deep Security Manager** service, and then click **Restart**.

Command prompt

Open the command prompt (`cmd.exe`) and run the following commands:

1. `net stop "Trend Micro Deep Security Manager"`
2. `net start "Trend Micro Deep Security Manager"`

PowerShell

Open PowerShell and run the following commands:

1. `Stop-Service 'Trend Micro Deep Security Manager'`
2. `Start-Service 'Trend Micro Deep Security Manager'`

Upgrade Deep Security

About upgrades

To ensure maximum protection, upgrade your software, security rules and malware patterns when updates are available. Upgrade types include:

- **Software update:** A package of new software such as the Deep Security Manager, Virtual Appliance, Agent and Relay. See ["Install or upgrade Deep Security" on page 144](#), ["Upgrade the Deep Security Virtual Appliance" on page 987](#), and ["Update the Deep Security Agent" on page 984](#).
- **Security update:** An update to the security rules and malware patterns that Deep Security uses to identify potential threats. See ["Get and distribute security updates" on page 1018](#).

Relays distribute both software updates and security updates to your agents and virtual appliances. Software updates (but not security updates) can alternatively be [distributed by a local mirror web server](#).

Warning: All Deep Security Relays must be upgraded before upgrading the Deep Security Agent. Failure to do so may cause the relay upgrade to fail.




In this topic:

- ["How agents validate the integrity of updates" on the next page](#)
- ["How Deep Security Manager checks for software updates" on page 983](#)

How agents validate the integrity of updates

All security updates are verified for integrity by Deep Security using methods that include digital signatures and checksums (hashes) as well as other, non-disclosed methods. Software updates are digitally signed.

Agent Amazon ▼ [Show All Versions](#)

Software	Release Type	Build	Release Date	File Size	Download
1  Deep Security Agent 10.0.0-2775 for amzn1-x86_64	Update: 10.0_U9	10.0.0-2775	2018-04-04	64 MB	
2  Filename: Agent-amzn1-10.0.0-2775-x86_64.zip SHA256: ae057659377494c3275a87ef49332e10ab86c2ad2daf6538d73f268d4dba993b MD5: 38467af6e4aa681b00a279cd1e02b1ab Release Notes					

If you want to manually validate signatures or the checksums available on the [Download Center](#), you can also use a tool such as:

- sha256sum (Linux)
- Checksum Calculator (Windows)
- jarsigner (Java Development Kit (JDK))

For example, you could enter this command to verify a download's signature:

```
jarsigner -verify <filename>.zip
```

How Deep Security Manager checks for software updates

Deep Security Manager periodically connects to Trend Micro update servers to check for updates to software that you have [imported into the Deep Security Manager database](#), such as:

- Deep Security Agent
- Deep Security Virtual Appliance
- Deep Security Manager

The check is made against the local inventory, not against what is available on the Download Center. (There is a separate alert for new software on the Download Center.)

Note: Deep Security will only inform you of **minor** version updates-not major-of software.

For example, if you have agent version **9.6.100**, and Trend Micro releases agent version **9.6.200**, an alert will tell you that software updates are available. However, if Trend Micro then releases agent version **10.0.xxx** (a major version difference) and you don't have any **10.0** agents in the database, no alert will appear (even though **10.0** is newer than **9.6.100**).

An alert on the manager will notify you that software updates are available. The "Trend Micro Download Center" section on **Administration > Updates > Software** also indicates whether there are updates available. Once you import (download) software into the Deep Security Manager database, you can upgrade the software in your deployment. See ["Update the Deep Security Agent" on the next page](#) and ["Upgrade the Deep Security Virtual Appliance" on page 987](#).

Tip: To see *all* software packages that are available for download (even if you haven't imported it before), go to **Administration > Updates > Software > Download Center**.

To determine when the last check was performed, whether it was successful, or to manually initiate a check for updates, go to **Administration > Updates > Software** and view the "Deep Security" section. If you have configured a scheduled task to check for

Trend Micro Deep Security On-Premise 11.3

updates, the date and time of the next scheduled check is also listed here. See ["Schedule Deep Security to perform tasks" on page 418](#).

When imported, software is stored in the Deep Security Manager database. Imported software is periodically replicated to relay-enabled agents.

Update the Deep Security Agent

Software updates can be initiated via the Deep Security Manager, manually, or a third-party deployment system.

Tip: If your environment includes Deep Security Agents installed on Linux computers, you can choose to automatically upgrade those agents to the latest software version that's compatible with your Deep Security Manager when the agent is activated or reactivated. For details, see ["Automatically upgrade agents on activation" on page 341](#).


Warning: All Deep Security Relays must be upgraded before upgrading the Deep Security Agent. Failure to do so may cause the relay upgrade to fail.

In this topic:

- ["Update available notifications" below](#)
- ["Initiate an agent update" on the next page](#)
- ["Select the agent for newly-activated virtual appliances" on page 986](#)
- ["Manually upgrade the agent" on page 986](#)

Update available notifications

When a new agent software version is available, a message appears on **Alerts**.

 **Upgrade of the Agent/Appliance software is recommended on one or more Computers.**May 3, 2017 17:19

Deep Security Manager has detected one or more computers with a version of the Agent/Appliance that is older than the latest version imported into the Manager. An upgrade of the Agent/Appliance software is recommended.

[▼ Show Details](#)

1. In the alert, click **Show Details** and then click **View all out-of-date computers**.
Computers opens with all computers showing a **Software Update Status** of **Out-of-Date**.
2. Continue with "[Initiate an agent update](#)" below or "[Manually upgrade the agent](#)" on the next page.

Initiate an agent update

Tip: Upgrade when the server is less busy.

On **Administration > Updates > Software**, the "Computers" section indicates whether any computers or virtual appliances are running agents for which updates are available. The check is only performed against software that has been imported into Deep Security, not against software available from the Download Center. If any computers are out of date, either:

- To upgrade all out-of-date computers, click **Upgrade Agent / Appliance Software**.
- To upgrade a specific agent computer or appliance image, go to **Computers**, select the computers that you want to upgrade, and click **Actions > Upgrade Agent Software**. You will be prompted to select the **Agent Version**. We recommend that you select the default **Use the latest version for platform (X.Y.Z.NNNN)**. Depending on your preference, select to **Upgrade Now** or **Use a Schedule for Upgrade** and specify the time window when the upgrade will be performed. If you choose to use a schedule, the manager will upgrade the agent to the specified version once; it does not continue to upgrade the agent to future versions.

Note: If you are using anti-malware on a Windows platform, the computer might require a reboot to complete the upgrade. If this is the case, a Reboot Required alert will be triggered, which you must dismiss manually after completing the reboot. You can

also check the Agent Software Upgraded event or Virtual Appliance Upgraded event to see if a reboot is necessary. If you are using anti-malware, plan your upgrades during maintenance windows when reboots are possible.

Note: When you activate a virtual appliance on a computer, Deep Security upgrades the Red Hat Agent to the version specified for the Virtual Appliance Deployment option. (See ["Select the agent for newly-activated virtual appliances" below](#).) You cannot delete the latest Red Hat Agent unless you first remove all virtual appliance software packages. You can delete older versions of the Red Hat Agent only if they are not in use.

Select the agent for newly-activated virtual appliances

Note: For more information on upgrading the Deep Security Virtual Appliance, see ["Upgrade the Deep Security Virtual Appliance" on the next page](#).

The Deep Security Virtual Appliance uses the protection module plug-in software packages from an agent for 64-bit Red Hat Enterprise Linux. Use the **Virtual Appliance Deployment** option to select the version of the Red Hat Enterprise Linux Agent software that is deployed to any newly activated virtual appliances.

When the default item of **Latest Available (Recommended)** is selected, the software used is the latest version of imported agent software that is compatible with the latest version of the appliance software that is imported.

Versions of the agent software that pre-date the imported appliance do not appear in the list.

Manually upgrade the agent

Sometimes you may not be able to update the agent software from the Deep Security Manager because of connectivity restrictions, or you may prefer to deploy updates using a third-party system. If so, you can update the agent software using an installer that you have copied to the computer.

Trend Micro Deep Security On-Premise 11.3

Download the new agent software either from the [Download Center](#), or by exporting it from the Deep Security Manager (see "[Get Deep Security Agent software](#)" on page 318). Then run the installer. Method varies by operating system.

Windows

1. Disable agent self-protection. To do this, on the Deep Security Manager, go to **Computer editor**¹ > **Settings** > **General**. In **Agent Self Protection**, and then either deselect **Prevent local end-users from uninstalling, stopping, or otherwise modifying the Agent** or enter a password for local override.
2. Copy the agent installer to the computer.
3. Run the agent installer. It will detect the previous agent and perform the upgrade.

Linux

1. Copy the agent installer to the computer.
2. Run the following command:

```
rpm -U <new agent installer rpm>
```

(The "-U" argument instructs the installer to perform an upgrade.)

Upgrade the Deep Security Virtual Appliance

Trend Micro recommends that you upgrade the Deep Security Virtual Appliance with the newest version to take advantage of the latest security patches, updates, and ongoing support. You can upgrade the appliance service virtual machine (SVM), or just the agent embedded in the appliance SVM.

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Note: The term 'appliance SVM' refers to the Deep Security Virtual Appliance virtual machine deployed in your VMware infrastructure.

You have a few upgrade options:

- Option 1: ["Upgrade an existing appliance SVM automatically" below](#) (recommended if you have no other ESXi hosts and protection loss during the upgrade period is acceptable)
- Option 2: ["Upgrade an existing appliance SVM manually" on page 995](#) (recommended if you have another ESXi host to which you can vMotion your VMs and keep protection)
- Option 3: ["Upgrade the agent embedded on the appliance SVM and apply OS patches" on page 1007](#) (only use this option if upgrading the appliance SVM is not feasible)

Note: See also ["Upgrade the NSX license to Advanced or Enterprise" on page 1010](#).

Upgrade an existing appliance SVM automatically

With this upgrade option, your guest VMs lose protection during the upgrade process, which takes five to fifteen minutes depending on the resources of your VMware components and network stability. If you would like to maintain protection of the guest VMs, see instead ["Upgrade an existing appliance SVM manually" on page 995](#).

Note: Any resource adjustments or custom configurations you may have made to the current appliance SVM, such as extending the CPU or memory or changing a password, will not be carried over to the new appliance SVM after the upgrade. You will need to manually re-apply these configurations when the upgrade finishes.

Step 1: Verify permissions

1. Make sure that the vCenter account that you registered in Deep Security Manager has these permissions:
 - `VirtualMachine.Interaction.Power Off`, and
 - `VirtualMachine.Inventory.Remove`, and
 - `ESX Agent Manager.Modify`
2. Make sure that the NSX Manager account that you registered in Deep Security Manager belongs to one of these NSX Manager roles:
 - `Security Engineer`, or
 - `Security Administrator`, or
 - `Enterprise Administrator`

Step 2: Import the new virtual appliance packages into the manager

1. On your Deep Security Manager computer, go to the software page at <https://help.deepsecurity.trendmicro.com/software.html>.
2. Download the latest Deep Security Virtual Appliance package to your computer.
3. On Deep Security Manager, go to **Administration > Updates > Software > Local**.
4. Click **Import** and upload the package to Deep Security Manager.

When you import the appliance package, Deep Security Manager automatically downloads Deep Security Agent software that is compatible with the operating system of the appliance's virtual machine. This agent software appears under **Administration > Updates > Software > Local**. When you deploy the appliance, the embedded agent software will be auto-upgraded to the latest compatible version in **Local Software** by default. You can change the auto-upgrade version by clicking **Administration > System Settings > Updates tab > Virtual Appliance Deployment**.

Note: It is acceptable to have multiple versions of the Deep Security Virtual Appliance package appear under **Local Software**. The newest version is always selected when you deploy a new Deep Security Virtual Appliance.

5. Optionally, for guest VMs that run Microsoft Windows, you can also download the Deep Security Notifier. The notifier is a component that displays messages for Deep Security system events in the system tray. For details, see ["Install the Deep Security Notifier" on page 377](#).


Step 3: Upgrade the appliance SVM in the manager

1. In Deep Security Manager, click **Computers** at the top.
2. Right-click the ESXi host where your existing appliance SVM is located, and select **Actions > Upgrade Appliance (SVM)**.

Tip: You can use Shift+click to select multiple ESXi hosts, if you want to upgrade several at once.

Note: The **Upgrade Appliance (SVM)** option is only available if the latest virtual appliance package in **Local Software** is newer than the one that's currently in use. To make the option available, try [importing the latest appliance package](#). If that doesn't work, it's likely because you're already using the latest version of the appliance SVM. To check, look at the **Appliance (SVM) Version** property on the computer details page of the appliance virtual machine.

Trend Micro Deep Security On-Premise 11.3



The **Upgrade Appliance (SVM)** page appears with a check box, warnings, and a note.

Upgrade Appliance (SVM)

Upgrade the appliance (SVM) to version 11.1.0.77.
The process takes approximately 10 minutes.

☒ Check NSX alarms before upgrading, and cancel the process if any alarms exist.

WARNING Upgrading the appliance SVM deletes the original appliance Service Virtual Machine. Back up any customized VM settings and files before continuing. Consult the Deep Security [Help Center](#) for more information"

WARNING Upgrading the appliance (SVM) may take ten minutes or more in a LAN environment. During this time, protection is terminated, and is resumed when the upgrade has finished. Consult the Deep Security [Help Center](#) for upgrading without protection loss.

NOTE Ensure at that there is at least 4 GB of RAM and 40 GB of disk space remaining in ESXi.

OK

Cancel

3. (Optional.) Select **Check NSX alarms before upgrade, and cancel the process if any alarms exist** if you want the manager to check the service status from NSX Manager before the upgrade begins. Deselect the check box if you want to skip the check and proceed with the upgrade despite possible alarms.
4. Review the warnings and note on the page.
5. Click **OK**.

The upgrade process begins, including a pre-upgrade service status check, if you enabled it.

6. (Optional.) Still in the manager, go back to the **Computers** page, find your ESXi host, and look at its **TASK(S)** column to view the status of the upgrade.

Note: If you previously shift+clicked several ESXi hosts on which to perform an upgrade, the ESXi hosts are processed sequentially (one at a time). You can look at the **TASK(S)** column to find out which server is currently being processed.

The **TASK(S)** column displays one of the following:

- **Upgrading Appliance (SVM) (Pending):** The manager has received the upgrade request, but has not yet put it into the queue.
 - **Upgrading Appliance (SVM) (In Queue):** The manager has queued the process, and will start the upgrade soon.
 - **Upgrading Appliance (SVM) (In Progress):** The manager is processing the upgrade.
7. (Optional.) Still in the manager, go to the **Computer Details** page of one of your ESXi hosts and click the **System Events** tab to verify that the upgrade is proceeding successfully.

Below is a sample of the system events you'll see when an upgrade is successful. For more events, see [this complete list of appliance SVM upgrade events](#).

TIME ▾	LEVEL	EVENT ID	EVENT
November 28, 2018 10:51:49	Info	2963	Appliance (SVM) Upgraded
November 28, 2018 10:48:38	Info	2961	Appliance (SVM) Upgrade Started
November 28, 2018 10:48:38	Info	2960	Appliance (SVM) Upgrade Requested

Note: If you see the **Appliance (SVM) Upgrade Failed** system event, see ["Troubleshooting the 'Appliance \(SVM\) Upgrade Failed' system event"](#) below.

Troubleshooting the 'Appliance (SVM) Upgrade Failed' system event

If you see the **Appliance (SVM) Upgrade Failed** system event, review its detailed description for the reason and possible fix. In the worst case scenario, you can go to the NSX Manager console and click the **Resolve** button (see the image below). Clicking this button manually resolves any alarms and redeploys the appliance. Guest VMs are activated according to [how you set up activation](#) when you deployed your old Deep Security Virtual Appliance.

Installation and Upgrade


Management Host Preparation Logical Network Preparation **Service Deployments** Upgrade











NSX Manager: 10.0.0.10

EAM Status: Up

Network & Security Service Deployments

Network & security services are deployed on a set of clusters. Manage service deployments here by adding new services or deleting existing ones.

 **Resolve**

Service	Version	Installation Status	Service Status	Cluster	Datastore	Port Group	IP Address Range
 Trend Micro Deep S...	11.0	 Failed	Unknown	 Cluster_1	 Specified on-host	 Specified on-host	IP pool
 Guest Introspection	6.4.0.7412345	 Failed	Unknown	 Cluster_1	 Specified on-host	 Specified on-host	IP pool

Step 4: Final step

The appliance SVM should be upgraded successfully. Go to the manager's **Computers** page and double-check that the appliance SVM and all the guest VMs are back in their protected state (green dot).

Upgrade an existing appliance SVM manually

With this upgrade option, you'll use the vMotion mechanism to preserve the guest VMs' protection while the upgrade occurs.

To upgrade the appliance SVM, follow these steps:

- "Step 1: Import the new virtual appliance packages into the manager" below
- "Step 2: Review or restore identified files" on the next page
- "Step 3: Migrate guest VMs to another ESXi host" on the next page
- "Step 4: Upgrade your old appliance SVM" on page 998
- "Step 5: Check that maintenance mode was turned off" on page 1004
- "Step 6: Check that the new appliance SVM is activated" on page 1004
- "Step 7: Final step" on page 1007

Step 1: Import the new virtual appliance packages into the manager

1. On your Deep Security Manager computer, go to the software page at <https://help.deepsecurity.trendmicro.com/software.html>.
2. Download the latest Deep Security Virtual Appliance package to your computer.
3. On Deep Security Manager, go to **Administration > Updates > Software > Local**.

Trend Micro Deep Security On-Premise 11.3

4. Click **Import** and upload the package to Deep Security Manager.

When you import the appliance package, Deep Security Manager automatically downloads Deep Security Agent software that is compatible with the operating system of the appliance's virtual machine. This agent software appears under **Administration > Updates > Software > Local**. When you deploy the appliance, the embedded agent software will be auto-upgraded to the latest compatible version in **Local Software** by default. You can change the auto-upgrade version by clicking **Administration > System Settings > Updates tab > Virtual Appliance Deployment**.

Note: It is acceptable to have multiple versions of the Deep Security Virtual Appliance package appear under **Local Software**. The newest version is always selected when you deploy a new Deep Security Virtual Appliance.

5. Optionally, for guest VMs that run Microsoft Windows, you can also download the Deep Security Notifier. The notifier is a component that displays messages for Deep Security system events in the system tray. For details, see ["Install the Deep Security Notifier" on page 377](#).

Step 2: Review or restore identified files

1. [Review or restore identified files](#) as necessary because quarantined files will be lost when you move your VMs or delete the Deep Security Virtual Appliance.
2. There is no need to shut down the guest VMs while replacing the appliance SVM.


Step 3: Migrate guest VMs to another ESXi host

For brevity, this procedure uses these terms:

- `ESXi_A` is the ESXi server with the virtual appliance that you want to upgrade.
- `ESXi_B` is the ESXi server where guest VMs are migrated to while the appliance SVM upgrade occurs. We assume it is under

Trend Micro Deep Security On-Premise 11.3

the same cluster as ESXi_A.



1. Enable DRS for the cluster and make sure it has an automation level of **Fully Automated**. See [this VMware article](#) for details.
2. Find ESXi_A and [place this ESXi server in maintenance mode](#).

When you enter maintenance mode:

- ESXi_A's guest VMs are migrated automatically (using [vMotion](#)) to ESXi_B in your cluster.
- The Deep Security Virtual Appliance that is protecting ESXi_A is shut down automatically.
- Your guest VMs can no longer be powered on until ESXi_A is out of maintenance mode.


Step 4: Upgrade your old appliance SVM

1. Go to **VMware vSphere Web Client > Hosts and Clusters**.
2. Find the **Trend Micro Deep Security** appliance SVM that is powered off. It's the one without a green arrow (shown in the following image). The appliance SVM was automatically powered off when you put the corresponding ESXi server into maintenance mode.

Trend Micro Deep Security On-Premise 11.3


3. Right-click the **Trend Micro Deep Security** appliance SVM that is powered off and select **Delete from Disk**.

Trend Micro Deep Security On-Premise 11.3



Trend Micro Deep Security On-Premise 11.3

4. If you see a **Confirm Delete** message, click **Yes**.



5. If the deletion fails with this message...


`This operation not allowed in the current state`

Do this:

- a. Right-click the **Trend Micro Deep Security** appliance SVM again, and this time select **Remove from Inventory** (which appears just above **Delete from Disk**). This removes the appliance SVM from vCenter but preserves it in the datastore.
- b. In the navigation pane, select the datastore tab and select the datastore where the old virtual appliance resides.
- c. In the main pane, select the **Files** tab.

Trend Micro Deep Security On-Premise 11.3

- d. Right-click the old appliance SVM folder and select **Delete File**.



6. In VMware vSphere Web Client, go to **Home > Networking and Security > Installation > Service Deployments**.

You see the following:

Trend Micro Deep Security On-Premise 11.3

- The deleted Trend Micro Deep Security appliance SVM **Installation Status** column shows **Failed**.
- If you are in maintenance mode, the **Guest Introspection** service also shows as **Failed**.

Installation and Upgrade

Management Host Preparation Logical Network Preparation **Service Deployments** Upgrade

NSX Manager: [dropdown]
EAM Status: Up

Network & Security Service Deployments

Network & security services are deployed on a set of clusters. Manage service deployments here by adding new services or deleting existing ones.

+ × ↕

Service	Version	Installation Status	Service Status	Cluster	Datastore	Port Group	IP Address Range
Trend Micro Deep S...	11.0	Failed	Unknown	Cluster_1	Specified on-host	Specified on-host	IP pool
Guest Introspection	6.4.0.7412345	Failed	Unknown	Cluster_1	Specified on-host	Specified on-host	IP pool

7. Click the **Resolve** button on the **Guest Introspection** service if its **Installation Status** is **Failed**.

The Guest Introspection service is powered on and maintenance mode is exited.

Check that the **Failed** status changes to **Enabling** and then to **Succeeded**.

8. Click the **Resolve** button on the **Trend Micro Deep Security** service that is **Failed**.

The following occurs:

- The Trend Micro Deep Security appliance SVM is redeployed with the latest software that you loaded into Deep Security Manager.
- The appliance SVM is activated.

Trend Micro Deep Security On-Premise 11.3

- The embedded agent on the appliance SVM is auto-upgraded to the latest compatible version in **Local Software** by default.

Check that the **Failed** status changes to **Enabling** and then to **Succeeded**.

Step 5: Check that maintenance mode was turned off

- [Check that maintenance mode was turned off](#) if you enabled it previously. If it is still on, turn it off now.

Step 6: Check that the new appliance SVM is activated

1. In Deep Security Manager, at the top, click **Computers**.
2. Find **Trend Micro Deep Security** in the list and double-click it. This is the appliance.
3. Check the following:
 - a. Check that the status is set to **Managed (Online)**. This indicates that the agent was successfully activated.
 - b. Check that the **Virtual Appliance Version** is set to the version of the embedded Deep Security Agent. This version should match the version of the newest agent software found under **Administration > Updates > Software > Local** or a specific version you set in **Administration > System Settings > Updates > Virtual Appliance Deployment**.
 - c. Check that the **Appliance (SVM) Version** is set to the version of the newest Deep Security Virtual Appliance package

Trend Micro Deep Security On-Premise 11.3

under **Administration > Updates > Software > Local**.

Computer: localhost.localdomain (Trend Micro Deep Security (5))

Overview

Anti-Malware

Web Reputation

Firewall

Intrusion Prevention

Integrity Monitoring

Log Inspection

Application Control

Interfaces

Settings

Updates

Overrides

General

Actions

System Events

Hostname:

localhost.localdomain

Display Name:

Trend Micro Deep Security (161)

Description:

Platform:

Deep Security Virtual Appliance

Group:

18.30 ▶ Virtual Machines ▶ Datacenter1 ▶ ESX Agents ▼

Policy:

Policy ▶ Deep Security ▶ Deep Security Virtual Appliance ▼

Asset Importance:

None ▼

Download Security Updates From:

Default Relay Group ▼

Appliance

Online

Last Communication

Virtual Appliance Version

Appliance (SVM) Version

Managed (Online)

Yes

November 29, 2018 14:04

11.1.0.76

11.1.0.76

Check Status

Clear Warnings/Errors

Protected Guests On

WIN-6ZJ7ITZEL

Trend Micro Deep Security On-Premise 11.3

You have now upgraded your appliance SVM.

Step 7: Final step

1. Repeat all the steps in this section, starting at ["Step 2: Review or restore identified files" on page 996](#) and ending at ["Step 6: Check that the new appliance SVM is activated" on page 1004](#) for each appliance SVM that needs to be upgraded.

Guest VMs are activated according to [how you set up activation](#) when you deployed your old Deep Security Virtual Appliance.

Upgrade the agent embedded on the appliance SVM and apply OS patches

Although Trend Micro recommends that you [upgrade your appliance SVM](#) with the latest version, we understand that this might not be possible. In such a case, you can upgrade just the Deep Security Agent that's embedded on the appliance SVM, and apply OS patches at the same time, without redeploying the appliance SVM.

Follow these instructions to complete the upgrade.

1. ["Determine the installed appliance version" on page 1009](#). You'll need this information to complete the remaining steps in this procedure.
2. Import appliance patches, if they exist (failure to do so generates system event `740` to indicate that the patch was not imported):
 - a. Log in to Deep Security Manager.
 - b. On the left, expand **Updates > Software > Download Center**.
 - c. In the main pane, enter `Agent-DSVA` in the search bar on the top-right and press Enter.
One or more patches appear with the name `Agent-DSVA-CentOS<version>-<patch-version>-<date>.x86_64.zip`.
 - d. Select a patch that is compatible with your appliance SVM. Consult the [compatibility table](#) that follows for guidance. If you don't see a compatible patch, it's because it doesn't exist, and no patch needs to be installed.
 - e. Click the button in the **Import Now** column to import the patch into Deep Security Manager.

Trend Micro Deep Security On-Premise 11.3

- f. On the left, click **Local Software** to verify that the patch was imported successfully.
 - g. Repeat for any additional patches.
3. Import the compatible agent:
 - a. Still in Deep Security Manager, on the left, expand **Updates > Software > Download Center**.
 - b. Select the agent software that is compatible with your appliance SVM. Consult the [compatibility table](#) that follows for guidance.
 - c. Click the button in the **Import Now** column to import the agent into Deep Security Manager.
 - d. On the left, click **Local Software** to verify that the agent was imported successfully.

You have now imported the patches and Deep Security Agent that are compatible with your appliance SVM version. You are ready to upgrade the agent on the appliance SVM and apply the patches.

4. Upgrade the agent on the appliance SVM and apply the patches:
 - a. Click **Computers** and double-click your appliance computer.
 - b. Click **Actions > Upgrade Appliance**.
 - c. Select the agent version to install on the appliance. This is the agent you just imported.
 - d. Click **OK**.
5. Click **Events & Reports** and search on **710** to find the report about the installation of the update file.

You have now upgraded the agent on the appliance SVM and installed one or more OS patches (if they existed).

If you upgraded the Deep Security Agent before importing the OS patch for the appliance SVM, you will see system event **740**. To fix this problem, use the following procedure.

1. Import the appliance patches for the version of the appliance SVM that you are upgrading. See above in this section for instructions. The appliance patches appear on the **Local Software** page in Deep Security Manager.
2. Go to the **Computers** page.

Trend Micro Deep Security On-Premise 11.3

3. Right-click the virtual machine where you want to upgrade the appliance and click **Send Policy**. The appliance downloads and installs the patches.

Tip: If the appliance fails to download the patches, it could be that the relay hasn't received the patch files yet. Wait until the relay receives the files and then click **Send Policy**. For information on relays, see ["Distribute security and software updates with relays" on page 380](#).

Compatibility table: appliance, agent, and patch

Appliance SVM version	Image OS	Compatible agent software	Compatible appliance patch (if it exists)
Appliance-ESX-10.0 or higher	CentOS 7	Agent-RedHat_EL7-<version>.x86_64.zip	Agent-DSVA_CENTOS7.0-<patch-version>-<date-stamp>.x86_64.zip

Determine the installed appliance version

Click **Computers**, select the appliance virtual machine, and click **Details > General**.

- The **Virtual Appliance Version** property indicates the version of the Deep Security Agent that is deployed on the appliance SVM.
- The **Appliance (SVM) Version** property indicates the version of the Deep Security Virtual Appliance package that is used to deploy this virtual machine.

Error: The installer could not establish a secure connection to the database server

When installing or upgrading Deep Security Manager, the following error message can occur if you are using Microsoft SQL Server as your Deep Security database:

Trend Micro Deep Security On-Premise 11.3

The installer could not establish a secure connection to the database server. Please upgrade or configure your database server to support TLS 1.2 encryption.

The error message appears if the `java.security` file on the Deep Security Manager includes `TLSv1` and `TLSv1.1` in the `jdk.tls.disabledAlgorithms=` setting, which disables early TLS and only allows TLS 1.2. (The `java.security` file is set this way if you are doing a fresh install of Deep Security Manager 11.1 or higher, where only TLS 1.2 is allowed, or if you are upgrading and previously [enforced TLS 1.2](#).) During the upgrade or installation, the database drivers on the manager try to communicate with the SQL Server using TLS 1.2, and if your SQL Server version does not support TLS 1.2, you'll see this error.

To solve the problem, you must upgrade your SQL Server database to a version that supports TLS 1.2 and then retry the Deep Security Manager installation or upgrade. For a list of SQL Server versions that support TLS 1.2, see [this Microsoft article](#).

Upgrade the NSX license to Advanced or Enterprise

If you deployed the Deep Security Virtual Appliance onto NSX for vShield Endpoint (free), NSX Standard Edition, or NSX Professional Edition, the following Deep Security features are *not* available:

- Deep Security firewall
- Deep Security intrusion prevention
- Deep Security web reputation

If you want these features, you'll need to upgrade to NSX Advanced Edition or Enterprise Edition, and then redeploy the Deep Security Virtual Appliance. Follow these steps:

- ["Step 1: Upgrade to NSX Advanced or Enterprise" on the next page](#)
- ["Step 2: Remove Deep Security from NSX completely" on page 1017](#)

- ["Step 3: Redeploy the Deep Security Virtual Appliance" on page 1017](#)

Note: As an alternative to upgrading your NSX license, you can deploy Deep Security Agents on your guest VMs to get the above-mentioned features. For details, see the ["Before you begin" on page 239](#) section under ["Deploy the Deep Security Virtual Appliance with NSX" on page 238](#).


Step 1: Upgrade to NSX Advanced or Enterprise

1. In your vSphere Web Client, go to **Home > Administration > Licenses**.
2. In the main pane, click **Assets**, and then click the **Solutions** button.


The screenshot shows the VMware vSphere Web Client interface. The top navigation bar includes the VMware logo, 'vSphere Web Client', a home icon, a refresh icon, the user 'Administrator@VSPHERE.LOCAL', and a help icon. The left sidebar contains a 'Navigator' pane with a 'Home' button and a tree view under 'Administration'. The tree view includes 'Access Control' (Roles, Global Permissions), 'Single Sign-On' (Users and Groups, Configuration), 'Licensing' (Licenses, Reports), 'Solutions', and 'Client Plug-Ins'. The 'Licenses' section is selected. The main pane shows the 'Licenses' section with a 'License provider' dropdown set to 'All 6.0 vCenter Server instances'. Below this are tabs for 'Getting Started', 'Licenses', 'Products', and 'Assets'. The 'Assets' tab is active, showing sub-tabs for 'vCenter Server systems', 'Hosts', 'Clusters', and 'Solutions'. The 'Solutions' sub-tab is selected, displaying a table of assets. The table has columns for 'Asset', 'Usage', 'Product', and 'License'. One asset is listed: 'NSX for vSphere' with usage '0 CPUs', product 'NSX for vShield Endpoint (CPUs)', and license 'License 1'. A search filter is visible in the top right of the table area.

Asset	Usage	Product	License
NSX for vSphere	0 CPUs	NSX for vShield Endpoint (CPUs)	License 1

3. Right-click **NSX for vSphere** and select **Assign License**.



4. Click the green + on the left to create a new license.



A wizard appears, guiding you through the process of adding a license key.

New Licenses

✓ **1 Enter license keys**

2 Edit license names

3 Ready to complete

Enter license keys
Enter license keys from which to create new licenses.

License keys (one per line):

Back Next Finish Cancel

5. In the wizard, enter the NSX Advanced or Enterprise edition license key and a license name. At the end of the wizard, click **Finished**.

Trend Micro Deep Security On-Premise 11.3

The new license (Advanced or Enterprise) appears in the list on the **Assign License** page.

Trend Micro Deep Security On-Premise 11.3

6. Select the new license and click **OK**.

NSX for vSphere - Assign License

Licenses

Filter

	License	License Key	Product	Usage	Ce
<input checked="" type="radio"/>	(New) NSX Advanced	H1436-J7L00-Q8LCG-03A24-20C4H	NSX for vSphere - Advanced (CPUs)	0 CPUs	3
<input type="radio"/>	License 1	4J6VQ-DTHEQ-58TX9-00AU6-3T952	NSX for vShield Endpoint (CPUs)	0 CPUs	U
<input type="radio"/>	NSX Standard	HJ03P-J8H10-38KC6-081A6-9XL4H	NSX for vSphere - Standard (CPUs)	0 CPUs	3

3 items

Assignment Validation for NSX Advanced


The license assignment is valid.






OK

Cancel

Trend Micro Deep Security On-Premise 11.3

The NSX license now in use is Advanced or Enterprise.



Getting Started Licenses Products Assets			
vCenter Server systems Hosts Clusters Solutions			
    All Actions ▾			
Asset	Usage	Product	
 NSX for vSphere	0 CPUs	NSX for vSphere - Advanced (CPUs)	

Step 2: Remove Deep Security from NSX completely

In order for the new license to take effect, you'll need to remove Deep Security entirely from NSX. To remove the Deep Security from NSX, see ["Uninstall Deep Security from your NSX environment" on page 1425](#).

Step 3: Redeploy the Deep Security Virtual Appliance

After completely removing Deep Security from NSX, you'll need to redeploy the Deep Security Virtual Appliance. To redeploy, follow all the steps in ["Deploy the Deep Security Virtual Appliance with NSX" on page 238](#).

You can now use the firewall, intrusion prevention and web reputation features, and you can continue to use the anti-malware and integrity monitoring features, which were available to you previously.

Get and distribute security updates

You must keep your Deep Security deployment up to date with the security updates that Deep Security uses to identify potential threats.

There are two types of security updates:

- **Pattern Updates** are used by the anti-malware module.
- **Rule Updates** are used by these modules:
 - Firewall
 - Intrusion Prevention
 - Integrity Monitoring
 - Log Inspection Security

Note: Before configuring security updates, you must have installed and activated your agents, appliances, and relays. See ["Manually install the Deep Security Agent" on page 322](#).

Trend Micro releases new rule updates every Tuesday, with additional updates as new threats are discovered. You can get information about the latest updates from the Trend Micro [Threat Encyclopedia](#).


To configure security updates, you will need to:

1. ["Configure a security update source and settings" on page 1021](#)
2. ["Configure Anti-Malware Engine Update" on page 1022](#)
3. Organize your relay-enabled agents into relay groups, assign relay groups to your agents and appliances, and configure relay settings for security and software updates. (See ["Distribute security and software updates with relays" on page 380](#).)

Trend Micro Deep Security On-Premise 11.3

4. ["Perform security updates" on page 1023](#)
5. ["Special case: configure updates on a relay-enabled agent in an air-gapped environment" on page 1023](#)

At any time, you can ["Check your security update status" on page 1024](#).



Note: Alerts are raised if a rule update has been downloaded from Trend Micro and available for more than thirty minutes but computers have yet to be updated.

Note: Alerts are raised if a pattern update has been downloaded from Trend Micro and available for more than an hour but computers have yet to be updated.

Configure a security update source and settings

1. Go to **Administration > System Settings > Updates**.
2. Set your **Primary Security Update Source**. By default this will be the **Trend Micro Update Server** accessed over the internet. Unless your support provider has told you to do otherwise, leave the setting as is. If you were given an alternative source for updates, enter the URL, including "http://" or "https://" in the **Other update source** box.
3. Set your pattern updates under **Secondary Source**. Normally, agents connect to a relay-enabled agent to get security updates. But if you have agents installed on roaming computers that are not always in contact with a Deep Security Manager or relay, you can select **Allow Agents/Appliances to download security updates directly from Primary Security Update Source if Relays are not accessible** to allow agents to use the update source specified in the previous step when their relay group is not available.
4. Normally, the Deep Security Manager instructs agents or appliances to download pattern updates. When **Allow Agents/Appliances to download security updates when Deep Security Manager is not accessible** is selected, even though an agent cannot communicate with the Deep Security Manager, it will continue to download updates from its configured source.

Tip: You may want to deselect this option on computers where you do not want to risk a potentially problematic security update when the computer is not in contact with a manager and therefore possibly far away from any support services.

Trend Micro Deep Security On-Premise 11.3

5. Trend Micro will occasionally issue an update to an existing Deep Security rule. The **Automatically apply Rule Updates to Policies** setting determines whether updated rules will automatically be applied to Deep Security policies. If this option is not selected, you will have to manually apply downloaded rule updates to policies from the **Administration > Updates > Security** page by clicking on the **Apply Rules to Policies** button.

Tip: Updates to existing rules are either improvements to the efficiency of the rule or bug fixes. So although it's a good idea to test new rules (either in detect-only mode or in a test environment) before deploying them to a production environment, automatically applying updates to existing rules is usually a safe option.

Note: By default, changes to policies are automatically applied to computers. You can change this behavior by opening a **Computer or Policy editor**¹ > **Settings > General** window and changing the **Automatically send Policy changes to computers** setting in the **Send Policy Changes Immediately** area.

6. You can configure amount of time that can pass between an instruction to perform a security update being sent and the instruction being carried out before an alert is raised. Click **Administration > System Settings > Alerts** and change the value for **Length of time an Update can be pending before raising an Alert**.

Configure Anti-Malware Engine Update

You can choose to automatically update the Anti-Malware engine separately from the Deep Security Agent for more secure protection. By default, this setting is turned off and appears as N/A in the **Is Latest** section on **Computer Details > Updates > Advanced Threat Scan Engine**.

To turn the Anti-Malware engine update on:

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

1. Go to **Computers or Policies** and double-click the computer or policy you want to update.
2. Go to **Settings > Engine Update**. Next to **Automatically update anti-malware engine**, select **Yes** from the drop-down menu.

Note: Relays always receive the latest Anti-Malware engine updates in order to keep the relay's local protection and engine update source for the same relay group up-to-date. Therefore, you cannot enable or disable engine updates directly on a relay.

Perform security updates

The recommended way to check for security updates is to set up a "Check for Security Updates" scheduled task that performs a check on a regular basis. For details, see ["Schedule Deep Security to perform tasks" on page 418](#)

You can also manually initiate security updates:

- For a system-wide update, go to **Administration > Updates > Security**, and click the **Check For Updates and Download** button.
- To perform security updates on specific agents and appliances, go to **Computers**, select the agent or appliance, then right-click and select **Actions > Download Security Update**.

Special case: configure updates on a relay-enabled agent in an air-gapped environment

In a typical environment, at least one relay-enabled agent is configured and able to download updates from the Trend Micro Update Server and the rest of the agents and appliances connect to that relay-enabled agent for update distribution. However, if your relay-enabled agent cannot to connect to the Update Server over the Internet, you'll need to set up a relay in your [demilitarized zone \(DMZ\)](#) that can obtain the security updates, which you can then copy to your air-gapped relays. For details, see ["Configure agents that have no Internet access" on page 354](#).

Check your security update status

The Security Updates Overview page (**Administration > Updates > Security**) displays the state of your security updates:

- **Trend Micro Update Server:** Indicates whether relays can connect to the Trend Micro Update Server to check for the latest security updates.
- **Deep Security:** Indicates when the last successful check and download were performed, and when the next schedule check will be performed.

Tip: **All Relays are in sync** indicates that all relays are distributing the latest successfully downloaded pattern updates. Relays that are out of sync are usually in that state because they cannot communicate with Trend Update Servers. This could be because they are intentionally "air-gapped" and need to be manually updated or because of network connectivity problems. If any relays are out of sync, a link to those relays will be provided.

- **Computers:** Indicates whether any computers are out of date *with respect to the Pattern Updates being stored in the Relays*. You can click **Send Patterns to Computers** to instruct all computers to retrieve the latest pattern updates from their assigned relays.

See details about pattern updates

The **Administration > Updates > Security > Patterns** page displays a list of the components that make up a pattern update. This page is displayed only when Deep Security has an active relay.

- **Component:** The type of update component.
- **Product Name:** The Deep Security product this component is intended for.
- **Platform:** The operating system for which the update is intended.

Trend Micro Deep Security On-Premise 11.3


- **Current Version:** The version of the component within the Update currently downloaded from Trend Micro to Deep Security and being distributed by the relays and the Deep Security Manager.
- **Last Updated:** When the currently downloaded security update was retrieved from Trend Micro.

Tip: You can find the version numbers of the security update components in effect on a specific computer on **Computer Editor > Updates**.

See details about rule updates

The **Administration > Updates > Security > Rules** page displays a list of the most recent Intrusion Prevention, Integrity Monitoring, and Log Inspection Rules that have been downloaded to the Deep Security Manager database.

From this page, you can:

- **View details about a rule update:** Select a rule update and click **View** to see details, including a list of the specific rules included in the update.
- **Roll back a rule update:** If a recent rule update has caused problems in your environment, you may want to roll back to a previous rule update. If you roll back to a previous update, all policies affected by the rollback will be immediately updated on *all computers using those policies*. Select the rule update that you want to roll back to and click **Rollback**. Deep Security Manager generates a summary of changes that will take place so that you can confirm the changes before finalizing the rollback.
- **Reapply the current rule set:**  indicates that a rule update has been applied. To reapply that rule update to computers being protected by Deep Security, right-click the rule update and click **Reapply**.
- **Import a rule update:** Rule updates are automatically imported into Deep Security during the "Check for Security Updates" scheduled task, or when you click **Check for Updates and Download** on the **Administration > Updates > Security** page. The

Trend Micro Deep Security On-Premise 11.3

only time you might have to manually import a rule update is if your installation has no connectivity to the Trend Micro Update Servers or if you are asked to do so by your support provider.

- **Export a rule update:** Under normal circumstances you should not have to export a rule update unless asked to do so by your support provider.
- **Delete a rule update:** Click **Delete** to remove the selected rule update from the Deep Security Manager database.

Tip: You can configure the number of rule updates that are kept in the Deep Security Manager database by going to the **Administration > System Settings > Storage** tab.

Tip: If the relay functionality is enabled for a computer, the **Computer editor > Security Updates** page displays the components that the relay is currently distributing to the agents and appliances that rely on it for security updates. If the anti-malware module is enabled for a computer, the security updates page also displays the set of patterns that are in effect locally on this computer. From this page, you can also download or roll back security updates.

Use a web server to distribute software updates

Deep Security software updates are normally hosted and distributed by relays. However, if you already have a web server, you can provide software updates via the web server instead of a relay. To do this, you must mirror the software repository of the relay on your web server.

Note: Although Deep Security Agents can download their *software* updates from the web server, at least one relay is still required to distribute *security* package updates such as anti-malware and IPS signatures (see "[Get and distribute security updates](#)" on page 1018).

Note: Even though you are using your own web servers to distribute software, you must still go to **Administration > Updates > Software** and import software into the Deep Security Manager's database. Then you must ensure that your software web server

Trend Micro Deep Security On-Premise 11.3

contains the same software that has been imported into Deep Security Manager. Otherwise the alerts and other indicators that tell you about available updates will not function properly.

Web server requirements

Disk Space: 20 GB

Ports: [Web server port](#), [relay port](#)

Copy the folder structure

Mirror the folder structure of the software repository folder on a relay-enabled agent. Methods vary by platform and network. For example, you could use `rsync` over SSH for a Linux computer and network that allows SSH.

On Windows, the default location for the relay-enabled agent's software repository folder is:

```
C:\ProgramData\Trend Micro\Deep Security Agent\relay\www\dsa\
```

On Linux, the default location for the Relay's software repository folder is:

```
/var/opt/ds_agent/relay/www/dsa/
```

The structure of the folder is like this:

```
|-- dsa
|   |-- <Platform>.<Architecture>
|       |-- <Filename>
|       |-- <Filename>
|       |-- ...
```

Trend Micro Deep Security On-Premise 11.3

```
|
|      |-- <Platform>.<Architecture>
|          |-- <Filename>
|          |-- <Filename>
|          |-- ...
```

For example:

```
|-- dsa
|      |-- CentOS_<version>.x86_64
|          |-- Feature-AM-CentOS_<version>.x86_64.dsp
|          |-- Feature-DPI-CentOS_<version>.x86_64.dsp
|          |-- Feature-FW-CentOS_<version>.x86_64.dsp
|          |-- Feature-IM-CentOS_<version>.x86_64.dsp
|          |-- ...
|
|      |-- RedHat_EL6.x86_64
|          |-- Agent-Core-RedHat_<version>.x86_64.rpm
|          |-- Feature-AM-RedHat_<version>.x86_64.dsp
|          |-- Feature-DPI-RedHat_<version>.x86_64.dsp
|          |-- Feature-FW-RedHat_<version>.x86_64.dsp
|          |-- ...
|          |-- Plugin-Filter_2_6_32_131_0_15_el6_x86_64-RedHat_<version>.x86_64.dsp
|          |-- Plugin-Filter_2_6_32_131_12_1_el6_x86_64-RedHat_<version>.x86_64.dsp
|          |-- ...
|
```

Trend Micro Deep Security On-Premise 11.3

```
|      |-- Windows.x86_64
|          |-- Agent-Core-Windows-<version>.x86_64.msi
|          |-- Agent-Core-Windows-<version>.x86_64.msi
|          |-- Feature-AM-Windows-<version>.x86_64.dsp
|          |-- Feature-AM-Windows-<version>.x86_64.dsp
|          |-- Feature-DPI-Windows-<version>.x86_64.dsp
|          |-- Feature-DPI-Windows-<version>.x86_64.dsp
|          |-- ...
|          |-- Plugin-Filter-Windows-<version>.x86_64.dsp
|          |-- Plugin-Filter-Windows-<version>.x86_64.dsp
|          |-- ...
```

The example above shows only a few files and folders. Inside a complete `dsa` folder, there are more. If you need to save disk space or bandwidth, you don't need to mirror all of them. You're only required to mirror the files that apply to your computers' platforms.

Configure agents to use the new software repository

When the mirror on the web server is complete, configure Deep Security Agents to get their software updates from your web server.

1. On Deep Security Manager, go to **Administration > System Settings > Updates**.
2. In the Software Updates section, enter the URL(s) of the mirror folder(s) on your web server(s).
3. Click **Save**.

Note: Verify that connectivity between agents and your web server is reliable. If the connection is blocked, agents will instead use the relay.

Disable emails for New Pattern Update alerts

The "New Pattern Update is Downloaded and Available" alert is raised when a security update has not been applied to an agent one hour after Deep Security Manager has downloaded it. The one-hour time span is not configurable. The alert is sent via email when the alert is raised by default.

If you are receiving too many of these email alerts because one hour is not long enough to disperse the updates, you can disable email notifications for this alert. Instead, you can receive email messages for the "Computer Not Receiving Updates" alert for which you can configure the time that passes before the alert is raised.

1. To ensure that Deep Security Manager is configured to automatically download security updates, in Deep Security Manager, click **Administration > Scheduled Tasks**.
2. If there is no scheduled task of type Check for Security Updates, create one (see ["Schedule Deep Security to perform tasks" on page 418](#)).
3. Click **Administration > System Settings > Updates**. In the Rules section under Security Updates, make sure **Automatically apply Rule Updates to Policies** is selected.
For Deep Security as a Service, rule updates are automatically applied by default.
4. Click **Alerts > Configure Alerts**.
5. In the Alert Configuration window, click the **New Pattern Update is Downloadable and Available** alert and then click **Properties**.
6. On the Alert Information window, deselect **Send Email to notify when this alert is raised** and then click **OK**.
7. Click the **Computer Not Receiving Updates** alert and then click **Properties**.
8. Make sure **Send Email to notify when this alert is raised** is selected, and click **OK**.
The alert is raised when an update is pending for 7 days.
9. To raise the alert after a different amount of time has passed since the update was pending, click **Administration > System**

Settings > Alerts.

10. In the alerts area, use the drop-down to select the period of time, and then click **Save**.

Harden Deep Security

There are several measures you can take to increase the security of your Deep Security deployment.

- ["Protect Deep Security Manager with an agent" below](#)
- ["Replace the Deep Security Manager SSL certificate" on page 1035](#)
- ["Encrypt communication between the Deep Security Manager and the database" on page 1043](#)
- ["Change the Deep Security Manager database password" on page 1051](#)
- ["Enable Content Security Policy and HTTP Public Key Pinning" on page 1054](#)
- ["Enforce user password rules" on page 1056](#)

Protect Deep Security Manager with an agent

To protect the server where Deep Security Manager is installed, install an agent on it and apply the Deep Security Manager policy.

1. Install an agent on the same computer as the manager.
2. Go to **Computers**.
3. Add the manager's computer. Do not choose to apply a policy yet.
4. Double-click the new computer to display its **Details** window and go to **Intrusion Prevention > Advanced > SSL Configurations**.
5. Click **New** to start the wizard to create a new SSL Configuration.
6. Specify the interface used by the manager. Click **Next**.

Trend Micro Deep Security On-Premise 11.3

7. On the **Port** page, select whether to protect the Deep Security Manager GUI's port number. (See [the port number](#).) Click **Next**.
8. Specify whether SSL Intrusion Prevention analysis should take place on all IP addresses for this computer, or just one. (This feature can be used to set up multiple virtual computers on a single computer.)
9. Select **Use the SSL Credentials built into the Deep Security Manager**. (This option only appears when creating an SSL Configuration for the Manager's computer.) Click **Next**.
10. Finish the wizard and close the **SSL Configuration** page.
11. Return to the computer's **Details** window. Apply the **Deep Security Manager Policy**, which includes the Firewall Rules and Intrusion Prevention Rules required to protect the Deep Security Manager's GUI port number.

You have now protected the Manager's computer and are now filtering the traffic (including SSL) to the Manager.

Note: After configuring the Agent to filter SSL traffic, you may notice that the Deep Security Agent will return several **Renewal Error** events. These are certificate renewal errors caused by the new SSL certificate issued by the Manager computer. To fix this, refresh the web page and reconnect to the Deep Security Manager's GUI.

The **Deep Security Manager** Policy has the basic Firewall Rules assigned to enable remote use of the Manager. Additional Firewall Rules may need to be assigned if the Manager's computer is being used for other purposes. The Policy also includes the Intrusion Prevention Rules in the **Web Server Common** Application Type. Additional Intrusion Prevention Rules can be assigned as desired.

Because the **Web Server Common** Application Type typically filters on the **HTTP** Port List and does not include the Deep Security Manager GUI's port number, it is added as an override to the ports setting in the **Intrusion Prevention Rules** page of the Policy's **Details** window. (See ["Port numbers, URLs, and IP addresses" on page 111](#).)

For more information on SSL data inspection, see ["Inspect SSL or TLS traffic" on page 760](#).

Protect Deep Security Agent

If you have enabled manager-initiated communication (see ["Agent-manager communication" on page 344](#) for details), and by extension, manager-initiated activation, it is highly recommended that you bind the agent to a specific manager during this activation. For details, see the section below.

Bind Deep Security Agent to a specific Deep Security Manager

If manager-initiated activation is enabled between Deep Security Agent and Deep Security Manager, Trend Micro strongly recommends that you protect the agent by allowing it to only be contacted by a known and specific manager during the activation. This configuration should be used if you are in an environment that might include malicious Deep Security Managers.

To bind the agent to a manager, you'll need to export the SSL certificate that is used for securing agent-manager communication, and then add it to the agent computer. Follow these instructions:

1. On the Deep Security Manager, export the Deep Security Manager SSL certificate by running this command:

```
dsm_c -action exportdsmcert -output ds_agent_dsm.crt [-tenantname TENANTNAME | -tenantid TENANTID]
```

where:

- `ds_agent_dsm.crt` must be specified exactly as shown (you cannot use another name). It is the name of the Deep Security Manager SSL certificate that is used to secure the communication between the agent and manager.
- `-tenantname TENANTNAME` is only required if you have a multi-tenant environment. `TENANTNAME` is replaced with the name of a tenant where agents are deployed.
- `-tenantid TENANTID` is an alternative to `-tenantname TENANTNAME`. `TENANTID` is replaced with the ID of a tenant where agents are deployed.

Trend Micro Deep Security On-Premise 11.3

- To specify multiple tenants, see the last step of this procedure.
 - For details on multi-tenancy, see ["Set up a multi-tenant environment" on page 201](#).
2. On the computer where the agent that you want to activate is installed, put the `ds_agent_dsm.crt` file in one of these locations:
 - Windows: `%ProgramData%\Trend Micro\Deep Security Agent\dsa_core`
 - Linux: `/var/opt/ds_agent/dsa_core`
 3. If you have multiple tenants, run the command above for each tenant and then copy the certificate to each tenant's agents.

Example:

If you have two tenants, run:

```
dsm_c -action exportdsmcert -output ds_agent_dsm.crt -tenantname TENANT1
```

```
dsm_c -action exportdsmcert -output ds_agent_dsm.crt -tenantname TENANT2
```

...then copy:

the first `ds_agent_dsm.crt` to agents controlled by TENANT1.

the second `ds_agent_dsm.crt` to agents controlled by TENANT2.

You have now added the Deep Security Manager certificate to the agent. The agent now only accepts activations from the Deep Security Manager that owns the certificate. If you have tenants, the agent can only be activated by the tenant that was specified in the export command.

Note: After completing these steps, the agent enters a 'pre-activated' state. While in this state, operations initiated by other Deep Security Managers or by the agent's local `dsa_control` utility do not work properly, by design. After the agent is fully activated, all normal operation resumes.

Note: After resetting or deactivating an agent, the Deep Security Manager certificate is cleared, so the above steps must be re-applied.

Replace the Deep Security Manager SSL certificate

Deep Security Manager creates a 10-year self-signed certificate for the connections between the Deep Security Manager console and users' web browsers. However, for added security, you can replace it with certificates from a trusted certificate authority (CA). (Such certificates are maintained after a Deep Security Manager upgrade.)

You will be working with the following two Deep Security Manager keystore files

- `<DSM_installation_folder>/jre/lib/security/cacerts`

The `cacerts` file contains the Deep Security Manager trusted public keys for the CA server, intermediate CA server and the Deep Security application server.

- `<DSM_installation_folder>/keystore`

The `keystore` file contains the certificate and private key for the Deep Security application server. To use your own certificate(s), you will need to import them to the `keystore` file.

To replace the SSL certificate in a **Windows** environment you will need to:

1. ["Create a new .keystore file and add your certificates to the cacerts file" on the next page](#)
2. ["Create a PKCS12 keychain file and import it into the new .keystore file" on page 1038](#)
3. ["Configure Deep Security Manager to use the new .keystore file" on page 1039](#)

To replace the SSL certificate in a **Linux** environment you will need to:

Trend Micro Deep Security On-Premise 11.3

1. ["Create a new .keystore file and add your certificates to the cacerts file" on page 1040](#)
2. ["Create a PKCS12 keychain file and import it into the new .keystore file" on page 1041](#)
3. ["Configure the Deep Security Manager to use the new .keystore file" on page 1042](#)

Note: If you have enabled FIPS mode (see ["FIPS 140-2 support" on page 1381](#)), you will need to disable FIPS mode before replacing the certificate and then re-enable FIPS mode when you're finished.

See your trusted certificates

Click **Administration > System Settings > Security > View Certificate List** to view a list of all security certificates accepted by Deep Security Manager.

Replace the SSL certificate in a Windows environment

Create a new .keystore file and add your certificates to the cacerts file

1. Create backups of the following files:

- `<DSM_installation_folder>/jre/lib/security/cacerts`
- `<DSM_installation_folder>/keystore`
- `<DSM_installation_folder>/configuration.properties`

2. Create a new `.keystore` file:

```
"%ProgramFiles%\Trend Micro\Deep Security Manager\jre\bin\keytool.exe" -genkey -alias tomcat -keyalg RSA -  
dname cn=<Deep Security Manager server hostname or FQDN> -storepass <keystore password>
```

3. Generate a certificate signing request file from the new `.keystore` file with the following commands:

Trend Micro Deep Security On-Premise 11.3

```
cd "%ProgramFiles%\Trend Micro\Deep Security Manager\jre\bin\"
```

```
keytool.exe -certreq -keyalg RSA -alias tomcat -keystore %userprofile%\keystore -storepass <keystore  
password> -file certrequest.csr
```

4. Send the `certrequest.csr` file to your CA for signing. Your CA will provide you with the following certificates:

Root CA certificate: `rootCA.cer`

Intermediate CA certificate: `intermediateCA.cer`

Application server certificate: `dsm.cer`

5. Move the certificates and the new `.keystore` file into the `%userprofile%\certs\` directory.
6. Import the certificates into the `cacerts` file with the following commands:

Note: The `cacerts` file requires a unique alias for each certificate. If you have multiple intermediate CA certificates, each one should have a unique alias (for example, `intermd1`, `intermd2`, `intermd3`). You must import the certificates in the same order as that determined by your CA.

```
cd "%ProgramFiles%\Trend Micro\Deep Security Manager\jre\bin\"
```

```
keytool.exe -import -alias root -trustcacerts -file %userprofile%\certs\rootCA.cer -keystore  
"%ProgramFiles%\Trend Micro\Deep Security Manager\jre\lib\security\cacerts" -storepass changeit
```

```
keytool.exe -import -alias intermd1 -trustcacerts -file %userprofile%\certs\intermediateCA.cer -keystore  
"%ProgramFiles%\Trend Micro\Deep Security Manager\jre\lib\security\cacerts" -storepass changeit
```

```
keytool.exe -import -alias tomcat -trustcacerts -file %userprofile%\certs\dsm.cer -keystore  
"%ProgramFiles%\Trend Micro\Deep Security Manager\jre\lib\security\cacerts" -storepass changeit
```


Create a PKCS12 keychain file and import it into the new .keystore file

To maintain the relationship between the certificates, you must create a PKCS12 keychain file and import the root CA, the intermediate CA and the application server certificates into it using [openssl](#).

1. Generate the private key from the new `.keystore` file with the following commands:

```
cd %ProgramFiles%\Trend Micro\Deep Security Manager\jre\bin\
```

```
keytool.exe -importkeystore -srckeystore %userprofile%\certs\.keystore -srcstorepass <keystore password> -  
deststoretype PKCS12 -destkeystore %userprofile%\certs\keystore.p12 -storepass <p12 keystore password>
```

```
cd %ProgramFiles(x86)%\GnuWin32\bin\
```

```
openssl pkcs12 -in %userprofile%\certs\keystore.p12 -passin pass:<above p12 keystore password you specified> -  
nocerts -out %userprofile%\certs\private.pem -passout pass:<private pem password>
```

```
openssl rsa -in %userprofile%\certs\private.pem -passin pass:<above private pem password> -out  
%userprofile%\certs\private.key
```

2. Create a certificate for the keychain file from the root and intermediate CA certificates:

Note: Combine the certificates in the order provided by your CA.

```
copy %userprofile%\certs\intermediateCA.cer+%userprofile%\certs\rootCA.cer  
%userprofile%\certs\CACertchain.cer
```

3. Create the PKCS12 keychain:

Note: You will need to create the PKCS12 keychain in a Linux environment. At the time of this article's publication, there is an openssl bug in Windows that will cause openssl to crash if you use the `-name` option. As Java requires each key have an

Trend Micro Deep Security On-Premise 11.3

alias, you will not be able to import the PKCS12 keychain into the new `.keystore` file without using this option. Create the PKCS12 keychain in a Linux environment with the below command.

```
openssl pkcs12 -export -in ~/certs/dsm.cer -inkey ~/certs/private.key -certfile ~/certs/CAcertchain.cer -out dsm.p12 -name tomcat -passout pass:<keychain password>
```

4. Import the PKCS12 keychain into the new `.keystore` file:

```
cd %ProgramFiles%\Trend Micro\Deep Security Manager\jre\bin\  
  
keytool.exe -importkeystore -srckeystore %userprofile%\certs\dsm.p12 -srcstoretype pkcs12 -srcalias tomcat -  
srcstorepass <keychain password> -destkeystore %userprofile%\certs\.keystore -storepass <keystore password>  
-destalias tomcat
```

Configure Deep Security Manager to use the new `.keystore` file

1. Overwrite the `.keystore` file in the Deep Security Manager installation directory with the new `.keystore` file:

Note: Only the default `.keystore` file is kept when you upgrade Deep Security Manager. We recommend that you replace the existing `.keystore` file.

2. Open the `configuration.properties` file, find the `keystorePass=` parameter, and replace the value with the one you specified for the `<keystore password>` in step 2 of the ["Create a new .keystore file and add your certificates to the cacerts file" on page 1036](#) procedure.
3. Restart the Deep Security Manager service.
4. Open the Deep Security Manager console with `https://< Deep Security Manager server hostname or FQDN>:4119` and make sure there is no certificate error message. The `<Deep Security Manager server hostname or FQDN>` should be the one used in step 2 of the ["Create a new .keystore file and add your certificates to the cacerts file" on page 1036](#) procedure.

Replace the SSL certificate in a Linux environment

Create a new `.keystore` file and add your certificates to the `cacerts` file

1. Create backups of the following files:

```
<DSM_installation_folder>/jre/lib/security/cacerts
```

```
<DSM_installation_folder>/.keystore
```

```
<DSM_installation_folder>/configuration.properties
```

2. Create a new `.keystore` file:

```
/opt/dsm/jre/bin/keytool -genkey -alias tomcat -keyalg RSA -dname cn=<Deep Security Manager server hostname or FQDN> -storepass <keystore password>
```

3. Generate a certificate signing request file from the new `.keystore` file:

```
/opt/dsm/jre/bin/keytool -certreq -keyalg RSA -alias tomcat -keystore ~/.keystore -storepass <keystore password> -file certrequest.csr
```

4. Send the `certrequest.csr` file to your CA for signing. Your CA will provide you with the following certificates:

Root CA certificate: `rootCA.cer`

Intermediate CA certificate: `intermediateCA.cer`

Application server certificate: `dsm.cer`

5. Move the certificates and the new `.keystore` file into the `~/certs` directory.
6. Import the certificates into the `cacerts` file with the following commands:

Trend Micro Deep Security On-Premise 11.3

Note: The `cacerts` file requires a unique alias for each certificate. If you have multiple intermediate CA certificates, each one should have a unique alias (for example, `intermd1`, `intermd2`, `intermd3`). You must import the certificates in the same order as that determined by your CA.

```
keytool -import -alias root -trustcacerts -file ~/certs/rootCA.cer -keystore  
/opt/dsm/jre/lib/security/cacerts -storepass changeit
```

```
keytool -import -alias intermd1 -trustcacerts -file ~/certs/intermediateCA.cer -keystore  
/opt/dsm/jre/lib/security/cacerts -storepass changeit
```

```
keytool -import -alias tomcat -trustcacerts -file ~/certs/dsm.cer -keystore  
/opt/dsm/jre/lib/security/cacerts -storepass changeit
```

Create a PKCS12 keychain file and import it into the new `.keystore` file

To maintain the relationship between the certificates, you must create a PKCS12 keychain file and import the root CA, the intermediate CA and the application server certificates into it using [openssl](#).

1. Generate the private key from the new `.keystore` file with the following commands:

```
/opt/dsm/jre/bin/keytool -importkeystore -srckeystore ~/certs/.keystore -srcstorepass <keystore password> -  
deststoretype PKCS12 -destkeystore ~/certs/keystore.p12 -storepass <p12 keystore password>
```

```
openssl rsa -in ~/certs/keystore.p12 -inform PKCS12 -passin pass:<above p12 keystore password you specified>  
-out ~/certs/private.key
```

2. Create a certificate for the keychain file from the root and intermediate CA certificates:

```
cat ~/certs/intermediateCA.cer ~/certs/rootCA.cer > ~/certs/CAcertchain.cer
```

Note: Combine the certificates in the order provided by your CA.

Trend Micro Deep Security On-Premise 11.3

3. Create the PKCS12 keychain:

```
openssl pkcs12 -export -in ~/certs/dsm.cer -inkey ~/certs/private.key -certfile ~/certs/CAcertchain.cer -out dsm.p12 -name tomcat -passout pass:<keychain password>
```

4. Import the PKCS12 keychain into the new `.keystore` file:

```
/opt/dsm/jre/bin/keytool -importkeystore -srckeystore ~/certs/dsm.p12 -srcstoretype pkcs12 -srcalias tomcat -srcstorepass <keychain password> -destkeystore ~/certs/.keystore -storepass <keystore password> -destalias tomcat
```

Configure the Deep Security Manager to use the new `.keystore` file

1. Overwrite the `.keystore` file in the Deep Security Manager installation directory with the new `.keystore` file:

```
cp ~/certs/.keystore /opt/dsm/.keystore
```

Note: Only the default `.keystore` file is kept when you upgrade Deep Security Manager. We recommend that you replace the existing `.keystore` file.

2. Open the `configuration.properties` file, find the `keystorePass=` parameter, and replace the value with the one you specified for the `<keystore password>` in step 2 of the ["Create a new .keystore file and add your certificates to the cacerts file" on page 1036](#) procedure.
3. Restart the Deep Security Manager service.
4. Open the Deep Security Manager console with `https://< Deep Security Manager server hostname or FQDN>:4119` and make sure there is no certificate error message. The `<Deep Security Manager server hostname or FQDN>` should be the one used in step 2 of the ["Create a new .keystore file and add your certificates to the cacerts file" on page 1036](#) procedure.

Encrypt communication between the Deep Security Manager and the database

Communication between the Deep Security Manager and the database is not encrypted by default. This is for performance reasons and because the channel between the manager and the database may already be secure (either they are running on the same computer or they are connected by crossover cable, a private network segment, or tunneling via IPSec).

However, if the communication channel between the Deep Security Manager and the database is not secure, you should encrypt the communications between them. Do this by editing the `dsm.properties` file located in `\\[Deep Security Manager install directory]\\webclient\\webapps\\ROOT\\WEB-INF\\`

The instructions vary depending on the database you are using:

- ["Microsoft SQL Server database \(Linux\)" below](#)
- ["Microsoft SQL Server \(Windows\)" on page 1045](#)
- ["Oracle Database" on page 1047](#)
- ["PostgreSQL" on page 1049](#)

Note: If you are running the Deep Security Manager in multi-node mode, these changes must be made on each node.

This section also provides information on ["Running an agent on the database server" on page 1049](#) and how to ["Disable encryption between the manager and database" on page 1049](#).

Encrypt communication between the manager and database

Microsoft SQL Server database (Linux)

1. Stop the Deep Security Manager service:

```
# service dsm_s stop
```

Trend Micro Deep Security On-Premise 11.3

2. Edit `/opt/dsm/webclient/webapps/ROOT/WEB-INF/dsm.properties` to add the following lines:

```
database.SqlServer.encrypt=true
```

```
database.SqlServer.trustServerCertificate=true
```


Note: If you upgraded from Deep Security 10.1 or a previous version, and your connection to the database uses named pipes as the transport, add the following line instead:

```
database.SqlServer.ssl=require
```


3. If you upgraded from Deep Security 10.1 or a previous version, and your connection to the database uses named pipes as the transport, under `/opt/dsm`, create a file named `dsm_s.vmoptions` that contains the following line:

```
-Djsse.enableCBCProtection=false
```

4. In the SQL Server Configuration Manager, enable "Force Encryption" in the protocol properties for the instance:



Trend Micro Deep Security On-Premise 11.3



5. Start the Deep Security Manager service:

```
# service dsm_s start
```

For additional information, see [Enable Encrypted Connections to the Database Engine](#) on the Microsoft MSDN site.

Microsoft SQL Server (Windows)

1. Stop the Deep Security Manager service.
2. Edit `\Program Files\Trend Micro\Deep Security Manager\webclient\webapps\ROOT\WEB-INF\dsm.properties` to add the following line:


```
database.SqlServer.encrypt=true  
database.SqlServer.trustServerCertificate=true
```

Note: If you upgraded from Deep Security 10.1 or a previous version, and your connection to the database uses named pipes as the transport, add the following line instead:


```
database.SqlServer.ssl=require
```


Trend Micro Deep Security On-Premise 11.3

3. If you upgraded from Deep Security 10.1 or a previous version, and your connection to the database uses named pipes as the transport, under `\Program Files\Trend Micro\Deep Security Manager`, create a file named `Deep Security Manager.vmoptions` that contains the following line:
`-Djsse.enableCBCProtection=false`
4. In the SQL Server Configuration Manager, enable "Force Encryption" in the protocol properties for the instance:



Trend Micro Deep Security On-Premise 11.3



5. Start the Deep Security Manager service.

For additional information, see [Enable Encrypted Connections to the Database Engine](#) on the Microsoft MSDN site.

Oracle Database

1. Add the following lines to `dsm.properties` (example):

```
database.Oracle.oracle.net.encryption_types_client=(AES256)
```

```
database.Oracle.oracle.net.encryption_client=REQUIRED
```

```
database.Oracle.oracle.net.crypto_checksum_types_client=(SHA1)
```

```
database.Oracle.oracle.net.crypto_checksum_client=REQUIRED
```

2. Save and close the file. ["Restart the Deep Security Manager" on page 979](#) service.

(All parameters prefixed with `database.Oracle.` will be passed to the Oracle driver.)

Possible values for the `encryption_types_client` are:

Trend Micro Deep Security On-Premise 11.3

- AES256
- AES192
- AES128
- 3DES168
- 3DES112
- DES56C
- DES40C
- RC4_256
- RC4_128
- RC4_40
- RC4_56

Possible values for `crypto_checksum_types_client` are:

- MD5
- SHA1

For additional options consult: https://docs.oracle.com/cd/B28359_01/java.111/b31224/clntsec.htm

Trend Micro Deep Security On-Premise 11.3

PostgreSQL

1. Turn on SSL in PostgreSQL. For information, on how to do this for an on-premise PostgreSQL database, see [Secure TCP/IP Connections with SSL](#). For an Amazon RDS for PostgreSQL, see [Using SSL with a PostgreSQL DB Instance](#).
2. Stop the Trend Micro Deep Security Manager service.
3. In the `dsm.properties` file, add the following line:
4. Restart the Trend Micro Deep Security Manager service.
5. To check that the manager is connecting using TLS, use the following query and check the SSL column:

```
database.PostgreSQL.connectionParameters=ssl=true
```

```
select a.client_addr, a.application_name, a.username, s.* from pg_stat_ssl s join pg_stat_activity a using  
(pid) where a.datname='<Deep Security database name>';
```

Running an agent on the database server

Encryption should be enabled if you are using an agent to protect the database. When you perform a security update, the Deep Security Manager stores new intrusion prevention rules in the database. The rule names themselves will almost certainly generate false positives as they get parsed by the agent if the data is not encrypted.

Disable encryption between the manager and database

If you have encrypted communication between Deep Security Manager and the database, you will need to disable the encryption before performing an upgrade to Deep Security Manager.

Trend Micro Deep Security On-Premise 11.3

Microsoft SQL Server database (Linux)

1. Stop the Deep Security Manager service:

```
# service dsm_s stop
```

2. Edit the `/opt/dsm/webclient/webapps/ROOT/WEB-INF/dsm.properties` to remove the following lines:

```
database.SqlServer.encrypt=true
```

```
database.SqlServer.trustServerCertificate=true
```

Note: If you upgraded from Deep Security 10.1 or a previous version, and your connection to the database uses named pipes as the transport, remove the following line instead:

```
database.SqlServer.ssl=require
```

3. In the SQL Server Configuration Manager, disable "Force Encryption" in the protocol properties for the instance:
4. Start the Deep Security Manager service:

```
# service dsm_s start
```

Microsoft SQL Server (Windows)

1. Stop the Deep Security Manager service.
2. Edit `\Program Files\Trend Micro\Deep Security Manager\webclient\webapps\ROOT\WEB-INF\dsm.properties` to remove the following lines:

```
database.SqlServer.encrypt=true
```

```
database.SqlServer.trustServerCertificate=true
```

Note: If you upgraded from Deep Security 10.1 or a previous version, and your connection to the database uses named pipes as the transport, remove the following line instead:

```
database.SqlServer.ssl=require
```

Trend Micro Deep Security On-Premise 11.3

3. In the SQL Server Configuration Manager, disable "Force Encryption" in the protocol properties for the instance:
4. Start the Deep Security Manager service.

Oracle Database

1. Remove the following lines from `dsm.properties` (example):

```
database.Oracle.oracle.net.encryption_types_client=(AES256)
database.Oracle.oracle.net.encryption_client=REQUIRED
database.Oracle.oracle.net.crypto_checksum_types_client=(SHA1)
database.Oracle.oracle.net.crypto_checksum_client=REQUIRED
```

2. Save and close the file. Stop and restart the Deep Security Manager service.

PostgreSQL

1. Stop the Trend Micro Deep Security Manager service.
2. In the `dsm.properties` file, remove the following line:

```
database.PostgreSQL.connectionParameters=ssl=true
```
3. Restart the Trend Micro Deep Security Manager service.

Change the Deep Security Manager database password

Your organization's security policies may require that you periodically change the password that Deep Security Manager uses to access the database.

- ["Change your Microsoft SQL Server password" on the next page](#)
- ["Change your Oracle password" on page 1053](#)

- ["Change your PostgreSQL password" on the next page](#)

Change your Microsoft SQL Server password

1. On Windows, stop the Trend Micro Deep Security Manager service on each of your Deep Security Manager instances.

On Linux, the command to stop the service is:

```
# service dsm_s stop
```

2. Use SQL Server Management Studio to change the SQL user password.
3. On each Deep Security Manager instance, modify the `/opt/dsm/webclient/webapps/ROOT/WEB-INF/dsm.properties` file to specify the new password. When you open this file, you will see an obfuscated value for the password, similar to this:

```
database.SqlServer.password=$1$4ec04f9550e0bf378fa6b1bc9698d0bbc59ac010bfef7ea1e6e47f30394800b1a9554fe206a3ee9ba5f774d205ba03bb86c91c0664c7f05f8c467e03e0d8ebbe
```

Overwrite that value with your new password (the new password will be obfuscated when the service restarts):

```
Database.SqlServer.password=NEW PASSWORD GOES HERE
```

4. On Windows, start the Trend Micro Deep Security Manager service on each of your Deep Security Manager instances.

On Linux, the command to start the service is:

```
# service dsm_s start
```

Change your Oracle password

1. On Windows, stop the Trend Micro Deep Security Manager service on each of your Deep Security Manager instances.

On Linux, the command to stop the service is:

```
# service dsm_s stop
```

2. Use your Oracle tools to change the password.
3. On each Deep Security Manager instance, modify the `/opt/dsm/webclient/webapps/ROOT/WEB-INF/dsm.properties` file to specify the new password. When you open this file, you will see an obfuscated value for the password, similar to this:

```
database.Oracle.password=$1$4ec04f9550e0bf378fa6b1bc9698d0bbc59ac010bfef7ea1e6e47f30394800b1a9554fe206a3ee9ba  
5f774d205ba03bb86c91c0664c7f05f8c467e03e0d8ebbe
```

Overwrite that value with your new password (the new password will be obfuscated when the service restarts):

```
Database.Oracle.password=NEW PASSWORD GOES HERE
```

4. On Windows, start the Trend Micro Deep Security Manager service on each of your Deep Security Manager instances.

On Linux, the command to start the service is:

```
# service dsm_s start
```

Change your PostgreSQL password

1. On Windows, stop the Trend Micro Deep Security Manager service on each of your Deep Security Manager instances.

On Linux, the command to stop the service is:

```
# service dsm_s stop
```


Trend Micro Deep Security On-Premise 11.3

2. Follow instructions from your PostgreSQL documentation to change the password.
3. On each Deep Security Manager instance, modify the `/opt/dsm/webclient/webapps/ROOT/WEB-INF/dsm.properties` file to specify the new password. When you open this file, you will see an obfuscated value for the password, similar to this:

```
database.PostgreSQL.password=$1$4ec04f9550e0bf378fa6b1bc9698d0bbc59ac010bfef7ea1e6e47f30394800b1a9554fe206a3e  
e9ba5f774d205ba03bb86c91c0664c7f05f8c467e03e0d8ebbe
```

Overwrite that value with your new password (the new password will be obfuscated when the service restarts):

```
Database.PostgreSQL.password=NEW PASSWORD GOES HERE
```

4. On Windows, start the Trend Micro Deep Security Manager service on each of your Deep Security Manager instances.

On Linux, the command to start the service is:

```
# service dsm_s start
```

Enable Content Security Policy and HTTP Public Key Pinning

Enabling Content Security Policy and HTTP Public Key Pinning in the Deep Security Manager can provide additional protection against cross-site scripting attacks and fraudulent certificates.

Note: In multi-tenant mode, the Content Security Policy and HTTP Public Key Pin Policy settings are only available to the primary tenant.

Add a content security policy or public key pin policy

1. Go to **Administration > System Settings > Security**.
2. Enter your Content Security Policy or HTTP Public Key Pin Policy directives in the corresponding field.

Note: Before you enable your policies, test them by selecting the **Report Only** option and verifying that the policy violation reports are correct.

Tip: You can enter individual policy directives on separate lines.

3. Click **Save** at the bottom of the page.

Reset your configuration

If you experience trouble while configuring your content security policy or public key pin policy and cannot correct it in the Deep Security Manager, SSH into the Deep Security Manager and run the corresponding commands to reset your configuration(s):

Content security policy

```
dsm_c -action changesetting -name settings.configuration.contentSecurityPolicy -value ""
```

```
dsm_c -action changesetting -name settings.configuration.contentSecurityPolicyReportOnly -value "true"
```

Public key pin policy

```
dsm_c -action changesetting -name settings.configuration.publicKeyPinPolicy -value ""
```

```
dsm_c -action changesetting -name settings.configuration.publicKeyPinPolicyReportOnly -value "true"
```

Enforce user password rules

You can specify password requirements for Deep Security Manager passwords, and other settings related to user authentication.

Specify password requirements

Note: For greater security, enforce stringent password requirements: minimum 8 characters, include both numbers and letters, use upper and lower case, include non-alphanumeric characters, and expire regularly.

Go to **Administration > System Settings > Security**. In the **User Security** section, you can change these settings:

- **Session idle timeout:** Specify the period of inactivity after which a user will be required to sign in again.
- **Maximum session duration:** Maximum length of time that a user can be signed into the Deep Security Manager before they'll be required to sign in again.
- **Number of incorrect sign-in attempts allowed (before lock out):** The number of times an individual user (i.e. with a specific username) can attempt to sign in with an incorrect password before they are locked out. Only a user with "Can Edit User Properties" rights can unlock a locked-out user (see ["Define roles for users" on page 1313](#)).

Note: If a user gets locked out for a particular reason (too many failed sign-in attempts, for example), and no user remains with the sufficient rights to unlock that account, please contact Trend Micro for assistance.

- **Number of concurrent sessions allowed per User:** Maximum number of simultaneous sessions allowed per user.

Note: A note about being signed in as two users at once: Remember that Firefox sets session cookies on a per-process basis, and not on a per-window basis. This means that if for some reason you want to be signed in as two users at the

same time, you will either have to use two different browsers (if one of them is Firefox), or sign in from two separate computers.

- **Action when concurrent session limit is exceeded:** Specifies what happens when a user reaches the maximum number of concurrent sessions.
- **User password expires:** Number of days that passwords are valid. You can also set passwords to never expire.
- **User password minimum length:** The minimum number of characters required in a password.
- **User password requires both letters and numbers:** Letters (a-z, A-Z) as well as numbers (0-9) must be used as part of the password.
- **User password requires both upper and lower case characters:** Upper and lower case characters must be used.
- **User password requires non-alphanumeric characters:** Passwords must include non-alphanumeric characters.
- **Send email when a user's password is about the expire:** Before a user's password expires, they will receive an email message. To use this feature, you must ["Configure SMTP settings for email notifications" on page 237](#).

Use another identity provider for sign-on

You can also configure Deep Security to use SAML single sign-on. For details, see ["Getting started with SAML single sign-on" on page 1341](#).

Add a message to the Deep Security Manager Sign In page

On the **Administration > System Settings > Security** page, use **Sign-In Page Message** to enter text that will be displayed on the Deep Security Manager's sign in page.

Present users with terms and conditions

You can configure Deep Security Manager so that users must agree to terms and conditions before they can sign in to the Deep Security Manager.

To enable this feature, select **User must agree to the terms and conditions** on the **Administration > System Settings > Security** page. In the two text boxes, enter a title and the list of terms and conditions that will be displayed when a user clicks the **Terms and Conditions** link on the Sign In page.

Other Security settings

The **Administration > System Settings > Security** page also enables you to:

- ["Manage trusted certificates" on page 364](#)
- ["Enable Content Security Policy and HTTP Public Key Pinning" on page 1054](#)

Set up multi-factor authentication

The Deep Security Manager allows you the option to use multi-factor authentication (MFA). MFA is a method of access control requiring more than a user name and password that is recommended as a best practice.

In this article:

- ["Enable multi-factor authentication" on the next page](#)
- ["Disable multi-factor authentication" on page 1061](#)


- ["Supported multi-factor authentication \(MFA\) applications" on page 1062](#)
- ["Troubleshooting MFA" on page 1063](#)

Enable multi-factor authentication

1. In Deep Security Manager, select **User Properties** from the menu under your user name in the upper-right corner.
2. On the **General** tab, click the **Enable MFA** button. This will open the **Enable Multi-Factor Authentication** wizard to guide you through the rest of the process.
3. The first screen of the wizard will remind you to install a compatible virtual MFA application, such as Google Authenticator. For more information, see ["Supported multi-factor authentication \(MFA\) applications" on page 1062](#) at the bottom of this article.
4. If your device supports scanning QR codes, you can use your camera to configure your MFA application and click **Next**.


Otherwise, you can choose **My device does not support scanning QR codes. Show secret key for manual time-based configuration**.

5. Enter the **Authentication Code** (without the space), for example: 228045.



Trend Micro Deep Security On-Premise 11.3

6. If the authorization code is correct, MFA will be enabled for your account and you will be required to enter a new MFA code each time you sign in.




The screenshot shows the Trend Micro Deep Security Sign In interface. At the top, there is a dark header with the Trend Micro logo on the left, the text "Deep Security" in the center, and a "Support" link on the right. Below the header, the title "Sign In" is centered. The form contains three input fields: "Username" with the value "MasterAdmin", "Password" with masked characters and a key icon on the right, and "Authentication Code" with the value "264387". A checkbox labeled "Use Multi-Factor Authentication" is checked. A "Sign In" button is located at the bottom right of the form.

Disable multi-factor authentication

1. In the Deep Security Manager, select **User Properties** from the menu under your user name in the upper-right corner.
2. On the **General** tab, click the **Disable MFA** button.

Trend Micro Deep Security On-Premise 11.3

- 3. Click **OK** on the confirmation screen to disable MFA.



- 4. Your user properties screen displays with a note to indicate the changes to MFA. Click **OK** to close the screen.

Supported multi-factor authentication (MFA) applications

The following smartphones and applications are actively supported for MFA. However, any application implementing an RFC 6238 compliant Time-base One-time Password Algorithm should work.

Smartphone	MFA App
Android	Google Authenticator , Duo
iPhone	Google Authenticator , Duo
Blackberry	Google Authenticator

Troubleshooting MFA

What if my MFA is enabled but not working?

The most common source of MFA login issues is caused by the time on your Deep Security Manager being out of sync with your device.

Follow the instructions below for your chosen operating system to make sure the time is properly synced:

If your Deep Security Manager is Linux:

Check that NTP is working correctly by entering `ntpstat` in the command line. To view the current system time and date, enter `date`.

If your Deep Security Manager is Windows:

Check that the Windows Time Service is working correctly. To view the current system time and date, enter `time` and `date` in the command line.

What if my MFA device is lost or stops working?

If your MFA device is lost, destroyed, or stops working, you'll need to have MFA disabled for your account in order to be able to sign in.

1. Get in touch with the person who provided you with your sign in credentials and ask them to follow the instructions in ["Disable multi-factor authentication" on page 1061](#). (You'll then be able to sign in with just your user name and password.)
2. After you've signed in, change your password.
3. Follow the instructions for ["Enable multi-factor authentication" on page 1059](#).

Trend Micro Deep Security On-Premise 11.3

If you are the only administrative user for a Deep Security as a Service account, contact technical support (sign in Deep Security as a Service, and click **Support** in the top right-hand corner) for assistance in temporarily deactivating MFA for your account.

Manage AWS regions

Add an Amazon Web Services region

If the Amazon Web Services (AWS) region hosting your EC2 resources does not appear when you try to add a cloud account using the **Add AWS Cloud Account** wizard, manually add the region.

On the server that is hosting Deep Security Manager, enter the command:

```
1. dsm_c -action addregion -region REGION -display DISPLAY -endpoint ENDPOINT
```

where the parameters are:

Parameter	Description	Example
REGION	The Amazon Web Services identifier for the region.	ca-east-1
DISPLAY	The display string to use for the region in the Add AWS Cloud Account wizard.	Canada East (Ottawa)
ENDPOINT	The fully-qualified domain name of the Amazon Elastic Compute Cloud (EC2) endpoint to use for the region.	ec2.ca-east-1.amazonaws.com

Note: If Deep Security Manager is running on a Linux server, you must run the command with `sudo` or use a superuser account such as root.

Trend Micro Deep Security On-Premise 11.3

2. If the specific AWS region requires that you import a trusted certificate (most don't), see ["Manage trusted certificates" on page 364](#).

Viewing your Amazon Web Services regions

You can view any AWS regions that you have added using the CLI.

On the server that is hosting Deep Security Manager, enter the command:

```
dsm_c -action listregions
```

Note: If Deep Security Manager is running on a Linux server, you must run the command with `sudo` or use a superuser account such as `root`.

Removing an Amazon Web Services region

You can delete any AWS regions that you have added using the CLI. Any existing cloud accounts for the region will continue to work unless you remove them, but administrators won't be able to create new cloud accounts for the region.

1. On the server that is hosting Deep Security Manager, enter the command:

```
dsm_c -action listregions
```

2. Find the identifier for the that you want to remove.
3. Enter the command:

```
dsm_c -action removerregion -region REGION
```

The `REGION` parameter is required.

Parameter	Description	Example
REGION	The Amazon Web Services identifier for the region.	ca-east-1

Note: If Deep Security Manager is running on a Linux server, you must run the command with `sudo` or use a superuser account such as `root`.

Configure alerts

Alerts are generated when Deep Security requires your attention, such as an administrator-issued command failing, or a hard disk running out of space. Deep Security includes a pre-defined set of alerts (for a list, see ["Predefined alerts" on page 1205](#)). Additionally, when you create protection module rules, you can configure them to generate alerts if they are triggered.

There are several ways to see which alerts have been triggered:

- They're displayed in the "Alert Status" dashboard widget in Deep Security Manager.
- They're displayed on the Alerts page in Deep Security Manager (see ["View alerts in Deep Security Manager" on the next page](#)).
- You can get an email notification when an alert is triggered (see ["Set up email notification for alerts" on page 1068](#).)
- You can generate alert reports (see ["Generate reports about alerts and other activity" on page 1071](#)).

Unlike security events and system events, alerts are not purged from the database after a period of time. Alerts remain until they are dismissed, either manually or automatically.

View alerts in Deep Security Manager

The **Alerts** page in Deep Security Manager displays all alerts that have been triggered, but not yet responded to. You can display alerts in a summary view that groups similar alerts together, or in list view, which lists all alerts individually. To switch between the two views, use the menu next to "Alerts" in the page's title. You can also sort the alerts by time or by severity.

In summary view, expanding an Alert panel (by clicking **Show Details**) displays all the computers (or users) that have generated that particular alert. Clicking the computer will display the computer's **Details** window. If an alert applies to more than five computers, an ellipsis ("...") appears after the fifth computer. Clicking the ellipsis displays the full list. Once you have taken the appropriate action to deal with an alert, you can dismiss the alert by selecting the check box next to the target of the alert and clicking **Dismiss**. (In list view, right-click the alert to see the list of options in the context menu.)

Alerts that can't be dismissed (like "Relay Update Service Not Available") will be dismissed automatically when the condition no longer exists.

Note: In cases where an alert condition occurs more than once on the same computer, the alert will show the timestamp of the first occurrence of the condition. If the alert is dismissed and the condition reoccurs, the timestamp of the first re-occurrence will be displayed.

Tip: Use the Computers filtering bar to view only alerts for computers in a particular computer group, with a particular policy, etc.

Unlike security events and system events, alerts are not purged from the database after a period of time. Alerts remain until they are dismissed, either manually or automatically.

Configure alert settings

To configure the settings for individual alerts, go to the **Alerts** page in Deep Security Manager and click **Configure Alerts**. This displays a list of all alerts. A green check mark next to an alert indicates that it is enabled. An alert will be triggered if the corresponding situation occurs, and it will appear in the Deep Security Manager.

You can select an alert and click **Properties** to change other settings for the alert, such as the severity level and email notification settings.

Set up email notification for alerts















































Deep Security Manager can send emails to specific users when selected alerts are triggered.

To enable email notifications:

1. Give Deep Security Manager access to an SMTP mail server (see ["Configure SMTP settings for email notifications" on page 237](#)).
2. Specify which alerts cause email notifications to be sent. For example, you can send email only for the most critical alerts. Most alerts send email notifications by default. (see ["Turn alert emails on or off" on the next page](#)).
3. Specify who will receive email notifications. You can configure user accounts so that they receive alert emails (see ["Configure an individual user to receive alert emails" on page 1071](#)). You can also configure alerts to specify the email account of a user or a distribution list. With this option, email is sent regardless of the configuration of the user accounts (see ["Configure recipients for all alert emails" on page 1071](#)).

Turn alert emails on or off

1. Go to the **Alerts** page and click **Configure Alerts** to display the list of alerts.

Alert Configuration No Grouping ▾		
Properties...		
ALERT ▾	SEVERITY	ON
 Abnormal Restart Detected	Warning	
 Activation Failed	Critical	
 Agent configuration package too large	Warning	
 Agent Installation Failed	Critical	
 Agent Upgrade Recommended (Incompatible with Appliance)	Warning	
 Agent/Appliance Upgrade Recommended	Warning	
 Agent/Appliance Upgrade Recommended (Incompatible Security U...	Warning	
 Agent/Appliance Upgrade Recommended (New Version Available)	Warning	
 Agent/Appliance Upgrade Required	Warning	
 An update to the Rules is available	Warning	
 Anti-Malware Alert	Warning	
 Anti-Malware Component Failure	Critical	
 Anti-Malware Component Update Failed	Warning	
 Anti-Malware Engine Offline	Critical	
 Anti-Malware protection is absent or out of date	Warning	
 Anti-Malware Quarantine Alert for Storage Limit	Warning	
 Application Control Engine Offline	Critical	
 Application Type Misconfiguration	Warning	
 Application Type Recommendation	Warning	
 Azure AD Application Need Renew	Critical	
 Azure AD Application Password Expires Soon	Warning	
 Azure Key Pair Expired	Critical	
 Azure Key Pair Expires Soon	Warning	
Item 1 to 100 of 104 < > >>		

Trend Micro Deep Security On-Premise 11.3

2. A green check mark next to an alert indicates that it is enabled. An alert will be triggered if the corresponding situation occurs, and appear in the Deep Security Manager GUI. If you also want to receive email about the alert, double-click on an alert to display its Properties window, then select at least one of the "Send Email" check boxes.

General

Alert Information

Alert: Anti-Malware Alert

Description: A Malware Scan Configuration that is configured for alerting has raised an event on one or more computers.

Dismissible: Yes

☒ On
When on, the alert will be raised when the conditions are met.

Options

Severity: Warning

☐ Alert for all rules (Regardless of rule settings)

☒ Send Email to notify when this alert is raised.

☒ Send Email to notify when conditions for this alert change (such as the # of items).

☒ Send Email to notify when this alert no longer exists.

☐ Off
When off, the alert will not be raised. Use this setting if you do not wish this condition to raise an alert.

OK Cancel Apply

Configure an individual user to receive alert emails

1. Go to **Administration > User Management > Users** and double-click a user account to display its Properties window.
2. On the **Contact Information** tab, enter an email address and select **Receive Alert Emails**.

Configure recipients for all alert emails

Note: All alert emails will be sent to this address or email distribution list, even if the recipients have not been set up in their user account properties to receive email notifications.

1. Go to **Administration > System Settings > Alerts**.
2. For **Alert Email Address - The email address to which all alert emails should be sent**, provide an email address or a distribution list email address.

Generate reports about alerts and other activity

Deep Security Manager produces reports in PDF or RTF formats. Most of the reports have configurable parameters such as date range or reporting by computer group. Parameter options will be disabled for reports to which they don't apply. You can set up a one-time report (see "[Set up a single report](#)" below) or set up a schedule to run a report on a regular basis (see "[Set up a recurring report](#)" on page 1075).

Set up a single report

1. In the Deep Security Manager, go to the **Events & Reports** tab and then in the left pane, click **Generate Reports**. Go to the **Single Report** tab.

Trend Micro Deep Security On-Premise 11.3

2. In the **Report** list, select the type of report that you want to generate. Depending on which protection modules you are using, these reports may be available:
 - **Alert Report:** List of the most common alerts
 - **Anti-Malware Report:** List of the top 25 infected computers
 - **Attack Report:** Summary table with analysis activity, divided by mode
 - **AWS Metered Billing Report:** Summary table of AWS Metered Billing consumption in hours per day by instance size and deployment type
 - **Computer Report:** Summary of each computer listed on the Computers tab
 - **DPI Rule Recommendation Report:** Intrusion prevention rule recommendations. This report can be run for only one security policy or computer at a time
 - **Firewall Report:** Record of firewall rule and stateful configuration activity
 - **Forensic Computer Audit Report:** Configuration of an agent on a computer
 - **Integrity Monitoring Baseline Report:** Baseline of the computer(s) at a particular time, showing Type, Key, and Fingerprinted Date
 - **Integrity Monitoring Detailed Change Report:** Details about the changes detected
 - **Integrity Monitoring Report:** Summary of the changes detected
 - **Intrusion Prevention Report:** Record of intrusion prevention rule activity
 - **Log Inspection Detailed Report:** Details of log data that has been collected
 - **Log Inspection Report:** Summary of log data that has been collected
 - **Recommendation Report:** Record of recommendation scan activity

Trend Micro Deep Security On-Premise 11.3

- **Security Module Usage Cumulative Report:** Current computer usage of protection modules, including a cumulative total and the total in blocks of 100
 - **Security Module Usage Report:** Current computer usage of protection modules
 - **Summary Report:** Consolidated summary of Deep Security activity
 - **Suspicious Application Activity Report:** Information about suspected malicious activity
 - **System Event Report:** Record of system (non-security) activity
 - **System Report:** Overview of computers, contacts, and users
 - **User and Contact Report:** Content and activity detail for users and contacts
 - **Web Reputation Report:** List of computers with the most web reputation events
3. Select the **Format** for the report, either PDF or RTF. (The "Security Module Usage Report" and "Security Module Usage Cumulative Report" are exceptions and are always output as CSV files.)
 4. You can also add an optional **Classification** to PDF or RTF reports: BLANK, TOP SECRET, SECRET, CONFIDENTIAL, FOR OFFICIAL USE ONLY, LAW ENFORCEMENT SENSITIVE (LES), LIMITED DISTRIBUTION, UNCLASSIFIED, INTERNAL USE ONLY.
 5. You can use the **Tag Filter** area to filter the report data using event tags (if you have selected a report that contains event data). Select **All** for all events, **Untagged** for only untagged events, or select **Tag(s)** and specify one or more tags to include only those events with your selected tag(s).
- Note:** If you apply multiple contradicting tags, the tags will counteract each other, rather than combine. For example, if you select "User Signed In" and "User Signed Out", there will be no system events.
6. You can use the **Time Filter** area to set a time filter for any period for which records exist. This is useful for security audits. Time filter options:

Trend Micro Deep Security On-Premise 11.3

- **Last 24 Hours:** Includes events from the past 24 hours, starting and ending at the top of the hour. For example if you generate a report on December 5th at 10:14am, you will get a report for events that occurred between December 4th at 10:00am and December 5th at 10:00am.
- **Last 7 Days:** Includes events from the past week. Weeks start and end at midnight (00:00). For example if you generate a report on December 5th at 10:14am, you will get a report for events that occurred between November 28th at 0:00am and December 5th at 0:00am.
- **Previous Month:** Includes events from the last full calendar month, starting and ending at midnight (00:00). For example, if you select this option on November 15, you will receive a report for events that occurred between midnight October 1 to midnight November 1.
- **Custom Range:** Enables you to specify your own date and time range for the report. In the report, the start time may be changed to midnight if the start date is more than two days ago.

- **Note:** Reports use data stored in counters. Counters are data aggregated periodically from Events. Counter data is aggregated on an hourly basis for the most recent three days. Data from the current hour is not included in reports. Data older than three days is stored in counters that are aggregated on a daily basis. For this reason, the time period covered by reports for the last three days can be specified at an hourly level of granularity, but beyond three days, the time period can only be specified on a daily level of granularity.

7. In the **Computer Filter** area, select the computers whose data will be included in the report.

- **All Computers:** Every computer in Deep Security Manager
- **My Computers:** If the signed in user has restricted access to computers based on their user role's rights settings, these are the computers the signed in User has view access right to.
- **In Group:** The computers in a Deep Security group.
- **Using Policy:** The computers using a specific protection Policy.

- **Computer:** A single computer.

Note: To generate a report on specific computers from multiple computer groups, create a user who has viewing rights only to the computers in question and then either create a scheduled task to regularly generate an "All Computers" report for that user or sign in as that user and run an "All Computers" report. Only the computers to which that user has viewing rights will be included in the report.


8. In the **Encryption** area, you can protect the report with the password of the currently signed in user or with a new password for this report only:
 - **Disable Report Password:** Report is not password protected.
 - **Use Current User's Report Password:** Use the current user's PDF report password. To view or modify the user's PDF report password, go to **Administration > User Management > Users > Properties > Settings > Reports**.
 - **Use Custom Report Password:** Create a one-time-only password for this report. The password does not have any complexity requirements.

Set up a recurring report

Recurring reports are scheduled tasks that periodically generate and distribute reports to any number of users and contacts.

To set up a recurring report, go to the **Events & Reports** tab and then in the left pane, click **Generate Reports**. Go to the **Recurring Reports** tab and click **New**. The New Scheduled Task wizard opens and will step you through the configuration process. Most of the options are identical to those for single reports, with the exception of Time Filter:

Trend Micro Deep Security On-Premise 11.3



Time Filter

Last Hour(s) ▼

Computer Filter

☒ All Computer

- Hour(s)
- Day(s)
- Week(s)
- Month(s)

- **Last [N] Hour(s):** When [N] is less than 60, the start and end times will be at the top of the specified hour. When [N] is more than 60, hourly data is not available for the beginning of the time range, so the start time in the report will be changed to midnight (00:00) of the start day.
- **Last [N] Day(s):** Includes data from midnight [N] days ago to midnight of the current day.
- **Last [N] Week(s):** Includes events from the last [N] weeks, starting and ending at midnight (00:00).
- **Last [N] Month(s):** Includes events from the last [N] full calendar month, starting and ending at midnight (00:00). For example, if you select "Last 1 Month(s)" on November 15, you will receive a report for events that occurred between midnight October 1 to midnight November 1.


Note: Reports use data stored in counters. Counters are data aggregated periodically from events. Counter data is aggregated on an hourly basis for the most recent three days. Data from the current hour is not included in reports. Data older than three days is stored in counters that are aggregated on a daily basis. For this reason, the time period covered by reports for the last three days can be specified at an hourly level of granularity, but beyond three days, the time period can only be specified on a daily level of granularity.

For more information on scheduled tasks, see the ["Schedule Deep Security to perform tasks" on page 418](#).

Customize the dashboard


The dashboard is the first page that appears after you log into Deep Security Manager.

Each user can customize the contents and layout of their dashboard. Deep Security Manager automatically saves your settings, and will remember your dashboard the next time that you log in. You can also configure the data's time period, and which computer's or computer group's data is displayed.



Date and time range


The dashboard can display data from either the last 24 hours, or the last seven days.



Computers and computer groups

Use the **Computer** menu to filter the displayed data to display only data from specific computers. For example, only those using the **Linux Server** security policy:


Trend Micro Deep Security On-Premise 11.3



Filter by tags

In Deep Security, a **Tag** is a unit of meta-data that you can apply to an Event in order to create an additional attribute for the Event that is not originally contained within the Event itself. Tags can be used to filter Events in order to simplify the task of Event monitoring and management. A typical use of tagging is to distinguish between Events that require action and those that have been investigated and found to be benign.


The data displayed in the Dashboard can be filtered by tags:



For more information on tagging see ["Apply tags to identify and group events" on page 1099](#).

Select dashboard widgets

Click **Add/Remove Widgets** to display the widget selection window and choose which widgets to display.



Note: If widgets take up extra space on the dashboard (more than 1x1), their dimensions are listed next to their names.

Trend Micro Deep Security On-Premise 11.3

The following widgets are available:

Monitoring:

- **Activity Overview:** Overview of activity, including the number of protected hours and size of database.
- **Alert History [2x1]:** Displays recent alert history, including the severity of alerts.
- **Alert Status:** Summary of alerts, including their age and severity.
- **Computer Status:** Summary of computers, including whether they are managed or unmanaged, and if there are any warnings or critical alerts.
- **Manager Node Status [3x1]:** Displays the name, CPU usage, memory, jobs, and system events on the manager node.
- **Security Update Status:** Displays the update status of computers, including the number of computers that are up-to-date, out-of-date, and unknown.
- **Tenant Database Usage:** Displays the top five tenants ranked by their database size.
- **Tenant Job Activity:** Displays the top five tenants ranked by their total number of jobs.
- **Tenant Protection Activity:** Displays the top five tenants ranked by the hours they've been protected.
- **Tenant Security Event Activity:** Displays the top five tenants ranked by their total number of security events.
- **Tenant Sign-In Activity:** Displays the top five tenants ranked by their sign-in activity.
- **Tenant System Event Activity:** Displays the top five tenants ranked by their total number of system events.
- **Tenants:** Displays tenant information, including the number of tenants and the amount of hours they've been protected.

System:

- **My Sign-in History:** Displays the last 50 sign-in attempts and whether or not they were successful.
- **My User Summary [2x1]:** Displays a summary of the user, including name, role, and sign-in information.
- **Software Updates:** Displays out-of-date computers.
- **System Event History [2x1]:** Displays recent system event history, including the number of events that are categorized as info, warning, or error.

Ransomware:

- **Ransomware Event History [3x1]:** Displays recent ransomware event history, including the event type.
- **Ransomware Status:** Displays the status of ransomware, including the number of ransomware events that occurred in the last 24 hours, the last 7 days, or the last 13 weeks.

Anti-Malware:

- **Anti-Malware Event History [2x1]:** Displays recent Anti-Malware event history, including the action taken for the events.
- **Anti-Malware Protection Status:** Displays a summary of Anti-Malware Protection status on computers, including whether they are protected, unprotected, or not capable of being protected.
- **Anti-Malware Status (Computers) [2x1]:** Displays the top five infected computers, including the amount of uncleanable files and the total number of files affected.
- **Anti-Malware Status (Malware) [2x1]:** Displays the top five detected malware, including their name, amount of uncleanable

Trend Micro Deep Security On-Premise 11.3

files, and number of times it was triggered.

- **Malware scan Status [2x1]:** Displays the top five appliances with incomplete scheduled malware scans.

Web Reputation:

- **Web Reputation Computer Activity:** Displays the top five computers with Web Reputation events, including the number of events.
- **Web Reputation Event History [2x1]:** Displays recent Web Reputation event history, including the events severity.
- **Web Reputation URL Activity:** Displays the top five URLs that triggered Web Reputation events, including the number of times they were accessed.

Firewall:

- **Firewall Activity (Detected):** Displays the top five reasons packets were detected, including the number of times.
- **Firewall Activity (Prevented):** Displays the top five reasons packets were prevented, including the number of times.
- **Firewall Computer Activity (Detected):** Displays the top five computers that generated detected Firewall events and the number of times they occurred.
- **Firewall Computer Activity (Prevented):** Displays the top five computers that generated prevented Firewall events and the number of times they occurred.
- **Firewall Event History [2x1]:** Displays recent Firewall event history, including if the events were detected or prevented.
- **Firewall IP Activity (Detected):** Displays the top five source IPs that generated detected Firewall events and the number of times they occurred.

Trend Micro Deep Security On-Premise 11.3

- **Firewall IP Activity (Prevented):** Displays the top five source IPs that generated prevented Firewall events and the number of times they occurred.
- **Firewall Port Activity (Detected):** Displays the top five destination ports for detected Firewall events and the number of times they occurred.
- **Firewall Port Activity (Prevented):** Displays the top five computers that generated prevented Firewall events and the number of times they occurred.
- **Reconnaissance Scan Activity:** Displays the top five detected reconnaissance scans, including the number of times they occurred.
- **Reconnaissance Scan Computers:** Displays the top five computers where reconnaissance scans occurred and the number of times they occurred.
- **Reconnaissance Scan History [2x1]:** Displays recent reconnaissance scan history, including the type of scan that occurred.

Intrusion Prevention:

- **Application Type Activity (Detected):** Displays the top five detected application types, including the number of times they were triggered.
- **Application Type Activity (Prevented):** Displays the top five prevented application types, including the number of times they were triggered.
- **Application Type Treemap (Detected) [2x2]:** Displays a map of detected application types. Hover over the boxes to display the severity of the events, the number of times it was triggered, and the percentage for each severity level.
- **Application Type Treemap (Prevented) [2x2]:** Displays a map of prevented application types. Hover over the boxes to display the severity of the events, the number of times it was triggered, and the percentage for each severity level.

Trend Micro Deep Security On-Premise 11.3

- **IPS Activity (Detected):** Displays the top five reasons Intrusion Prevention events were detected, including the number of times it was triggered.
- **IPS Activity (Prevented):** Displays the top five reasons Intrusion Prevention events were prevented, including the number of times it was triggered.
- **IPS Computer Activity (Detected):** Displays the top five computers with detected Intrusion Prevention events.
- **IPS Computer Activity (Prevented):** Displays the top five computers with prevented Intrusion Prevention events.
- **IPS Event History [2x1]:** Displays recent Intrusion Prevention event history, including if the events were detected or prevented.
- **IPS IP Activity (Detected):** Displays the top five source IPs that generated detected Intrusion Prevention events.
- **IPS IP Activity (Prevented):** Displays the top five source IPs that generated prevented Intrusion Prevention events.
- **Latest IPS Activity (Detected):** Displays the top five reasons Intrusion Prevention events were detected since the latest update.
- **Latest IPS Activity (Prevented):** Displays the top five reasons Intrusion Prevention events were prevented since the latest update.

Integrity Monitoring:

- **Integrity Monitoring Activity:** Displays the top five reasons Integrity Monitoring events occurred, including the number of times. In this case, the reason refers to the rule that was triggered.
- **Integrity Monitoring Computer Activity:** Displays the top five computers where Integrity Monitoring events occurred, including the number of events.
- **Integrity Monitoring Event History [2x1]:** Displays recent Integrity Monitoring event history, including the severity of events.

Trend Micro Deep Security On-Premise 11.3

- **Integrity Monitoring Key Activity:** Displays the top five keys for Integrity Monitoring events. The source of the key varies by Entity Set - for files and directories it's their path, whereas for ports it's their unique protocol, IP, port number, or tuple.

Log Inspection:

- **Log Inspection Activity:** Displays the top five reasons Integrity Monitoring events occurred, including the number. In this case, the reason refers to the rule that was triggered.
- **Log Inspection Computer Activity:** Displays the top five computers where Log Inspection events occurred, including the number of events.
- **Log Inspection Description Activity:** Displays the top five descriptions for Log Inspection events, including the number of times they occurred. The description refers to the event that was triggered.
- **Log Inspection Event History [2x1]:** Displays recent Log Inspection event history, including the severity of events.


Application Control:

- **Application Control Maintenance Mode Status [2x1]:** Displays the computers in maintenance mode, including their start and end time.

Change the layout

The selected widgets can be moved around the dashboard by dragging them by their title bar. Move the widget over an existing one and they will exchange places. (The widget that is about to be displaced will temporarily gray out.)

Trend Micro Deep Security On-Premise 11.3




Save and manage dashboard layouts

You can create multiple dashboard layouts and save them as separate tabs. Your Dashboard settings and layouts will not be visible to other Users after you sign out. To create a new Dashboard tab, click the "plus" symbol to the right of the last tab on the

Trend Micro Deep Security On-Premise 11.3

Dashboard:



Events in Deep Security

Deep Security Agents record when a protection module rule or condition is triggered (a "security event"). Agents and Deep Security Manager also records when administrative or system-related events occur (a "system event"), such as an administrator logging in, or agent software being upgraded. Event data is used to populate the various reports and graphs in Deep Security Manager.

To view events, go to **Events & Reports** in Deep Security Manager.

Where are event logs on the agent?

Location varies by the computer's operating system. On Windows, event logs are stored in this location:

```
C:\Program Data\Trend Micro\Deep Security Agent\Diag
```

On Linux, event logs are stored here:

```
/var/opt/ds_agent/diag
```

Note: These locations only contain standard-level logs; diagnostic debug-level logs have a different location. For performance reasons, debug-level logging is not enabled by default. You should only enable debug logging if diagnosing an issue with Trend Micro technical support, and make sure to disable debug logging when you are done. For more information, see [Enabling detailed logging on Deep Security Agent \(DSA\)](#).

When are events sent to the manager?

Most events that take place on a computer are sent to the Deep Security Manager during the next heartbeat operation except the following, which will be sent right away if communication settings allow relays/agents/appliances to initiate communication:

- Smart Scan Server is offline
- Smart Scan Server is back online
- Integrity Monitoring scan is complete
- Integrity Monitoring baseline created
- Unrecognized elements in an Integrity Monitoring Rule
- Elements of an Integrity Monitoring Rule are unsupported on the local platform
- Abnormal restart detected
- Low disk space warning
- Log Inspection offline

Trend Micro Deep Security On-Premise 11.3

- Log Inspection back online
- Reconnaissance scan detected (if the setting is enabled in **Computer or Policy editor**¹ > Firewall > Reconnaissance

How long are events stored?

Once collected by the Deep Security Manager, events are kept for a period of time, which is specified on the **Administration > System Settings > Storage** page. For details, see ["Log and event storage best practices" on page 1094](#).

System events

All the Deep Security system events are listed and can be configured on the **Administration > System Settings > System Events** tab. You can set whether to record the individual events and whether to forward them to a SIEM system. For details on system events, see ["System events" on page 1220](#).

Security events

Each protection module generates events when rules are triggered or other configuration conditions are met. Some of this security event generation is configurable. For information on specific types of security events, refer to these articles:

- ["Anti-malware events" on page 1251](#)
- ["View and restore identified malware" on page 713](#)

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

- [Application control events](#)
- "Firewall events" on page 1254
- "Integrity monitoring events" on page 1269
- "Intrusion prevention events" on page 1264
- "Log inspection events" on page 1272
- "Web reputation events" on page 1274

The firewall stateful configuration in effect on a computer can be modified to enable or disable TCP, UDP, and ICMP event logging. To edit the properties of a stateful firewall configuration, go to **Policies > Common Objects > Other > Firewall Stateful Configurations**. The logging options are in the **TCP**, **UDP**, and **ICMP** tabs of the firewall stateful configuration's **Properties** window. For more information about firewall events, see ["Firewall events" on page 1254](#).

See the events associated with a policy or computer

The **Policy editor**¹ and the **Computer editor**² both have **Events** tabs for each protection module. The policy editor displays events associated with the current policy. The computer editor displays events specific to the current computer.

View details about an event

To see details about an event, double-click it.

The **General** tab displays:

¹To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

²To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

- **Time:** The time according to the system clock on the computer hosting the Deep Security Manager.
- **Level:** The severity level of event that occurred. Event levels include **Info**, **Warning**, and **Error**.
- **Event ID:** The event type's unique identifier.
- **Event:** The name of the event (associated with the event ID.)
- **Target:** The system object associated with the event will be identified here. Clicking the object's identification will display the object's properties sheet.
- **Event Origin:** The Deep Security component from which the event originated.
- **Action Performed By:** If the event was initiated by a user, that user's username will be displayed here. Clicking the username will display the **User Properties** window.
- **Manager:** The hostname of the Deep Security Manager computer.
- **Description:** If appropriate, the specific details of what action was performed to trigger this event are displayed here.

The **Tags** tab displays tags that have been attached to this event. For more information on event tagging, see **Policies > Common Objects > Other > Tags**, and ["Apply tags to identify and group events" on page 1099](#).

Filter the list to search for an event

The **Period** toolbar lets you filter the list to display only those events that occurred within a specific timeframe.

The **Computers** toolbar lets you organize the display of event log entries by computer groups or computer policies.

Clicking **Search > Open Advanced Search** toggles the display of the advanced search bar.

Trend Micro Deep Security On-Premise 11.3

The screenshot shows the 'System Events' interface. At the top, there's a search bar with a magnifying glass icon and a dropdown arrow. Below it, the 'Period' section has a 'Custom Range' dropdown, 'From' and 'To' date and time pickers (July 1, 2016 11:17 to July 8, 2016 12:17). The 'Computers' section has an 'In Group' dropdown and a 'Computers' dropdown. The 'Search' section has a 'Level' dropdown, a 'Contains' dropdown, and a text input field with 'Base Policy'. To the right of the search bar is a blue vertical bar with a refresh icon and a plus sign. At the bottom, there are buttons for 'View', 'Export', 'Auto-Tagging...', and 'Columns...'.

Clicking the "Add Search Bar" button (+) to the right of the search bar will display an additional search bar so you can apply multiple parameters to your search. When you are ready, press the "Submit Request" button (at the right of the toolbars with the right-arrow on it).

Export events

You can export displayed events to a CSV file. (Paging is ignored, all pages will be exported.) You have the option of exporting the displayed list or the selected items.

Improve logging performance

Here are some suggestions to help maximize the performance of event collection:

- Reduce or disable log collection for computers that are not of interest.
- Consider reducing the logging of firewall rule activity by disabling some logging options in the firewall stateful configuration **Properties** window. For example, disabling the UDP logging will eliminate the "Unsolicited UDP" log entries.

Log and event storage best practices

Best practices for log and event data storage depend on the data compliance regulations you must meet, such as PCI and HIPAA. Also consider optimizing the use of your database. Storing too much data may affect database performance and size requirements.

If you're storing too much data in your database, these symptoms may occur:

- Error messages that systems may be experiencing loss of database activity
- Inability to import software updates
- General slow-down in Deep Security

To avoid those symptoms:

1. Store system events according to the compliance standard requirement.
2. Forward system and security events to external storage. See ["Forward Deep Security events to an external syslog or SIEM server" on page 1111](#). Then you can reduce how long events are kept in the local database.
3. Set thresholds in the log inspection module for event storage or event forwarding. **Severity clipping** allows you to send events to a Syslog server (if enabled) or to store events based on the severity level of the log inspection rule. See ["Configure log inspection event forwarding and storage" on page 892](#).

Default local storage settings are in the table below. To change these settings, go to **Administration > System Settings > Storage**. To delete software versions or older rule updates, go to **Administration > Updates > Software > Local** or **Administration > Updates > Security > Rules**.

Tip: To reduce database disk space usage, forward events to an external Syslog server or SIEM and reduce the local event retention time. Only keep counters locally.

Trend Micro Deep Security On-Premise 11.3

Data type settings	Data pruning default setting
Automatically delete Anti-Malware Events older than	7 Days
Automatically delete Web Reputation Events older than:	7 Days
Automatically delete Firewall Events older than:	7 Days
Automatically delete Intrusion Prevention Events older than:	7 Days
Automatically delete Integrity Monitoring Events older than:	7 Days
Automatically delete Log Inspection Events older than:	7 Days
Automatically delete Application Control Events older than:	7 Days
Automatically delete System Events older than:	53 Weeks
Automatically delete Server Logs older than:	7 Days
Automatically delete Counters older than:	13 Weeks
Number of older software versions to keep per platform:*	5
Number of older Rule Updates to keep:	10

* If multi-tenancy is enabled, this setting will not be available.

Note: If using a PostgreSQL database, old events might not be pruned immediately. PostgreSQL maintenance jobs periodically remove the old events' database partitions. Pruning will occur during the next scheduled job.

Trend Micro Deep Security On-Premise 11.3

Events are records of individual events. They populate the **Events** pages.

Counters are the number of times individual events have occurred. They populate the dashboard widgets (number of firewall events over the last 7 days, etc.) and the reports.

Server log files are from Deep Security Manager's web server. They don't include event logs from agents installed on your network's web servers.

Troubleshooting

During troubleshooting, it may be useful to increase the logging level and record more detailed events.

Increased logging can significantly increase disk space usage. Reduce the logging level again when you have finished troubleshooting.

1. Open the **Computer or Policy editor**¹.
2. Go to **Settings > General > Logging Level**.
3. Choose whether to inherit the logging override settings from the policy assigned to this computer (**Inherited**), to not override logging settings (**Do Not Override**), to log all triggered firewall rules (**Full Firewall Event Logging**), to log all triggered intrusion prevention rules (**Full Intrusion Prevention Event Logging**), or to log all triggered rules (**Full Logging**).
4. Click **Save**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Limit log file sizes

You can set the maximum size of each individual log file and how many of the most recent files are kept. Event log files will be written to until they reach the maximum allowed size, at which point a new file will be created and written to until it reaches the maximum size and so on. Once the maximum number of files is reached, the oldest will be deleted before a new file is created. Event log entries usually average around 200 bytes in size and so a 4 MB log file will hold about 20,000 log entries. How quickly your log files fill up depends on the number of rules in place.

1. Open the **Computer or Policy editor**¹ for the policy that you want to configure.
2. Go to **Settings > Advanced > Events**.
3. Configure these properties:
 - **Maximum size of the event log files (on Agent/Appliance):** Maximum size that the log file can reach before a new log file is created.
 - **Number of event log files to retain (on Agent/Appliance):** Maximum number of log files that will be kept. Once the maximum number of log files is reached, the oldest file will be deleted before a new one is created.
 - **Do Not Record Events with Source IP of:** This option is useful if you don't want Deep Security to make record events for traffic from certain trusted computers.

Note: The following three settings let you fine tune event aggregation. To save disk space, Deep Security Agents and Appliances will take multiple occurrences of identical events and aggregate them into a single entry and append a

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

"repeat count", a "first occurrence" timestamp, and a "last occurrence" timestamp. To aggregate event entries, Deep Security Agents and Appliances need to cache the entries in memory and then write them to disk.

- **Cache Size:** Determines how many types of events to track at any given time. Setting a value of 10 means that 10 types of events will be tracked (with a repeat count, first occurrence timestamp, and last occurrence timestamp). When a new type of event occurs, the oldest of the 10 aggregated events will be flushed from the cache and written to disk.
- **Cache Lifetime:** Determines how long to keep a record in the cache before flushing it to disk. If this value is 10 minutes and nothing else causes the record to be flushed, any record that reaches an age of 10 minutes gets flushed to disk.
- **Cache Stale time:** Determines how long to keep a record whose repeat count has not been recently incremented. If Cache Lifetime is 10 minutes and Cache Staletime is two minutes, an event record which has gone two minutes without being incremented will be flushed and written to disk.

Note: Regardless of the above settings, the cache is flushed whenever events are sent to the Deep Security Manager.

4. Click **Save**.

Event logging tips

- On computers that are less important, modify the amount of logs collected. This can be done in the **Events** and **Advanced Network Engine Options** areas on the **Computer or Policy editor**¹ > **Settings** > **Advanced** tab.
- Consider reducing the event logging of firewall rule activity by disabling the event logging options in the firewall stateful configuration. (For example, if you disable UDP logging, it will eliminate unsolicited UDP log entries.)

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

- For intrusion prevention rules, the best practice is to log only dropped packets. If you log packet modifications, it may cause too many log entries.
- For intrusion prevention rules, only include packet data (an option in the intrusion prevention rule's **Properties** window) when you are interested in examining the behavior of a specific attack. Packet data increases log sizes, so it shouldn't be used for everything.

Apply tags to identify and group events

Deep Security enables you to create tags that you can use to identify and sort events. For example, you might use tags to separate events that are benign from those that require further investigation. You can use tags to create customized dashboards and reports.

Although you can use event tagging for a variety of purposes, it was designed to ease the burden of event management. After you have analyzed an event and determined that it is benign, you can look through the event logs of the computer (and any other similarly configured and tasked computers) to find similar events and apply the same label to them, eliminating the need to analyze each event individually.

To view tags that are currently in use, go to **Policies > Common Objects > Other > Tags**.

Note: Tags do not alter the data in the events themselves, nor do they allow users to delete events. They are simply extra attributes provided by the manager.

You can perform tagging the following ways:

- ["Manual tagging" on the next page](#) lets you tag specific events as needed.

Trend Micro Deep Security On-Premise 11.3

- ["Auto-tagging" below](#) lets you use an existing event as the model for auto-tagging similar events on the same or other computers. You define the parameters for "similarity" by selecting which event attributes have to match the model event attributes for a tag to be applied.
- ["Trusted source tagging" on page 1103](#) lets you auto-tag integrity monitoring events based on their similarity to known-good events from a trusted source.

Note: An important difference between standard tagging and trusted source tagging is that "Run on Existing Events Now" can only be done with standard event tagging

Manual tagging

1. Go to **Events & Reports > Events** and select an event list. Right-click the event (or select multiple events and right-click) and select **Add Tag(s)**.
2. Type a name for the tag. Deep Security Manager will suggest matching names of existing tags as you type.
3. Select **The Selected [Event Type] Event**. Click **Next**.
4. Enter some optional comments and click **Finish**.

In the events list, you can see your tag in the **TAG(S)** column.

Auto-tagging

Deep Security Manager enables you to define rules that apply the same tag to similar events automatically. To view existing saved auto-tagging rules, click **Auto-Tagging** in the menu bar on any **Events** page. You can run saved rules manually from this page.

1. Go to **Events & Reports > Events** and select an event list. Right-click a representative event and select **Add Tag(s)**.
2. Type a name for the tag. Deep Security Manager will suggest matching names of existing tags as you type.

Trend Micro Deep Security On-Premise 11.3

3. Select **Apply to selected and similar [Event Type] Events** and click **Next**.
4. Select the computers where you want to auto-tag events and click **Next**. When applying tags to system events, this page is skipped.
5. Select which attributes will be examined to determine whether events are similar. For the most part, the attribute options are the same as the information displayed in the columns of the **Events** list pages. When you have selected which attributes to include in the event selection process, click **Next**.
6. On the next page, specify when events should be tagged. If you select **Existing [Event Type] Events**, you can select **Apply Auto-Tag Rule now** to apply the auto-tagging rule immediately, or **Apply Auto-Tag Rule in the background** to have it run in the background at a lower priority. Select **Future [Event Type] Events** to apply the auto-tagging rule to events that will happen in the future. You can also save the auto-tagging rule by selecting **Save Auto-Tag Rule** and optionally entering a name. Click **Next**.
7. Review the summary of your auto-tagging rule and click **Finish**.

In the events list, you can see that your original event and all similar events have been tagged

Note: Event tagging only occurs after events have been retrieved from the agents or appliances to the Deep Security Manager database.

Set the precedence for an auto-tagging rule

Once an auto-tagging rule is created, you can assign it a **Precedence** value. If the auto-tagging rule has been configured to run on future events, the rule's precedence determines the order in which all auto-tagging rules are applied to incoming events. For example, you can have a rule with a precedence value of "1" that tags all "User Signed In" events as "suspicious", and a rule with a precedence value of "2" that removes the "suspicious" tag from all "User Signed In" events where the target (user) is you. This will result in a "suspicious" tag being applied to all future "User Signed In" events where the user is not you.

Trend Micro Deep Security On-Premise 11.3

1. In an events list, click **Auto-Tagging** to display a list of saved auto-tagging rules.
2. Right-click an auto-tagging rule and select **Details**.
3. In the **General** tab, select a **Precedence** for the rule.

Auto-tagging log inspection events

Log inspection events are auto-tagged based upon their grouping in the log file structure. This simplifies and automates the processing of log inspection events within Deep Security Manager. You can use auto-tagging to automatically apply tags for the log inspection groups. Log inspection rules have groups associated with them in the rules. For example:

```
<rule id="18126" level="3">
  <if_sid>18101</if_sid>
  <id>^20158</id>
  <description>Remote access login success</description>
  <group>authentication_success,</group>
</rule>

<rule id="18127" level="8">
  <if_sid>18104</if_sid>
  <id>^646|^647</id>
  <description>Computer account changed/deleted</description>
  <group>account_changed,</group>
</rule>
```

Each group name has a "friendly" name string associated with it. In the above example, "authentication_success" would be "Authentication Success", "account_changed" would be "Account Changed". When this checkbox is set, the friendly names are automatically added as a tag for that event. If multiple rules trigger, multiple tags will be attached to the event.

Trusted source tagging

Note: Trusted source event tagging can only be used with events generated by the integrity monitoring protection module.

The integrity monitoring module allows you to monitor system components and associated attributes on a computer for changes. ("Changes" include creation and deletion as well as edits.) Among the components that you can monitor for changes are files, directories, groups, installed software, listening port numbers, processes, registry keys, and so on.

Trusted source event tagging is designed to reduce the number of events that need to be analyzed by automatically identifying events associated with authorized changes.

In addition to auto-tagging similar events, the integrity monitoring module allows you to tag events based on their similarity to events and data found on **Trusted Sources**. A trusted source can be either:

1. A **local trusted computer**,
2. The **Trend Micro Certified Safe Software Service**, or
3. A **trusted common baseline**, which is a set of file states collected from a group of computers.

Local trusted computer

A trusted computer is a computer that will be used as a "model" computer that you know will only generate benign or harmless events. A "target" computer is a computer that you are monitoring for unauthorized or unexpected changes. The auto-tagging rule examines events on target computers and compares them to events from the trusted computer. If any events match, they are tagged with the tag defined in the auto-tagging rule.

You can establish auto-tagging rules that compare events on protected computers to events on a trusted computer. For example, a planned rollout of a patch can be applied to the trusted computer. The events associated with the application of the patch can be

Trend Micro Deep Security On-Premise 11.3

tagged as "Patch X". Similar events raised on other systems can be auto-tagged and identified as acceptable changes and filtered out to reduce the number of events that need to be evaluated.

How does Deep Security determine whether an event on a target computer matches an event on a trusted source computer?

Integrity monitoring events contain information about transitions from one state to another. In other words, events contain *before* and *after* information. When comparing events, the auto-tagging engine will look for matching before and after states; if the two events share the same before and after states, the events are judged to be a match and a tag is applied to the second event. This also applies to creation and deletion events.

Note: Remember that when using a trusted computer for trusted source event tagging, the events being tagged are events generated by integrity monitoring rules. This means that the integrity monitoring rules that are generating events on the target computer must also be running on the trusted source computer.

Note: Trusted source computers must be scanned for malware before applying trusted source event tagging.

Note: Utilities that regularly make modifications to the content of files on a system (prelinking on Linux, for example) can interfere with trusted source event tagging.

Tag events based on a local trusted computer

1. Make sure the trusted computer is free of malware by running a full anti-malware scan.
2. Make sure the computer(s) on which you want to auto-tag events are running the same (or some of the same) integrity monitoring rules as the trusted source computer.
3. In Deep Security Manager, go to **Events & Reports > Integrity Monitoring Events** and click **Auto-Tagging** in the toolbar.
4. In the **Auto-Tag Rules (Integrity Monitoring Events)** window, click **New Trusted Source** to display the **Tag Wizard**.
5. Select **Local Trusted Computer** and click **Next**.

Trend Micro Deep Security On-Premise 11.3

6. From the list, select the computer that will be the trusted source and click **Next**.
7. Specify one or more tags to apply to events on target computers when they match events on this trusted source computer. Click **Next**.

Note: You can enter the text for a new tag or select from a list of existing tags.

8. Identify the target computers whose events will be matched to those of the trusted source. Click **Next**.
9. Optionally, give the rule a name and click **Finish**.

Tag events based on the Trend Micro Certified Safe Software Service

The Certified Safe Software Service is an allow list of known-good file signatures maintained by Trend Micro. This type of trusted source tagging will monitor target computers for file-related integrity monitoring events. When an event has been recorded, the file's signature (after the change) is compared to Trend Micro's list of known good file signatures. If a match is found, the event is tagged.

1. In Deep Security Manager, go to **Events & Reports > Integrity Monitoring Events** and click **Auto-Tagging** in the toolbar.
2. In the **Auto-Tag Rules (Integrity Monitoring Events)** window, click **New Trusted Source** to display the **Tag Wizard**.
3. Select **Certified Safe Software Service** and click **Next**.
4. Specify one or more tags to apply to events on target computers when they match the Certified Safe Software Service. Click **Next**.
5. Identify the target computers whose events will be matched to the Certified Safe Software Service. Click **Next**.
6. Optionally, give the rule a name and click **Finish**.

Tag events based on a trusted common baseline

The trusted common baseline method compares events within a group of computers. A group of computers is identified and a common baseline is generated based on the files and system states targeted by the integrity monitoring rules in effect on the computers in the group. When an integrity monitoring event occurs on a computer within the group, the signature of the file after the

Trend Micro Deep Security On-Premise 11.3

change is compared to the common baseline. If the file's new signature has a match elsewhere in the common baseline, a tag is applied to the event. In trusted computer method, the before and after states of an integrity monitoring event are compared, but in the trusted common baseline method, only the after state is compared.

Note: This method relies on all the computers in the common group being secure and free of malware. A full anti-malware scan should be run on all the computers in the group before the common baseline is generated.

Note: When an integrity monitoring baseline is generated for a computer, Deep Security will first check if that computer is part of a trusted common baseline group. If it is, it will include the computer's baseline data in the trusted common baseline for that group. For this reason, the trusted common baseline auto-tagging rule must be in place before any integrity monitoring rules have been applied to the computers in the common baseline group.

1. Make sure all the computers that will be in the group that will make up the trusted common baseline are free of malware by running a full anti-malware scan on them.
2. In Deep Security Manager, go to **Events & Reports > Integrity Monitoring Events** and click **Auto-Tagging** in the toolbar.
3. In the **Auto-Tag Rules (Integrity Monitoring Events)** window, click **New Trusted Source** to display the **Tag Wizard**.
4. Select **Trusted Common Baseline** and click **Next**.
5. Specify one or more tags to apply to events when they have a match in the trusted common baseline and click **Next**.
6. Identify the computers to include in the group used to generate the trusted common baseline. Click **Next**.
7. Optionally, give this rule a name and click **Finish**.

Delete a tag

1. In an events list, right-click the events with the tag you want to delete, and select **Remove Tag(s)**.
2. Select the tag you'd like to remove. Choose to remove the tag from **The Selected [Event Type] Event** or to **Apply to selected similar [Event Type] Events**. Click **Next**.
3. Enter some optional comments and click **Finish**.

Reduce the number of logged events

To reduce the number of events being logged, the Deep Security Manager can be configured to operate in one of several **Advanced Logging Policy** modes. These modes are set in the **Computer or Policy editor**¹ on the **Settings > Advanced > Advanced Network Engine Settings** area.

The following table lists the types of events that are ignored in four of the more complex Advanced Logging Policy modes:

Mode	Ignored Events
Stateful and Normalization Suppression	Out Of Connection Invalid Flags Invalid Sequence Invalid ACK Unsolicited UDP Unsolicited ICMP Out Of Allowed Policy Dropped Retransmit
Stateful, Normalization, and Frag Suppression	Out Of Connection Invalid Flags Invalid Sequence Invalid ACK Unsolicited UDP Unsolicited ICMP Out Of Allowed Policy CE Flags Invalid IP Invalid IP Datagram Length Fragmented

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

Mode	Ignored Events
	Invalid Fragment Offset First Fragment Too Small Fragment Out Of Bounds Fragment Offset Too Small IPv6 Packet Max Incoming Connections Max Outgoing Connections Max SYN Sent License Expired IP Version Unknown Invalid Packet Info Maximum ACK Retransmit Packet on Closed Connection Dropped Retransmit
Stateful, Frag, and Verifier Suppression	Out Of Connection Invalid Flags Invalid Sequence Invalid ACK Unsolicited UDP Unsolicited ICMP Out Of Allowed Policy CE Flags Invalid IP Invalid IP Datagram Length Fragmented Invalid Fragment Offset First Fragment Too Small Fragment Out Of Bounds Fragment Offset Too Small IPv6 Packet Max Incoming Connections Max Outgoing Connections Max SYN Sent License Expired

Trend Micro Deep Security On-Premise 11.3

Mode	Ignored Events
	IP Version Unknown Invalid Packet Info Invalid Data Offset No IP Header Unreadable Ethernet Header Undefined Same Source and Destination IP Invalid TCP Header Length Unreadable Protocol Header Unreadable IPv4 Header Unknown IP Version Maximum ACK Retransmit Packet on Closed Connection Dropped Retransmit
Tap Mode	Out Of Connection Invalid Flags Invalid Sequence Invalid ACK Maximum ACK Retransmit Packet on Closed Connection Dropped Retransmit

Rank events to quantify their importance

The ranking system provides a way to quantify the importance of events. By assigning "asset values" to computers, and assigning severity or risk values to rules, the importance ("rank") of an event is calculated by multiplying the two values together. This allows you to sort events by rank.

Web reputation event risk values

Risk values for web reputation events are linked to the three levels of risk used by the web reputation settings on the **General** tab of the **Web Reputation** page:

- **Dangerous:** corresponds to "A URL that has been confirmed as fraudulent or a known source of threats."
- **Highly Suspicious:** corresponds to "A URL that is suspected to be fraudulent or a known source of threats."
- **Suspicious:** corresponds to "A URL that is associated with spam or possibly compromised."
- **Blocked by Administrator:** A URL that is on the Web Reputation Service **Blocked** list.
- **Untested:** A URL that does not have a risk level.

Firewall rule severity values

Severity values for firewall rules are linked to their actions: Deny, Log Only, and Packet Rejection. (The latter refers to packets rejected because of a firewall stateful configuration setting.) Use this panel to edit the severity values which will be multiplied by a computer's asset value to determine the rank of a firewall event. (A firewall rule's actions can be viewed and edited in the rule's **Properties** window.)

Intrusion prevention rule severity values

Intrusion prevention rule severity values are linked to their severity levels: Critical, High, Medium, Low, or Error. Use this panel to edit their values which will be multiplied by a computer's asset value to determine the rank of an intrusion prevention event. An intrusion prevention rule's severity setting can be viewed in the rule's **Properties** window.

Integrity monitoring rule severity values

Integrity monitoring rule severity values are linked to their severity levels: Critical, High, Medium, or Low. Use this panel to edit their values which will be multiplied by a computer's asset value to determine the rank of an integrity monitoring event. An integrity monitoring rule's severity can be viewed in the rule's **Properties** window.

Log inspection rule severity values

Log inspection rule severity values are linked to their severity levels: Critical, High, Medium, or Low. Use this panel to edit their values which will be multiplied by a computer's asset value to determine the rank of a log inspection event. A log inspection rule's severity level can be viewed and edited from the rule's **Properties** window.

Asset values

Asset values are not associated with any of their other properties like intrusion prevention rules or firewall rules. Instead, asset values are properties in themselves. A computer's asset value can be viewed and edited from the computer's **Details** window. To simplify the process of assigning asset values, you can predefine some values that will appear in the **Asset Importance** list in the first page of the computer's **Details** window. To view existing predefined computer asset values, click the **View Asset Values** button in this panel. The **Asset Values** window displays the predefined settings. These values can be changed, and new ones can be created. (New settings will appear in the list for all computers.)

Forward Deep Security events to an external syslog or SIEM server

Note: If you want to publish events to Amazon SNS, see ["Access events with Amazon SNS" on page 1158](#).

Deep Security records two types of events:

Trend Micro Deep Security On-Premise 11.3

- **System events:** Administrative or system-related events such as an administrator logging in or agent software being upgraded. These events are generated by the Deep Security Manager.
- **Security events:** Recorded when a protection module rule or condition is triggered. These events are generated by the Deep Security Agent.

You can configure Deep Security to forward both types of events to an external syslog or Security Information and Event Management (SIEM) server. The content and format of the log messages differs slightly depending on whether they are sent by the Deep Security Manager or from an agent computer. For more information on the format, see ["Syslog message formats" on page 1119](#)

The two different types of events that can be forwarded have to be configured separately:

- ["Forward system events to a syslog or SIEM server" below](#)
- ["Forward security events to a syslog or SIEM server" on the next page](#)

Note: Deep Security still records all system and security events and display them in reports and graphs in the Deep Security Manager even if you enable event forwarding to a syslog or SIEM server.

Tip: If you are using Splunk as your syslog or SIEM server, consider using the [Deep Security app for Splunk](#), which provides dashboards and saved searches.

Forward system events to a syslog or SIEM server

1. Go to **Administration > System Settings > Event Forwarding**.
2. In the **Forward System Events to a remote computer (via Syslog) using configuration** list, select an existing syslog

configuration or select **New** and define a new configuration (for details, see ["Define a syslog configuration" on page 1115.](#))

3. Click **Save**.

Forward security events to a syslog or SIEM server

Security events are generated by the agents for each protection module. You have two options for forwarding these types of events:

- ["Forward security events directly from agent computers to a syslog or SIEM server" below](#)
- ["Forward security events from the agent computers via the Deep Security Manager" on the next page](#)

If you want to use TLS to send secure syslog messages, they must be sent via the Deep Security Manager. Syslog messages sent directly from the agent use UDP and are sent as clear text.

Note: The best practice is to use a high-level parent policy to propagate configuration settings throughout your environment. Like with other settings in Deep Security, you can override event forwarding settings for specific policies or computers (see ["Policies, inheritance, and overrides" on page 524.](#))

Forward security events directly from agent computers to a syslog or SIEM server

1. Go to **Policies**.
2. Double-click the policy you want to use for computers to forward events directly to a syslog server.
3. Go to **Settings > Event Forwarding**.
4. Under **Event Forwarding Frequency (from the Agent/Appliance)**, specify how often events are sent from the agent or appliance to the syslog or SIEM server.
5. Under **Event Forwarding Configuration (from the Agent/Appliance)**, specify the syslog configuration to use for each protection module. The options are:

Trend Micro Deep Security On-Premise 11.3

- Inherited (*configuration name*): The behavior is being inherited from a parent policy or computer
- None: Events are not forwarded
- *Syslog configuration name*: Events are forwarded to the specified syslog configuration. To see details about the configuration or edit it, click **Edit**. The configuration must have **Transport** set to "UDP" and **Agents should forward logs** set to "Directly to the Syslog server".
- New: Enables you to define a new configuration (for details, see ["Define a syslog configuration" on the next page.](#)) The configuration must have **Transport** set to "UDP" and **Agents should forward logs** set to "Directly to the Syslog server".

6. Click **Save**.

Forward security events from the agent computers via the Deep Security Manager

When you choose to forward events via the Deep Security Manager, the manager collects the events at every heartbeat (**Settings > General > Heartbeat Interval**.)

1. Go to **Policies**.
2. Double-click the policy you want to use for computers to forward security events via the Deep Security Manager.
3. Go to **Settings > Event Forwarding**.
4. Under **Event Forwarding Configuration (from the Agent/Appliance)**, specify the syslog configuration to use for each protection module. The options are:
 - Inherited (*configuration name*): The behavior is being inherited from a parent policy or computer
 - None: Events are not forwarded
 - *Syslog configuration name*: Events are forwarded to the specified syslog configuration. To see details about the configuration or edit it, click **Edit**. The configuration must have **Agents should forward logs** set to "Via the Deep Security Manager".

Trend Micro Deep Security On-Premise 11.3

- **New:** Enables you to define a new configuration (for details, see ["Define a syslog configuration" below.](#)) The configuration must have **Agents should forward logs** set to "Via the Deep Security Manager".

5. Click **Save**.

Define a syslog configuration

You can define a syslog configuration and assign it to system events, security events, or both. You can define as many syslog configurations as you need.

To see any existing syslog configurations, go to **Policies > Common Objects > Other > Syslog Configurations**. From that page, you can add or edit configurations. You can also import and export configurations.

Note: If you configured syslog or SIEM server settings prior to January 26th, 2017, they have been converted to syslog configurations and appear on the **Syslog Configurations** page. Any identical configurations are merged together.

To add a new configuration:

1. Click **New > New Configuration**.
2. On the **General** tab:
 - **Name:** Meaningful name that identifies the configuration. The name must be unique.
 - **Description:** Optional description of the configuration.
 - **Log Source Identifier:** When syslog messages are sent to a syslog or SIEM server, they include a reported hostname that identifies the source of the messages. If you leave the Log Source Identifier setting empty and you are running a multi-node Deep Security Manager, each node sends a different hostname as the identifier. If you want to use the same identifier for each manager node (to treat the syslog messages as if they all come from the same source), you can specify

a common Log Source Identifier. Note that syslog messages sent directly from the Deep Security Agent to a syslog or SIEM server use the reported computer hostname and cannot use the Log Source Identifier instead.

- **Server Name:** Hostname or IP address to which events should be sent. The syslog or SIEM server and any routers, firewalls, and security groups must allow inbound traffic from the Deep Security Manager for event forwarding to work.

Note: If you are going to forward events directly from the Deep Security Agent, traffic from the agent must also be allowed.

- **Server Port:** UDP or TLS port to which events should be sent. For UDP, this is usually port 514. For TLS, it's usually port 6514. For more information, see ["Port numbers, URLs, and IP addresses" on page 111](#).
- **Event Format:** The format of the log message. For more information on formats, see ["Syslog message formats" on page 1119](#)

Note: The LEEF format is only supported for messages sent from the Deep Security Manager. Basic Syslog format is not supported by the anti-malware, web reputation, integrity monitoring, and application control protection modules.

- **Transport:** UDP or TLS. Security events sent directly from the agent must be sent with UDP. System events and security events sent via the manager can be sent via UDP or TLS (which is the newer version of SSL). If you select UDP, the events are sent in clear text. If you select TLS, the events are sent encrypted over TLS 1.2, 1.1, or 1.0. (TLS is not supported as a transport mode when operating in FIPS mode. See ["FIPS 140-2 support" on page 1381](#).) Syslog messages are limited to 64 KB if they are transferred over UDP. If the message is longer, data may be truncated.
- **Include time zone in events:** This option is available when agents forward logs via the Deep Security Manager. It is not available when agents forward events directly to a syslog server. When this option is selected, full date and time zone information is added to the event. Example: 2018-09-14T01:02:17.123+04:00. When it's not selected, only the month, day, and time are added (no time zone or year). Example: Sep 14 01:02:17.

Trend Micro Deep Security On-Premise 11.3

- **Facility:** The type of program or process that is logging the message.
- **Agents should forward logs:** This setting applies when forwarding security events. You can choose to send the syslog messages **Directly to the Syslog server** or **Via the Deep Security Manager**.

Note: When either LEEF or TLS is selected, this option is hard-coded to **Via the Deep Security Manager**.

3. If you selected TLS as the transport mechanism, perform these additional steps:

- If your syslog or SIEM server is configured to require TLS client authentication, you'll need to provide a TLS certificate for the secure syslog configuration. This certificate will be used for all connections between a Deep Security Manager and the SIEM or syslog server. To provide the certificate, click the **Credentials** tab and supply the Deep Security Manager certificate's **Private Key**, **Certificate**, and **Certificate Chain** (if required) in PEM format (also known as base64 encoded format). The syslog or SIEM server may or may not accept a self-signed certificate. Consult its documentation for details.
- Click **Test Connection**.
- An **Accept Server Certificate?** message appears if the syslog or SIEM server certificate is not yet known to Deep Security Manager. The message shows the contents of the certificate. Review it and click **OK**. The certificate is added to the manager's Deep Security list, under **Administration > System Settings > Security**. Deep Security Manager accepts self-signed certificates as long as they pass standard validation such as expiry checks.
- Click **Test Connection** again to establish a TLS connection using the certificate you just accepted. (See [this article on the TLS handshake](#) for details on how the TLS session is established.) You see a pass or fail message at the top of the manager.

Troubleshooting

"Failed to Send Syslog Message" alert

If there is a problem with your syslog configuration, you might see this alert:

```
Failed to Send Syslog Message
The Deep Security Manager was unable to forward messages to a Syslog Server.
Unable to forward messages to a Syslog Server
```

The alert also contains a link to the affected syslog configuration. Click the link to open the configuration and then click the **Test Connection** button to get more troubleshooting information. An indication that the connection was successful or an error message that provides more detailed information on what's causing the problem is displayed.

Can't edit syslog configurations

If you can see the syslog configurations but can't edit them, the role associated with your account might not have the appropriate rights. An administrator who is able to configure roles can check your rights by going to **Administration > User Management**. Then select your name and click **Properties**. On the **Other Rights** tab, the **Syslog Configurations** setting controls your ability to edit syslog configurations. For more information on users and roles, see ["Create and manage users" on page 1306](#).

Can't see the syslog configuration sections of Deep Security Manager

If you can't see the syslog configurations UI in Deep Security Manager, you may be a tenant in a multi-tenant environment where the primary tenant has disabled this feature or configured it for you.

Trend Micro Deep Security On-Premise 11.3

Syslog not transferred due to an expired certificate

If you set up TLS client authentication and the certificate expires, syslog messages are not sent to the syslog server. To fix this problem, obtain a new certificate, update the syslog configuration with the new certificate values, test the connection, and then save the configuration.

Syslog not delivered due to an expired or changed server certificate

If the syslog server's certificate has expired or changed, open the syslog configuration and click the **Test Connection** button. You are prompted to accept the new certificate.

Syslog or SIEM servers used for testing

Deep Security has been tested with the Enterprise version of these products:

- Splunk 6.5.1
- IBM QRadar 7.2.8 Patch 3 (with the TLS protocol patch, PROTOCOL-TLSSyslog-7.2-20170104125004.noarch)
- HP ArcSight 7.2.2 (with a TLS Syslog-NG connector created using the ArcSight-7.2.2.7742.0-Connector tool)

Syslog message formats

Common Event Format (CEF) and Log Event Extended Format (LEEF) log message formats are slightly different. For example, the "Source User" column in the GUI corresponds to a field named "suser" in CEF; in LEEF, the same field is named "usrName" instead. Log message fields also vary by whether the event originated on the agent or Deep Security Manager and which feature created the log message.

Trend Micro Deep Security On-Premise 11.3

Note: If your syslog messages are being truncated, it may be because you're using User Datagram Protocol (UDP). To prevent truncation, transfer your syslog messages over Transport Layer Security (TLS) instead. For instructions on switching to TLS, see ["Define a syslog configuration" on page 1115](#).

Note: Basic syslog format is not supported by the anti-malware, web reputation, integrity monitoring, and application control protection modules.

If the syslog messages are sent from the Manager, there are several differences. In order to preserve the original Deep Security Agent hostname (the source of the event), a new extension ("dvc" or "dvchost") is present. "dvc" is used if the hostname is an IPv4 address; "dvchost" is used for hostnames and IPv6 addresses. Additionally, the extension "TrendMicroDsTags" is used if the events are tagged (This applies only to auto-tagging with run on future, since events are forwarded via syslog only as they are collected by the manager). The product for logs relayed through the Manager will still read "Deep Security Agent"; however, the product version is the version of the Manager.

CEF syslog message format

All CEF events include dvc=IPv4 Address or dvchost=Hostname (or the IPv6 address) for the purposes of determining the original Deep Security Agent source of the event. This extension is important for events sent from a virtual appliance or the manager, since in this case the syslog sender of the message is not the originator of the event.

Base CEF format: CEF:Version|Device Vendor|Device Product|Device Version|Signature ID|Name|Severity|Extension

To determine whether the log entry comes from the Deep Security Manager or a Deep Security Agent, look at the "Device Product" field:

Sample CEF Log Entry: Jan 18 11:07:53 dsmhost CEF:0|Trend Micro|**Deep Security Manager**|<DSM version>|600|Administrator Signed In|4|suser=Master...

Trend Micro Deep Security On-Premise 11.3

Note: Events that occur on a VM that is protected by a virtual appliance, but that don't have an in-guest agent, will still be identified as coming from an agent.

To further determine what kind of rule triggered the event, look at the "Signature ID" and "Name" fields:

Sample Log Entry: Mar 19 15:19:15 root CEF:0|Trend Micro|Deep Security Agent|<DSA version>|123|Out Of Allowed Policy|5|cn1=1...

The "Signature ID" value indicates what kind of event has been triggered:

Signature IDs	Description
10	Custom intrusion prevention (IPS) rule
20	Log-only firewall rule
21	Deny firewall rule
30	Custom integrity monitoring rule
40	Custom log inspection rule
100-7499	System events
100-199	Policy firewall rule and firewall stateful configuration
200-299	IPS internal errors
300-399	SSL/TLS events
500-899	IPS normalization
1,000,000-1,999,999	Trend Micro IPS rule. The signature ID is the same as the IPS rule ID.
2,000,000-2,999,999	Integrity monitoring rule. The signature ID is the integrity monitoring rule ID + 1,000,000.
3,000,000-3,999,999	Log inspection rule. The signature ID is the log inspection rule ID + 2,000,000.
4,000,000-4,999,999	Anti-malware events. Currently, only these signature IDs are used: <ul style="list-style-type: none">• 4,000,000• 4,000,001• 4,000,002• 4,000,003

Trend Micro Deep Security On-Premise 11.3

Signature IDs	Description
	<ul style="list-style-type: none">• 4,000,010• 4,000,011• 4,000,012• 4,000,013• 4,000,020• 4,000,030
5,000,000-5,999,999	Web reputation events. Currently, only these signature IDs are used: <ul style="list-style-type: none">• 5,000,000• 5,000,001
6,000,000-6,999,999	Application control events. Currently, only these signature IDs are used: <ul style="list-style-type: none">• 6,001,100• 6,001,200• 6,002,100• 6,002,200

Note: Log entries don't always have all CEF extensions described in the event log format tables below. CEF extensions also may not be always in the same order. If you are using regular expressions (regex) to parse the entries, make sure your expressions do not depend on each key-value pair to exist, or to be in a specific order.

Trend Micro Deep Security On-Premise 11.3

Note: Syslog messages are limited to 64 KB by the syslog protocol specification. If the message is longer, data may be truncated. The basic syslog format is limited to 1 KB.

LEEF 2.0 syslog message format

Base LEEF 2.0 format: LEEF:2.0|Vendor|Product|Version|EventID|(Delimiter Character, optional if the Delimiter Character is tab)|Extension

Sample LEEF 2.0 Log Entry (DSM System Event Log Sample): LEEF:2.0|Trend Micro|Deep Security Manager|<DSA version>|192|cat=System name=Alert Ended desc=Alert: CPU Warning Threshold Exceeded\nSubject: 10.201.114.164\nSeverity: Warning sev=3 src=10.201.114.164 usrName=System msg=Alert: CPUWarning Threshold Exceeded\nSubject: 10.201.114.164\nSeverity:Warning TrendMicroDsTenant=Primary

Events originating in the Manager

System event log format

Base CEF Format: CEF:Version|Device Vendor|Device Product|Device Version|Signature ID|Name|Severity|Extension

Sample CEF Log Entry: CEF:0|Trend Micro|Deep Security Manager|<DSM version>|600|User Signed In|3|src=10.52.116.160
suser=admin target=admin msg=User signed in from 2001:db8::5

Base LEEF 2.0 format: LEEF:2.0|Vendor|Product|Version|EventID|(Delimiter Character, optional if the Delimiter Character is tab)|Extension

Sample LEEF 2.0 Log Entry: LEEF:2.0|Trend Micro|Deep Security Manager|<DSA version>|192|cat=System name=Alert Ended desc=Alert: CPU Warning Threshold Exceeded\nSubject: 10.201.114.164\nSeverity: Warning sev=3 src=10.201.114.164
usrName=System msg=Alert: CPU Warning Threshold Exceeded\nSubject: 10.201.114.164\nSeverity: Warning
TrendMicroDsTenant=Primary

Trend Micro Deep Security On-Premise 11.3

Note: LEEF format uses a reserved "sev" key to show severity and "name" for the Name value.

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
src	src	Source IP Address	Deep Security Manager IP address.	src=10.52.116.23
suser	usrName	Source User	Deep Security Manager administrator's account.	suser=MasterAdmin
target	target	Target Entity	The subject of the event. It can be the administrator account logged into Deep Security Manager, or a computer.	target=MasterAdmin target=server01
targetID	targetID	Target Entity ID	The identifier added in the manager.	targetID=1
targetType	targetType	Target Entity Type	The event target entity type.	targetType=Host
msg	msg	Details	Details of the system event. May contain a verbose description of the event.	msg=User password incorrect for username MasterAdmin on an attempt to sign in from 127.0.0.1 msg=A Scan for Recommendations on computer (localhost) has completed...
TrendMicroDsTags	TrendMicroDsTags	Event Tags	Deep Security event tags assigned to the event	TrendMicroDsTags=suspicious
TrendMicroDsTenant	TrendMicroDsTenant	Tenant Name	Deep Security tenant	TrendMicroDsTenant=Primary
TrendMicroDsTenantId	TrendMicroDsTenantId	Tenant ID	Deep Security tenant ID	TrendMicroDsTenantId=0
None	sev	Severity	The severity of the event. 1 is the least severe; 10 is the most severe.	sev=3
None	cat	Category	Event category	cat=System
None	name	Name	Event name	name=Alert Ended
None	desc	Description	Event description	desc:Alert: CPU Warning Threshold Exceeded

Events originating in the agent

Anti-malware event format

Base CEF format: CEF:Version|Device Vendor|Device Product|Device Version|Signature ID|Name|Severity|Extension

Trend Micro Deep Security On-Premise 11.3

Sample CEF Log Entry: CEF:0|Trend Micro|Deep Security Agent|<DSA version>|4000000|Eicar_test_file|6|cn1=1 cn1Label=Host ID dvchost=hostname cn2=205 cn2Label=Quarantine File Size cs6=ContainerImageName | ContainerName | ContainerID cs6Label=Container filePath=C:\\Users\\trend\\Desktop\\leicar.exe act=Delete msg=Realtime TrendMicroDsMalwareTarget=N/A TrendMicroDsMalwareTargetType=N/TrendMicroDsFileMD5=44D88612FEA8A8F36DE82E1278ABB02F TrendMicroDsFileSHA1=3395856CE81F2B7382DEE72602F798B642F14140 TrendMicroDsFileSHA256=275A021BBFB6489E54D471899F7DB9D1663FC695EC2FE2A2C4538AABF651FD0F TrendMicroDsDetectionConfidence=95 TrendMicroDsRelevantDetectionNames=Ransom_CERBER.BZC;Ransom_CERBER.C;Ransom_CRYPNISCA.SM

Base LEEF 2.0 format: LEEF:2.0|Vendor|Product|Version|EventID|(Delimiter Character, optional if the Delimiter Character is tab)|Extension

Sample LEEF Log Entry: LEEF: 2.0|Trend Micro|Deep Security Agent|<DSA version>|4000030|cat=Anti-Malware name=HEU_AEGIS_CRYPT desc=HEU_AEGIS_CRYPT sev=6 cn1=241 cn1Label=Host ID dvc=10.0.0.1 TrendMicroDsTags=FS TrendMicroDsTenant=Primary TrendMicroDsTenantId=0 filePath=C:\\Windows\\System32\\virus.exe act=Terminate msg=Realtime TrendMicroDsMalwareTarget=Multiple TrendMicroDsMalwareTargetType=File System TrendMicroDsFileMD5=1947A1BC0982C5871FA3768CD025453E#011 TrendMicroDsFileSHA1=5AD084DDCD8F80FBF2EE3F0E4F812E812DEE60C1#011 TrendMicroDsFileSHA256=25F231556700749F8F0394CAABDED83C2882317669DA2C01299B45173482FA6E TrendMicroDsDetectionConfidence=95 TrendMicroDsRelevantDetectionNames=Ransom_CERBER.BZC;Ransom_CERBER.C;Ransom_CRYPNISCA.SM

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
cn1	cn1	Host Identifier	The agent computer's internal unique identifier.	cn1=1

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
cn1Label	cn1Label	Host ID	The name label for the field cn1.	cn1Label=Host ID
cn2	cn2	File Size	The size of the quarantine file. This extension is included only when the "direct forward" from agent /appliance is selected.	cn2=100
cn2Label	cn2Label	File Size	The name label for the field cn2.	cn2Label=Quarantine File Size
cs3	cs3	Infected Resource	The path of the spyware item. This field is only for spyware detection events.	cs3=C:\test\atse_samples\SPYW_Test_Virus.exe
cs3Label	cs3Label	Infected Resource	The name label for the field cs3. This field is only for spyware detection events.	cs3Label=Infected Resource
cs4	cs4	Resource Type	Resource Type	cs4=10

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			values: 10=Files and Directories 11=System Registry 12=Internet Cookies 13=Internet URL Shortcut 14=Programs in Memory 15=Program Startup Areas 16=Browser Helper Object	

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			17=Layere d Service Provider	
			18=Hosts File	
			19=Windo ws Policy Settings	
			20=Browse r	
			23=Windo ws Shell Setting	
			24=IE Downloade d Program Files	
			25=Add/Re move Programs	

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			26=Services other=Other For example, if there's a spyware file named spy.exe that creates a registry run key to keep its persistence after system reboot, there will be two items in the spyware	

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			<p>report: the item for spy.exe has cs4=10 (Files and Directories), and the item for the run key registry has cs4=11 (System Registry).</p> <p>This field is only for spyware detection events.</p>	
cs4Label	cd4Label	Resource Type	<p>The name label for the field cs4. This field is only for spyware detection events.</p>	cs4Label=Resource Type

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
cs5	cs5	Risk Level	<p>Risk level values:</p> <p>0=Very Low</p> <p>25=Low</p> <p>50=Medium</p> <p>75=High</p> <p>100=Very High</p> <p>This field is only for spyware detection events.</p>	cs5=25
cs5Label	cs5Label	Risk Level	<p>The name label for the field cs5. This field is only for spyware detection events.</p>	cs5Label=Risk Level

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
cs6	cs6	Container	The image name of the Docker container, container name, and container ID where the malware was detected.	cs6=ContainerImageName ContainerName ContainerID
cs6Label	cs6Label	Container	The name label for the field cs6.	cs6Label=Container
filePath	filePath	File Path	The location of the malware file.	filePath=C:\\Users\\Mei\\Desktop\\virus.exe
act	act	Action	The action performed by the anti-malware engine. Possible values are: Deny Access, Quarantine, Delete, Pass, Clean, Terminate, and Unspecified.	act=Clean act=Pass
msg	msg	Message	The type of scan.	msg=Realtime msg=Scheduled

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			Possible values are: Realtime, Scheduled, and Manual.	
dvc	dvc	Device addresses	The IPv4 address for cn1. Does not appear if the source is an IPv6 address or hostname. (Uses dvchost instead.)	dvc=10.1.144.199
dvchost	dvchost	Device host name	The hostname or IPv6 address for cn1. Does not	dvchost=www.example.com dvchost=fe80::f018:a3c6:20f9:afa6%5

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			appear if the source is an IPv4 address. (Uses dvc field instead.)	
TrendMicroDsTags	TrendMicroDsTags	Events tags	Deep Security event tags assigned to the event	TrendMicroDsTags=suspicious
TrendMicroDsTenant	TrendMicroDsTenant	Tenant name	Deep Security tenant	TrendMicroDsTenant=Primary
TrendMicroDsTenantId	TrendMicroDsTenantId	Tenant ID	Deep Security tenant ID	TrendMicroDsTenantId=0
TrendMicroDsMalwareTarget	TrendMicroDsMalwareTarget	Target(s)	The file, process, or registry key (if any) that the malware was trying to affect. If the malware	<p>TrendMicroDsMalwareTarget=N/A TrendMicroDsMalwareTarget=C:\\Windows\\System32\\cmd.exe</p> <p>TrendMicroDsMalwareTarget=HKCU\\Software\\Microsoft\\Windows\\CurrentVersion\\Internet Settings TrendMicroDsMalwareTarget=Multiple</p>

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			<p>was trying to affect more than one, this field will contain the value "Multiple."</p> <p>Only suspicious activity monitoring and unauthorized change monitoring have values for this field.</p>	
TrendMicroDsMalwareTargetType	TrendMicroDsMalwareTargetType	Target Type	The type of system resource	<p>TrendMicroDsMalwareTargetType=N/A</p> <p>TrendMicroDsMalwareTargetType=Exploit</p> <p>TrendMicroDsMalwareTargetType=File System</p> <p>TrendMicroDsMalwareTargetType=Process</p> <p>TrendMicroDsMalwareTargetType=Registry</p>

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			<p>that this malware was trying to affect, such as the file system, a process, or Windows registry.</p> <p>Only suspicious activity monitoring and unauthorized change monitoring have values for this field.</p>	
TrendMicroDsFileMD5	TrendMicroDsFileMD5	File MD5	The MD5 hash of the file	TrendMicroDsFileMD5=1947A1BC0982C5871FA3768CD025453E

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
TrendMicroDsFileSHA1	TrendMicroDsFileSHA1	File SHA1	The SHA1 hash of the file	TrendMicroDsFileSHA1=5AD084DDCD8F80FBF2EE3F0E4F812E812DEE60C1
TrendMicroDsFileSHA256	TrendMicroDsFileSHA256	File SHA256	The SHA256 hash of the file	TrendMicroDsFileSHA256=25F231556700749F8F0394CAABDED83C2882317669DA2C01299B45173482FA6E
TrendMicroDsDetectionConfidence	TrendMicroDsDetectionConfidence	Threat Probability	Indicates how closely (in %) the file matched the malware model	TrendMicroDsDetectionConfidence=95
TrendMicroDsRelevantDetectionNames	TrendMicroDsRelevantDetectionNames	Probable Threat Type	Indicates the most likely type of threat contained in the file after Predictive Machine Learning compared the analysis to other known threats (separate by semicolon";")	TrendMicroDsRelevantDetectionNames=Ransom_CERBER.BZC;Ransom_CERBER.C;Ransom_CRYPNISCA.SM
None	sev	Severity	The severity of the event. 1 is the least severe; 10 is the most severe.	sev=6
None	cat	Category	Category	cat=Anti-Malware

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
None	name	Name	Event name	name=SPYWARE_KEYL_ACTIVE
None	desc	Description	Event description. Anti-malware uses the event name as the description.	desc=SPYWARE_KEYL_ACTIVE

Application control event format

Base CEF format: CEF:Version|Device Vendor|Device Product|Device Version|Signature ID|Name|Severity|Extension

Example CEF Log Entry: CEF: 0|Trend Micro|Deep Security Agent|10.2.229|6001200|AppControl detectOnly|6|cn1=202
cn1Label=Host ID dvc=192.168.33.128 TrendMicroDsTenant=Primary TrendMicroDsTenantId=0
fileHash=80D4AC182F97D2AB48EE4310AC51DA5974167C596D133D64A83107B9069745E0 suser=root suid=0 act=detectOnly
filePath=/home/user1/Desktop/Directory1//heartbeatSync.sh fsize=20 aggregationType=0 repeatCount=1
cs1=notWhitelisted cs1Label=actionReason cs2=0CC9713BA896193A527213D9C94892D41797EB7C cs2Label=sha1
cs3=7EA8EF10BEB2E9876D4D7F7E5A46CF8D cs3Label=md5

Base LEEF 2.0 format: LEEF:2.0|Vendor|Product|Version|EventID|(Delimiter Character, optional if the Delimiter Character is tab)|Extension

Example LEEF Log Entry: LEEF:2.0|Trend Micro|Deep Security Agent|10.0.2883|60|cat=AppControl name=blocked
desc=blocked sev=6 cn1=2 cn1Label=Host ID dvc=10.203.156.39 TrendMicroDsTenant=Primary TrendMicroDsTenantId=0
fileHash=E3B0C44298FC1C149AFBF4C8996FB92427AE41E4649B934CA495991B7852B855 suser=root suid=0 act=blocked
filePath=/bin/my.jar fsize=123857 aggregationType=0 repeatCount=1 cs1=notWhitelisted cs1Label=actionReason

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
cn1	cn1	Host Identifier	The agent computer's internal unique identifier.	cn1=2
cn1Label	cn1Label	Host ID	The name label for the field cn1.	cn1Label=Host ID
cs1	cs1	Reason	The reason why application control performed the specified action, such as "notWhitelisted" (the software did not have a matching rule, and application control was configured to block unrecognized software).	cs1=notWhitelisted
cs1Label	cs1Label		The name label for the field cs1.	cs1Label=actionReason
cs2	cs2		If it was calculated, the SHA-1 hash of the file.	cs2=156F4CB711FDBD668943711F853FB6DA89581AAD
cs2Label	cs2Label		The name label for the field cs2.	cs2Label=sha1
cs3	cs3		If it was calculated, the MD5 hash of the file.	cs3=4E8701AC951BC4537F8420FDAC7EFBB5
cs3Label	cs3Label		The name label for the field cs3.	cs3Label=md5

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
act	act	Action	The action performed by the application control engine. Possible values are: Blocked, Allowed.	act=blocked
dvc	dvc	Device address	The IPv4 address for cn1. Does not appear if the source is an IPv6 address or hostname. (Uses dvchost instead.)	dvc=10.1.1.10
dvchost	dvchost	Device host name	The hostname or IPv6 address for cn1. Does not appear if the source is an IPv4 address.	dvchost=www.example.com dvchost=2001:db8::5

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			(Uses dvc field instead.)	
suid	suid	User ID	The account ID number of the user name.	suid=0
suser	suser	User Name	The name of the user account that installed the software on the protected computer.	suser=root
TrendMicroDsTenant	TrendMicroDsTenant	Tenant name	Deep Security tenant name.	TrendMicroDsTenant=Primary
TrendMicroDsTenantId	TrendMicroDsTenantId	Tenant ID	Deep Security tenant ID number.	TrendMicroDsTenantId=0
fileHash	fileHash	File hash	The SHA 256 hash that identifies the software file.	fileHash=E3B0C44298FC1C149AFBF4C8996FB92427AE41E4649B934CA495991B7852B855
filePath	filePath	File Path	The location of the malware file.	filePath=/bin/my.jar
fsize	fsize	File Size	The file size in bytes.	fsize=16
aggregationType	aggregationType	Aggregation Type	<p>An integer that indicates how the event is aggregated:</p> <ul style="list-style-type: none"> 0: The event is 	aggregationType=2

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			<div>not aggregated</div> <ul style="list-style-type: none">1: The event is aggregated based on file name, path, and event type.2: The event is aggregated based on event type. <div>For information, about event aggregation,</div>	

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			see "View application control event logs" on page 642.	
repeatCount	repeatCount	Repeat Count	The number of occurrences of the event. Non-aggregated events have a value of 1. Aggregated events have a value of 2 or more.	repeatCount=4
None	sev	Severity	The severity of the event. 1 is the least severe; 10 is the most severe.	sev=6
None	cat	Category	Category	cat=AppControl
None	name	Name	Event name	name=blocked
None	desc	Description	Event description. Application control uses the action as the description.	desc=blocked

Firewall event log format

Base CEF format: CEF:Version|Device Vendor|Device Product|Device Version|Signature ID|Name|Severity|Extension

Sample CEF Log Entry: CEF:0|Trend Micro|Deep Security Agent|<DSA version>|20|Log for TCP Port 80|0|cn1=1 cn1Label=Host ID dvc=hostname act=Log dmac=00:50:56:F5:7F:47 smac=00:0C:29:EB:35:DE TrendMicroDsFrameType=IP

Trend Micro Deep Security On-Premise 11.3

src=192.168.126.150 dst=72.14.204.147 out=1019 cs3=DF MF cs3Label=Fragmentation Bits proto=TCP spt=49617 dpt=80
cs2=0x00 ACK PSH cs2Label=TCP Flags cnt=1 TrendMicroDsPacketData=AFB...

Sample LEEF Log Entry: LEEF:2.0|Trend Micro|Deep Security Agent|<DSA version>|21|cat=Firewall name=Remote Domain Enforcement (Split Tunnel) desc=Remote Domain Enforcement (Split Tunnel) sev=5 cn1=37 cn1Label=Host ID dvchost=www.example.com TrendMicroDsTenant=Primary TrendMicroDsTenantId=0 act=Deny dstMAC=67:BF:1B:2F:13:EE srcMAC=78:FD:E7:07:9F:2C TrendMicroDsFrameType=IP src=10.0.110.221 dst=105.152.185.81 out=177 cs3=
cs3Label=Fragmentation Bits proto=UDP srcPort=23 dstPort=445 cnt=1

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
act	act	Action		act=Log act=Deny
cn1	cn1	Host Identifier	The agent computer's internal unique identifier.	cn1=113
cn1Label	cn1Label	Host ID	The name label for the field cn1.	cn1Label=Host ID
cnt	cnt	Repeat Count	The number of times this event was sequentially repeated.	cnt=8
cs2	cs2	TCP Flags		cs2=0x10 ACK cs2=0x14 ACK RST
cs2Label	cs2Label	TCP Flags	The name label for the field cs2.	cs2Label=TCP Flags
cs3	cs3	Packet Fragmentation Information		cs3=DF cs3=MF cs3=DF MF
cs3Label	cs3Label	Fragmentation Bits	The name label for the field cs3.	cs3Label=Fragmentation Bits
cs4	cs4	ICMP Type and Code	(For the ICMP protocol only) The ICMP type and code, delimited by a space.	cs4=11 0 cs4=8 0
cs4Label	cs4Label	ICMP	The name label for the field cs4.	cs4Label=ICMP Type and Code
dmac	dstMAC	Destination MAC Address	MAC address of the destination computer's network interface.	dmac= 00:0C:29:2F:09:B3
dpt	dstPort	Destination Port	(For TCP and UDP protocol only) Port number of the destination computer's connection or session.	dpt=80 dpt=135

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
dst	dst	Destination IP Address	IP address of the destination computer.	dst=192.168.1.102 dst=10.30.128.2
in	in	Inbound Bytes Read	(For inbound connections only) Number of inbound bytes read.	in=137 in=21
out	out	Outbound Bytes Read	(For outbound connections only) Number of outbound bytes read.	out=216 out=13
proto	proto	Transport protocol	Name of the transport protocol used.	proto=tcp proto=udp proto=icmp
smac	srcMAC	Source MAC Address	MAC address of the source computer's network interface.	smac= 00:0E:04:2C:02:B3
spt	srcPort	Source Port	(For TCP and UDP protocol only) Port number of the source computer's connection or session.	spt=1032 spt=443
src	src	Source IP Address	The packet's source IP address at this event.	src=192.168.1.105 src=10.10.251.231
TrendMicroDsFrameType	TrendMicroDsFrameType	Ethernet frame type	Connection ethernet frame type.	TrendMicroDsFrameType=IP TrendMicroDsFrameType=ARP TrendMicroDsFrameType=RevARP TrendMicroDsFrameType=NetBEUI
TrendMicroDsPacketData	TrendMicroDsPacketData	Packet data		TrendMicroDsPacketData=AA...BA\=
dvc	dvc	Device address	The IPv4 address for cn1. Does not appear if the source is an IPv6 address or hostname. (Uses dvchost instead.)	dvc=10.1.144.199
dvchost	dvchost	Device host name	The hostname or IPv6 address for cn1. Does not appear if the source is an IPv4 address. (Uses dvc field instead.)	dvchost=exch01.example.com dvchost=2001:db8::5
TrendMicroDsTags	TrendMicroDsTags	Event Tags	Deep Security event tags assigned to the event	TrendMicroDsTags=suspicious
TrendMicroDsTenant	TrendMicroDsTenant	Tenant Name	Deep Security tenant	TrendMicroDsTenant=Primary

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
TrendMicroDsTenantId	TrendMicroDsTenantId	Tenant ID	Deep Security tenant ID	TrendMicroDsTenantId=0
None	sev	Severity	The severity of the event. 1 is the least severe; 10 is the most severe.	sev=5
None	cat	Category	Category	cat=Firewall
None	name	Name	Event name	name=Remote Domain Enforcement (Split Tunnel)
None	desc	Description	Event description. Firewall events use the event name as the description.	desc=Remote Domain Enforcement (Split Tunnel)

Integrity monitoring log event format

Base CEF format: CEF:Version|Device Vendor|Device Product|Device Version|Signature ID|Name|Severity|Extension

Sample CEF Log Entry: CEF:0|Trend Micro|Deep Security Agent|<DSA version>|30|New Integrity Monitoring Rule|6|cn1=1
cn1Label=Host ID dvchost=hostname act=updated filePath=c:\\windows\\message.dll suser=admin msg=lastModified,sha1,size

Base LEEF 2.0 format: LEEF:2.0|Vendor|Product|Version|EventID|(Delimiter Character, optional if the Delimiter Character is tab)|Extension

Sample LEEF Log Entry: LEEF:2.0|Trend Micro|Deep Security Agent|<DSA version>|2002779|cat=Integrity Monitor
name=Microsoft Windows - System file modified desc=Microsoft Windows - System file modified sev=8 cn1=37 cn1Label=Host ID
dvchost=www.example.com TrendMicroDsTenant=Primary TrendMicroDsTenantId=0 act=updated suser=admin

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
act	act	Action	The action detected by the integrity rule. Can contain: created, updated, deleted or renamed.	act=created act=deleted
cn1	cn1	Host Identifier	The agent computer's internal unique identifier.	cn1=113
cn1Label	cn1Label	Host ID	The name label for the field cn1.	cn1Label=Host ID
filePath	filePath	Target	The integrity rule target entity. May contain a	filePath=C:\\WINDOWS\\system32\\drivers\\etc\\hosts

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
		Entity	file or directory path, registry key, etc.	
suser	suser	Source User	Deep Security Manager administrator's account.	suser=MasterAdmin
msg	msg	Attribute changes	(For "renamed" action only) A list of changed attribute names. If "Relay via Manager" is selected, all event action types include a full description.	msg=lastModified,sha1,size
oldfilePath	oldfilePath	Old target entity	(For "renamed" action only) The previous integrity rule target entity to capture the rename action from the previous target entity to the new, which is recorded in the filePath field.	oldFilePath=C:\WINDOWS\system32\logfiles\ds_agent.log
dvc	dvc	Device address	The IPv4 address for cn1. Does not appear if the source is an IPv6 address or hostname. (Uses dvchost instead.)	dvc=10.1.144.199
dvchost	dvchost	Device host name	The hostname or IPv6 address for cn1. Does not appear if the source is an IPv4 address. (Uses dvc field instead.)	dvchost=www.example.com dvchost=2001:db8::5
TrendMicroDsTags	TrendMicroDsTags	Events tags	Deep Security event tags assigned to the event	TrendMicroDsTags=suspicious
TrendMicroDsTenant	TrendMicroDsTenant	Tenant name	Deep Security tenant	TrendMicroDsTenant=Primary
TrendMicroDsTenantId	TrendMicroDsTenantId	Tenant ID	Deep Security tenant ID	TrendMicroDsTenantId=0
None	sev	Severity	The severity of the event. 1 is the least severe; 10 is the most severe.	sev=8
None	cat	Category	Category	cat=Integrity Monitor

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
None	name	Name	Event name	name=Microsoft Windows - System file modified
None	desc	Description	Event description. Integrity monitoring uses the event name as the description.	desc=Microsoft Windows - System file modified

Intrusion prevention event log format

Base CEF format: CEF:Version|Device Vendor|Device Product|Device Version|Signature ID|Name|Severity|Extension

Sample CEF Log Entry: CEF:0|Trend Micro|Deep Security Agent|<DSA version>|1001111|Test Intrusion Prevention Rule|3|cn1=1 cn1Label=Host ID dvchost=hostname dmac=00:50:56:F5:7F:47 smac=00:0C:29:EB:35:DE TrendMicroDsFrameType=IP src=192.168.126.150 dst=72.14.204.105 out=1093 cs3=DF MF cs3Label=Fragmentation Bits proto=TCP spt=49786 dpt=80 cs2=0x00 ACK PSH cs2Label=TCP Flags cnt=1 act=IDS:Reset cn3=10 cn3Label=Intrusion Prevention Packet Position cs5=10 cs5Label=Intrusion Prevention Stream Position cs6=8 cs6Label=Intrusion Prevention Flags TrendMicroDsPacketData=R0VUIC9zP3...

Base LEEF 2.0 format: LEEF:2.0|Vendor|Product|Version|EventID|(Delimiter Character, optional if the Delimiter Character is tab)|Extension

Sample LEEF Log Entry: LEEF:2.0|Trend Micro|Deep Security Agent|<DSA version>|1000940|cat=Intrusion Prevention name=Sun Java RunTime Environment Multiple Buffer Overflow Vulnerabilities desc=Sun Java RunTime Environment Multiple Buffer Overflow Vulnerabilities sev=10 cn1=6 cn1Label=Host ID dvchost=exch01 TrendMicroDsTenant=Primary TrendMicroDsTenantId=0 dstMAC=55:C0:A8:55:FF:41 srcMAC=CA:36:42:B1:78:3D TrendMicroDsFrameType=IP src=10.0.251.84 dst=56.19.41.128 out=166 cs3= cs3Label=Fragmentation Bits proto=ICMP srcPort=0 dstPort=0 cnt=1 act=IDS:Reset cn3=0 cn3Label=DPI Packet Position cs5=0 cs5Label=DPI Stream Position cs6=0 cs6Label=DPI Flags

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
act	act	Action	(IPS rules written before Deep Security version 7.5	act=Block

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			SP1 could additionally perform Insert, Replace, and Delete actions. These actions are no longer performed. If an older IPS Rule is triggered which still attempts to perform those actions, the event will indicate that the rule was applied in detect-only mode.)	
cn1	cn1	Host Identifier	The agent computer's internal unique identifier.	cn1=113
cn1Label	cn1Label	Host ID	The name label for the field cn1.	cn1Label=Host ID
cn3	cn3	Intrusion Prevention Packet Position	Position within packet of data that triggered the event.	cn3=37
cn3Label	cn3Label	Intrusion Prevention Packet Position	The name label for the field cn3.	cn3Label=Intrusion Prevention Packet Position
cnt	cnt	Repeat Count	The number of times this event was sequentially repeated.	cnt=8
cs1	cs1	Intrusion Prevention Filter Note	(Optional) A note field which can contain a short binary or text note associated with the payload file. If the value of the note field is all printable ASCII characters, it will be logged as text with spaces converted to underscores. If it contains binary data, it will be logged using Base-64 encoding.	cs1=Drop_data
cs1Label	cs1Label	Intrusion Prevention Note	The name label for the field cs1.	cs1Label=Intrusion Prevention Note
cs2	cs2	TCP Flags	(For the TCP protocol only) The raw TCP flag byte followed by the URG, ACK, PSH, RST, SYN and FIN fields may be present if the TCP header was set.	cs2=0x10 ACK cs2=0x14 ACK RST
cs2Label	cs2Label	TCP Flags	The name label for the field cs2.	cs2Label=TCP Flags
cs3	cs3	Packet Fragmentation		cs3=DF cs3=MF

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
		Information		cs3=DF MF
cs3Label	cs3Label	Fragmentation Bits	The name label for the field cs3.	cs3Label=Fragmentation Bits
cs4	cs4	ICMP Type and Code	(For the ICMP protocol only) The ICMP type and code stored in their respective order delimited by a space.	cs4=11 0 cs4=8 0
cs4Label	cs4Label	ICMP	The name label for the field cs4.	cs4Label=ICMP Type and Code
cs5	cs5	Intrusion Prevention Stream Position	Position within stream of data that triggered the event.	cs5=128 cs5=20
cs5Label	cs5Label	Intrusion Prevention Stream Position	The name label for the field cs5.	cs5Label=Intrusion Prevention Stream Position
cs6	cs6	Intrusion Prevention Filter Flags	A combined value that includes the sum of the flag values: 1 - Data truncated - Data could not be logged. 2 - Log Overflow - Log overflowed after this log. 4 - Suppressed - Logs threshold suppressed after this log. 8 - Have Data - Contains packet data 16 - Reference Data - References previously logged data.	The following example would be a summed combination of 1 (Data truncated) and 8 (Have Data): cs6=9
cs6Label	cs6Label	Intrusion Prevention Flags	The name label for the field cs6.	cs6=Intrusion Prevention Filter Flags
dmac	dstMAC	Destination MAC Address	Destination computer network interface MAC address.	dmac= 00:0C:29:2F:09:B3
dpt	dstPort	Destination Port	(For TCP and UDP protocol only) Destination computer connection port.	dpt=80 dpt=135
dst	dst	Destination IP Address	Destination computer IP Address.	dst=192.168.1.102 dst=10.30.128.2

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
xff	xff	X-Forwarded-For	The IP address of the last hub in the X-Forwarded-For header. This is typically originating IP address, beyond the proxy that may exist. See also the src field. To include xff in events, enable the "1006540 - Enable X-Forwarded-For HTTP Header Logging" Intrusion Prevention rule .	xff=192.168.137.1
in	in	Inbound Bytes Read	(For inbound connections only) Number of inbound bytes read.	in=137 in=21
out	out	Outbound Bytes Read	(For outbound connections only) Number of outbound bytes read.	out=216 out=13
proto	proto	Transport protocol	Name of the connection transport protocol used.	proto=tcp proto=udp proto=icmp
smac	srcMAC	Source MAC Address	Source computer network interface MAC address.	smac= 00:0E:04:2C:02:B3
spt	srcPort	Source Port	(For TCP and UDP protocol only) Source computer connection port.	spt=1032 spt=443
src	src	Source IP Address	Source computer IP Address. This is the IP of the last proxy server, if it exists, or the client IP. See also the xff field.	src=192.168.1.105 src=10.10.251.231
TrendMicroDsFrameType	TrendMicroDsFrameType	Ethernet frame type	Connection ethernet frame type.	TrendMicroDsFrameType=IP TrendMicroDsFrameType=ARP TrendMicroDsFrameType=RevARP TrendMicroDsFrameType=NetBEUI
TrendMicroDsPacketData	TrendMicroDsPacketData	Packet data		TrendMicroDsPacketData=AA...BA\=
dvc	dvc	Device address	The IPv4 address for cn1. Does not appear if the source is an IPv6 address or hostname. (Uses dvchost instead.)	dvc=10.1.144.199
dvchost	dvchost	Device host name	The hostname or IPv6 address for cn1.	dvchost=www.example.com dvchost=2001:db8::5

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
			Does not appear if the source is an IPv4 address. (Uses dvc field instead.)	
TrendMicroDsTags	TrendMicroDsTags	Event tags	Deep Security event tags assigned to the event	TrendMicroDsTags=Suspicious
TrendMicroDsTenant	TrendMicroDsTenant	Tenant name	Deep Security tenant name	TrendMicroDsTenant=Primary
TrendMicroDsTenantId	TrendMicroDsTenantId	Tenant ID	Deep Security tenant ID	TrendMicroDsTenantId=0
None	sev	Severity	The severity of the event. 1 is the least severe; 10 is the most severe.	sev=10
None	cat	Category	Category	cat=Intrusion Prevention
None	name	Name	Event name	name=Sun Java RunTime Environment Multiple Buffer Overflow Vulnerabilities
None	desc	Description	Event description. Intrusion prevention events use the event name as the description.	desc=Sun Java RunTime Environment Multiple Buffer Overflow Vulnerabilities

Log inspection event format

Base CEF format: CEF:Version|Device Vendor|Device Product|Device Version|Signature ID|Name|Severity|Extension

Sample CEF Log Entry: CEF:0|Trend Micro|Deep Security Agent|<DSA version>|3002795|Microsoft Windows Events|8|cn1=1
cn1Label=Host ID dvchost=hostname cs1Label=LI Description cs1=Multiple Windows Logon Failures fname=Security
src=127.0.0.1 duser=(no user) shost=WIN-RM6HM42G65V msg=WinEvtLog Security: AUDIT_FAILURE(4625): Microsoft-
Windows-Security-Auditing: (no user): no domain: WIN-RM6HM42G65V: An account failed to log on. Subject: ..

Base LEEF 2.0 format: LEEF:2.0|Vendor|Product|Version|EventID|(Delimiter Character, optional if the Delimiter Character is tab)|Extension

Sample LEEF Log Entry: LEEF:2.0|Trend Micro|Deep Security Agent|<DSA version>|3003486|cat=Log Inspection name=Mail
Server - MDaemon desc=Server Shutdown. sev=3 cn1=37 cn1Label=Host ID dvchost=exch01.example.com
TrendMicroDsTenant=Primary TrendMicroDsTenantId=0 cs1=Server Shutdown. cs1Label=LI Description fname= shost= msg=

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
cn1	cn1	Host Identifier	The agent computer's internal unique identifier.	cn1=113
cn1Label	cn1Label	Host ID	The name label for the field cn1.	cn1Label=Host ID
cs1	cs1	Specific Sub-Rule	The Log Inspection sub-rule which triggered this event.	cs1=Multiple Windows audit failure events
cs1Label	cs1Label	LI Description	The name label for the field cs1.	cs1Label=LI Description
duser	duser	User Information	(If parse-able username exists) The name of the target user initiated the log entry.	duser=(no user) duser=NETWORK SERVICE
fname	fname	Target entity	The log inspection rule target entity. May contain a file or directory path, registry key, etc.	fname=Application fname=C:\Program Files\CMS\logs\server0.log
msg	msg	Details	Details of the log inspection event. May contain a verbose description of the detected log event.	msg=WinEvtLog: Application: AUDIT_FAILURE (20187): pgEvent: (no user): no domain: SERVER01: Remote login failure for user 'xyz'
shost	shost	Source Hostname	Source computer hostname.	shost=webserver01.corp.com
src	src	Source IP Address	Source computer IP address.	src=192.168.1.105 src=10.10.251.231
dvc	dvc	Device address	The IPv4 address for cn1. Does not appear if the source is an IPv6 address or hostname. (Uses dvchost instead.)	dvc=10.1.144.199
dvchost	dvchost	Device host name	The hostname or IPv6 address for cn1. Does not appear if the source is an IPv4 address. (Uses dvc field instead.)	dvchost=www.example.com dvchost=2001:db8::5

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
TrendMicroDsTags	TrendMicroDsTags	Events tags	Deep Security event tags assigned to the event	TrendMicroDsTags=suspicious
TrendMicroDsTenant	TrendMicroDsTenant	Tenant name	Deep Security tenant	TrendMicroDsTenant=Primary
TrendMicroDsTenantId	TrendMicroDsTenantId	Tenant ID	Deep Security tenant ID	TrendMicroDsTenantId=0
None	sev	Severity	The severity of the event. 1 is the least severe; 10 is the most severe.	sev=3
None	cat	Category	Category	cat=Log Inspection
None	name	Name	Event name	name=Mail Server - MDaemon
None	desc	Description	Event description.	desc=Server Shutdown

Web reputation event format

Base CEF format: CEF:Version|Device Vendor|Device Product|Device Version|Signature ID|Name|Severity|Extension

Sample CEF Log Entry: CEF:0|Trend Micro|Deep Security Agent|<DSA version>|5000000|WebReputation|5|cn1=1
cn1Label=Host ID dvchost=hostname request=example.com msg=Blocked By Admin

Base LEEF 2.0 format: LEEF:2.0|Vendor|Product|Version|EventID|(Delimiter Character, optional if the Delimiter Character is tab)|Extension

Sample LEEF Log Entry: LEEF:2.0|Trend Micro|Deep Security Agent|<DSA version>|5000000|cat=Web Reputation
name=WebReputation desc=WebReputation sev=6 cn1=3 cn1Label=Host ID dvchost=exch01.example.com
TrendMicroDsTenant=Primary TrendMicroDsTenantId=0 request=http://yw.olx5x9ny.org.it/HvuauRH/eighgSS.htm
msg=Suspicious

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
cn1	cn1	Host Identifier	The agent computer's internal unique identifier.	cn1=1

Trend Micro Deep Security On-Premise 11.3

CEF Extension Field	LEEF Extension Field	Name	Description	Examples
cn1Label	cn1Label	Host ID	The name label for the field cn1.	cn1Label=Host ID
request	request	Request	The URL of the request.	request=http://www.example.com/index.php
msg	msg	Message	The type of action. Possible values are: Realtime, Scheduled, and Manual.	msg=Realtime msg=Scheduled
dvc	dvc	Device address	The IPv4 address for cn1. Does not appear if the source is an IPv6 address or hostname. (Uses dvchost instead.)	dvc=10.1.144.199
dvchost	dvchost	Device host name	The hostname or IPv6 address for cn1. Does not appear if the source is an IPv4 address. (Uses dvc field instead.)	dvchost=www.example.com dvchost=2001:db8::5
TrendMicroDsTags	TrendMicroDsTags	Events tags	Deep Security event tags assigned to the event	TrendMicroDsTags=suspicious
TrendMicroDsTenant	TrendMicroDsTenant	Tenant name	Deep Security tenant	TrendMicroDsTenant=Primary
TrendMicroDsTenantId	TrendMicroDsTenantId	Tenant ID	Deep Security tenant ID	TrendMicroDsTenantId=0
None	sev	Severity	The severity of the event. 1 is the least severe; 10 is the most severe.	sev=6
None	cat	Category	Category	cat=Web Reputation
None	name	Name	Event name	name=WebReputation
None	desc	Description	Event description. Web reputation uses the event name as the description.	desc=WebReputation

Configure Red Hat Enterprise Linux to receive event logs

Set up a Syslog on Red Hat Enterprise Linux 6 or 7

The following steps describe how to configure rsyslog on Red Hat Enterprise Linux 6 or 7 to receive logs from Deep Security.

1. Log in as root

2. Execute:

```
vi /etc/rsyslog.conf
```

3. Uncomment the following lines near the top of the `rsyslog.conf` to change them from:

```
#$ModLoad imudp
#$UDPServerRun 514

#$ModLoad imtcp
#$InputTCPServerRun 514
```

to

```
$ModLoad imudp
$UDPServerRun 514

$ModLoad imtcp
$InputTCPServerRun 514
```

Trend Micro Deep Security On-Premise 11.3

4. Add the following two lines of text to the end of the `rsyslog.conf`:

- `#Save Deep Security Manager logs to DSM.log`
- `Local4.* /var/log/DSM.log`

Note: You may need to replace `Local4` with another value, depending on your Manager settings.

5. Save the file and exit

6. Create the `/var/log/DSM.log` file by typing `touch /var/log/DSM.log`

7. Set the permissions on the DSM log so that syslog can write to it

8. Save the file and exit

9. Restart syslog:

- On Red Hat Enterprise Linux 6: `service rsyslog restart`
- On Red Hat Enterprise Linux 7: `systemctl restart rsyslog`

When Syslog is functioning you will see logs populated in: `/var/log/DSM.log`

Set up a Syslog on Red Hat Enterprise Linux 5

The following steps describe how to configure Syslog on Red Hat Enterprise Linux to receive logs from Deep Security.

1. Log in as root

2. Execute:

```
vi /etc/syslog.conf
```

3. Add the following two lines of text to the end of the `syslog.conf` :

- `#Save Deep Security Manager logs to DSM.log`
- `Local4.* /var/log/DSM.log`

Note: You may need to replace `Local14` with another value, depending on your Manager settings.

4. Save the file and exit
5. Create the `/var/log/DSM.log` file by typing `touch /var/log/DSM.log`
6. Set the permissions on the DSM log so that syslog can write to it
7. Execute:

```
vi /etc/sysconfig/syslog
```

8. Modify the line `" SYSLOGD_OPTIONS "` and add a `" -r "` to the options
9. Save the file and exit
10. Restart syslog: `/etc/init.d/syslog restart`

When Syslog is functioning you will see logs populated in: `/var/log/DSM.log`

Access events with Amazon SNS

If you have an AWS account, you can take advantage of the Amazon Simple Notification Service (SNS) to publish notifications about Deep Security events and deliver them to subscribers. For details about SNS, see <https://aws.amazon.com/sns/>.

To set up Amazon SNS:

1. ["Create an AWS user" on the next page.](#)
2. ["Create an Amazon SNS topic" on page 1160.](#)
3. ["Enable SNS" on page 1160.](#)
4. ["Create subscriptions" on page 1161.](#)

See the sections below for details on how to perform these tasks.

Create an AWS user

In order to use Amazon SNS with Deep Security, you need to create an AWS user with the appropriate permissions for SNS. Note the access key and secret key for the user, because you will need that information for step 3, below.

The AWS user will need the "sns:Publish" permission on all SNS topics that Deep Security will publish to. This is an example of a policy with this permission:

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Action": [
        "sns:Publish"
      ],
      "Effect": "Allow",
      "Resource": "*"
    }
  ]
}
```

If you want to limit publishing rights to a single topic, you can replace `"Resource": "*" with "Resource": "TOPIC ARN".`

For more information, see [Controlling User Access to Your AWS Account](#) and [Special Information for Amazon SNS Policies](#) in the Amazon AWS documentation.

Create an Amazon SNS topic

In AWS, create an SNS topic where the events will be published. For instructions on how to create an Amazon SNS topic, see "Create a Topic" in the [Amazon SNS documentation](#). Note the SNS Topic ARN because you will need this information in step 3, below.

Enable SNS

1. In the Deep Security Manager, go to **Administration > System Settings > Event Forwarding**.
2. In the Amazon SNS section, select **Publish Events to Amazon Simple Notification Service**.
3. Enter this information:
 - **Access Key:** The access key of the AWS user you created in section 1.
 - **Secret Key:** The secret key of the AWS user you created in section 1.
 - **SNS Topic ARN:** The SNS Topic ARN that events will be sent to. This is the ARN that you noted in section 2.
4. Select the types of events that you want to forward to SNS.

Selecting the events automatically generates a JSON SNS configuration.

5. (Optional) You can also click **Edit JSON SNS configuration** to edit the JSON SNS configuration directly if you want to filter the events in greater detail and configure the forwarding instructions for each filter. For details on the configuration language, see ["SNS configuration in JSON format" on the next page](#).

Note: If you edit the JSON, the event check boxes will become unavailable. If you want to select or deselect any of the event check boxes, you can click **Revert to basic SNS configuration**, but any customizations you have made to the JSON SNS configuration will be discarded.

6. Click **Save**.

Create subscriptions

Now that SNS is enabled and events are being published to the topic, go to the Amazon SNS console and subscribe to the topic to access the events. There are several ways that you can subscribe to events, including [email](#), [SMS](#), and [Lambda endpoints](#).

Note: Lambda is not available in all AWS regions.

SNS configuration in JSON format

You can edit the [JSON](#) configuration that is used when you have [enabled event forwarding to Amazon SNS topics](#). It defines which conditions an event must meet in order to be published to a topic. The configuration language is modeled after [Amazon's Policy language for SNS](#).

Each field is specified below. Basic SNS configuration looks like:

```
{
  "Version": "2014-09-24",
  "Statement": [statement1, statement2, ...]
}
```

For examples, see ["Example SNS configurations" on page 1180](#).

Version

The **Version** element specifies the version of the configuration language.

Note: The only currently valid value of "Version" is the string "2014-09-24".

Trend Micro Deep Security On-Premise 11.3

```
"Version": "2014-09-24",
```

Statement

The **Statement** element is an array of individual statements. Each individual statement is a distinct JSON object giving the SNS topic to send to if an event meets given conditions.

```
"Statement": [{...}, {...}, ...]
```

An individual statement has the form:

```
{  
  "Topic": "destination topic",  
  "Condition": {conditions event must meet to be published to the destination topic}  
}
```

Topic

The **Topic** element must be the Amazon Resource Name of the SNS Topic to publish to.

```
"Topic": "arn:aws:sns:us-east-1:012345678901:myTopic"
```

Condition

The **Condition** element is the most complex part of the configuration. It contains one or more conditions an event must match in order to be published to the topic.

Trend Micro Deep Security On-Premise 11.3

Each condition can have one or more key-value pairs that the event must match (or not match, depending on the type of condition) to be included in the topic. Keys are any valid event property. (For event properties, see ["Events in JSON format" on page 1182](#)). Valid values vary by key. Some keys support multiple values.

```
"Condition": {  
  "ConditionName": {  
    "key1": [value1, value2],  
    "key2": value3  
  },  
  "ConditionName2": {  
    "key3": [value4]  
  },  
  ...  
}
```

Valid condition names and their syntax are described below.

Bool

The **Bool** condition performs Boolean matching. To match, an event must have a property with the desired Boolean value. If the property in the event exists but is not itself a Boolean value, the property is tested as follows:

- Numbers equal to 0 evaluate to false. Numbers not equal to 0 evaluate to true.
- Empty strings and the special strings "false" and "0" evaluate to false. Other strings evaluate to true.
- Any other property value in an event cannot be converted to a Boolean and will not match.

Trend Micro Deep Security On-Premise 11.3

Allows for multiple values? No

The following example shows a configuration that publishes events that have a "DetectOnly" property with a value false:

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
        "Bool": {
          "DetectOnly": false
        }
      }
    }
  ]
}
```

Exists

The **Exists** condition tests for the existence or non-existence of a property in an event. The value of the property is not considered.

Allows for multiple values? No

The following example shows a configuration that publishes events when the event has the property "Severity" but does not have the property "Title":

Trend Micro Deep Security On-Premise 11.3

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
        "Exists": {
          "Severity": true,
          "Title": false
        }
      }
    }
  ]
}
```

IpAddress

The **IpAddress** condition tests the value of an event's property is an IP address in a range given in CIDR format, or exactly equals a single IP address.

Allows for multiple values? Yes

The following example shows a configuration that publishes events when the event has the property "DestinationIP" with an IP address in the range 10.0.1.0/24, or to 10.0.0.5:

Trend Micro Deep Security On-Premise 11.3

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
        "IpAddress": {
          "DestinationIP": ["10.0.1.0/24", "10.0.0.5"]
        }
      }
    }
  ]
}
```

NotIpAddress

The **NotIpAddress** condition tests the value of an event's property is not an IP address in any of the specified IP address ranges.

Allows for multiple values? Yes

The following example shows a configuration that publishes events when the event has the property "DestinationIP" with an IP address not in the range 10.0.0.0/8:

```
{
  "Version": "2014-09-24",
  "Statement": [
```

Trend Micro Deep Security On-Premise 11.3

```
{
  "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
  "Condition": {
    "NotIpAddress": {
      "DestinationIP": "10.0.0.0/8"
    }
  }
}
```

NumericEquals

The **NumericEquals** condition tests the numeric value of an event's property equals one or more desired values. If the property in the event exists but is not itself a numeric value, the property is tested as follows:

- Strings are converted to numbers. Strings that cannot be converted to numbers will not match.
- Any other property value in an event cannot be converted to a number and will not match.

Allows for multiple values? Yes

The following example shows a configuration that publishes events when the event has the property "Protocol" with the value 6 or 17:

```
{
  "Version": "2014-09-24",
```

Trend Micro Deep Security On-Premise 11.3

```
"Statement": [  
  {  
    "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",  
    "Condition": {  
      "NumericEquals": {  
        "Protocol": [6, 17]  
      }  
    }  
  }  
]
```

NumericNotEquals

The **NumericNotEquals** condition tests the numeric value of an event's property is not equal to any one of an undesired set of values.

Allows for multiple values? Yes

The following example shows a configuration that publishes events when the event has the property "Protocol" not equal to 6, and the property "Risk" not equal to 2 or 3:

```
{  
  "Version": "2014-09-24",  
  "Statement": [  
    {
```

Trend Micro Deep Security On-Premise 11.3

```
    "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
    "Condition": {
      "NumericNotEquals": {
        "Protocol": 6,
        "Risk" : [2, 3]
      }
    }
  ]
}
```

NumericGreaterThan

The **NumericGreaterThan** condition tests the numeric value of an event's property is strictly greater than a desired value. If the property in the event exists but is not itself a numeric value it is converted to a number as described for NumericEquals.

Allows for multiple values? No

The following example shows a configuration that publishes events when the event has the property "Protocol" with the value greater than 6:

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
```

Trend Micro Deep Security On-Premise 11.3

```
    "Condition": {
      "NumericGreaterThan": {
        "Protocol": 6
      }
    }
  }
]
```

NumericGreaterThanEquals

The **NumericGreaterThanEquals** condition tests the numeric value of an event's property is greater than or equal to a desired value. If the property in the event exists but is not itself a numeric value it is converted to a number as described for **NumericEquals**.

Allows for multiple values? No

The following example shows a configuration that publishes events when the event has the property "Number" with a value greater than or equal to 600:

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
```

Trend Micro Deep Security On-Premise 11.3

```
        "NumericGreaterThanEquals": {
            "Number": 600
        }
    }
}
]
```

NumericLessThan

The **NumericLessThan** condition tests the numeric value of an event's property is strictly less than a desired value. If the property in the event exists but is not itself a numeric value it is converted to a number as described for NumericEquals.

Allows for multiple values? No

The following example shows a configuration that publishes events when the event has the property "Number" with a value greater than 1000:

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
        "NumericLessThan": {
          "Number": 1000
        }
      }
    }
  ]
}
```

```
    }  
  }  
}  
]  
}
```

NumericLessThanEquals

The **NumericLessThanEquals** condition tests the numeric value of an event's property is less than or equal to a desired value. If the property in the event exists but is not itself a numeric value it is converted to a number as described for NumericEquals.

Allows for multiple values? No

The following example shows a configuration that publishes events when the event has the property "Number" with a value less than or equal to 500:

```
{  
  "Version": "2014-09-24",  
  "Statement": [  
    {  
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",  
      "Condition": {  
        "NumericLessThanEquals": {  
          "Number": 500  
        }  
      }  
    }  
  ]  
}
```

```
    }  
  ]  
}
```

StringEquals

The **StringEquals** condition tests the string value of an event's property is strictly equal to or more desired values.

Allows for multiple values? Yes

The following example shows a configuration that publishes events when the event has the property "EventType" equal to "SystemEvent" and property "TargetType" equal to "User" or "Role":

```
{  
  "Version": "2014-09-24",  
  "Statement": [  
    {  
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",  
      "Condition": {  
        "StringEquals": {  
          "EventType": ["SystemEvent"],  
          "TargetType" : ["User", "Role"]  
        }  
      }  
    }  
  ]  
}
```



```
}
```

StringNotEquals

The **StringNotEquals** condition tests the string value of an event's property does not equal any of an undesired set of values.

Allows for multiple values? Yes

The following example shows a configuration that publishes events when the event has the property "EventType" not equal to "PacketLog" or "IntegrityEvent":

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
        "StringNotEquals": {
          "EventType": ["PacketLog", "IntegrityEvent"]
        }
      }
    }
  ]
}
```

StringEqualsIgnoreCase

The **StringEqualsIgnoreCase** condition is the same as the `StringEquals` condition, except string matching is performed in a case-insensitive manner.

StringNotEqualsIgnoreCase

The **StringNotEqualsIgnoreCase** condition is the same as the `StringNotEquals` condition, except string matching is performed in a case-insensitive manner.

StringLike

The **StringLike** condition tests the string value of an event's property is equal to or more desired values, where the desired values may include the wildcard '*' to match any number of characters or '?' to match a single character. String comparisons are case-sensitive.

Allows for multiple values? Yes

The following example shows a configuration that publishes events when the event has the property "Title" which contains the string "User" or "Role":

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
```

Trend Micro Deep Security On-Premise 11.3

```
    "StringLike": {
      "Title": ["*User*", "*Role*"]
    }
  }
}
]
```

StringNotLike

The **StringNotLike** condition tests that the string value of an event's property is not equal to any of an undesired set of values, where the values may include the wildcard '*' to match any number of characters or '?' to match a single character. String comparisons are case-sensitive.

Allows for multiple values? Yes

The following example shows a configuration that publishes all events except the "System Settings Saved" event:

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
        "StringNotLike": {
          "Title": "System Settings Saved"
        }
      }
    }
  ]
}
```

Trend Micro Deep Security On-Premise 11.3

```
    }  
  }  
}  
]  
}
```

The next example shows a configuration that publishes events when the event has the property "Title" that does not start with "User" and does not end with "Created":

```
{  
  "Version": "2014-09-24",  
  "Statement": [  
    {  
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",  
      "Condition": {  
        "StringNotLike": {  
          "Title": ["User*", "*Created"]  
        }  
      }  
    }  
  ]  
}
```

Multiple statements vs. multiple conditions

If you create multiple statements for the same SNS topic, those statements are evaluated as if they are joined by "or". If a statement contains multiple conditions, those conditions are evaluated as if they are joined by "and".

Multiple statements

This is an example of what not to do. The first statement says to forward all events other than "System Settings Saved". The second statement says to forward all "System Settings Saved" events. The result is that all events will be forwarded because any event will match either the condition in the first statement or the one in the second statement:

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
        "StringNotLike" : {
          "Title" : "System Settings Saved"
        }
      }
    },
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
        "StringLike" : {
          "Title" : "System Settings Saved"
        }
      }
    }
  ]
}
```

Trend Micro Deep Security On-Premise 11.3

```
    }  
  }  
}  
]  
}
```

Multiple conditions

This is another example of what not to do. The first condition says to forward all events other than "System Settings Saved". The second condition says to forward all "System Settings Saved" events. The result is that no events will be forwarded because no events will match both the condition in the first statement **and** the one in the second statement:

```
{  
  "Version": "2014-09-24",  
  "Statement": [  
    {  
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",  
      "Condition": {  
        "StringNotLike" : {  
          "Title" : "System Settings Saved"  
        },  
        "StringLike" : {  
          "Title" : "System Settings Saved"  
        }  
      }  
    }  
  ]  
}
```

Trend Micro Deep Security On-Premise 11.3

```
]
}
```

Example SNS configurations

These configurations send matching events for some specific scenarios. For more event property names and values that you can use to filter SNS topics, see ["Events in JSON format" on page 1182](#).

Send all critical intrusion prevention events to an SNS topic

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:myTopic",
      "Condition": {
        "NumericEquals": {
          "Severity": 4
        },
        "StringEquals" : {
          "EventType" : "PayloadLog"
        }
      }
    }
  ]
}
```

Trend Micro Deep Security On-Premise 11.3

Send different events to different SNS topics

This example shows sending all system events to one topic and all integrity monitoring events to a different topic.

```
{
  "Version": "2014-09-24",
  "Statement": [
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:systemEventsTopic",
      "Condition": {
        "StringEquals" : {
          "EventType" : "SystemEvent"
        }
      }
    },
    {
      "Topic": "arn:aws:sns:us-east-1:012345678901:integrityTopic",
      "Condition": {
        "StringEquals" : {
          "EventType" : "IntegrityEvent"
        }
      }
    }
  ]
}
```


Events in JSON format

When published to Amazon SNS, events are sent in the SNS `Message` as an array of JSON objects that are encoded as strings. Each object in the array is one event.

Valid properties vary by the type of event. For example, `MajorVirusType` is a valid property only for Deep Security Anti-Malware events, not system events etc. Valid property values vary for each property. For examples, see ["Example events in JSON format" on page 1198](#).

Event property values can be used to filter which events are published to the SNS topic. For details, see ["SNS configuration in JSON format" on page 1161](#).

Valid event properties

Note: Some events don't have all of the properties that usually apply to their event type.

Property Name	Data Type	Description	Applies To Event Type(s)
Action	String (enum)	Action taken for the application control event, such as "Execution of Software Blocked by Rule", "Execution of Unrecognized Software Allowed" (due to detect-only mode) or "Execution of Unrecognized Software Blocked".	Application control events
Action	Integer (enum)	Action taken for the firewall event. "Detect Only" values show what would have happened if the rule had been enabled. 0=Unknown, 1=Deny, 6=Log Only, 0x81=Detect Only: Deny.	Firewall events
Action	Integer (enum)	Action taken for the intrusion prevention event. 0=Unknown, 1=Deny, 2=Reset, 3=Insert, 4=Delete, 5=Replace, 6=Log Only, 0x81=Detect Only: Deny, 0x82=Detect Only: Reset, 0x83=Detect Only: Insert, 0x84=Detect Only: Delete, 0x85=Detect Only: Replace.	Intrusion prevention events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
ActionBy	String	Name of the Deep Security Manager user who performed the event, or "System" if the event was not generated by a user.	System events
ActionString	String	Conversion of Action to a readable string.	Firewall events, intrusion prevention events
AdministratorID	Integer	Unique identifier of the Deep Security user who performed an action. Events generated by the system and not by a user will not have an identifier.	System events
AggregationType	Integer (enum)	Whether or not the Application Control event occurred repeatedly. If "AggregationType" is not "0", then the number of occurrences is in "RepeatCount." 0=Not aggregated, 1=Aggregated based on file name, path and event type, 2=Aggregated based on event type	Application control events
ApplicationType	String	Name of the network application type associated with the Intrusion Prevention rule, if available.	Intrusion prevention events
BlockReason	Integer (enum)	A reason that corresponds to the Action. 0=Unknown, 1=Blocked due to rule, 2=Blocked due to unrecognized	Application control events
Change	Integer (enum)	What type of change was made to a file, process, registry key, etc. for an Integrity Monitoring event. 1=Created, 2=Updated, 3=Deleted, 4=Renamed.	Integrity monitoring events
ContainerID	String	ID of the Docker container where the malware was found.	Anti-malware events
ContainerImageName	String	Image name of the Docker container where the malware was found.	Anti-malware events
ContainerName	String	Name of the Docker container where the malware was found.	Anti-malware events
Description	String	Description of the change made to the entity (created, deleted, updated) along with	Integrity monitoring events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
		details about the attributes changed.	
Description	String	Brief description of what happened during an event.	System events
DestinationIP	String (IP)	The IP address of the destination of a packet.	Firewall events, intrusion prevention events
DestinationMAC	String (MAC)	The MAC address of the destination of a packet.	Firewall events, intrusion prevention events
DestinationPort	Integer	The network port number a packet was sent to.	Firewall events, intrusion prevention events
DetectionCategory	Integer (enum)	The detection category for a web reputation event. 12=User Defined, 13=Custom, 91=Global.	Web reputation events
DetectOnly	Boolean	Whether or not the event was returned with the Detect Only flag turned on. If true, this indicates that the URL was not blocked, but access was detected.	Web reputation events
Direction	Integer (enum)	Network packet direction. 0=Incoming, 1=Outgoing.	Firewall events, intrusion prevention events
DirectionString	String	Conversion Direction to a readable string.	Firewall events, intrusion prevention events
DriverTime	Integer	The time the log was generated as recorded by the driver.	Firewall events, intrusion prevention events
EndLogDate	String (Date)	The last log date recorded for repeated events. Will not be present for events that did not repeat.	Firewall events, intrusion prevention events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
EngineType	Integer	The Anti-Malware engine type.	Anti-malware events
EngineVersion	String	The Anti-Malware engine version.	Anti-malware events
EntityType	String (enum)	The type of entity an integrity monitoring event applies to: Directory, File, Group, InstalledSoftware, Port, Process, RegistryKey, RegistryValue, Service, User, or Wql	Integrity monitoring events
ErrorCode	Integer	Error code for malware scanning events. If non-zero the scan failed, and the scan action and scan result fields contain more details.	Anti-malware events
EventID	Integer	The identifier of the event. Identifiers are unique per event type, but events of different types may share the same identifier. For example, it is possible for events with both EventType firewall and ips to have EventID equal to 1. The combination of EventID, EventType and TenantID are required to completely, uniquely identify an event in Deep Security. Note that this property is not related to the "Event ID" property of a System Event in the Deep Security Manager.	All event types
EventType	String (enum)	The type of the event. One of: "SystemEvent", "PacketLog", "PayloadLog", "AntiMalwareEvent", "WebReputationEvent", "IntegrityEvent", "LogInspectionEvent", "AppControlEvent".	All event types
FileName	String	File name of the software that was allowed or blocked, such as "script.sh". (The full path is separate, in "Path".)	Application control events
Flags	String	Flags recorded from a network packet; a space-separated list of strings.	Firewall events, intrusion prevention events
Flow	Integer (enum)	Network connection flow. Possible values: -1=Not Applicable, 0=Connection Flow, 1=Reverse Flow	Firewall events, intrusion prevention events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
FlowString	String	Conversion of Flow to a readable string.	Firewall events, intrusion prevention events
Frame	Integer (enum)	Frame type. -1=Unknown, 2048=IP, 2054=ARP, 32821=REVARP, 33169=NETBEUI, 0x86DD=IPv6	Firewall events, intrusion prevention events
FrameString	String	Conversion of Frame to a readable string.	Firewall events, intrusion prevention events
GroupID	String	The group ID, if any, of the user account that tried to start the software, such as "0".	Application control events
GroupName	String	The group name, if any, of the user account that tried to start the software, such as "root".	Application control events
HostAgentVersion	String	The version of the Deep Security Agent that was protecting the computer where the event was detected.	Anti-malware events, web reputation events, integrity monitoring events, log inspection events, firewall events, intrusion prevention events
HostAgentGUID	String	The global unique identifier (GUID) of the Deep Security Agent when activated with the Deep Security Manager.	Application control events
HostAssetValue	Integer	The asset value assigned to the computer at the time the event was generated.	Anti-malware events, web reputation events, integrity monitoring events, log inspection events, firewall events, intrusion prevention events, application control events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
HostGroupID	Integer	The unique identifier of the Computer Group of the computer where the event was detected.	Anti-malware events, web reputation events, integrity monitoring events, log inspection events, firewall events, intrusion prevention events
HostGroupName	String	The name of the Computer Group of the computer where the event was detected. Note that Computer Group names may not be unique.	Anti-malware events, web reputation events, integrity monitoring events, log inspection events, firewall events, intrusion prevention events
HostID	Integer	Unique identifier of the computer where the event occurred.	Anti-malware events, web reputation events, integrity monitoring events, log inspection events, firewall events, intrusion prevention events, application control events
HostInstanceID	String	The cloud instance ID of the computer where the event was detected. This property will only be set for computers synchronized with a Cloud Connector.	Anti-malware events, web reputation events, integrity monitoring events, log inspection events, firewall events, intrusion prevention events
Hostname	String	Hostname of the computer on which the event was generated.	Anti-malware events, web reputation events, integrity

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
			monitoring events, log inspection events, firewall events, intrusion prevention events, application control events
HostOS	String	The operating system of the computer where the event was detected.	Anti-malware events, web reputation events, integrity monitoring events, log inspection events, firewall events, intrusion prevention events, application control events
HostOwnerID	String	The cloud account ID of the computer where the event was detected. This property will only be set for computers synchronized with a Cloud Connector.	Anti-malware events, web reputation events, integrity monitoring events, log inspection events, firewall events, intrusion prevention events
HostSecurityPolicyID	Integer	The unique identifier of the Deep Security policy applied to the computer where the event was detected.	Anti-malware events, web reputation events, integrity monitoring events, log inspection events, firewall events, intrusion prevention events, application control events
HostSecurityPolicyName	String	The name of the Deep Security policy applied to the computer where the event was detected. Note that security policy names may not be unique.	Anti-malware events, web reputation events, integrity

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
			monitoring events, log inspection events, firewall events, intrusion prevention events, application control events
HostVCUID	String	The vCenter UUID of the computer the event applies to, if known.	Anti-malware events, web reputation events, integrity monitoring events, log inspection events, firewall events, intrusion prevention events
InfectedFilePath	String	Path of the infected file in the case of malware detection.	Anti-malware events
InfectionSource	String	The name of the computer that's the source of a malware infection, if known.	Anti-malware events
Interface	String (MAC)	MAC address of the network interface sending or receiving a packet.	Firewall events, intrusion prevention events
IPDatagramLength	Integer	The length of the IP datagram.	Intrusion prevention events
IsHash	String	The SHA-1 content hash (hexadecimal encoded) of the file after it was modified.	Integrity monitoring events
Key	String	The file or registry key an integrity event refers to.	Integrity monitoring events
LogDate	String (Date)	The date and time when the event was recorded. For Deep Security Agent-generated events (Firewall, IPS, etc.), the time is when the event was recorded by the agent, not when the event was received by Deep Security Manager.	All event types

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
MajorVirusType	Integer (enum)	The classification of malware detected. 0=Joke, 1=Trojan, 2=Virus, 3=Test, 4=Spyware, 5=Packer, 6=Generic, 7=Other	Anti-malware events
MajorVirusTypeString	String	Conversion of MajorVirusType to a readable string.	Anti-malware events
MalwareName	String	The name of the malware detected.	Anti-malware events
MalwareType	Integer (enum)	The type of malware detected. 1=General malware, 2=Spyware. General malware events will have an InfectedFilePath, spyware events will not.	Anti-malware events
ManagerNodeID	Integer	Unique identifier of the Deep Security Manager Node where the event was generated.	System events
ManagerNodeName	String	Name of the Deep Security Manager Node where the event was generated.	System events
MD5	String	The MD5 checksum (hash) of the software, if any.	Application control events
Number	Integer	System events have an additional ID that identifies the event. Note that in the Deep Security Manager, this property appears as "Event ID".	System events
Operation	Integer (enum)	0=Unknown, 1=Allowed due to detect-only mode, 2=Blocked	Application control
Origin	Integer (enum)	The origin of the event. -1=Unknown, 0=Deep Security Agent, 1=In-VM guest agent, 2=Deep Security Appliance, 3=Deep Security Manager	All event types
OriginString	String	Conversion of Origin to a human-readable string.	All event types
OSSEC_Action	String	OSSEC action	Log inspection events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
OSSEC_Command	String	OSSEC command	Log inspection events
OSSEC_Data	String	OSSEC data	Log inspection events
OSSEC_Description	String	OSSEC description	Log inspection events
OSSEC_DestinationIP	String	OSSEC dstip	Log inspection events
OSSEC_DestinationPort	String	OSSEC dstport	Log inspection events
OSSEC_DestinationUser	String	OSSEC dstuser	Log inspection events
OSSEC_FullLog	String	OSSEC full log	Log inspection events
OSSEC_Groups	String	OSSEC groups result (e.g. syslog,authentication_failure)	Log inspection events
OSSEC_Hostname	String	OSSEC hostname. This is the name of the host as read from a log entry, which is not necessarily the same as the name of the host on which the event was generated.	Log inspection events
OSSEC_ID	String	OSSEC id	Log inspection events
OSSEC_Level	Integer (enum)	OSSEC level. An integer in the range 0 to 15 inclusive. 0-3=Low severity, 4-7=Medium severity, 8-11=High severity, 12-15=Critical severity.	Log inspection events
OSSEC_Location	String	OSSEC location	Log inspection events
OSSEC_Log	String	OSSEC log	Log inspection events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
OSSEC_ProgramName	String	OSSEC program_name	Log inspection events
OSSEC_Protocol	String	OSSEC protocol	Log inspection events
OSSEC_RuleID	Integer	OSSEC rule id	Log inspection events
OSSEC_SourceIP	Integer	OSSEC srcip	Log inspection events
OSSEC_SourcePort	Integer	OSSEC srcport	Log inspection events
OSSEC_SourceUser	Integer	OSSEC srcuser	Log inspection events
OSSEC_Status	Integer	OSSEC status	Log inspection events
OSSEC_SystemName	Integer	OSSEC systemname	Log inspection events
OSSEC_URL	Integer	OSSEC url	Log inspection events
PacketData	Integer	Hexadecimal encoding of captured packet data, if the rule was configured to capture packet data.	Intrusion prevention events
PacketSize	Integer	The size of the network packet.	Firewall events
Path	String	Directory path of the software file that was allowed or blocked, such as "/usr/bin/". (The file name is separate, in "FileName".)	Application control events
PatternVersion	Integer (enum)	The malware detection pattern version.	Anti-malware events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
PayloadFlags	Integer	Intrusion Prevention Filter Flags. A bitmask value that can include the following flag values: 1 - Data truncated - Data could not be logged. 2 - Log Overflow - Log overflowed after this log. 4 - Suppressed - Logs threshold suppressed after this log. 8 - Have Data - Contains packet data. 16 - Reference Data - References previously logged data.	Intrusion prevention events
PosInBuffer	Integer	Position within packet of data that triggered the event.	Intrusion prevention events
PosInStream	Integer	Position within stream of data that triggered the event.	Intrusion prevention events
Process	String	The name of the process that generated the event, if available.	Integrity monitoring events
ProcessID	Integer	The identifier (PID) of the process that generated the event, if available.	Application control events
ProcessName	String	The name of the process that generated the event, if available, such as "/usr/bin/bash".	Application control events
Protocol	Integer (enum)	The numerical network protocol identifier. -1=Unknown, 1=ICMP, 2=IGMP, 3=GGP, 6=TCP, 12=PUP, 17=UDP, 22=IDP, 58=ICMPv6, 77=ND, 255=RAW	Firewall events, Intrusion prevention events
ProtocolString	String	Conversion of Protocol to a readable string.	Firewall events, intrusion prevention events
Rank	Integer	The numerical rank of the event; the product of the computer's assigned asset value and the severity value setting for an event of this severity.	Integrity monitoring events, log inspection events, firewall events, intrusion prevention events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
Reason	String	Name of the Deep Security rule or configuration object that triggered the event, or (for Firewall and Intrusion Prevention) a mapping of Status to String if the event was not triggered by a rule. For Application Control, "Reason" may be "None"; see "BlockReason" instead.	Firewall, intrusion prevention, integrity monitoring, anti-malware, and application control events
RepeatCount	Integer	The number of times this event occurred repeatedly. A repeat count of 1 indicates the event was only observed once and did not repeat.	Firewall events, intrusion prevention events, application control events
Risk	Integer (enum)	Translated risk level of the URL accessed. 2=Suspicious, 3=Highly Suspicious, 4=Dangerous, 5=Untested, 6=Blocked by Administrator	Web reputation events
RiskLevel	Integer	The raw risk level of the URL from 0 to 100. Will not be present if the URL was blocked by a block rule.	Web reputation events
RiskString	String	Conversion of Risk to a readable string.	Web reputation events
ScanAction1	Integer	Scan action 1. Scan action 1 & 2 and scan result actions 1 & 2 and ErrorCode are combined to form the single "summaryScanResult".	Anti-malware events
ScanAction2	Integer	Scan action 2.	Anti-malware events
ScanResultAction1	Integer	Scan result action 1.	Anti-malware events
ScanResultAction2	Integer	Scan result action 2.	Anti-malware events
ScanResultString	String	Malware scan result, as a string. A combination of ScanAction 1 and 2, ScanActionResult 1 and 2, and ErrorCode.	Anti-malware events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
ScanType	Integer (enum)	Malware scan type that created the event. 0=Real-Time, 1=Manual, 2=Scheduled, 3=Quick Scan	Anti-malware events
ScanTypeString	String	Conversion of ScanType to a readable string.	Anti-malware events
Severity	Integer	1=Info, 2=Warning, 3=Error	System events
Severity	Integer (enum)	1=Low, 2=Medium, 3=High, 4=Critical	Integrity monitoring events, intrusion prevention events
SeverityString	String	Conversion of Severity to a human-readable string.	System events, integrity monitoring events, intrusion prevention events
SeverityString	String	Conversion of OSSEC_Level to a human-readable string.	Log inspection events
SHA1	String	The SHA-1 checksum (hash) of the software, if any.	Application control events
SHA256	String	The SHA-256 checksum (hash) of the software, if any.	Application control events
SourceIP	String (IP)	The source IP address of a packet.	Firewall events, intrusion prevention events
SourceMAC	String (MAC)	The source MAC Address of the packet.	Firewall events, intrusion prevention events
SourcePort	Integer	The network source port number of the packet.	Firewall events, intrusion prevention events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
Status	Integer	If this event was not generated by a specific Firewall rule, then this status is one of approximately 50 hard-coded rules, such as 123=Out Of Allowed Policy	Firewall events
Status	Integer	If this event was not generated by a specific IPS rule, then this status is one of approximately 50 hard-coded reasons, such as -504=Invalid UTF8 encoding	Intrusion prevention events
Tags	String	Comma-separated list of tags that have been applied to the event. This list will only include tags that are automatically applied when the event is generated.	All event types
TagSetID	Integer	Identifier of the group of tags that was applied to the event.	All event types
TargetID	Integer	Unique identifier of the target of the event. This identifier is unique for the targets of the same type within a tenant. It is possible for target IDs to be reused across different types, for example, both a Computer and a Policy may have target ID 10.	System events
TargetIP	String (IP)	IP Address that was being contacted when a Web Reputation Event was generated.	Web reputation events
TargetName	String	The name of the target of the event. The target of a system event can be many things, including computers, policies, users, roles, and tasks.	System events
TargetType	String	The type of the target of the event.	System events
TenantID	Integer	Unique identifier of the tenant associated with the event.	All event types
TenantName	String	Name of the tenant associated with the event.	All event types
Title	String	Title of the event.	System events
URL	String	The URL being accessed that generated the event.	Web reputation events

Trend Micro Deep Security On-Premise 11.3

Property Name	Data Type	Description	Applies To Event Type(s)
	(URL)		
User	String	The user account that was the target of an integrity monitoring event, if known.	Integrity monitoring events
UserID	String	The user identifier (UID), if any, of the user account that tried to start the software, such as "0".	Application control events
UserName	String	The user name, if any, of the user account that tried to start the software, such as "root".	Application control events

Data types of event properties

Events forwarded as JSON usually use strings to encode other data types.

Data Type	Description
Boolean	JSON <code>true</code> or <code>false</code> .
Integer	JSON <code>int</code> . Deep Security does not output floating point numbers in events. Note: Integers in events may be more than 32 bits. Verify the code that processes events can handle this. For example, JavaScript's <code>Number</code> data type cannot safely handle larger than 32-bit integers .
Integer (enum)	JSON <code>int</code> , restricted to a set of enumerated values.
String	JSON <code>string</code> .

Trend Micro Deep Security On-Premise 11.3

Data Type	Description
String (Date)	JSON <code>string</code> , formatted as a date and time in the pattern YYYY-MM-DDThh:mm:ss.sssZ (ISO 8601). 'Z' is the time zone. 'sss' are the three digits for sub-seconds. See also the W3C note on date and time formats .
String (IP)	JSON <code>string</code> , formatted as an IPv4 or IPv6 address.
String (MAC)	JSON <code>string</code> , formatted as a network MAC address.
String (URL)	JSON <code>string</code> , formatted as a URL.
String (enum)	JSON <code>string</code> , restricted to a set of enumerated values.

Example events in JSON format

System event

```
{
  "Type" : "Notification",
  "MessageId" : "123abc-123-123-123-123abc",
  "TopicArn" : "arn:aws:sns:us-west-2:123456789:DS_Events",
  "Message" : "[
    {
      \"ActionBy\":\"System\",
      \"Description\":\"Alert: New Pattern Update is Downloaded and
Available\\nSeverity: Warning\",
```

Trend Micro Deep Security On-Premise 11.3

```
        "EventID":6813,
        "EventType":"SystemEvent",
        "LogDate":"2018-12-04T15:54:24.086Z",
        "ManagerNodeID":123,
        "ManagerNodeName":"job7-123",
        "Number":192,
        "Origin":3,
        "OriginString":"Manager",
        "Severity":1,
        "SeverityString":"Info",
        "Tags":"\\",
        "TargetID":1,
        "TargetName":"ec2-12-123-123-123.us-west-
2.compute.amazonaws.com",
        "TargetType":"Host",
        "TenantID":123,
        "TenantName":"Umbrella Corp.",
        "Title":"Alert Ended"
    }
],
"Timestamp" :      "2018-12-04T15:54:25.130Z",
"SignatureVersion" : "1",
"Signature" :      "500PER10NG5!gnaTURE==",
"SigningCertURL" :  "https://sns.us-west-2.amazonaws.com/SimpleNotificationService-
```

Trend Micro Deep Security On-Premise 11.3

```
abc123.pem",
  "UnsubscribeURL" : "https://sns.us-west-
2.amazonaws.com/?Action=Unsubscribe&SubscriptionArn=arn:aws:sns:us-west-2:123456:DS_
Events:123abc-123-123-123-123abc"
}
```

Anti-malware events

Multiple virus detection events can be in each SNS `Message`. (For brevity, repeated event properties are omitted below, indicated by "...".)

```
{
  "Type" : "Notification",
  "MessageId" : "123abc-123-123-123-123abc",
  "TopicArn" : "arn:aws:sns:us-west-2:123456789:DS_Events",
  "Message" : "[
    {
      "AMTargetTypeString": "N/A",
      "ATSEDetectionLevel": 0,
      "CreationTime": "2018-12-04T15:57:18.000Z",
      "EngineType": 1207959848,
      "EngineVersion": "10.0.0.1040",
      "ErrorCode": 0,
      "EventID": 1,
      "EventType": "AntiMalwareEvent",
```

Trend Micro Deep Security On-Premise 11.3

```
"HostAgentGUID":"4A5BF25A-4446-DD8B-DFB7-564C275F5F6B",
"HostAgentVersion":"11.1.0.163",
"HostID":1,
"HostOS":"Amazon Linux (64 bit) (4.14.62-65.117.amzn1.x86_64)",
"HostSecurityPolicyID":3,
"HostSecurityPolicyName":"PolicyA",
"Hostname":"ec2-12-123-123-123.us-west-
2.compute.amazonaws.com",
"InfectedFilePath":"/tmp/eicar_1543939038890.txt",
"LogDate":"2018-12-04T15:57:19.000Z",
"MajorVirusType":2,
"MajorVirusTypeString":"Virus",
"MalwareName":"Eicar_test_file",
"MalwareType":1,
"ModificationTime":"2018-12-04T15:57:18.000Z",
"Origin":0,
"OriginString":"Agent",
"PatternVersion":"14.665.00",
"Protocol":0,
"Reason":"Default Real-Time Scan Configuration",
"ScanAction1":4,
"ScanAction2":3,
"ScanResultAction1":-81,
"ScanResultAction2":0,
```

Trend Micro Deep Security On-Premise 11.3

```
        "ScanResultString": "Quarantined",
        "ScanType": 0,
        "ScanTypeString": "Real Time",
        "Tags": "\\",
        "TenantID": 123,
        "TenantName": "Umbrella Corp."},
    {
        "AMTargetTypeString": "N/A",
        "ATSEDetectionLevel": 0,
        "CreationTime": "2018-12-04T15:57:21.000Z",
        ...},
    {
        "AMTargetTypeString": "N/A",
        "ATSEDetectionLevel": 0,
        "CreationTime": "2018-12-04T15:57:29.000Z",
        ...
    }
],
"Timestamp" : "2018-12-04T15:57:50.833Z",
"SignatureVersion" : "1",
"Signature" : "500PER10NG5!gnaTURE==",
"SigningCertURL" : "https://sns.us-west-2.amazonaws.com/SimpleNotificationService-
abc123.pem",
"UnsubscribeURL" : "https://sns.us-west-
```

Trend Micro Deep Security On-Premise 11.3

```
2.amazonaws.com/?Action=Unsubscribe&SubscriptionArn=arn:aws:sns:us-west-2:123456:DS_Events:123abc-123-123-123-123abc"
}
```

DevOps, automation and scaling

DevOps, automation and scaling

To support DevOps workflows, Deep Security offers APIs to automate, monitor, and manage security throughout the release lifecycle. (See ["Use the Deep Security API to automate tasks" on page 417.](#))

To accelerate integration with popular DevOps tools, we've provided the following resources in Github for Chef, Puppet, and Ansible:

- <https://github.com/deep-security/puppet>
- <https://github.com/deep-security/chef>
- <https://github.com/deep-security/ansible>

These resources provide a starting point to integrate Deep Security with your specific deployment, including agent deployment and configuration and support for elastic workloads.

Deep Security also offers many other ways to speed up the protection of your computers and other resources:

- ["Schedule Deep Security to perform tasks" on page 418](#)
- ["Automatically perform tasks when a computer is added or changed" on page 422](#)
- ["AWS Auto Scaling and Deep Security" on page 427](#)

Trend Micro Deep Security On-Premise 11.3

- ["Use deployment scripts to add and protect computers" on page 437](#)
- ["Automatically assign policies by AWS instance tags" on page 441](#)
- ["Command-line basics" on page 390](#)

In addition, Deep Security provides the ability to forward events to SIEMs such as Splunk, QRadar, ArcSight, as well as Amazon SNS. For details, see:

- ["Forward Deep Security events to an external syslog or SIEM server" on page 1111](#)
- ["Access events with Amazon SNS" on page 1158](#)

Forward system events to a remote computer via SNMP

Deep Security supports SNMP for forwarding system events to a computer from Deep Security Manager. On Windows, the MIB file ("DeepSecurity.mib") is located in \Trend Micro\Deep Security Manager\util. On Linux, the default location is /opt/dsm/util.

Lists of events and alerts

The following sections list all of the Deep Security alerts and events you could encounter.

- ["Predefined alerts" on the next page](#)
- ["Agent events" on page 1215](#)
- ["System events" on page 1220](#)
- ["Anti-malware events" on page 1251](#)
- ["Firewall events" on page 1254](#)
- ["Intrusion prevention events" on page 1264](#)

- ["Integrity monitoring events" on page 1269](#)
- ["Log inspection events" on page 1272](#)

Predefined alerts

Alert	Default Severity	Dismissible	Description
Abnormal Restart Detected	Warning	Yes	<p>An abnormal restart has been detected on the computer. This condition may be caused by a variety of conditions. If the agent/appliance is suspected as the root cause then the diagnostics package (located in the Support section of the Computer Details dialog) should be invoked.</p> <p>This alert indicates that the Deep Security Agent service was restarted abnormally. You can safely dismiss this alert, or, if the alert reoccurs, create a diagnostics package and open a case with Technical Support.</p>
Activation Failed	Critical	No	<p>This may indicate a problem with the agent/appliance, but it also can occur if agent self-protection is enabled. On the Deep Security Manager, go to Computer editor¹ > Settings > General. In Agent Self Protection, and then either deselect Prevent local end-users from uninstalling, stopping, or otherwise modifying the Agent or enter a password for local override.</p>
A Deep Security Relay cannot download security components	Critical	No	<p>A Deep Security Relay can't successfully download security components. This might be due to network connectivity issues or misconfigurations in Deep Security Manager under Administration > System Settings > Updates. Check your network configurations (for example, the proxy settings of the relay group) and System Settings, and then manually initiate an update on the relay using the Download Security Update option on the Administration > Updates > Software page.</p>
Agent configuration package too large	Warning	Yes	<p>This is usually caused by too many firewall and intrusion prevention rules being assigned. Run a recommendation scan on the computer to determine if any rules can be safely unassigned.</p>
Agent Installation Failed	Critical	Yes	<p>The agent failed to install successfully on one or more computers. Those computers</p>

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

Alert	Default Severity	Dismissible	Description
			<p>are currently unprotected. You must reboot the computers which will automatically restart the agent install program.</p> <p>This may indicate a problem with the agent/appliance, but it also can occur if agent self-protection is enabled. On the Deep Security Manager, go to Computer editor¹ > Settings > General. In Agent Self Protection, and then either deselect Prevent local end-users from uninstalling, stopping, or otherwise modifying the Agent or enter a password for local override.</p>
Agent Upgrade Recommended (Incompatible with Appliance)	Warning	No	Deep Security Manager has detected a computer with a version of the agent that is not compatible with the appliance. The appliance will always filter network traffic in this configuration resulting in redundant protection. (Deprecated in 9.5)
Agent/Appliance Upgrade Recommended	Warning	No	The Deep Security Manager has detected an older agent/appliance version on the computer that does not support all available features. An upgrade of the agent/appliance software is recommended. (Deprecated in 9.5)
Agent/Appliance Upgrade Recommended (Incompatible Security Update(s))	Warning	No	Deep Security Manager has detected a computer with a version of the agent/appliance that is not compatible with one or more security updates assigned to it. An upgrade of the agent/appliance software is recommended.
Agent/Appliance Upgrade Recommended (New Version Available)	Warning	No	Deep Security Manager has detected one or more computers with a version of the agent/appliance that is older than the latest version imported into the manager. An upgrade of the agent/appliance software is recommended.
Agent/Appliance Upgrade Required	Warning	No	Deep Security Manager has detected a computer with a version of the agent/appliance that is not compatible with this version of the manager. An upgrade of the agent/appliance software is required.
An update to the Rules is available	Warning	No	Updated rules have been downloaded but not applied to your policies. To apply the rules, go to Administration > Updates > Security and in the Rule Updates column, click Apply Rules to Policies .
Anti-Malware Alert	Warning	Yes	A malware scan configuration that is configured for alerting has raised an event on one or more computers.
Anti-Malware	Critical	Yes	An anti-malware component failed on one or more computers. See the event descriptions on the individual

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

Alert	Default Severity	Dismissible	Description
Component Failure			computers for specific details.
Anti-Malware Component Update Failed	Warning	No	One or more agent or relay failed to update anti-malware components. See the affected computers for more information.
Anti-Malware Engine Offline	Critical	No	The agent or appliance has reported that the anti-malware engine is not responding. Please check the system events for the computer to determine the cause of the failure.
Anti-Malware protection is absent or out of date	Warning	No	The agent on this computer has not received its initial anti-malware protection package, or its anti-malware protection is out of date. Make sure a relay is available and that the agent has been properly configured to communicate with it. To configure relays and other update options, go to Administration > System Settings > Updates.
Anti-malware module maximum disk space used to store identified files exceeded	Warning	Yes	The Anti-Malware module was unable to analyze or quarantine a file because the maximum disk space used to store identified files was reached. To change the maximum disk space for identified files setting, open the computer or policy editor and go to the Anti-malware > Advanced tab.
Application Control Ruleset is incompatible with agent version	Critical	No	An application control ruleset could not be assigned to one or more computers because the ruleset is not supported by the installed version of the agent. Typically, the problem is that a hash-based ruleset (which is compatible only with Deep Security Agent 11.0 or newer) has been assigned to an older Deep Security Agent. Deep Security Agent 10.x supports only file-based rulesets. (For details, see "Differences in how Deep Security Agent 10.x and 11.x compare files" on page 632.) To fix this issue, upgrade the Deep Security Agent to version 11.0 or newer. Alternatively, if you are using local rulesets, reset application control for the agent. Or if you are using a shared ruleset, use a shared ruleset that was created with Deep Security 10.x until all agents using the shared ruleset are upgraded to Deep Security Agent 11.0 or newer.
Application Type Misconfiguration	Warning	No	Misconfiguration of application types may prevent proper security coverage.
Application Type Recommendation	Warning	Yes	Deep Security Manager has determined that a computer should be assigned an application type. This could be because an agent was installed on a new computer and vulnerable applications were detected, or because a new vulnerability has been discovered in an installed application that was previously thought to be safe. To assign the application type to the computer, open the 'Computer Details' dialog box, click on 'Intrusion Prevention Rules', and assign the application type.
Maintenance Mode Active	Warning	No	Maintenance mode is currently active for application control on one or more computers. While this mode is active, application control continues to enforce block rules (if you selected Block unrecognized software until it is explicitly allowed), but will allow software updates, and automatically add them to the inventory part of the ruleset. When the software update is finished for each computer, disable maintenance mode so

Trend Micro Deep Security On-Premise 11.3

Alert	Default Severity	Dismissible	Description
			that unauthorized software is not accidentally added to the ruleset.
Census, Good File Reputation, and Predictive Machine Learning Service Disconnected			<p>Disconnected from Census, Good File Reputation, and Predictive Machine Learning Service. Please see the event details below for possible solutions.</p> <p>Refer to "Warning: Census, Good File Reputation, and Predictive Machine Learning Service Disconnected" on page 1302 for troubleshooting tips.</p>
Certified Safe Software Service Offline	Warning	No	A Deep Security Manager node cannot connect to the Trend Micro Certified Safe Software Service to perform file signature comparisons for the integrity monitoring module. A locally cached database will be used until connectivity is restored. Make sure the manager node has internet connectivity and that proxy settings (if any) are correct.
Clock Change Detected	Warning	Yes	A clock change has been detected on the computer. Unexpected clock changes may indicate a problem on the computer and should be investigated before the alert is dismissed.
Cloud Computer Not Managed as Part of Cloud Account	Warning	Yes	An agent was activated on one or more Amazon WorkSpace but WorkSpaces are not enabled for your AWS account. To enable WorkSpaces, click 'Edit AWS Account' above, and select the 'Include Amazon WorkSpaces' check box. Your Workspace(s) are moved into the WorkSpaces folder of the AWS Account.
Communications Problem Detected	Warning	Yes	A communications problem has been detected on the computer. Communications problems indicate that the computer cannot initiate communication with the Deep Security Manager(s) because of network configuration or load reasons. Please check the system events in addition to verifying communications can be established to the Deep Security Manager(s) from the computer. The cause of the issue should be investigated before the alert is dismissed.
Computer Not Receiving Updates	Warning	No	These computer(s) have stopped receiving updates. Manual intervention may be required.
Computer Reboot Required	Critical	Yes	The agent software upgrade was successful, but the computer must be rebooted for the install to be completed. The computer(s) should be manually updated before the alert is dismissed.
Computer Reboot Required for Anti-Malware Protection	Critical	No	The anti-malware protection on the agent has reported that the computer needs to be rebooted. Please check the system events for the computer to determine the reason for the reboot.
Configuration Required	Warning	No	One or more computers are using a policy that defines multiple interface types where not all interfaces have been mapped.
Connection to Filter Driver Failure	Critical	No	An appliance has reported a failure connecting to the filter driver. This may indicate a configuration issue with the filter driver running on the ESXi or with the appliance. The appliance must be able to connect to the filter driver in order to protect guests. The cause of the issue should be investigated and resolved.

Trend Micro Deep Security On-Premise 11.3

Alert	Default Severity	Dismissible	Description
CPU Critical Threshold Exceeded	Critical	No	The CPU critical threshold has been exceeded.
CPU Warning Threshold Exceeded	Warning	No	The CPU warning threshold has been exceeded.
Duplicate Computer Detected	Warning	Yes	A duplicate computer has been activated or imported. Please remove the duplicate computer and reactivate the original computer if necessary.
Duplicate Unique Identifiers Detected	Warning	No	Duplicate UUIDs have been detected. Please remove the duplicate UUID.
Empty Relay Group Assigned	Critical	No	These computers have been assigned an empty relay group. Assign a different relay group to the computers or add relays to the empty relay group(s).
Events Suppressed	Warning	Yes	The agent/appliance encountered an unexpectedly high volume of events. As a result, one or more events were not recorded (suppressed) to prevent a potential denial of service. Check the firewall events to determine the cause of the suppression.
Events Truncated	Warning	Yes	Some events were lost because the data file grew too large for the agent/appliance to store. This may have been caused by an unexpected increase in the number of events being generated, or the inability of the agent/appliance to send the data to the Deep Security Manager. For more information, see the properties of the "Events Truncated" system event on the computer.
Files Could Not Be Scanned for Malware	Warning	No	Files could not be scanned for malware because the file path exceeded the maximum file path length limit or the directory depth exceeded the maximum directory depth limit. Please check the system events for the computer to determine the reason.
Firewall Engine Offline	Critical	No	The agent/appliance has reported that the firewall engine is offline. Please check the status of the engine on the agent/appliance.
Firewall Rule Alert	Warning	Yes	A firewall rule that is selected for alerting has been encountered on one or more computers.
Firewall Rule Recommendation	Warning	Yes	Deep Security Manager has determined that a computer on your network should be assigned a firewall rule. This could be because an agent was installed on a new computer and vulnerable applications were detected, or because a new vulnerability has been discovered in an installed application that was previously thought to be safe. To assign the firewall rule to the computer, open the 'Computer Details' dialog box, click on the 'Firewall Rules' node, and assign the firewall rule.
Heartbeat Server Failed	Warning	No	The heartbeat server failed to start properly. This may be due to a port number conflict. Agents/appliances will not be able to contact the manager until this problem is resolved. To resolve this problem ensure that another service is not using the port number reserved for use by the heartbeat server and "Restart the Deep Security Manager" on page 979 service. If you do not wish to use the heartbeat you can turn this alert off in the Alert Configuration section.

Trend Micro Deep Security On-Premise 11.3

Alert	Default Severity	Dismissible	Description
Incompatible Agent/Appliance Version	Warning	No	Deep Security Manager has detected a more recent agent/appliance version on the computer that is not compatible with this version of the manager. An upgrade of the manager software is recommended.
Insufficient Disk Space	Warning	Yes	The agent/appliance has reported that it was forced to delete an old log file to free up disk space for a new log file. Please immediately free up disk space to prevent loss of intrusion prevention, firewall and agent/appliance events. See "Warning: Insufficient disk space" on page 1306 .
Integrity Monitoring Engine Offline	Critical	No	The agent/appliance has reported that the integrity monitoring engine is not responding. Please check the system events for the computer to determine the cause of the failure.
Integrity Monitoring information collection has been delayed	Warning	No	The rate at which integrity monitoring information is collected has been temporarily delayed due to an increased amount of integrity monitoring data. During this time the baseline and integrity event views may not be current for some computers. This alert will be dismissed automatically once integrity monitoring data is no longer being delayed.
Integrity Monitoring Rule Alert	Warning	Yes	An integrity monitoring rule that is selected for alerting has been encountered on one or more computers.
Integrity Monitoring Rule Compilation Error	Critical	No	An error was encountered compiling an integrity monitoring rule on a computer. This may result in the integrity monitoring rule not operating as expected.
Integrity Monitoring Rule Recommendation	Warning	Yes	Deep Security Manager has determined that a computer on your network should be assigned an integrity monitoring rule. To assign the integrity monitoring rule to the computer, open the 'Computer Details' dialog box, click on the 'Integrity Monitoring > Integrity Monitoring Rules' node, and assign the integrity monitoring rule.
Integrity Monitoring Rule Requires Configuration	Warning	No	An integrity monitoring rule that requires configuration before use has been assigned to one or more computers. This rule will not be sent to the computer(s). Open the integrity monitoring rule properties and select the Configuration tab for more information.
Integrity Monitoring Trusted Platform Module Not Enabled	Warning	Yes	Trusted platform module not enabled. Please ensure the hardware is installed and the BIOS setting is correct.
Integrity Monitoring Trusted Platform Module Register Value Changed	Warning	Yes	Trusted platform module register value changed. If you have not modified the ESXi hypervisor configuration this may represent an attack.
Intrusion Prevention Engine Offline	Critical	No	The agent/appliance has reported that the intrusion prevention engine is offline. Please check the status of the engine on the agent/appliance.
Intrusion Prevention Rule Alert	Warning	Yes	An intrusion prevention rule that is selected for alerting has been encountered on one or more computers.
Intrusion Prevention	Warning	Yes	Deep Security Manager has determined that a computer on your network should be assigned an intrusion

Trend Micro Deep Security On-Premise 11.3

Alert	Default Severity	Dismissible	Description
Rule Recommendation			prevention rule. This could be because an agent was installed on a new computer and vulnerable applications were detected, or because a new vulnerability has been discovered in an installed application that was previously thought to be safe. To assign the intrusion prevention rule to the computer, open the 'Computer Details' dialog box, click on 'Intrusion Prevention Rules', and assign the intrusion prevention rule.
Intrusion Prevention Rule Removal Recommendation	Warning	Yes	Deep Security Manager has determined that a computer on your network has an intrusion prevention rule assigned to it that is not required. This could be because a vulnerable application was uninstalled, an existing vulnerability was patched, or the rule was unnecessarily assigned to begin with. To unassign the intrusion prevention rule from the computer, open the 'Computer Details' dialog box, click on Intrusion Prevention > Intrusion Prevention Rules, and clear the checkbox next to the intrusion prevention rule.
Intrusion Prevention Rule Requires Configuration	Warning	No	An intrusion prevention rule that requires configuration before use has been assigned to one or more computers. This rule will not be sent to the computer(s). Open the intrusion prevention rule properties and select the Configuration tab for more information.
Log Inspection Engine Offline	Critical	No	The agent/appliance has reported that the log inspection engine has failed to initialize. Please check the system events for the computer to determine the cause of the failure.
Log Inspection Rule Alert	Warning	Yes	A log inspection rule that is selected for alerting has been encountered on one or more computers.
Log Inspection Rule Recommendation	Warning	Yes	Deep Security Manager has determined that a computer on your network should be assigned a log inspection rule. To assign the log inspection rule to the computer, open the 'Computer Details' dialog box, click on the 'Log Inspection > Log Inspection Rules' node, and assign the log inspection rule.
Log Inspection Rule Requires Configuration	Warning	No	A log inspection rule that requires configuration before use has been assigned to one or more computers. This rule will not be sent to the computer(s). Open the Log Inspection Rule properties and select the Configuration tab for more information.
Low Disk Space	Warning	No	A Deep Security Manager Node has less than 10% remaining disk space. Please free space by deleting old or unnecessary files, or add more storage capacity.
Manager Offline	Warning	No	A Deep Security Manager node is offline. It is possible the computer has a hardware or software problem, or has simply lost network connectivity. Please check the status of the manager's computer.
Manager Time Out of Sync	Critical	No	The clock on each manager node must be synchronized with the clock on the database. If the clocks are too far out of sync (more than 30 seconds) the manager node will not perform its tasks correctly. Synchronize the clock on your manager node with the clock on the database.
Memory Critical Threshold Exceeded	Critical	No	The memory critical threshold has been exceeded.
Memory Warning Threshold Exceeded	Warning	No	The memory warning threshold has been exceeded.

Trend Micro Deep Security On-Premise 11.3

Alert	Default Severity	Dismissible	Description
Multiple Activated Appliances Detected	Warning	Yes	The appliance has reported that multiple connections have been made to the filter driver on the same ESXi. This indicates that there may be multiple activated Appliances running on the same ESXi, which is not supported. The cause of the issue should be investigated before the alert is dismissed.
Network Engine Mode Incompatibility	Warning	No	Setting "Network Engine Mode" to "Tap" is only available on agent versions 5.2 or higher. Review and update the agent's configuration or upgrade the agent to resolve the incompatibility.
New Pattern Update is Downloaded and Available	Warning	No	New patterns are available as part of a security update. The patterns have been downloaded to Deep Security but have not yet been applied to your computers. To apply the update to your computers, go to the Administration > Updates > Security page.
New Rule Update is Downloaded and Available	Warning	No	New rules are available as part of a security update. The rules have been downloaded to Deep Security but have not yet been applied to policies and sent to your computers. To apply the update and send the updated policies to your computers, go to the Administration > Updates > Security page.
Newer Version of Deep Security Manager is Available	Warning	No	A new version of the Deep Security Manager is available. Download the latest version from the Trend Micro Download Center at http://downloadcenter.trendmicro.com/
Newer Versions of Software Available	Warning	No	New software is available. Software can be downloaded from the Download Center.
Number of Computers exceeds database limit	Warning	No	The number of activated computers has exceeded the recommended limit for an embedded database. Performance will degrade rapidly if more computers are added and it is strongly suggested that another database option (Oracle or SQL Server) be considered at this point. Please contact Trend Micro for more information on upgrading your database.
Protection Module Licensing Expired	Warning	Yes	The protection module license has expired.
Protection Module Licensing Expires Soon	Warning	No	The protection module licensing will expire soon. You can remove this alert by changing your license on the Administration > Licenses page.
Recommendation	Warning	Yes	Deep Security Manager has determined that the security configuration of one of your computers should be updated. To see what changes are recommended, open the Computer editor ¹ and look through the module pages for warnings of unresolved recommendations. In the Assigned Rules area, click Assign/Unassign to display the list of available rules and then filter them using the "Show Recommended for Assignment" viewing filter option. (Select "Show Recommended for Unassignment" to display rules that can safely be unassigned.)

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

Alert	Default Severity	Dismissible	Description
Reconnaissance Detected: Computer OS Fingerprint Probe	Warning	Yes	The agent or appliance detected an attempt to identify the computer operating system via a "fingerprint" probe. Such activity is often a precursor to an attack that targets specific vulnerabilities. Check the computer's events to see the details of the probe and see "Warning: Reconnaissance Detected" on page 1304 .
Reconnaissance Detected: Network or Port Scan	Warning	Yes	The agent or appliance detected network activity typical of a network or port scan. Such activity is often a precursor to an attack that targets specific vulnerabilities. Check the computer's events to see the details of the probe and see "Warning: Reconnaissance Detected" on page 1304 .
Reconnaissance Detected: TCP Null Scan	Warning	Yes	The agent or appliance detected a TCP "Null" scan. Such activity is often a precursor to an attack that targets specific vulnerabilities. Check the computer's events to see the details of the probe and see "Warning: Reconnaissance Detected" on page 1304 .
Reconnaissance Detected: TCP SYNFIN Scan	Warning	Yes	The agent or appliance detected a TCP "SYNFIN" scan. Such activity is often a precursor to an attack that targets specific vulnerabilities. Check the computer's events to see the details of the probe and see "Warning: Reconnaissance Detected" on page 1304 .
Reconnaissance Detected: TCP Xmas Scan	Warning	Yes	The agent or appliance detected a TCP "Xmas" scan. Such activity is often a precursor to an attack that targets specific vulnerabilities. Check the computer's events to see the details of the probe and see "Warning: Reconnaissance Detected" on page 1304 .
SAP Virus Scan Adapter is not installed	Critical	No	The agent has reported that the SAP Virus Scan Adapter is not installed. Check the system events for the computer to determine the cause of the failure.
SAP Virus Scan Adapter is not up to date	Critical	No	The agent has reported that the SAP Virus Scan Adapter is not up to date. Check the system events for the computer to determine the cause of the failure.
Scheduled Malware Scan Missed	Warning	No	Scheduled malware scan tasks were initiated on computers that already had pending scan tasks. This may indicate a scanning frequency that is too high. Consider lowering the scanning frequency, or selecting fewer computers to scan during each scheduled scan job.
Send Policy Failed	Critical	No	Inability to send policy may indicate a problem with the agent/appliance. Please check the affected computers.
Smart Protection Server Connection Failed	Warning	Yes	Failed to connect to a Smart Protection Server. This could be due to a configuration issue, or due to network connectivity.
Software Package Not Found	Critical	No	An agent software package is required for the proper operation of one or more virtual appliance(s). Please import a Red Hat Enterprise Linux 6 (64 bit) agent software package with the correct version for each appliance. If the required version is not available then please import the latest package and upgrade the appliance to match.
Software Updates Available for Import	Warning	No	New software is available. To import new software to Deep Security, go to Administration > Updates > Software > Download Center.

Trend Micro Deep Security On-Premise 11.3

Alert	Default Severity	Dismissible	Description
Unable to communicate	Critical	No	Deep Security Manager has been unable to query the agent/appliance for its status within the configured period. Please check your network configuration and the affected computer's connectivity.
Unable to Upgrade the Agent Software	Warning	Yes	<p>Deep Security Manager was unable to upgrade the agent software on the computer.</p> <p>This may indicate a problem with the agent/appliance, but it also can occur if agent self-protection is enabled. On the Deep Security Manager, go to Computer editor¹ > Settings > General. In Agent Self Protection, and then either deselect Prevent local end-users from uninstalling, stopping, or otherwise modifying the Agent or enter a password for local override.</p>
Unrecognized Software Detected	Warning	No	During ongoing file system monitoring, application control detected that new software had been installed, and it did not match any configured allow or block rule. If your system administrators did not install the software, and no other users have permissions to install software, this could indicate a security compromise. If the software tries to launch, depending on your lockdown configuration at that time, it may or may not be allowed to execute.
Unresolved software change limit	Critical	No	Software changes detected on the file system exceeded the maximum amount. Application control will continue to enforce existing rules, but will not record any more changes, and it will stop displaying any of that computer's software changes. You must resolve and prevent excessive software change.
Upgrade of the Deep Security Manager Software Recommended (Incompatible Security Update(s))	Warning	No	Deep Security Manager has detected a computer that is using security updates that are not compatible with the current version of Deep Security Manager. An upgrade of Deep Security Manager software is recommended.
Upgrade of the Filter Driver Recommended (New Version Available)	Warning	No	Deep Security Manager has detected one or more ESXi Servers with a version of the filter driver that does not match the latest version available. An upgrade of the filter driver is recommended.
User Locked Out	Warning	No	Users can be locked out manually, by repeated incorrect sign-in attempts, if their password expires, or if they have been imported but not yet unlocked.
User Password Expires	Warning	No	The password expiry setting is enabled and one or more users have passwords that will expire within the

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

Alert	Default Severity	Dismissible	Description
Soon			next 7 days.
Virtual Appliance is Incompatible With Filter Driver	Warning	No	The appliance is incompatible with the filter driver. Please ensure both are upgraded to their latest versions.
Virtual Machine Interfaces Out of Sync	Warning	No	One or more of the virtual machines monitored by a Deep Security Virtual Appliance has reported that its interfaces are out of sync with the filter driver. This means that the appliance may not be properly monitoring the virtual machine's interfaces. The virtual machine may require manual intervention such as a configuration change, or a restart, to correct the issue.
Virtual Machine Moved to Unprotected ESXi Server	Warning	Yes	A virtual machine was moved to an ESXi Server that does not have an activated Deep Security Virtual Appliance.
Virtual Machine Unprotected after move to another ESXi	Warning	Yes	A virtual machine that was appliance-protected has been unprotected during or after it was moved to another ESXi. This may be due to an appliance reboot or power off during the move, or it may indicate a configuration issue. The cause of the issue should be investigated before the alert is dismissed.
VMware Tools Not Installed	Critical	Yes	A protected virtual machine in an NSX environment does not have VMware Tools installed. VMware Tools is required to protect virtual machines in an NSX environment.
Web Reputation Event Alert	Warning	Yes	A web reputation event has been encountered on one or more computers that are selected for alerting.
WorkSpaces Disabled for AWS Account	Warning	Yes	An agent was activated on one or more Amazon WorkSpaces but WorkSpaces are not enabled for your AWS account. To enable WorkSpaces, click 'Edit AWS Account' above, and select the 'Include Amazon WorkSpaces' check box. Your Workspace(s) will be moved into the WorkSpaces folder of the AWS account.

Agent events

ID	Severity	Event	Notes
Special Events			
0	Error	Unknown Agent/Appliance Event	
Driver-Related Events			
1000	Error	Unable To Open Engine	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Notes
1001	Error	Engine Command Failed	
1002	Warning	Engine List Objects Error	
1003	Warning	Remove Object Failed	
1004	Error	Driver Upgrade Stalled	
1005	Warning	Upgrading Driver	
1006	Warning	Driver Upgrade Requires Reboot	
1007	Warning	Driver Upgrade Succeeded	
1008	Error	Kernel Unsupported	
Configuration-Related Events			
2000	Info	Policy Sent	
2001	Warning	Invalid Firewall Rule Assignment	
2002	Warning	Invalid Firewall Stateful Configuration	
2003	Error	Save Security Configuration Failed	
2004	Warning	Invalid Interface Assignment	
2005	Warning	Invalid Interface Assignment	
2006	Warning	Invalid Action	
2007	Warning	Invalid Packet Direction	
2008	Warning	Invalid Rule Priority	
2009	Warning	Unrecognized IP Format	
2010	Warning	Invalid Source IP List	
2011	Warning	Invalid Source Port List	
2012	Warning	Invalid Destination IP List	
2013	Warning	Invalid Destination Port List	
2014	Warning	Invalid Schedule	
2015	Warning	Invalid Source MAC List	
2016	Warning	Invalid Destination MAC List	
2017	Warning	Invalid Schedule Length	
2018	Warning	Invalid Schedule String	
2019	Warning	Unrecognized IP Format	
2020	Warning	Object Not Found	
2021	Warning	Object Not Found	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Notes
2022	Warning	Invalid Rule Assignment	
2050	Warning	Firewall Rule Not Found	
2075	Warning	Traffic Stream Not Found	
2076	Warning	Intrusion Prevention Rule Not Found	
2077	Warning	Pattern List Not Found	
2078	Warning	Traffic Stream Conversion Error	
2080	Warning	Conditional Firewall Rule Not Found	
2081	Warning	Conditional Intrusion Prevention Rule Not Found	
2082	Warning	Empty Intrusion Prevention Rule	
2083	Warning	Intrusion Prevention Rule XML Rule Conversion Error	
2085	Error	Security Configuration Error	
2086	Warning	Unsupported IP Match Type	
2087	Warning	Unsupported MAC Match Type	
2088	Warning	Invalid SSL Credential	
2089	Warning	Missing SSL Credential	
Hardware-Related Events			
3000	Warning	Invalid MAC Address	
3001	Warning	Get Event Data Failed	
3002	Warning	Too Many Interfaces	
3003	Error	Unable To Run External Command	
3004	Error	Unable To Read External Command Output	
3005	Error	Operating System Call Error	
3006	Error	Operating System Call Error	
3007	Error	File Error	
3008	Error	Machine-Specific Key Error	
3009	Error	Unexpected Agent/Appliance Shutdown	
3010	Error	Agent/Appliance Database Error	
3300	Warning	Get Event Data Failed	Linux error.
3302	Warning	Get Security Configuration Failed	Linux error.
3303	Error	File Mapping Error	Linux error. File type error.
3600	Error	Get Windows System Directory Failed	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Notes
3601	Warning	Read Local Data Error	Windows error.
3602	Warning	Windows Service Error	Windows error.
3603	Error	File Mapping Error	Windows error. File size error.
3700	Warning	Abnormal Restart Detected	Windows error.
3701	Info	System Last Boot Time Change	Windows error.
Communications-Related Events			
4000	Warning	Invalid Protocol Header	Content length out of range.
4001	Warning	Invalid Protocol Header	Content length missing.
4002	Info	Command Session Initiated	
4003	Info	Configuration Session Initiated	
4004	Info	Command Received	
4011	Warning	Failure to Contact Manager	
4012	Warning	Heartbeat Failed	
Agent-Related Events			
5000	Info	Agent/Appliance Started	
5001	Error	Thread Exception	
5002	Error	Operation Timed Out	
5003	Info	Agent/Appliance Stopped	
5004	Warning	Clock Changed	
5005	Info	Agent/Appliance Auditing Started	
5006	Info	Agent/Appliance Auditing Stopped	
5007	Info	Appliance Protection Change	
5008	Warning	Filter Driver Connection Failed	
5009	Info	Filter Driver Connection Success	
5010	Warning	Filter Driver Informational Event	
5100	Info	Protection Module Deployment Started	
5101	Info	Protection Module Deployment Succeeded	
5102	Error	Protection Module Deployment Failed	
5103	Info	Protection Module Download Succeeded	
5104	Info	Protection Module Disablement Started	
5105	Info	Protection Module Disablement Succeeded	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Notes
5106	Error	Protection Module Disablement Failed	
5107	Info	Agent Self-Protection enabled	
5108	Info	Agent Self-Protection disabled	
Logging-Related Events			
6000	Info	Log Device Open Error	
6001	Info	Log File Open Error	
6002	Info	Log File Write Error	
6003	Info	Log Directory Creation Error	
6004	Info	Log File Query Error	
6005	Info	Log Directory Open Error	
6006	Info	Log File Delete Error	
6007	Info	Log File Rename Error	
6008	Info	Log Read Error	
6009	Warning	Log File Deleted Due To Insufficient Space	
6010	Warning	Events Were Suppressed	
6011	Warning	Events Truncated	
6012	Error	Insufficient Disk Space	See "Warning: Insufficient disk space" on page 1306 .
6013	Warning	Agent configuration package too large	
Attack-, Scan-, and Probe-Related Events			
7000	Warning	Computer OS Fingerprint Probe	
7001	Warning	Network or Port Scan	
7002	Warning	TCP Null Scan	
7003	Warning	TCP SYNFIN Scan	
7004	Warning	TCP Xmas Scan	
Download Security Update Events			
9050	Info	Update of Anti-Malware Component on Agent Succeeded	
9051	Error	Update of Anti-Malware Component on Agent Failed	
9100	Info	Security Update Successful	
9101	Error	Security Update Failure	
9102	Error	Security Update Failure	Specific information recorded in error message.
Relay Events			

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Notes
9103	Info	Relay Web Server Disabled	
9104	Info	Relay Web Server Enabled	
9105	Error	Enable Relay Web Server Failed	
9106	Error	Disable Relay Web Server Failed	
9107	Error	Relay Web Server failed	
9108	Info	Unable to Connect to Update Source	
9109	Error	Component Update Failure	
9110	Error	Anti-Malware license is expired	
9111	Info	Security Update Rollback Success	
9112	Error	Security Update Rollback Failure	
9113	Info	Relay Replicated All Packages	
9114	Error	Relay Failed to Replicate All Packages	
Integrity Scan Status Events			
9201	Info	Integrity Scan Started	
9203	Info	Integrity Scan Terminated Abnormally	
9204	Info	Integrity Scan Paused	
9205	Info	Integrity Scan Resumed	
9208	Warning	Integrity Scan failed to start	
9209	Warning	Integrity Scan Stalled	
Smart Protection Server Status Events			
9300	Warning	Smart Protection Server Disconnected for Web Reputation	See "Troubleshoot "Smart Protection Server disconnected" errors" on page 1278.
9301	Info	Smart Protection Server Connected for Web Reputation	See "Troubleshoot "Smart Protection Server disconnected" errors" on page 1278.

System events

To view system events, go to **Events & Reports > Events**.

Trend Micro Deep Security On-Premise 11.3

To configure system events, go to the **Administration > System Settings > System Events** tab. On this tab you can set whether to record individual events and whether to [forward them to a SIEM server](#). If you select **Record**, then the event is saved to the database. If you deselect **Record**, then the event won't appear under the **Events & Reports** tab (or anywhere in Deep Security Manager) and it won't be forwarded either.

Depending on whether it's a system configuration change or security incident, each log will appear in either the **System Events** sub-menu, or the sub-menu corresponding to the event's protection module, such as **Anti-Malware Events**.

These events sometimes also appear in the Status column on **Computers**.

ID	Severity	Event	Description or Solution
0	Error	Unknown Error	
100	Info	Deep Security Manager Started	
101	Info	License Changed	
102	Info	Trend Micro Deep Security Customer Account Changed	
103	Warning	Check For Updates Failed	
104	Warning	Automatic Software Download Failed	
105	Warning	Scheduled Rule Update Download and Apply Failed	
106	Info	Scheduled Rule Update Downloaded and Applied	
107	Info	Rule Update Downloaded and Applied	
108	Info	Script Executed	
109	Error	Script Execution Failed	
110	Info	System Events Exported	
111	Info	Firewall Events Exported	
112	Info	Intrusion Prevention Events Exported	
113	Warning	Scheduled Rule Update Download Failed	
114	Info	Scheduled Rule Update Downloaded	
115	Info	Rule Update Downloaded	
116	Info	Rule Update Applied	
117	Info	Deep Security Manager Shutdown	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
118	Warning	Deep Security Manager Offline	
119	Info	Deep Security Manager Back Online	
120	Error	Heartbeat Server Failed	The server within Deep Security Manager that listens for incoming agent heartbeats did not start. Check that the manager's incoming heartbeat port number is not in use by another application on the server. Once the port is free, the manager's heartbeat server should bind to it, and this error should be fixed.
121	Error	Scheduler Failed	
122	Error	Manager Message Thread Failed	An internal thread has failed. There is no resolution for this error. If it persists, please contact customer support.
123	Info	Deep Security Manager Forced Shutdown	
124	Info	Rule Update Deleted	
130	Info	Credentials Generated	
131	Warning	Credential Generation Failed	
140	Info	Discover Computers	
141	Warning	Discover Computers Failed	
142	Info	Discover Computers Requested	
143	Info	Discover Computers Canceled	
150	Info	System Settings Saved	
151	Info	Software Added	
152	Info	Software Deleted	
153	Info	Software Updated	
154	Info	Software Exported	
155	Info	Software Platforms Changed	
160	Info	Authentication Failed	
161	Info	Rule Update Exported	
162	Info	Log Inspection Events Exported	
163	Info	Anti-Malware Event Exported	
164	Info	Security Update Successful	
165	Error	Security Update Failed	
166	Info	Check for New Software Success	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
167	Error	Check for New Software Failed	
168	Info	Manual Security Update Successful	
169	Error	Manual Security Update Failed	
170	Error	Manager Available Disk Space Too Low	The manager does not have enough free disk space to function and will shut down. Either expand the disk space or delete unused files to free some disk space, then " Restart the Deep Security Manager " on page 979.
171	Info	Anti-Malware Spyware Item Exported	
172	Info	Web Reputation Events Exported	
173	Info	Anti-Malware Identified Files List Exported	
174	Info	Anti-Malware Unauthorized Change Targeted Item Exported	
180	Info	Alert Type Updated	
190	Info	Alert Started	
191	Info	Alert Changed	
192	Info	Alert Ended	
197	Info	Alert Emails Sent	
198	Warning	Alert Emails Failed	An alert email could not be sent. Verify that your SMTP settings are correct.
199	Error	Alert Processing Failed	The current alert status could be inaccurate because an alert was not completely processed. If the problem persists, contact your support provider.
248	Info	Software Update: Disable Relay Requested	
249	Info	Software Update: Enable Relay Requested	
250	Info	Computer Created	
251	Info	Computer Deleted	
252	Info	Computer Updated	
253	Info	Policy Assigned to Computer	
254	Info	Computer Moved	
255	Info	Activation Requested	
256	Info	Send Policy Requested	
257	Info	Locked	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
258	Info	Unlocked	
259	Info	Deactivation Requested	
260	Info	Scan for Open Ports	
261	Warning	Scan for Open Ports Failed	
262	Info	Scan for Open Ports Requested	
263	Info	Scan for Open Ports Canceled	
264	Info	Agent Software Upgrade Requested	
265	Info	Agent Software Upgrade Cancelled	
266	Info	Warnings/Errors Cleared	
267	Info	Check Status Requested	
268	Info	Get Events Requested	
269	Info	Computer Added to Cloud Connector	
270	Error	Computer Creation Failed	
271	Info	Agent Software Upgrade Timed Out	
272	Info	Appliance Software Upgrade Timed Out	
273	Info	Security Update: Security Update Check and Download Requested	
274	Info	Security Update: Security Update Rollback Requested	
275	Warning	Duplicate Computer	
276	Info	Update: Summary Information	
277	Info	Auto Agent Software Upgrade Skipped	The agent was eligible for an automatic upgrade, but the upgrade did not occur. For more information, see "Automatically upgrade agents on activation" on page 341 .
280	Info	Computers Exported	
281	Info	Computers Imported	
286	Info	Computer Log Exported	
287	Info	Relay Group Assigned to Computer	
290	Info	Group Added	
291	Info	Group Removed	
292	Info	Group Updated	
293	Info	Interface Renamed	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
294	Info	Computer Bridge Renamed	
295	Info	Interface Deleted	
296	Info	Interface IP Deleted	
297	Info	Recommendation Scan Requested	
298	Info	Recommendations Cleared	
299	Info	Asset Value Assigned to Computer	
300	Info	Recommendation Scan Completed	
301	Info	Agent Software Deployment Requested	
302	Info	Agent Software Removal Requested	
303	Info	Computer Renamed	
305	Info	Scan for Integrity Requested	
306	Info	Rebuild Baseline Requested	
307	Info	Cancel Update Requested	
308	Info	Integrity Monitoring Rule Compile Issue	
309	Info	Integrity Monitoring Rule Compile Issue Resolved	
310	Info	Directory Added	
311	Info	Directory Removed	
312	Info	Directory Updated	
320	Info	Directory Synchronization	
321	Info	Directory Synchronization Finished	
322	Error	Directory Synchronization Failed	
323	Info	Directory Synchronization Requested	
324	Info	Directory Synchronization Cancelled	
325	Info	User Synchronization	Synchronization of the user accounts with Microsoft Active Directory has been started.
326	Info	User Synchronization Finished	Synchronization of the user accounts with Microsoft Active Directory has completed.
327	Error	User Synchronization Failed	
328	Info	User Synchronization Requested	
329	Info	User Synchronization Cancelled	
330	Info	SSL Configuration Created	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
331	Info	SSL Configuration Deleted	
332	Info	SSL Configuration Updated	
333	Info	Host Merge Finished	
334	Error	Host Merge Failed	
350	Info	Policy Created	
351	Info	Policy Deleted	
352	Info	Policy Updated	
353	Info	Policies Exported	
354	Info	Policies Imported	
355	Info	Scan for Recommendations Canceled	
360	Info	VMware vCenter Added	
361	Info	VMware vCenter Removed	
362	Info	VMware vCenter Updated	
363	Info	VMware vCenter Synchronization	
364	Info	VMware vCenter Synchronization Finished	
365	Error	VMware vCenter Synchronization Failed	
366	Info	VMware vCenter Synchronization Requested	
367	Info	VMware vCenter Synchronization Cancelled	
368	Warning	Interfaces Out of Sync	Interfaces reported by the Deep Security Virtual Appliance are different than the interfaces reported by the vCenter. This can typically be resolved by rebooting the VM.
369	Info	Interfaces in Sync	
370	Info	Filter Driver Installed	
371	Info	Filter Driver Removed	The VMware ESXi server has been restored to the state it was in before the filter driver software was installed.
372	Info	Filter Driver Upgraded	
373	Info	Virtual Appliance Deployed	
374	Info	Virtual Appliance Upgraded	
375	Warning	Virtual Appliance Upgrade Failed	
376	Warning	Virtual Machine Moved to Unprotected ESXi	
377	Info	Virtual Machine Moved to Protected ESXi	
378	Warning	Virtual Machine unprotected after move to another ESXi	A VM was moved to an ESXi where there is no Deep Security

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
			Virtual Appliance.
379	Info	Virtual Machine unprotected after move to another ESXi Resolved	
380	Error	Filter Driver Offline	The filter driver on an ESXi server is offline. Use the VMware vCenter console to troubleshoot problems with the hypervisor and the ESXi.
381	Info	Filter Driver Back Online	
382	Info	Filter Driver Upgrade Requested	
383	Info	Appliance Upgrade Requested	
384	Warning	Prepare ESXi Failed	
385	Warning	Filter Driver Upgrade Failed	
386	Warning	Removal of Filter Driver from ESXi Failed	
387	Error	Connection to Filter Driver Failure	
388	Info	Connection to Filter Driver Success	
389	Error	Multiple Activated Appliances Detected	
390	Info	Multiple Activated Appliances Detected Resolved	
391	Error	Network Settings Out of Sync With vCenter Global Settings	
392	Info	Network Settings in Sync With vCenter Global Settings	
393	Error	Anti-Malware Engine Offline	The anti-malware protection module is not functioning. This is probably because the VMware environment does not meet the requirements. See "System requirements" on page 76 .
394	Info	Anti-Malware Engine Back Online	
395	Error	Virtual Appliance is Incompatible With Filter Driver	
396	Info	Virtual Appliance is Incompatible With Filter Driver Resolved	
397	Warning	VMware NSX Callback Authentication Failed	
398	Error	VMware Tools Not Installed	
399	Info	VMware Tools Not Installed Resolved	
410	Info	Firewall Rule Created	
411	Info	Firewall Rule Deleted	
412	Info	Firewall Rule Updated	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
413	Info	Firewall Rule Exported	
414	Info	Firewall Rule Imported	
420	Info	Firewall Stateful Configuration Created	
421	Info	Firewall Stateful Configuration Deleted	
422	Info	Firewall Stateful Configuration Updated	
423	Info	Firewall Stateful Configuration Exported	
424	Info	Firewall Stateful Configuration Imported	
460	Info	Application Type Created	An administrator configured a new IPS network application definition.
461	Info	Application Type Deleted	An administrator removed an IPS network application definition.
462	Info	Application Type Updated	An administrator changed an existing IPS network application definition.
463	Info	Application Type Exported	An administrator downloaded an IPS network application definition.
464	Info	Application Type Imported	An administrator uploaded an IPS network application definition.
470	Info	Intrusion Prevention Rule Created	
471	Info	Intrusion Prevention Rule Deleted	
472	Info	Intrusion Prevention Rule Updated	
473	Info	Intrusion Prevention Rule Exported	
474	Info	Intrusion Prevention Rule Imported	
480	Info	Integrity Monitoring Rule Created	
481	Info	Integrity Monitoring Rule Deleted	
482	Info	Integrity Monitoring Rule Updated	
483	Info	Integrity Monitoring Rule Exported	
484	Info	Integrity Monitoring Rule Imported	
490	Info	Log Inspection Rule Created	
491	Info	Log Inspection Rule Deleted	
492	Info	Log Inspection Rule Updated	
493	Info	Log Inspection Rule Exported	
494	Info	Log Inspection Rule Imported	
495	Info	Log Inspection Decoder Created	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
496	Info	Log Inspection Decoder Deleted	
497	Info	Log Inspection Decoder Updated	
498	Info	Log Inspection Decoder Exported	
499	Info	Log Inspection Decoder Imported	
505	Info	Context Created	
506	Info	Context Deleted	
507	Info	Context Updated	
508	Info	Context Exported	
509	Info	Context Imported	
510	Info	IP List Created	
511	Info	IP List Deleted	
512	Info	IP List Updated	
513	Info	IP List Exported	
514	Info	IP List Imported	
520	Info	Port List Created	
521	Info	Port List Deleted	
522	Info	Port List Updated	
523	Info	Port List Exported	
524	Info	Port List Imported	
525	Info	Scan Cache Configuration Created	
526	Info	Scan Cache Configuration Exported	
530	Info	MAC List Created	
531	Info	MAC List Deleted	
532	Info	MAC List Updated	
533	Info	MAC List Exported	
534	Info	MAC List Imported	
540	Info	Proxy Created	
541	Info	Proxy Deleted	
542	Info	Proxy Updated	
543	Info	Proxy Exported	
544	Info	Proxy Imported	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
550	Info	Schedule Created	
551	Info	Schedule Deleted	
552	Info	Schedule Updated	
553	Info	Schedule Exported	
554	Info	Schedule Imported	
560	Info	Scheduled Task Created	
561	Info	Scheduled Task Deleted	
562	Info	Scheduled Task Updated	
563	Info	Scheduled Task Manually Executed	
564	Info	Scheduled Task Started	
565	Info	Backup Finished	
566	Error	Backup Failed	
567	Info	Sending Outstanding Alert Summary	
568	Warning	Failed To Send Outstanding Alert Summary	
569	Warning	Email Failed	An e-mail notification could not be sent. Verify that your SMTP settings are correct.
570	Info	Sending Report	
571	Warning	Failed To Send Report	
572	Error	Invalid Report Jar	
573	Info	Asset Value Created	
574	Info	Asset Value Deleted	
575	Info	Asset Value Updated	
576	Error	Report Uninstall Failed	
577	Error	Report Uninstalled	
578	Warning	Integrity Monitoring Rules Require Configuration	
580	Warning	Application Type Port List Misconfiguration	
581	Warning	Application Type Port List Misconfiguration Resolved	
582	Warning	Intrusion Prevention Rules Require Configuration	
583	Info	Intrusion Prevention Rules Require Configuration Resolved	
584	Warning	Application Types Require Configuration	IPS rules require network application definitions, and cannot correctly scan traffic until you define them.

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
585	Info	Integrity Monitoring Rules Require Configuration Resolved	
586	Warning	Log Inspection Rules Require Configuration	
587	Info	Log Inspection Rules Require Configuration Resolved	
588	Warning	Log Inspection Rules Require Log Files	
589	Info	Log Inspection Rules Require Log Files Resolved	
590	Warning	Scheduled Task Unknown Type	
591	Info	Relay Group Created	
592	Info	Relay Group Updated	
593	Info	Relay Group Deleted	
594	Info	Event-Based Task Created	
595	Info	Event-Based Task Deleted	
596	Info	Event-Based Task Updated	
597	Info	Event-Based Task Triggered	
600	Info	User Signed In	
601	Info	User Signed Out	
602	Info	User Timed Out	
603	Info	User Locked Out	
604	Info	User Unlocked	
608	Error	User Session Validation Failed	Deep Security Manager could not confirm that a session was initiated after successful authentication. The user will be redirected to the login page, and asked to re-authenticate. This could be normal if the authenticated session list was cleared.
609	Error	User Made Invalid Request	Deep Security Manager received invalid request to access audit data (events). Access was denied.
610	Info	User Session Validated	
611	Info	User Viewed Firewall Event	
613	Info	User Viewed Intrusion Prevention Event	
615	Info	User Viewed System Event	
616	Info	User Viewed Integrity Monitoring Event	
617	Info	User Viewed Log Inspection Event	
618	Info	User Viewed Identified File Detail	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
619	Info	User Viewed Anti-Malware Event	
620	Info	User Viewed Web Reputation Event	
621	Info	User Signed In As Tenant	
622	Info	Access from Primary Tenant Enabled	
623	Info	Access from Primary Tenant Disabled	
624	Info	Access from Primary Tenant Allowed	
625	Info	Access from Primary Tenant Revoked	
626	Info	Access from Primary Tenant Expired	
630	Info	Syslog Configuration Created	
631	Info	Syslog Configuration Deleted	
632	Info	Syslog Configuration Updated	
633	Info	Syslog Configuration Exported	
634	Info	Syslog Configuration Imported	
650	Info	User Created	
651	Info	User Deleted	
652	Info	User Updated	
653	Info	User Password Set	
660	Info	Role Created	
661	Info	Role Deleted	
662	Info	Role Updated	
663	Info	Roles Imported	
664	Info	Roles Exported	
670	Info	Contact Created	
671	Info	Contact Deleted	
672	Info	Contact Updated	
680	Info	Created master encryption key	For details, see the masterkey parameter.
681	Info	Exported master encryption key	For details, see the masterkey parameter.
682	Info	Imported master encryption key	For details, see the masterkey parameter.
700	Info	Agent Software Installed	
701	Error	Agent Software Installation Failed	
702	Info	Credentials Generated	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
703	Error	Credential Generation Failed	
704	Info	Activated	
705	Error	Activation Failed	This can occur if agent self-protection is enabled. On the Deep Security Manager, go to Computer editor ¹ > Settings > General . In Agent Self Protection , and then either deselect Prevent local end-users from uninstalling, stopping, or otherwise modifying the Agent or enter a password for local override.
706	Info	Software Update: Agent Software Upgraded	
707	Warning	Software Update: Agent Software Upgrade Failed	Refer to the event details for more information about why the upgrade was not successful.
708	Info	Deactivated	
709	Error	Deactivation Failed	
710	Info	Events Retrieved	
711	Info	Agent Software Deployed	
712	Error	Agent Software Deployment Failed	This can occur if agent self-protection is enabled. On the Deep Security Manager, go to Computer editor ² > Settings > General . In Agent Self Protection , and then either deselect Prevent local end-users from uninstalling, stopping, or otherwise modifying the Agent or enter a password for local override.
713	Info	Agent Software Removed	
714	Error	Agent Software Removal Failed	This can occur if agent self-protection is enabled. On the Deep Security Manager, go to Computer editor ³ > Settings > General . In Agent Self Protection , and then either deselect Prevent local end-users from

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

³To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
			uninstalling, stopping, or otherwise modifying the Agent or enter a password for local override.
715	Info	Agent/Appliance Version Changed	
716	Info	Reactivation Attempted by Unknown Agent	An agent that is currently unknown to the Deep Security Manager has attempted reactivation. This usually happens when a computer was deleted from Deep Security Manager without first removing the agent on the computer. For more information, see the 'Reactivation Attempted by Unknown Agent' section in Agent settings .
720	Info	Policy Sent	Agent/Appliance updated.
721	Error	Send Policy Failed	
722	Warning	Get Interfaces Failed	
723	Info	Get Interfaces Failure Resolved	
724	Warning	Insufficient Disk Space	An agent detected low disk space. Free space on the computer. See "Warning: Insufficient disk space" on page 1306 .
725	Warning	Events Suppressed	
726	Warning	Get Agent/Appliance Events Failed	Manager was unable to retrieve Events from Agent/Appliance. This error does not mean that the data was lost on the Agent/Appliance. This error is normally caused by a network interruption while events are being transferred. Clear the error and run a "Check Status" to retry the operation.
727	Info	Get Agent/Appliance Events Failure Resolved	
728	Error	Get Events Failed	Manager was unable to retrieve audit data from Agent/Appliance. This error does not mean that the data was lost on the Agent/Appliance. This error is normally caused by a network interruption while events are being transferred. Clear the error and run a "Get Events Now" to retry the operation.
729	Info	Get Events Failure Resolved	
730	Error	Offline	Manager cannot communicate with Computer. Usually, however, the offline Agent is still protecting the computer with its last configured settings. See Computer and Agent/Appliance Status and ""Offline" agent" on page 1452 .

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
731	Info	Back Online	
732	Error	Firewall Engine Offline	The Firewall Engine is offline and traffic is flowing unfiltered. This is normally due to an error during installation or verification of the driver on the computer's OS platform. Check the status of the network driver at the computer to ensure it is properly loaded.
733	Info	Firewall Engine Back Online	
734	Warning	Computer Clock Change	A clock change has occurred on the Computer which exceeds the maximum allowed specified in Computer or Policy editor ¹ > Settings > General > Heartbeat area. Investigate what has caused the clock change on the computer.
735	Warning	Misconfiguration Detected	The Agent's configuration does not match the configuration indicated in the Manager's records. This is typically because of a recent backup restoration of the Manager or the Agent. Unanticipated misconfiguration warnings should be investigated.
736	Info	Check Status Failure Resolved	
737	Error	Check Status Failed	See "Error: Check Status Failed" on page 1297 .
738	Error	Intrusion Prevention Engine Offline	The Intrusion Prevention Engine is offline and traffic is flowing unfiltered. This is normally due to an error during installation or verification of the driver on the computer's OS platform. Check the status of the network driver at the computer to ensure it is properly loaded.
739	Info	Intrusion Prevention Engine Back Online	
740	Error	Agent/Appliance Error	
741	Warning	Abnormal Restart Detected	
742	Warning	Communications Problem	The Agent is having problems communicating its status to Manager. It usually indicates network or load congestion in the Agent --> Manager direction. Further investigation is warranted if the situation persists

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
743	Info	Communications Problem Resolved	
745	Warning	Events Truncated	
748	Error	Log Inspection Engine Offline	
749	Info	Log Inspection Engine Back Online	
750	Warning	Last Automatic Retry	
755	Info	Deep Security Manager Version Compatibility Resolved	
756	Warning	Deep Security Manager Upgrade Recommended (Incompatible Security Update(s))	
760	Info	Agent/Appliance Version Compatibility Resolved	
761	Warning	Agent/Appliance Upgrade Recommended	
762	Warning	Agent/Appliance Upgrade Required	
763	Warning	Incompatible Agent/Appliance Version	
764	Warning	Agent/Appliance Upgrade Recommended (Incompatible Security Update(s))	
765	Error	Computer Reboot Required	
766	Warning	Network Engine Mode Configuration Incompatibility	
767	Warning	Network Engine Mode Version Incompatibility	
768	Warning	Network Engine Mode Incompatibility Resolved	
770	Warning	Agent/Appliance Heartbeat Rejected	
771	Warning	Contact by Unrecognized Client	
780	Info	Recommendation Scan Failure Resolved	
781	Warning	Recommendation Scan Failure	See "Troubleshooting: Recommendation Scan Failure" on page 539.
782	Info	Rebuild Baseline Failure Resolved	
783	Warning	Rebuild Baseline Failure	
784	Info	Security Update: Security Update Check and Download Successful	
785	Warning	Security Update: Security Update Check and Download Failed	
786	Info	Scan For Change Failure Resolved	
787	Warning	Scan For Change Failure	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
790	Info	Agent-Initiated Activation Requested	
791	Warning	Agent-Initiated Activation Failure	
792	Info	Manual Malware Scan Failure Resolved	
793	Warning	Manual Malware Scan Failure	A Malware Scan has failed. Use the VMware vCenter console to check the status of the VM on which the scan failed.
794	Info	Scheduled Malware Scan Failure Resolved	
795	Warning	Scheduled Malware Scan Failure	A scheduled Malware Scan has failed. Use the VMware vCenter console to check the status of the VM on which the scan failed.
796	Warning	Scheduled Malware Scan Task has been Missed	This occurs when a scheduled Malware Scan is initiated on a computer when a previous scan is still pending. This typically indicates that Malware Scans are being scheduled too frequently.
797	Info	Malware Scan Cancellation Failure Resolved	
798	Warning	Malware Scan Cancellation Failure	A Malware Scan cancellation has failed. Use the VMware vCenter console to check the status of the VM on which the scan failed.
799	Warning	Malware Scan Stalled	A Malware Scan has stalled. Use the VMware vCenter console to check the status of the VM on which the scan stalled.
800	Info	Alert Dismissed	
801	Info	Error Dismissed	
804	Error	Intrusion Prevention Rule Compiler Failed	
805	Error	Intrusion Prevention Rules Failed to Compile	
806	Error	Intrusion Prevention Rules Failed to Compile	
850	Warning	Reconnaissance Detected: Computer OS Fingerprint Probe	See "Warning: Reconnaissance Detected" on page 1304
851	Warning	Reconnaissance Detected: Network or Port Scan	See "Warning: Reconnaissance Detected" on page 1304
852	Warning	Reconnaissance Detected: TCP Null Scan	See "Warning: Reconnaissance Detected" on page 1304
853	Warning	Reconnaissance Detected: TCP SYNFIN Scan	See "Warning: Reconnaissance Detected" on page 1304
854	Warning	Reconnaissance Detected: TCP Xmas Scan	See "Warning: Reconnaissance Detected" on page 1304
900	Info	Deep Security Manager Audit Started	
901	Info	Deep Security Manager Audit Shutdown	
902	Info	Deep Security Manager Installed	
903	Warning	License Related Configuration Change	
910	Info	Diagnostic Package Generated	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
911	Info	Diagnostic Package Exported	
912	Info	Diagnostic Package Uploaded	
913	Error	Automatic Diagnostic Package Error	
914	Info	Identified File Deletion Succeeded	
915	Info	Identified File Deletion Failed	
916	Info	Identified File Download Succeeded	
917	Info	Identified File Download Failed	
918	Info	Identified File Administration Utility Download Succeeded	
919	Info	Identified File Not Found	
920	Info	Usage Information Generated	
921	Info	Usage Information Package Exported	
922	Info	Usage Information Package Uploaded	
923	Error	Usage Information Package Error	
924	Warning	File cannot be analyzed or quarantined (VM maximum disk space used to store identified files exceeded)	The Anti-Malware module was unable to analyze or quarantine a file because the VM maximum disk space used to store identified files was reached. To change the maximum disk space for identified files setting, open the computer or policy editor and go to the Anti-malware > Advanced tab.
925	Warning	File cannot be analyzed or quarantined (maximum disk space used to store identified files exceeded)	The Anti-Malware module was unable to analyze or quarantine a file because the maximum disk space used to store identified files was reached. To change the maximum disk space for identified files setting, open the computer or policy editor and go to the Anti-malware > Advanced tab.
926	Warning	Smart Protection Server Disconnected for Smart Scan	See "Troubleshoot "Smart Protection Server disconnected" errors" on page 1278.
927	Info	Smart Protection Server Connected for Smart Scan	
928	Info	Identified File Restoration Succeeded	
929	Warning	Identified File Restoration Failed	
930	Info	Certificate Accepted	
931	Info	Certificate Deleted	
932	Warning	Smart Protection Server Disconnected for Web Reputation	See "Troubleshoot "Smart Protection Server disconnected" errors" on page 1278.

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
933	Info	Smart Protection Server Connected for Web Reputation	
934	Info	Software Update: Anti-Malware Windows Platform Update Successful	
935	Error	Software Update: Anti-Malware Windows Platform Update Failed	See "Anti-Malware Windows platform update failed" on page 1458
936	Info	Submission of identified file to Deep Discovery Analyzer succeeded	
937	Info	Submission of identified file to Deep Discovery Analyzer failed	
938	Info	Identified File Submission Queued	
940	Info	Auto-Tag Rule Created	
941	Info	Auto-Tag Rule Deleted	
942	Info	Auto-Tag Rule Updated	
943	Info	Tag Deleted	
944	Info	Tag Created	
945	Warning	Census, Good File Reputation, and Predictive Machine Learning Service Disconnected	
946	Info	Census, Good File Reputation, and Predictive Machine Learning Service Connected	
970	Info	Command Line Utility Started	
978	Info	Command Line Utility Failed	
979	Info	Command Line Utility Shutdown	Deep Security Manager was manually stopped.
980	Info	System Information Exported	
990	Info	Manager Node Added	
991	Info	Manager Node Decommissioned	
992	Info	Manager Node Updated	
995	Info	Connection to the Certified Safe Software Service has been restored	
996	Warning	Unable to connect to the Certified Safe Software Service	
997	Error	Tagging Error	
998	Error	System Event Notification Error	
999	Error	Internal Software Error	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
1101	Error	Plug-in Installation Failed	
1102	Info	Plug-in Installed	
1103	Error	Plug-in Upgrade Failed	
1104	Info	Plug-in Upgraded	
1105	Error	Plug-in Start Failed	
1106	Error	Plug-in Uninstall Failed	
1107	Info	Plug-in Uninstalled	
1108	Info	Plug-in Started	
1109	Info	Plug-in Stopped	
1110	Error	Software Package Not Found	
1111	Info	Software Package Found	
1500	Info	Malware Scan Configuration Created	
1501	Info	Malware Scan Configuration Deleted	
1502	Info	Malware Scan Configuration Updated	
1503	Info	Malware Scan Configuration Exported	
1504	Info	Malware Scan Configuration Imported	
1505	Info	Directory List Created	
1506	Info	Directory List Deleted	
1507	Info	Directory List Updated	
1508	Info	Directory List Exported	
1509	Info	Directory List Imported	
1510	Info	File Extension List Created	
1511	Info	File Extension List Deleted	
1512	Info	File Extension List Updated	
1513	Info	File Extension List Exported	
1514	Info	File Extension List Imported	
1515	Info	File List Created	
1516	Info	File List Deleted	
1517	Info	File List Updated	
1518	Info	File List Exported	
1519	Info	File List Imported	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
1520	Info	Manual Malware Scan Pending	
1521	Info	Manual Malware Scan Started	
1522	Info	Manual Malware Scan Completed	
1523	Info	Scheduled Malware Scan Started	
1524	Info	Scheduled Malware Scan Completed	
1525	Info	Manual Malware Scan Cancellation In Progress	
1526	Info	Manual Malware Scan Cancellation Completed	
1527	Info	Scheduled Malware Scan Cancellation In Progress	
1528	Info	Scheduled Malware Scan Cancellation Completed	
1529	Info	Manual Malware Scan Paused	
1530	Info	Manual Malware Scan Resumed	
1531	Info	Scheduled Malware Scan Paused	
1532	Info	Scheduled Malware Scan Resumed	
1533	Info	Computer reboot required for Anti-Malware cleanup task	
1534	Error	Computer reboot required for Anti-Malware protection	
1536	Info	Quick Malware Scan Pending	
1537	Info	Quick Malware Scan Started	
1538	Info	Quick Malware Scan Completed	
1539	Info	Quick Malware Scan Cancellation In Progress	
1540	Info	Quick Malware Scan Cancellation Completed	
1541	Info	Quick Malware Scan Paused	
1542	Info	Quick Malware Scan Failure Resolved	
1543	Warning	Quick Malware Scan Failure	
1544	Info	Quick Malware Scan Resumed	
1545	Info	Files could not be scanned for malware	Anti-malware could not scan a file because its file path exceeded the maximum number of characters. Maximum file path length varies by OS and file system. To prevent this problem, try moving the file to a directory path and file name with fewer characters.
1546	Info	Files could not be scanned for malware	Anti-malware could not scan a file because its location exceeded the maximum directory depth. To prevent this problem, try reducing the number of layers of nested directories.
1550	Info	Web Reputation Settings Updated	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
1551	Info	Malware Scan Configuration Updated	
1552	Info	Integrity Configuration Updated	
1553	Info	Log Inspection Configuration Updated	
1554	Info	Firewall Stateful Configuration Updated	
1555	Info	Intrusion Prevention Configuration Updated	
1600	Info	Relay Group Update Requested	
1601	Info	Relay Group Update Success	
1602	Error	Relay Group Update Failed	
1603	Info	Security Update: Security Update Rollback Success	
1604	Warning	Security Update: Security Update Rollback Failure	
1605	Info	Successfully send file back up command to host	
1606	Warning	Failed to send file back up command to host	
1607	Info	Successfully back up file	
1608	Error	Failed to back up file	
1650	Warning	Anti-Malware protection is not enabled or is out of date	
1651	Info	Anti-Malware module is ready	
1660	Info	Rebuild Baseline Started	
1661	Info	Rebuild Baseline Paused	
1662	Info	Rebuild Baseline Resumed	
1663	Warning	Rebuild Baseline Failure	
1664	Warning	Rebuild Baseline Stalled	
1665	Info	Rebuild Baseline Completed	
1666	Info	Scan for Integrity Started	
1667	Info	Scan for Integrity Paused	
1668	Info	Scan for Integrity Resumed	
1669	Warning	Scan for Integrity Failure	
1670	Warning	Scan for Integrity Stalled	
1671	Info	Scan for Integrity Completed	
1675	Error	Integrity Monitoring Engine Offline	
1676	Info	Integrity Monitoring Engine Back Online	
1677	Error	Trusted Platform Module Error	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
1678	Info	Trusted Platform Module Register Values Loaded	
1679	Warning	Trusted Platform Module Register Values Changed	
1680	Info	Trusted Platform Module Checking Disabled	
1681	Info	Trusted Platform Module Information Unreliable	
1700	Info	No Agent Detected	
1800	Error	Deep Security Protection Module Failure	
1900	Info	Cloud Account Added	
1901	Info	Cloud Account Removed	
1902	Info	Cloud Account Updated	
1903	Info	Cloud Account Synchronization In Progress	
1904	Info	Cloud Account Synchronization Finished	
1905	Error	Cloud Account Synchronization Failed	
1906	Info	Cloud Account Synchronization Requested	
1907	Info	Cloud account Synchronization Cancelled	
1908	Info	AWS Account Synchronization Requested	
1909	Info	AWS Account Synchronization Finished	
1910	Error	AWS Account Synchronization Failed	
1911	Info	AWS Account Added	
1912	Info	AWS Account Removed	
1913	Info	AWS Account Updated	
1914	Info	Azure Account Added	
1915	Info	Azure Account Removed	
1916	Info	Azure Account Updated	
1917	Info	Azure Account Synchronization Finished	
1918	Error	Azure Account Synchronization Failed	
1919	Info	Azure Account Synchronization Requested	
1921	Info	vCloud Account Added	
1922	Info	vCloud Account Removed	
1923	Info	vCloud Account Updated	
1924	Info	vCloud Account Synchronization Finished	
1925	Error	vCloud Account Synchronization Failed	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
1926	Info	vCloud Account Synchronization Requested	
1927	Info	Upgrade Connector to AWS Account Requested	
1928	Warning	AWS Account Update Failed	
1929	Info	Upgrade Connector to AWS Account Finished	
1950	Info	Tenant Created	
1951	Info	Tenant Deleted	
1952	Info	Tenant Updated	
1953	Info	Tenant Database Server Created	
1954	Info	Tenant Database Server Deleted	
1955	Info	Tenant Database Server Updated	
1957	Error	Tenant Initialization Failure	
1958	Info	Tenant Features Updated	
2000	Info	Scan Cache Configuration Object Added	
2001	Info	Scan Cache Configuration Object Removed	
2002	Info	Scan Cache Configuration Object Updated	
2200	Info	Software Update: Anti-Malware Module Installation Started	
2201	Info	Software Update: Anti-Malware Module Installation Successful	
2202	Warning	Software Update: Anti-Malware Module Installation Failed	
2203	Info	Software Update: Anti-Malware Module Download Successful	
2204	Info	Security Update: Pattern Update on Agents/Appliances Successful	
2205	Warning	Security Update: Pattern Update on Agents/Appliances Failed	
2300	Info	Software Update: Web Reputation Module Installation Started	
2301	Info	Software Update: Web Reputation Module Installation Successful	
2302	Warning	Software Update: Web Reputation Module Installation Failed	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
2303	Info	Software Update: Web Reputation Download Successful	
2400	Info	Software Update: Firewall Module Installation Started	
2401	Info	Software Update: Firewall Module Installation Successful	
2402	Warning	Software Update: Firewall Module Installation Failed	
2403	Info	Software Update: Firewall Module Download Successful	
2500	Info	Software Update: Intrusion Prevention Module Installation Started	
2501	Info	Software Update: Intrusion Prevention Module Installation Successful	
2502	Warning	Software Update: Intrusion Prevention Module Installation Failed	
2503	Info	Software Update: Intrusion Prevention Module Download Successful	
2600	Info	Software Update: Integrity Monitoring Module Installation Started	
2601	Info	Software Update: Integrity Monitoring Module Installation Successful	
2602	Warning	Software Update: Integrity Monitoring Module Installation Failed	
2603	Info	Software Update: Integrity Monitoring Module Download Successful	
2700	Info	Software Update: Log Inspection Module Installation Started	
2701	Info	Software Update: Log Inspection Module Installation Successful	
2702	Warning	Software Update: Log Inspection Module Installation Failed	
2703	Info	Software Update: Log Inspection Module Download Successful	
2800	Info	Software Update: Software Automatically Downloaded	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
2801	Error	Software Update: Unable to retrieve Download Center inventory	
2802	Error	Software Update: Unable to download software from Download Center	
2803	Info	Online Help Update Started	
2804	Info	Online Help Update Ended	
2805	Info	Online Help Update Success	
2806	Warning	Online Help Update Failed	
2803	Info	Online Help Update Started	
2804	Info	Online Help Update Ended	
2805	Info	Online Help Update Success	
2806	Warning	Online Help Update Failed	
2900	Info	Software Update: Relay Module Installation Started	
2901	Info	Software Update: Relay Module Installation Successful	
2902	Warning	Software Update: Relay Module Installation Failed	
2903	Info	Software Update: Relay Module Download Successful	
2904	Info	VMware NSX Synchronization Finished	
2905	Error	VMware NSX Synchronization Failed	
2906	Info	Agent Self-Protection enabled	
2907	Info	Agent Self-Protection disabled	
2908	Info	Agent Self-Protection enabled	
2909	Info	Agent Self-Protection disabled	
2915	Info	Data migration complete	
2916	Warning	Data migration finished with error	
2920	Info	Querying report from DDAn Finished	
2921	Error	Querying report from DDAn Failed	
2922	Info	Submission to Deep Discovery Analyzer processed	
2923	Error	File submission to Deep Discovery Analyzer Failed	
2924	Info	Security Update: Suspicious Object Check and Update Successful	
2925	Error	Security Update: Suspicious Object Check and Update Failed	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
2926	Warning	Submission to Deep Discovery Analyzer queued	
2930	Info	File back up pending	
2931	Info	Smart Folder Added	
2932	Info	Smart Folder Removed	
2933	Info	Smart Folder Updated	
2934	Error	Failed to send Amazon SNS message	
2935	Info	System resumed sending SNS messages	
2953	Info	Inactive Agent Cleanup Completed Successfully	Inactive Agent Cleanup removed computers that have been offline and inactive for a specified period of time. For more information on Inactive Agent Cleanup, see "Automate offline computer removal with inactive agent cleanup" on page 1438 .
2960	Info	Appliance (SVM) Upgrade Requested	Deep Security Manager has received the upgrade request.
2961	Info	Appliance (SVM) Upgrade Started	Deep Security Manager is processing the upgrade.
2962	Info	Appliance (SVM) Upgrade Canceled	The appliance SVM is not available so the upgrade cannot be done. See the description of the system event for the reason.
2963	Info	Appliance (SVM) Upgraded	The appliance SVM is upgraded to the new version and is activated successfully. All guest VMs are auto-activated three minutes after the appliance activation.
2964	Warning	Appliance (SVM) Upgrade Failed	Deep Security Manager encountered one or more errors and failed the upgrade process. For details, see "Troubleshooting the 'Appliance (SVM) Upgrade Failed' system event" on page 994 .
2965	Error	Appliance (SVM) Upgraded but Not Ready	The appliance SVM was upgraded to the newer version but has not yet been activated, or the appliance SVM was activated but your guest VMs have not yet been auto-activated. See the description of the system event for details. You may need to confirm the appliance deployment and manually trigger activation of the appliance or guest VMs.
3000	Info	Software Update: SAP Module Installation Started	
3001	Info	Software Update: SAP Module Installation Successful	
3002	Error	Software Update: SAP Module Installation Failed	
3003	Info	Software Update: SAP Module Download Successful	
3004	Info	SAP VSA is installed	
3005	Error	SAP VSA is not installed	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
3006	Info	SAP VSA is up-to-date	
3007	Info	SAP VSA is not up-to-date	
7000	Info	Application Control Security Events Exported	An administrator downloaded application control event logs in CSV format.
7007	Info	User Viewed Application Control Event	An administrator dismissed an application control alert. This is normal unless your system has been compromised by an intruder that has gained an administrator login.
7008	Error	Application Control Engine Offline	An agent's application control engine failed to come online. This could happen if you have enabled application control on a computer whose kernel is not supported.
7009	Info	Application Control Engine Online Again	An agent's application control engine restarted.
7010	Info	Application Control Configuration Updated	Deep Security Manager updated the application control settings on an agent.
7011	Info	Software Update: Application Control Module Installation Started	The agent received a policy from Deep Security Manager where application control was selected, but detected that it did not have the application control engine installed or needed to update it, so it began to download it. This is normal when you enable application control on a computer for the first time, or when it has been disabled while application control engine updates were released.
7012	Info	Software Update: Application Control Module Installation Successful	The agent installed the application control engine. The application control engine is also used by the integrity monitoring feature.
7013	Error	Software Update: Application Control Module Installation Failed	The agent could not install the application control engine. This is not normal.
7014	Info	Software Update: Application Control Module Download Successful	The agent finished downloading the application control engine.
7015	Info	Application Control Ruleset Rules Updated	The API was used to allow or block software. This message does not occur when administrators perform the same action in the GUI.
7020	Info	Application Control Inventory Retrieved	The API uploaded a computer's initial allow rules to Deep Security Manager.
7021	Info	Application Control Inventory Scan Started	The application control engine was enabled, and the agent detected that it did not have any allow rules for that computer, so it began to build initial rules based on the currently installed

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
			software. This is normal when you enable application control for the first time. This message does not occur when you use the API to replace the allow rules.
7022	Info	Application Control Inventory Scan Completed	The agent finished building the initial allow rules for that computer. After this, any new software that is detected which is not in the allow or block rules will, if configured, cause and alert.
7023	Error	Application Control Inventory Scan Failed	The agent could not build the initial allow rules for that computer. This is not normal.
7024	Info	Application Control Software Changes Detected	An administrator allowed or blocked software in the Actions tab, or changed a rule by clicking Change rule in an application control log message. This message does not occur when you use the API to replace the allow rules.
7025	Info	Application Control Inventory Scan Requested	You manually forced application control to delete the current rules and rebuild them based on the currently installed software. This could be normal if you needed to change many rules at the same time.
7026	Info	Application Control Maintenance Mode Start Requested	Either an administrator sent or API received the command to enable maintenance mode.
7027	Info	Application Control Maintenance Mode Stop Requested	Either an administrator sent or API received the command to disable maintenance mode.
7028	Info	Application Control Maintenance Mode Started	Maintenance mode was enabled. While enabled, the agent automatically adds updated or newly installed software to its allow rules, indicating that you know and want to allow the software update. The agent continues to apply block rules during this time.
7029	Info	Application Control Maintenance Mode Stopped	Maintenance mode was disabled. Once maintenance mode is stopped, all new or changed software will be considered "unrecognized" until you specifically allow or block it.
7030	Info	Application Control Inventory Scan Cancelled	The agent began to build the initial allow rules, but an administrator canceled the process.
7031	Error	Sending Application Control Ruleset Failed	An agent could not download a shared ruleset for application control. This can occur if network connectivity is interrupted (such as a firewall or proxy between the agent and relay), or if there isn't enough free disk space on the agent.

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
7032	Info	Sending Application Control Ruleset Succeeded	An agent downloaded a shared ruleset for application control. This normally occurs whenever an administrator or API allows or blocks software, or when a different shared ruleset is applied.
7033	Info	Application Control Ruleset Created	The API was used to create an application control ruleset. This message does not occur when administrators perform the same action in the GUI.
7034	Info	Application Control Ruleset Updated	The API was used to allow or block software via an application control ruleset. This message does not occur when administrators perform the same action in the GUI.
7035	Info	Application Control Ruleset Deleted	The API was used to delete an application control ruleset. This message does not occur when administrators perform the same action in the GUI.
7036	Info	Application Control Maintenance Mode Reset Duration Requested	An administrator changed the time period for when maintenance mode is active.
7037	Error	Newly applied ruleset will block some running processes on restart	An administrator applied a new ruleset, but some of the currently running processes exist in block rules. Application control will not terminate the processes, but the next time you reboot or restart those services, depending on your configuration, it will either alert you or block them. If the processes are not authorized, you should terminate them manually. If they are authorized, but are missing from the ruleset, you should add them to the ruleset.
7038	Error	Unresolved software change limit reached	Software changes detected on the file system exceeded the maximum amount. Application control will continue to enforce existing rules, but will not record any more changes, and it will stop displaying any of that computer's software changes. You must resolve and prevent excessive software change.
7040	Error	Incompatible Application Control Ruleset	An application control ruleset could not be assigned to one or more computers because the ruleset is not supported by the installed version of the agent. Typically, the problem is that a hash-based ruleset (which is compatible only with Deep Security Agent 11.0 or newer) has been assigned to an older Deep Security Agent. Deep Security Agent 10.x supports only file-based rulesets. (For details, see " Differences in how Deep Security Agent 10.x and 11.x compare files " on page 632.) To fix

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Description or Solution
			this issue, upgrade the Deep Security Agent to version 11.0 or newer. Alternatively, if you are using local rulesets, reset application control for the agent. Or if you are using a shared ruleset, use a shared ruleset that was created with Deep Security 10.x until all agents using the shared ruleset are upgraded to Deep Security Agent 11.0 or newer.
7041	Info	Application Control Ruleset Upgraded	An application control ruleset was upgraded from a file-based ruleset to a hash-based ruleset. (For details, see "Differences in how Deep Security Agent 10.x and 11.x compare files" on page 632.)

Anti-malware events

For general best practices related to events, see ["Events in Deep Security" on page 1088](#).

To see the anti-malware events captured by Deep Security, go to **Events & Reports > Events > Anti-Malware Events**.

What information is displayed for anti-malware events?

These columns can be displayed on the Anti-Malware Events page. You can click **Columns** to select which columns are displayed in the table.

- **Time:** Time the event took place on the computer.
- **Computer:** The computer on which this event was logged. (If the computer has been removed, this entry will read "Unknown Computer".)
- **Infected File(s):** The location and name of the infected file.
- **Tag(s):** Event tags associated with this event.
- **Malware:** The name of the malware that was found.

Trend Micro Deep Security On-Premise 11.3

- **Action Taken:** Displays the results of the actions specified in the malware scan configuration associated with the event.
 - **Cleaned:** Deep Security successfully terminated processes or deleted registries, files, cookies, or shortcuts, depending on the type of malware.
 - **Clean Failed:** Malware could not be cleaned for a variety of possible reasons.
 - **Deleted:** An infected file was deleted.
 - **Delete Failed:** An infected file could not be deleted for a variety of possible reasons. For example, the file may be locked by another application, is on a CD, or is in use. If possible, Deep Security will delete the infected file once it is released.
 - **Quarantined:** An infected file was moved to the identified files folder.
 - **Quarantine Failed:** An infected file could not be quarantined for a variety of possible reasons. For example, the file may be locked by another application, is on a CD, or is in use. If possible, Deep Security will quarantine the infected file once it is released. It is also possible that the "Maximum disk space used to store identified files" (specified on the **Policy/Computer Editor > Anti-Malware > Advanced** tab) has been exceeded.
 - **Access Denied:** Deep Security has prevented the infected file from being accessed without removing the file from the system.
 - **Passed:** Deep Security did not take any action but logged the detection of the malware.
- **Scan Type:** The type of scan that found the malware (Real-Time, Scheduled, or Manual).
- **Event Origin:** Indicates from which part of the Deep Security system the event originated.
- **Reason:** The malware scan configuration that was in effect when the malware was detected.
- **Major Virus Type:** The type of malware detected. Possible values are: Joke, Trojan, Virus, Test, Spyware, Packer, Generic, or Other. For information on these types of malware, see the anti-malware event details or see ["Protect against malware" on page 657](#)

Trend Micro Deep Security On-Premise 11.3

- **Target(s):** The file, process, or registry key (if any) that the malware was trying to affect. If the malware was trying to affect more than one, this field will contain the value "Multiple."
- **Target Type:** The type of system resource that this malware was trying to affect, such as the file system, a process, or Windows registry.
- **Container ID:** ID of the Docker container where the malware was found.
- **Container Image Name:** Image name of the Docker container where the malware was found.
- **Container Name:** Name of the Docker container where the malware was found.
- **File MD5:** The MD5 hash of the file.

List of all anti-malware events

ID	Severity	Event
9001	Info	Anti-Malware Scan Started
9002	Info	Anti-Malware Scan Completed
9003	Info	Anti-Malware Scan Terminated Abnormally
9004	Info	Anti-Malware Scan Paused
9005	Info	Anti-Malware Scan Resumed
9006	Info	Anti-Malware Scan Cancelled
9007	Warning	Anti-Malware Scan Cancel Failed
9008	Warning	Anti-Malware Scan Start Failed
9009	Warning	Anti-Malware Scan Stalled
9010	Error	File cannot be analyzed or quarantined (VM maximum disk space used to store identified files exceeded)
9011	Error	File cannot be analyzed or quarantined (maximum disk space used to store identified files exceeded)
9012	Warning	Smart Protection Server Disconnected for Smart Scan
9013	Info	Smart Protection Server Connected for Smart Scan
9014	Warning	Computer reboot is required for Anti-Malware protection
9016	Info	Anti-Malware Component Update Successful
9017	Error	Anti-Malware Component Update Failed
9018	Error	Files could not be scanned for malware

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event
9019	Error	Directory could not be scanned for malware

Firewall events

For general best practices related to events, see ["Events in Deep Security" on page 1088](#).

To see the firewall events captured by Deep Security, go to **Events & Reports > Events > Firewall Events**.

Firewall event icons:



Single event



Single event with data



Folded event



Folded event with data

Note: Event folding occurs when multiple events of the same type occur in succession. This saves disk space and protects against DoS attacks that may attempt to overload the logging mechanism.

What information is displayed for firewall events?

These columns can be displayed on the firewall events page. You can click **Columns** to select which columns are displayed in the table.

Trend Micro Deep Security On-Premise 11.3

- **Time:** Time the event took place on the computer.
- **Computer:** The computer on which this event was logged. (If the computer has been removed, this entry will read "Unknown Computer".)
- **Reason:** Log entries on this page are generated either by firewall rules or by firewall stateful configuration settings. If an entry is generated by a firewall rule, the column entry will be prefaced by "Firewall Rule:" followed by the name of the firewall rule. Otherwise the column entry will display the firewall stateful configuration setting that generated the log entry.
- **Tag(s):** Event tags that are applied to this event.
- **Action:** The action taken by the firewall rule or firewall stateful configuration. Possible actions are: Allow, Deny, Force Allow, and Log Only.
- **Rank:** The ranking system provides a way to quantify the importance of intrusion prevention and firewall events. By assigning "asset values" to computers, and assigning "severity values" to intrusion prevention rules and firewall rules, the importance ("rank") of an event is calculated by multiplying the two values together. This allows you to sort events by rank when viewing intrusion prevention or firewall events.
- **Direction:** The direction of the affected packet (incoming or outgoing).
- **Interface:** The MAC address of the interface through which the packet was traveling.
- **Frame Type:** The frame type of the packet in question. Possible values are "IPV4", "IPV6", "ARP", "REVARP", and "Other: XXXX" where XXXX represents the four digit hex code of the frame type.
- **Protocol:** Possible values are "ICMP", "ICMPV6", "IGMP", "GGP", "TCP", "PUP", "UDP", "IDP", "ND", "RAW", "TCP+UDP", AND "Other: nnn" where nnn represents a three digit decimal value.
- **Flags:** Flags set in the packet.
- **Source IP:** The packet's source IP.
- **Source MAC:** The packet's source MAC address.

Trend Micro Deep Security On-Premise 11.3

- **Source Port:** The packet's source port.
- **Destination IP:** The packet's destination IP address.
- **Destination MAC:** The packet's destination MAC address.
- **Destination Port:** The packet's destination port.
- **Packet Size:** The size of the packet in bytes.
- **Repeat Count:** The number of times the event was sequentially repeated.
- **Time (microseconds):** Microsecond resolution for the time the event took place on the computer.
- **Event Origin:** The Deep Security component from which the event originated.

Note: Log-only rules will only generate a log entry if the packet in question is not subsequently stopped either by a **deny** rule, or an **allow** rule that excludes it. If the packet is stopped by one of those two rules, *those* rules will generate a log entry and *not* the log-only rule. If no subsequent rules stop the packet, the log-only rule will generate an entry.

List of all firewall events

ID	Event	Notes
100	Out Of Connection	A packet was received that was not associated with an existing connection.
101	Invalid Flags	Flag(s) set in a packet were invalid. This event can indicate that a flag does not make sense within the context of a current connection (if any), or that a nonsensical combination of flags. "Firewall Stateful Configuration" must be On for connection context to be assessed.
102	Invalid Sequence	A packet with an invalid sequence number or out-of-window data size was encountered.
103	Invalid ACK	A packet with an invalid acknowledgment number was encountered.
104	Internal Error	
105	CE Flags	A packet has congestion flags set and the policy's Anti Evasion settings use a custom configuration where the TCP Congestion Flags property is set to Log or Deny. (See "Configure anti-evasion settings" on page 765.)

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
106	Invalid IP	Packet's source IP was not valid.
107	Invalid IP Datagram Length	The length of the IP datagram is less than the length specified in the IP header.
108	Fragmented	A fragmented packet was encountered and fragmented packets are not allowed.
109	Invalid Fragment Offset	
110	First Fragment Too Small	<p>A fragmented packet was encountered, and the size of the first fragment is less than the size of a TCP packet (no data).</p> <p>A packet is dropped with this event when the packet header has the following configuration:</p> <ul style="list-style-type: none"> Fragment Offset = 0 (The fragment is the first in the packet) Total length (maximum combined header length) < 120 bytes (the default allowed minimum fragment size) <p>To prevent this event from occurring, configure the policy's Advanced Network Engine settings to use a lower value for the Minimum Fragment Size property, or set it to 0 to turn off this inspection. (See "Advanced Network Engine Options" in "Network engine settings" on page 549.)</p>
111	Fragment Out Of Bounds	The offsets(s) specified in a fragmented packet sequence is outside the range of the maximum size of a datagram.
112	Fragment Offset Too Small	A fragmented packet was encountered, the size of the fragment was less than the size of a TCP packet (no data).
113	IPv6 Packet	An IPv6 Packet was encountered, and IPv6 blocking is enabled. See the "Block IPv6 on Agents and Appliances versions 9 and later" property in the Advanced Network Engine Options (see "Network engine settings" on page 549.)
114	Max Incoming Connections	The number of incoming connections has exceeded the maximum number of connections allowed. See the "Enable TCP stateful inspection" property in "TCP packet inspection" on page 816.
115	Max Outgoing Connections	The number of outgoing connections has exceeded the maximum number of connections allowed. See the "Enable TCP stateful inspection" property in "TCP packet inspection" on page 816.
116	Max SYN Sent	The number of half open connections from a single computer exceeds that specified in the firewall stateful configuration. See the "Limit the

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
		number of half-open connections from a single computer to" property in "TCP packet inspection" on page 816 .
118	IP Version Unknown	An IP packet other than IPv4 or IPv6 was encountered.
119	Invalid Packet Info	
120	Internal Engine Error	Insufficient system memory. Add more system resources to fix this issue.
121	Unsolicited UDP	Incoming UDP packets that were not solicited by the computer are rejected.
122	Unsolicited ICMP	ICMP stateful has been enabled (in firewall stateful configuration) and an unsolicited packet that does not match any Force Allow rules was received.
123	Out Of Allowed Policy	The packet does not meet any of the Allow or Force Allow rules and so is implicitly denied.
124	Invalid Port Command	An invalid FTP port command was encountered in the FTP control channel data stream.
125	SYN Cookie Error	The SYN cookies protection mechanism encountered an error.
126	Invalid Data Offset	Invalid data offset parameter.
127	No IP Header	The packet IP header is invalid or incomplete.
128	Unreadable Ethernet Header	Data contained in this Ethernet frame is smaller than the Ethernet header.
129	Undefined	
130	Same Source and Destination IP	Source and destination IPs were identical.
131	Invalid TCP Header Length	
132	Unreadable Protocol Header	The packet contains an unreadable TCP, UDP or ICMP header.
133	Unreadable	The packet contains an unreadable IPv4 header.

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
	IPv4 Header	
134	Unknown IP Version	Unrecognized IP version.
135	Invalid Adapter Configuration	An invalid adapter configuration has been received.
136	Overlapping Fragment	This packet fragment overlaps a previously sent fragment.
138	Packet on Closed Connection	A packet was received belonging to a connection already closed.
139	Dropped Retransmit	<p>The network engine detected a TCP Packet that overlaps with data already received on the same TCP connection but does not match the already-received data. (The network engine compares the packet data that was queued in the engine's connection buffer to the data in the packet that was re-transmitted.)</p> <p>The network engine reconstructs the sequenced data stream of each TCP connection it processes. The sequence number and length in the received packet specify a specific region in this data stream. The note field in the log indicates the location of the changed content in the TCP stream: prev-full, prev-part, next-full and next-part:</p> <ul style="list-style-type: none"> "prev-full" and "prev-part": The changed area is in the packet that immediately precedes the retransmitted packet in the sequenced data stream. "prev-full" indicates that the changed area is completely contained in the packet which immediately precedes the retransmitted packet in the sequenced data stream. Otherwise, the note is "prev-part". "next-full" and "next-part": The changed area is in the packet that immediately follows the retransmitted packet in the sequenced data stream. "next-full" indicates that the changed area is completely contained in the packet that immediately follows the retransmitted packet in the sequenced data stream. Otherwise, the note is "next-part".
140	Undefined	

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
141	Out of Allowed Policy (Open Port)	
142	New Connection Initiated	
143	Invalid Checksum	
144	Invalid Hook Used	
145	IP Zero Payload	
146	IPv6 Source Is Multicast	
147	Invalid IPv6 Address	
148	IPv6 Fragment Too Small	
149	Invalid Transport Header Length	
150	Out of Memory	
151	Max TCP Connections	The maximum number of TCP connections has been exceeded. See "Event: Max TCP connections" on page 1301 .
152	Max UDP Connections	
200	Region Too Big	A region (edit region, uri etc) exceeded the maximum allowed buffering size (7570 bytes) without being closed. This is usually because the data does not conform to the protocol.
201	Insufficient Memory	The packet could not be processed properly because resources were exhausted. This can be because too many concurrent connections require buffering (max 2048) or matching resources (max 128) at the same time or because of excessive matches in a single IP packet (max 2048) or simply because the system is out of memory.
202	Maximum Edits Exceeded	The maximum number of edits (32) in a single region of a packet was exceeded.

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
203	Edit Too Large	Editing attempted to increase the size of the region above the maximum allowed size (8188 bytes).
204	Max Matches in Packet Exceeded	There are more than 2048 positions in the packet with pattern match occurrences. An error is returned at this limit and the connection is dropped because this usually indicates a garbage or evasive packet.
205	Engine Call Stack Too Deep	
206	Runtime Error	Runtime error.
207	Packet Read Error	Low level problem reading packet data.
257	Fail Open: Deny	Log the packet that should be dropped but not when Fail-Open feature is on and in Inline mode.
300	Unsupported Cipher	An unknown or unsupported cipher suite has been requested.
301	Error Generating Master Key(s)	Unable to derive the cryptographic keys, Mac secrets, and initialization vectors from the master secret.
302	Record Layer Message (not ready)	The SSL state engine has encountered an SSL record before initialization of the session.
303	Handshake Message (not ready)	The SSL state engine has encountered a handshake message after the handshake has been negotiated.
304	Out Of Order Handshake Message	A well formatted handshake message has been encountered out of sequence.
305	Memory Allocation Error	The packet could not be processed properly because resources were exhausted. This can be because too many concurrent connections require buffering (max 2048) or matching resources (max 128) at the same time or because of excessive matches in a single IP packet (max 2048) or simply because the system is out of memory.
306	Unsupported SSL Version	A client attempted to negotiate an SSL V2 session.
307	Error Decrypting Pre-master	Unable to un-wrap the pre-master secret from the ClientKeyExchange message.

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
	Key	
308	Client Attempted to Rollback	A client attempted to rollback to an earlier version of the SSL protocol than that which was specified in the ClientHello message.
309	Renewal Error	An SSL session was being requested with a cached session key that could not be located.
310	Key Exchange Error	The server is attempting to establish an SSL session with temporarily generated key.
311	Maximum SSL Key Exchanges Exceeded	The maximum number of concurrent key exchange requests was exceeded.
312	Key Too Large	The master secret keys are larger than specified by the protocol identifier.
313	Invalid Parameters In Handshake	An invalid or unreasonable value was encountered while trying to decode the handshake protocol.
314	No Sessions Available	
315	Compression Method Unsupported	
316	Unsupported Application-Layer Protocol	An unknown or unsupported SSL Application-Layer Protocol has been requested.
385	Fail Open: Deny	Log the packet that should be dropped but not when Fail-Open feature is on and in Tap mode.
500	URI Path Depth Exceeded	Too many "/" separators. Max 100 path depth.
501	Invalid Traversal	Tried to use "../" above root.
502	Illegal Character in URI	Illegal character used in uri.
503	Incomplete	URI ended in middle of utf8 sequence.

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
	UTF8 Sequence	
504	Invalid UTF8 encoding	Invalid or non-canonical encoding attempt.
505	Invalid Hex Encoding	%nn where nn are not hex digits.
506	URI Path Length Too Long	Path length is greater than 512 characters.
507	Invalid Use of Character	Use of disabled characters
508	Double Decoding Exploit	Double decoding exploit attempt (%25xx, %25%xxd, etc).
700	Invalid Base64 Content	Packet content that was expected to be encoded in Base64 format was not encoded correctly.
710	Corrupted Deflate/GZIP Content	Packet content that was expected to be encoded in Base64 format was not encoded correctly.
711	Incomplete Deflate/GZIP Content	Incomplete Deflate/GZIP content
712	Deflate/GZIP Checksum Error	Deflate/GZIP checksum error.
713	Unsupported Deflate/GZIP Dictionary	Unsupported Deflate/GZIP dictionary.
714	Unsupported GZIP Header Format/Method	Unsupported GZIP header format or method.
801	Protocol Decoding Search Limit	A protocol decoding rule defined a limit for a search or pdu object but the object was not found before the limit was reached.

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
	Exceeded	
802	Protocol Decoding Constraint Error	A protocol decoding rule decoded data that did not meet the protocol content constraints.
803	Protocol Decoding Engine Internal Error	
804	Protocol Decoding Structure Too Deep	A protocol decoding rule encountered a type definition and packet content that caused the maximum type nesting depth (16) to be exceeded.
805	Protocol Decoding Stack Error	A rule programming error attempted to cause recursion or use too many nested procedure calls.
806	Infinite Data Loop Error	

Intrusion prevention events

For general best practices related to events, see ["Events in Deep Security" on page 1088](#).

To see the intrusion prevention events captured by Deep Security, go to **Events & Reports > Events > Intrusion Prevention Events**.

What information is displayed for intrusion prevention events?

These columns can be displayed on the Intrusion Prevention Events page. You can click **Columns** to select which columns are displayed in the table.

Trend Micro Deep Security On-Premise 11.3

- **Time:** Time the event took place on the computer.
- **Computer:** The computer on which this event was logged. (If the computer has been removed, this entry will read "Unknown Computer".)
- **Reason:** The intrusion prevention rule associated with this event.
- **Tag(s):** Any tags attached with the event.
- **Application Type:** The application type associated with the intrusion prevention rule which caused this event.
- **Action:** What action the intrusion prevention rule took (Block or Reset). If the rule is in **Detect Only** mode, the action is prefaced with "Detect Only:").

Note: Intrusion prevention rules created before Deep Security 7.5 SP1 could also perform Insert, Replace, and Delete actions. These actions are no longer performed. If an older rule is triggered and attempts to perform those actions, the event will indicate that the rule was applied in detect-only mode.

- **Rank:** The ranking system provides a way to quantify the importance of intrusion prevention and firewall events. By assigning "asset values" to computers, and assigning "severity values" to intrusion prevention rules and firewall rules, the importance ("rank") of an event is calculated by multiplying the two values together. This allows you to sort events by rank when viewing intrusion prevention or firewall events.
- **Severity:** The intrusion prevention rule's severity value.
- **Direction:** The direction of the packet (incoming or outgoing)
- **Flow:** whether the packets(s) that triggered this event was travelling with ("Connection Flow") or against ("Reverse Flow") the direction of traffic being monitored by the intrusion prevention rule.
- **Interface:** The MAC address of the interface through which the packet was passing.

Trend Micro Deep Security On-Premise 11.3

- **Frame Type:** The frame type of the packet in question. Possible values are "IPv4", "IPv6", "ARP", "REVARP", and "Other: XXXX" where XXXX represents the four digit hex code of the frame type.
- **Protocol:** Possible values are "ICMP", "ICMPV6", "IGMP", "GGP", "TCP", "PUP", "UDP", "IDP", "ND", "RAW", "TCP+UDP", AND "Other: nnn" where nnn represents a three digit decimal value.
- **Flags:** Flags set in the packet.
- **Source IP:** The packet's source IP.
- **Source MAC:** The packet's source MAC address.
- **Source Port:** The packet's source port.
- **Destination IP:** The packet's destination IP address.
- **Destination MAC:** The packet's destination MAC address.
- **Destination Port:** The packet's destination port.
- **Packet Size:** The size of the packet in bytes.
- **Repeat Count:** The number of times the event was sequentially repeated.
- **Time (microseconds):** Microsecond resolution for the time the event took place on the computer.
- **Event Origin:** The Deep Security component from which the event originated.

List of all intrusion prevention events

ID	Event	Notes
200	Region Too Big	A region (edit region, uri etc) exceeded the maximum allowed buffering size (7570 bytes) without being closed. This is usually because the data does not conform to the protocol.
201	Insufficient Memory	The packet could not be processed properly because resources were exhausted. This can be because there are too many concurrent connections at the same time or simply because the system is out of memory.
202	Maximum Edits Exceeded	The maximum number of edits (32) in a single region of a packet was exceeded.

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
203	Edit Too Large	Editing attempted to increase the size of the region above the maximum allowed size (8188 bytes).
204	Max Matches in Packet Exceeded	There are more than 2048 positions in the packet with pattern match occurrences. An error is returned at this limit and the connection is dropped because this usually indicates a garbage or evasive packet.
205	Engine Call Stack Too Deep	
206	Runtime Error	Runtime error.
207	Packet Read Error	Low level problem reading packet data.
258	Fail Open: Reset	Log the connection that should be reset but not when Fail-Open feature is on and in Inline mode
300	Unsupported Cipher	An unknown or unsupported Cipher Suite has been requested.
301	Error Generating Master Key(s)	Unable to derive the cryptographic keys, Mac secrets, and initialization vectors from the master secret.
302	Record Layer Message (not ready)	The SSL state engine has encountered an SSL record before initialization of the session.
303	Handshake Message (not ready)	The SSL state engine has encountered a handshake message after the handshake has been negotiated.
304	Out Of Order Handshake Message	A well formatted handshake message has been encountered out of sequence.
305	Memory Allocation Error	The packet could not be processed properly because resources were exhausted. This can be because there are too many concurrent connections at the same time or simply because the system is out of memory.
306	Unsupported SSL Version	A client attempted to negotiate an SSL V2 session.
307	Error Decrypting Pre-master Key	Unable to un-wrap the pre-master secret from the ClientKeyExchange message.
308	Client Attempted to Rollback	A client attempted to rollback to an earlier version of the SSL protocol than that which was specified in the ClientHello message.
309	Renewal Error	An SSL session was being requested with a cached session key that could not be located.
310	Key Exchange Error	The server is attempting to establish an SSL session with temporarily generated key.
311	Maximum SSL Key Exchanges Exceeded	The maximum number of concurrent key exchange requests was exceeded.
312	Key Too Large	The master secret keys are larger than specified by the protocol identifier.
313	Invalid Parameters In Handshake	An invalid or unreasonable value was encountered while trying to decode the handshake protocol.

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
314	No Sessions Available	
315	Compression Method Unsupported	
316	Unsupported Application-Layer Protocol	An unknown or unsupported SSL Application-Layer Protocol has been requested.
386	Fail Open: Reset	Log the connection that should be reset but not when Fail-Open feature is on and in Tap mode.
500	URI Path Depth Exceeded	Too many "/" separators. Max 100 path depth.
501	Invalid Traversal	Tried to use "../" above root.
502	Illegal Character in URI	Illegal character used in uri.
503	Incomplete UTF8 Sequence	URI ended in middle of utf8 sequence.
504	Invalid UTF8 encoding	Invalid or non-canonical encoding attempt.
505	Invalid Hex Encoding	%nn where nn are not hex digits.
506	URI Path Length Too Long	Path length is greater than 512 characters.
507	Invalid Use of Character	Use of disabled characters
508	Double Decoding Exploit	Double decoding exploit attempt (%25xx, %25%xxd, etc).
700	Invalid Base64 Content	Packet content that was expected to be encoded in Base64 format was not encoded correctly.
710	Corrupted Deflate/GZIP Content	Packet content that was expected to be encoded in Base64 format was not encoded correctly.
711	Incomplete Deflate/GZIP Content	Incomplete Deflate/GZIP content
712	Deflate/GZIP Checksum Error	Deflate/GZIP checksum error.
713	Unsupported Deflate/GZIP Dictionary	Unsupported Deflate/GZIP dictionary.
714	Unsupported GZIP Header Format/Method	Unsupported GZIP header format or method.
801	Protocol Decoding Search Limit Exceeded	A protocol decoding rule defined a limit for a search or pdu object but the object was not found before the limit was reached.
802	Protocol Decoding Constraint Error	A protocol decoding rule decoded data that did not meet the protocol content constraints.

Trend Micro Deep Security On-Premise 11.3

ID	Event	Notes
803	Protocol Decoding Engine Internal Error	
804	Protocol Decoding Structure Too Deep	A protocol decoding rule encountered a type definition and packet content that caused the maximum type nesting depth (16) to be exceeded.
805	Protocol Decoding Stack Error	A rule programming error attempted to cause recursion or use too many nested procedure calls.
806	Infinite Data Loop Error	

Integrity monitoring events

For general best practices related to events, see ["Events in Deep Security" on page 1088](#).

To see the integrity monitoring events captured by Deep Security, go to **Events & Reports > Events > Integrity Monitoring Events**.

What information is displayed for integrity monitoring events?

These columns can be displayed on the Integrity Monitoring Events page. You can click **Columns** to select which columns are displayed in the table.

- **Time:** Time the event took place on the computer.
- **Computer:** The computer on which this event was logged. (If the computer has been removed, this entry will read "Unknown Computer".)
- **Reason:** The integrity monitoring rule associated with this event.
- **Tag(s):** Event tags that are applied to this event.
- **Change:** The change detected by the integrity rule. Can be: Created, Updated, Deleted, or Renamed.

Trend Micro Deep Security On-Premise 11.3

- **Rank:** The ranking system provides a way to quantify the importance of events. By assigning "asset values" to computers, and assigning "severity values" to rules, the importance ("rank") of an event is calculated by multiplying the two values together. This allows you to sort events by rank.
- **Severity:** The integrity monitoring rule's severity value
- **Type:** Type of entity from which the event originated
- **Key:** Path and file name or registry key from which the event originated
- **User:** User ID of the file owner
- **Process:** Process from which the event originated
- **Event Origin:** The Deep Security component from which the event originated

List of all integrity monitoring events

ID	Severity	Event	Notes
8000	Info	Full Baseline Created	Created when the agent has been requested to build a baseline or went from 0 integrity monitoring rules to n (causing the baseline to be built). This event includes information on the time taken to scan (ms), and number of entities cataloged.
8001	Info	Partial Baseline Created	Created when the agent had a security configuration where one or more integrity monitoring rules changed. This event includes information on the time taken to scan (ms), and number of entities cataloged.
8002	Info	Scan for Change Completed	Created when the agent is requested to do a full or partial on-demand scan. This event includes information on the time taken to scan (ms), and number of CHANGES cataloged. (Ongoing scans for changes based on the FileSystem Driver or the notify do not generate an 8002 event.)
8003	Error	Unknown Environment Variable in Integrity Monitoring Rule	Created when a rule uses a \${env.EnvironmentVar} and "EnvironmentVar" is not a known environment variable. This event includes the ID of the integrity monitoring rule containing the problem, the name of the integrity monitoring rule, and the name of the unknown environment variable.
8004	Error	Bad Base in Integrity Monitoring Rule	Created when a rule contains an invalid base directory or key. For example, specifying a FileSet with a base of "c:\foo\d:\bar" would generate this event, or the invalid value could be the result of environment variable substitution the yields a bad value. This event includes the ID of the integrity monitoring rule containing the problem, the name of the integrity monitoring rule, and the bad base value.
8005	Error	Unknown Entity in	Created when an unknown EntitySet is encountered in an integrity monitoring rule. This event includes the ID of the

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Notes
		Integrity Monitoring Rule	integrity monitoring rule containing the problem, the name of the integrity monitoring rule, and a comma-separated list of the unknown EntitySet names encountered.
8006	Error	Unsupported Entity in Integrity Monitoring Rule	Created when a known but unsupported EntitySet is encountered in an integrity monitoring rule. This event includes the ID of the integrity monitoring rule containing the problem, the name of the integrity monitoring rule, and a comma-separated list of the unsupported EntitySet names encountered. Some EntitySet types such as RegistryKeySet are platform-specific.
8007	Error	Unknown Feature in Integrity Monitoring Rule	Created when an unknown feature is encountered in an integrity monitoring rule. This event includes the ID of the integrity monitoring rule containing the problem, the name of the integrity monitoring rule, the type of entity set (for example, FileSet), and a comma-separated list of the unknown feature names encountered. Examples of valid feature values are "whereBaseInOtherSet", "status", and "executable".
8008	Error	Unsupported Feature in Integrity Monitoring Rule	Created when a known but unsupported feature is encountered in an integrity monitoring rule. This event includes the ID of the integrity monitoring rule containing the problem, the name of the integrity monitoring rule, the type of entity set (for example, FileSet), and a comma-separated list of the unsupported feature names encountered. Some feature values such as "status" (used for Windows service states) are platform-specific.
8009	Error	Unknown Attribute in Integrity Monitoring Rule	Created when an unknown attribute is encountered in an integrity monitoring rule. This event includes the ID of the integrity monitoring rule containing the problem, the name of the integrity monitoring rule, the type of entity set (for example, FileSet), and a comma-separated list of the unknown attribute names encountered. Examples of valid attribute values are "created", "lastModified" and "inodeNumber".
8010	Error	Unsupported Attribute in Integrity Monitoring Rule	Created when a known but unsupported attribute is encountered in an integrity monitoring rule. This event includes the ID of the integrity monitoring rule containing the problem, the name of the integrity monitoring rule, the type of entity set (for example, FileSet), and a comma-separated list of the unsupported attribute names encountered. Some attribute values such as "inodeNumber" are platform-specific.
8011	Error	Unknown Attribute in Entity Set in Integrity Monitoring Rule	Created when an unknown EntitySet XML attribute is encountered in an integrity monitoring rule. This event includes the ID of the integrity monitoring rule containing the problem, the name of the integrity monitoring rule, the type of entity set (for example, FileSet), and a comma-separated list of the unknown EntitySet attribute names encountered. You would get this event if you wrote <FileSet dir="c:\foo"> instead of <FileSet base="c:\foo">
8012	Error	Unknown Registry String in Integrity Monitoring Rule	Created when a rule references a registry key that doesn't exist. This event includes the ID of the integrity monitoring rule containing the problem, the name of the integrity monitoring rule, and the name of the unknown registry string.
8013	Error	Invalid WQLSet was used. Namespace or WQL query was missing.	Indicates that the namespace is missing from a WQL query because an integrity rule XML is incorrectly formatted. This can occur only in an advanced case, with custom integrity rules that use and monitor WQL queries.
8014	Error	Invalid WQLSet	

Trend Micro Deep Security On-Premise 11.3

ID	Severity	Event	Notes
		was used. An unknown provider value was used.	
8015	Warning	Inapplicable Integrity Monitoring Rule	Can be caused by a number of reasons, such as platform mismatch, nonexistent target directories or files, or unsupported functionality.
8016	Warning	Suboptimal Integrity Rule Detected	
8050	Error	Regular expression could not be compiled. Invalid wildcard was used.	

Log inspection events

For general best practices related to events, see ["Events in Deep Security" on page 1088](#).

To see the log inspection events captured by Deep Security, go to **Events & Reports > Events > Log Inspection Events**.

What information is displayed for log inspection events?

These columns can be displayed on the log inspection events page. You can click **Columns** to select which columns are displayed in the table.

- **Time:** Time the event took place on the computer.
- **Computer:** The computer on which this event was logged. (If the computer has been removed, this entry will read "Unknown Computer".)

Trend Micro Deep Security On-Premise 11.3

- **Reason:** The log inspection rule associated with this event.
- **Tag(s):** Any tags attached with the event.
- **Description:** Description of the rule.
- **Rank:** The ranking system provides a way to quantify the importance of events. By assigning "asset values" to computers, and assigning "severity values" to log inspection rules, the importance ("rank") of an event is calculated by multiplying the two values together. This allows you to sort events by rank.
- **Severity:** The log inspection rule's severity value.
- **Groups:** Group that the rule belongs to.
- **Program Name:** Program name. This is obtained from the syslog header of the event.
- **Event:** The name of the event.
- **Location:** Where the log came from.
- **Source IP:** The packet's source IP.
- **Source Port:** The packet's source port.
- **Destination IP:** The packet's destination IP address.
- **Destination Port:** The packet's destination port.
- **Protocol:** Possible values are "ICMP", "ICMPV6", "IGMP", "GGP", "TCP", "PUP", "UDP", "IDP", "ND", "RAW", "TCP+UDP", AND "Other: nnn" where nnn represents a three digit decimal value.
- **Action:** The action taken within the event
- **Source User:** Originating user within the event.
- **Destination User:** Destination user within the event.
- **Event HostName:** Hostname of the event source.

Trend Micro Deep Security On-Premise 11.3

- **ID:** Any ID decoded as the ID from the event.
- **Status:** The decoded status within the event.
- **Command:** The command being called within the event.
- **URL:** The URL within the event.
- **Data:** Any additional data extracted from the event.
- **System Name:** The system name within the event.
- **Rule Matched:** Rule number that was matched.
- **Event Origin:** The Deep Security component from which the event originated.

List of log inspection security events

Note: For system events related to log inspection, see ["System events" on page 1220](#).

ID	Severity	Event
8100	Error	Log Inspection Engine Error
8101	Warning	Log Inspection Engine Warning
8102	Info	Log Inspection Engine Initialized

Web reputation events

For general best practices related to events, see ["Events in Deep Security" on page 1088](#).

To see the web reputation events captured by Deep Security, go to **Events & Reports > Events > Web Reputation Events**.

What information is displayed for web reputation events?

These columns can be displayed on the web reputation events page. You can click **Columns** to select which columns are displayed in the table.

- **Time:** Time the event took place on the computer.
- **Computer:** The computer on which this event was logged. (If the computer has been removed, this entry will read "Unknown Computer".)
- **URL:** The URL that triggered this event.
- **Tag(s):** Event tags associated with this event.
- **Risk:** What was the risk level of the URL that triggered the event ("Suspicious", "Highly Suspicious", "Dangerous", "Untested", or "Blocked by Administrator").
- **Rank:** Rank provides a way to quantify the importance of events. It is calculated by multiplying the asset value of the computer by the severity of the rule. (See ["Rank events to quantify their importance" on page 1109.](#))
- **Event Origin:** Indicates from which part of the Deep Security system the event originated.

Add a URL to the list of allowed URLs

If you want to add the URL that triggered an event to the list of allowed URLs, right-click the event and select **Add to Allow List**. (To view or edit the **Allowed** and **Blocked** lists, go to the **Exceptions** tab on the main **Web Reputation** page.)

Troubleshoot common events, alerts, and errors

This section provides troubleshooting tips for some common events, alerts, and errors.

Trend Micro Deep Security On-Premise 11.3

- ["Why am I seeing firewall events when the firewall module is off?" on the next page](#)
- ["Why am I getting "Unrecognized Client" events?" on the next page](#)
- [Event: Configuration package too large \(See "Maximum size for configuration packages " on page 769.\)](#)
- ["Troubleshoot "Smart Protection Server disconnected" errors" on page 1278](#)
- ["Error: Activation Failed" on page 1279](#)
- ["Error: Agent version not supported" on page 1282](#)
- ["Error: Installation of Feature 'dpi' failed: Not available: Filter" on page 1282](#)
- ["Error: Interface out of sync" on page 1283](#)
- ["Error: Integrity Monitoring Engine Offline and other errors occur after activating a virtual machine" on page 1288](#)
- ["Error: Module installation failed \(Linux\)" on page 1289](#)
- ["Error: There are one or more application type conflicts on this computer" on page 1290](#)
- ["Error: Unable to connect to the cloud account" on page 1292](#)
- ["Error: Unable to resolve instance hostname" on page 1293](#)
- ["Error: Anti-malware engine offline" on page 1294](#)
- ["Error: Check Status Failed" on page 1297](#)
- ["Error: Log Inspection Rules Require Log Files" on page 1298](#)
- ["Alert: Integrity Monitoring information collection has been delayed" on page 1299](#)
- ["Alert: The memory warning threshold of Manager Node has been exceeded" on page 1300](#)
- ["Alert: Manager Time Out of Sync" on page 1301](#)
- ["Warning: Reconnaissance Detected" on page 1304](#)

- ["Warning: Insufficient disk space" on page 1306](#)

Why am I seeing firewall events when the firewall module is off?

If you have Intrusion Prevention or Web Reputation enabled, you may see some Firewall events because the Intrusion Prevention and Web Reputation modules leverage the Firewall's stateful configuration mechanism to perform inspections.

Why am I getting "Unrecognized Client" events?

The **Unrecognized Client** event message appears when the Deep Security Manager is contacted by a Deep Security Agent that it doesn't recognize.

The most common reason is that an instance has been manually deleted from the **Computers** page in Deep Security Manager *before* deactivating the agent on that instance.

The Deep Security Agent on the instance will continue to try to connect to the Deep Security Manager periodically, generating the **Contact by Unrecognized Client** event message.

In order to bring the deleted computer back into the list of computers in Deep Security Manager, you need to do the following:

1. Go to **Administration > System Settings > Agents > Agent-Initiated Activation** and select **Reactivate unknown Agents**. With this setting enabled, previously activated computers (computers, VMware virtual machines, AWS instances, or Azure VMs) that have been removed from their cloud environment and deleted from the Deep Security Manager can be reactivated if they are added back to the inventory of computers. Deep Security Manager will recognize a valid certificate on the computer and allow it to be reactivated. No policies or rules that may have been in place on the original computer will be assigned to the new one. It will be handled just like a newly-activated computer.
2. If you no longer want to protect this computer, use the **Computer > Actions** menu to deactivate the agent.

Note: After the agent has been deactivated, then you can manually delete the computer from the **Computers** list in the Deep Security Manager.

Troubleshoot "Smart Protection Server disconnected" errors

If you are using the anti-malware or web reputation modules, you may see either a "Smart Protection Server Disconnected for Smart Scan" or "Smart Protection Server Disconnected for Web Reputation" error in the Deep Security Manager console. To fix the error, try the following troubleshooting tips.

Check the error details

Double-click the error message to display more detailed information, including the URL that the server is trying to contact. The error may include:

- Timeout was reached
- Couldn't resolve hostname

From a command prompt, use nslookup to check whether the DNS name resolves to an IP address. If the URL doesn't resolve, then there is a DNS issue on the local server.

Use a telnet client to test connectivity to the URL on ports 80 and 443. If you can't connect, check that all of your firewalls, security groups, etc. are allowing outbound communication to the URL on those ports.

Is the issue on a Deep Security Virtual Appliance?

If the error is occurring for a Deep Security Virtual Appliance:

Trend Micro Deep Security On-Premise 11.3

1. Check the virtual appliance's internet connectivity.
2. Make sure the virtual appliance has a bi-directional connection to the internet via port 80.
3. Make sure there is sufficient memory assigned to the virtual appliance. For details on memory requirements, see ["Deep Security Virtual Appliance sizing" on page 109](#).

Error: Activation Failed

Several events can trigger an "Activation Failed" alert:

- ["Activation Failed - Protocol Error" below](#)
- ["Activation Failed - Unable to resolve hostname" on the next page](#)
- ["Activation Failed - No agent/appliance" on the next page](#)
- ["Activation Failed - Blocked port" on the next page](#)

Activation Failed - Protocol Error

This error typically occurs when you use Deep Security Manager to attempt to activate a Deep Security Agent and the manager is unable to communicate with the agent. The communication directionality that the agent uses determines the method that you should use to troubleshoot this error. (See ["Agent-manager communication" on page 344](#).)

Agent-initiated communication

When the agent uses agent-initiated communication, you need to activate the agent from the agent computer. (See ["Activate an agent" on page 402](#).)

When using Deep Security as a Service, agent-initiated communication is the recommended communication directionality.

Trend Micro Deep Security On-Premise 11.3

Bidirectional communication

Use the following troubleshooting steps when the error occurs and the agent uses bidirectional communication:

1. Ensure that the agent is installed on the computer and that the agent is running.
2. Ensure that the ports are open between the manager and the agent. (See ["Port numbers, URLs, and IP addresses" on page 111](#) and ["Create a firewall rule" on page 786](#).)

Activation Failed - Unable to resolve hostname

The error: Activation Failed (Unable to resolve hostname) could be the result of an unresolvable hostname in DNS or of activating the agent from Deep Security Manager when you are not using agent-initiated activation.

If your agent is in bidirectional or manager-initiated mode, your hostname must be resolvable in DNS. Check the DNS on your Deep Security Manager to ensure it can resolve your hosts.

If you are a Deep Security as a Service user or your computers are in cloud accounts, we recommend that you always use agent-initiated activation. Learn how to configure policy rules for agent-initiated communication and deploy agents using deployment scripts, see ["Use agent-initiated communication with cloud accounts" on page 350](#).

Activation Failed - No agent/appliance

This error message indicates that the agent software has not been installed on the computer that you would like to protect.

Review ["Get Deep Security Agent software" on page 318](#).

Activation Failed - Blocked port

If you are seeing 'Activation Failed' events with the following error messages in the `ds_agent.log`:

Trend Micro Deep Security On-Premise 11.3

```
• 2018-06-25 17:52:14.000000: [Error/1] | CHTTPServer::AcceptSSL(<IP>:<PORT>) - BIO_do_handshake() failed - peer
closed connection. | http\HTTPServer.cpp:246:DsaCore::CHTTPServer::AcceptSSL | 1E80:1FEC:ActivateThread

• 2018-06-25 17:52:14.143355: [dsa.Heartbeat/5] | Unable to reach a manager. | .\dsa\Heartbeat.lua:149:(null) |
1E80:1FEC:ActivateThread

• 2018-06-25 17:52:14.000000: [Info/5] | AgentEvent 4012 |
common\DomainPrivate.cpp:493:DsaCore::DomPrivateData::AgentEventWriteHaveLock | 1E80:1FEC:ActivateThread

• 2018-06-25 17:52:14.143355: [Cmd/5] | Respond() - sending status line of 'HTTP/1.1 400 OK' |
http\HTTPServer.cpp:369:DsaCore::CHTTPServer::Respond | 1E80:1D7C:ConnectionHandlerPool_0011
```

...and the following messages in your packet capture software (pcap):

```
• [TCP Retransmission] <Ephemeral Port> -> 443 [SYN, ECN, CWR] .....

• [TCP Retransmission] <Ephemeral Port> -> 443 [SYN] .....
```

...it may be because you have blocked a port used by the Deep Security Agents and manager to establish communication. agent-manager communication ports could be any of the following:

Agent-manager communication type	Source / Port	Destination / Port
Agent-initiated communication	Deep Security Agent / Ephemeral port	Manager / 4119
Agent-initiated communication	Deep Security Agent / Ephemeral port	Deep Security as a Service / 443
Manager-initiated communication	Deep Security Manager or Deep Security as a Service / Ephemeral port	Agent / 4118

Trend Micro Deep Security On-Premise 11.3

As you can see from the table above, [ephemeral ports](#) are used for the source port for outbound communication between agent and manager. If those are blocked, then the agent can't be activated and heartbeats won't work. The same problems arise if any of the destination ports are blocked.

To resolve this issue:

- Remove restrictions on client outbound ports (ephemeral) in your network configuration.
- Allow access to Deep Security Manager on port 4119, or Deep Security as a Service on 443.
- Allow inbound access to Deep Security Agent on port 4118 if you're using Manager-initiated communication.

For details on ports, see ["Port numbers, URLs, and IP addresses" on page 111](#).

Error: Agent version not supported

The error message "Agent version not supported" indicates that the agent version currently installed on the computer is not supported by the Deep Security Manager.

Although the unsupported agent will still protect the computer based on the last policy settings it received from the Deep Security Manager, we recommend that you upgrade the agent so that you can react quickly to the latest threats. For more information, see ["Update the Deep Security Agent" on page 984](#).

Error: Installation of Feature 'dpi' failed: Not available: Filter

The error message "Installation of Feature 'dpi' failed: Not available: Filter" indicates that your operating system kernel version is not supported by the network driver. You will typically get this message when installing Intrusion Prevention, Web Reputation, or Firewall because the Deep Security Agent installs a network driver at the same time in order to examine traffic. The same circumstances can cause **engine offline** alerts.

Trend Micro Deep Security On-Premise 11.3

An update may be on its way. Trend Micro actively monitors a variety of operating system vendors for new kernel releases. After completing quality assurance tests, we will release an update with support for these kernels.

Your system will install the required support automatically when an update for your operating system kernel version becomes available.

Contact technical support (sign in Deep Security, and click **Support** in the top right-hand corner) to find out when support for your operating system kernel version will be released.

Additional information

This only affects Intrusion Prevention, Web Reputation, and Firewall. All other protection modules (Anti-Malware, Integrity Monitoring, and Log Inspection) will operate correctly.

To review supported operating system kernel versions, visit the [Deep Security 9.6 Supported Linux Kernels](#) page and look for your operating system distribution.

Error: Interface out of sync

This error occurs when the network interface information (such as different MAC addresses) that the Deep Security Manager has stored in its database for the guest virtual machine (VM) is not the same as the interface information being reported by the Deep Security Virtual Appliance.

To determine the root cause of this issue, you need to find out where the information has become out of sync.

The first step is to check the error message from Deep Security Manager to determine which VM and which interface has the issue.

Check the interfaces on the VM

1. Log into the VM.
2. Open a command prompt.
3. Enter the command to display all network interfaces' information. For example, on Windows, enter: `ipconfig /all`
4. Verify all of the NICs and MAC addresses and make sure that the NICs have the correct driver and that they are working properly.

Check the VM's interface information in vCenter

Check the VM interface information from the Managed Object Reference (MoRef) in the vCenter Server.

1. Go to the virtual computer MOB at: `https://<VC_SERVER>/mob/?moid=<OBJECT_ID>`

For example, you might go to this URL: `https://192.168.100.100/mob/?moid=vm-1136&doPath=config`

where:

<VC_SERVER> is the FQDN or IP of the vCenter Server

=<OBJECT_ID> is the ID of the object you are looking up

For more information on accessing the VC MOB see [Looking up Managed Object Reference \(MoRef\) in vCenter Server](#).

2. Go to **Config > extraConfig["ethernet0.filter0....."] > hardware** to check all the NICs and MAC address.
3. Compare the MAC addresses with [the MAC in the VM's OS](#).

Check the vmx file and the VM's interface information in Deep Security Manager

1. Use the vCenter Server datastore browser to download the VM's vmx file.
2. Open the vmx file using a plain text editor such as Notepad.

Trend Micro Deep Security On-Premise 11.3

3. Check the IPs, uuid.bios, and MAC addresses.

For example:

```
Check virtual computer UUID
- uuid.bios = "42 23 d6 5d f2 d5 22 41-87 41 86 83 ea 2f 23 ac"
Check EPSec Settings
- VFILE.globaloptions = "svmip=169.254.50.39 svmpport=8888"
- scsi0:0.filters = "VFILE"
Check DvFilter Settings
- ethernet0.filter0.name = "dvfilter-dsa"
- ethernet0.filter0.onFailure = "failOpen"
- ethernet0.filter0.param0 = "4223d65d-f2d5-2241-8741-8683ea2f23ac"
- ethernet0.filter0.param2 = "1"
- ethernet0.filter0.param1 = "00:50:56:A3:02:D8"
```

4. Go to the Deep Security Manager dashboard, double-click the **VM > Interfaces**, and verify the IPs and MAC addresses.
5. Compare the IP and MAC address with the results from above.

Check the VM's interface information in the Deep Security Virtual Appliance

1. Use the vCenter Server datastore browser to download the specific vmx file of the virtual computer.
2. Open the vmx file using a plain text editor such as Notepad.
3. Check the uuid.bios value.
4. Log on to the Deep Security Virtual Appliance console and press **Alt + F2** to switch to command mode and then enter the Deep Security Virtual Appliance user name and password.
5. Run the following command to determine whether the VM's network interface was recognized by Deep Security Virtual Appliance. (Note: Replace \$uuid with your actual bios uuid.)

```
cd /var/opt/ds_agent/guests/$uuid
```


Trend Micro Deep Security On-Premise 11.3

```
>/opt/ds_guest_agent/ratt if
```

6. Execute the **ifconfig -a** command to verify if the Deep Security Virtual Appliance NIC settings and IP are configured correctly.
7. Compare the IP and MAC address with the results from above.

Workaround Options

If any of the above items are out of sync then you need to fix this issue.

Option 1

When cloning an activated VM in Deep Security, you might receive the out-of-sync interface alert if you power on and activate the cloned computer. As a work around, clean the dvfilter settings before powering on the cloned computer.

- ethernet0.filter0.name = "dvfilter-dsa"
- ethernet0.filter0.onFailure = "failOpen"
- ethernet0.filter0.param0 = "4223d65d-f2d5-2241-8741-8683ea2f23ac"
- ethernet0.filter0.param2 = "1"
- ethernet0.filter0.param1 = "00:50:56:A3:02:D8"

Option 2

1. Suspend the VM and power it on again.
2. Restart the Deep Security Virtual Appliance.
3. Deactivate the VM and then activate it again.

Option 3

Use vMotion to move the VM to a protected ESXi host and then dismiss the warning message.

Trend Micro Deep Security On-Premise 11.3

Note: The vCenter must be connected to the Deep Security Manager all the time. Otherwise, the out-of-sync interface issue will happen repeatedly.

Further Troubleshooting

1. Provide the results of the step from above where you [verified the IP and MAC Addresses](#) in "Check the VM's interface information in the Deep Security Virtual Appliance " on page 1285
2. Get the rattif.txt file from the step from above where you [verified that the VM's interface was recognized by Deep Security Virtual Appliance](#).

3. Get the output from the following commands:

```
$ ls -alR > /home/dsva/ls.txt
$ netstat -an > /home/dsva/netstat.txt
$ ps auxww > /home/dsva/ps.txt
$ lsof > /home/dsva/lsof.txt
$ ifconfig -a > /home/dsva/ifconfig.txt
$ cp /var/log/syslog /home/dsva/syslog.txt
```

4. Get the [diagnostic packages for the Deep Security Manager, Deep Security Agent, and the Deep Security Virtual Appliance](#).
5. Collect the following files and send them to [Trend Micro Technical Support](#).
 - rattif.txt
 - ls.txt
 - netstat.txt
 - ps.txt
 - lsof.txt

Trend Micro Deep Security On-Premise 11.3

- ifconfig.txt
- syslog.txt

If you cannot find the MAC address of the virtual computer from the output of the `ratt if` command, then use the following workaround:

1. Deploy a virtual computer from a template in vCenter.
2. Delete the existing NIC.
3. Power on this virtual computer but there is no need to log on.
4. Power off this virtual computer.
5. Add a new NIC.
6. Power on the virtual computer.

Error: Integrity Monitoring Engine Offline and other errors occur after activating a virtual machine

The following errors are displayed in Deep Security Manager when activating a virtual machine protected by Deep Security Virtual Appliance. These errors appear even when the activation is successful:

- Anti-Malware Engine Offline
- Rebuild Baseline Failure (Agent or Appliance error)
- Integrity Monitoring Engine Offline

The issue remains unresolved even when the following troubleshooting tasks are performed:

- Confirm that vSphere Endpoint is already installed.
- Confirm that VMware tools are installed and up to date.

Trend Micro Deep Security On-Premise 11.3

- Confirm that VMCI and VSEPFLT drivers are installed and running on the VM.
- Synchronize vCenter on the DSM console.
- Deactivate and reactivate the Deep Security Virtual Appliance.
- Deactivate and reactivate the particular VM with issue.
- Reinstall VMware tools.

These errors appear because the virtual machine is not running VMversion 7 or above. To resolve the issue, you need to [upgrade the VM to the latest hardware version](#).

Error: Module installation failed (Linux)

The error message "Module Installation Failed" indicates that your operating system's kernel version is not supported by the Deep Security network driver, or file system hook. These circumstances can cause **engine offline** alerts. Lack of a compatible network driver is the most common cause of this message.

When you apply intrusion prevention, web reputation, or firewall, the Deep Security Agent installs a network driver so it can examine traffic. Anti-malware and integrity monitoring install a file system hook module. This is required to monitor file system changes in real time. (Scheduled scans do not require the same file system hook.)

An update may be in progress. Trend Micro monitors many vendors for new kernel releases. After completing quality assurance tests, we release an update with support for these kernels. To ask when support for your kernel version will be supported, contact technical support. (When logged in, you can click **Support** in the top right corner.)

Your system will install the module support update automatically when it becomes available.

To view supported operating system kernel versions, see ["Deep Security Agent Linux kernel support" on page 83](#).

Error: There are one or more application type conflicts on this computer

This error message appears in the DPI Events tab in Deep Security Manager when updating the Deep Security Agents:

There are one or more application type conflicts on this computer. One or more DPI rules associated with one application type are dependent on one or more DPI rules associated with another application type. The conflict exists because the two application types use different ports.

The conflicting application types are:

```
[A] "Web Application Tomcat" Ports: [80,8080,4119]
```

```
[B] "Web Server Common" Ports: [80,631,8080,7001,7777,7778,7779,7200,7501,8007, 8004,4000,32000,5357,5358,9000]
```

```
[A] "Web Server Miscellaneous" Ports: [80,4000,7100,7101,7510,8043,8080,8081,8088,8300,8500,  
8800,9000,9060,19300,32000,3612,10001,8093,8094]
```

```
[B] "Web Server Common" Ports: [80,631,8080,7001,7777,7778,7779,7200,7501,8007, 8004,4000,32000,5357,5358,9000] "
```

Resolution

To resolve the conflict, edit the port numbers used by application types B so that they include the port numbers used by application types A. The two application types (Web Application Tomcat and Web Server Miscellaneous) are both dependent on the application type Web Server Common. This is why the ports listed in the first two application types should also appear in the Web Server Common ports.

If you consolidate the port numbers for these three application types, the result is as follows:

```
80,631,3612,4000,4119,5357,5358,7001,7100,7101,7200,7501,7510,7777,7778,7779,  
8004,8007,8043,8080,8081,8088,8093,8094,8300,8500,8800,9000,9060,10001,19300,32000
```

After adding this to the Web Server Common port list, you will see the following message in the Events tab: *The Application Type Port List Misconfiguration has been resolved.*

Trend Micro Deep Security On-Premise 11.3

Consolidate ports

1. Log on to Deep Security Manager and go to **Policies > Rules > Intrusion Prevention Rules**.
2. Search for **Web Server Common** in the search box in the and double-click the Web Server Common application type.
3. Go to **General > Details > Application type > Edit > Web server common**.
4. Go to **General > Connection > Port** and click **Edit** to replace all of the ports with this consolidated entry:

80, 631, 3612, 4000, 4119, 5357, 5358, 7001, 7100, 7101, 7200,

7501, 7510, 7777, 7778, 7779, 8004, 8007, 8043, 8080, 8081, 8088, 8093, 8094, 8300, 8500, 8800, 9000, 9060, 10001, 19300, 32000

5. Click **OK**.

Disable the inherit option

It is also recommended that administrators disable the inherit option for DPI for a security profile. Any change you make to the application type will only affect this particular security profile.

1. Log on to Deep Security Manager and go to **Security Profiles**.
2. Double-click a security profile in the right pane.
3. Go to the **DPI** section and click to clear **Inherit**.
4. Click **OK**.

Check the IPS rule 1000128.

1. Right-click **Application Type Properties**.
2. Click to clear **Inherit**.
3. Verify that the current inherited port list contains the [listening port number for the Deep Security Manager's GUI](#). If not, add this port to the Web Server Common port group.
4. Click **Inherit**.

Error: Unable to connect to the cloud account

When adding an Amazon Cloud account, the error "Unable to connect to the cloud account" can occur. The cause can be:

- invalid key ID or secret
- incorrect permissions
- failed network connectivity

Your AWS account access key ID or secret access key is invalid

To resolve this:

Verify the security credentials that you entered.

The incorrect AWS IAM policy has been applied to the account being used by Deep Security

To resolve this:

Go to your AWS account and review the IAM policy for that account.

The AWS IAM policy must have these permissions:

- Effect: Allow
- AWS Service: Amazon EC2
- Select the following Actions:
 - DescribeImages
 - DescribeInstances
 - DescribeTags

Trend Micro Deep Security On-Premise 11.3

- Amazon Resource Name (ARN) to: *

NAT, proxy, or firewall ports are not open, or settings are incorrect

This can occur in a few cases, including if you are deploying a new Deep Security Manager installation using the AMI on AWS Marketplace.

Your Deep Security Manager must be able to connect to the Internet, specifically to Amazon Cloud, on the [required port numbers](#).

To resolve this:

You may need to:

- configure NAT or port forwarding on a firewall or router between your AMI and the Internet
- get an external IP address for your AMI

The network connection must also be reliable. If it is intermittent, this error message may occur sometimes (but not every time).

Error: Unable to resolve instance hostname

The error message "Unable to Resolve Instance Hostname" may occur as a result of activating the Agent from Deep Security Manager when you are not using agent-initiated activation.

We recommend that you always use **Agent-Initiated Activation**. Learn how to configure policy rules for agent-initiated communication and deploy agents using deployment scripts, see "[Use agent-initiated communication with cloud accounts](#)" on [page 350](#).

Error: Anti-malware engine offline

This error can occur for a variety of reasons. To resolve the issue, follow the instructions below for the mode of protection that is being used:

- ["Agent-based protection" below](#)
- ["Agentless protection" on page 1296](#)

For an overview of the anti-malware module, see ["Protect against malware" on page 657](#).

Agent-based protection

1. In the Deep Security Manager, check for other errors on the same machine. If errors exist, there could be other issues that are causing your anti-malware engine to be offline, such as communications or agent installation failure.
2. Check communications from the agent to the relay and the Deep Security Manager.
3. In the Deep Security Manager, view the details for the agent with the issue. Verify that the policy or setting for anti-malware is turned on, and that the configuration for each scan (real-time, manual, scheduled) is in place and active. (See ["Enable and configure anti-malware" on page 665](#).)
4. Deactivate and uninstall the agent before reinstalling and re-activating it. See ["Uninstall Deep Security" on page 1419](#) and ["Activate the agent" on page 370](#) for more information.
5. In the Deep Security Manager, go to the **Updates** section for that computer. Verify that the Security Updates are present and current. If not, click **Download Security Updates** to initiate an update.
6. Check if there are conflicts with another anti-virus product, such as OfficeScan. If conflicts exist, uninstall the other agent and Deep Security Agent, reboot, and reinstall the Deep Security Agent. To remove OfficeScan, see [Uninstalling clients or agents in OfficeScan \(OSCE\)](#).

Trend Micro Deep Security On-Premise 11.3

If your agent is Windows:

1. Make sure the following services are running:
 - Trend Micro Deep Security Agent
 - Trend Micro Solution Platform
2. Check that all the anti-malware related drivers are running properly by running the following commands:

- `# sc query AMSP`
- `# sc query tmcomm`
- `# sc query tmactmon`
- `# sc query tmevtmgr`

If a driver is not running, restart the Trend Micro services. If it is still not running, continue with the following steps below.

3. Verify the installation method. Only install the MSI, not the zip file.
4. The agent might need to be manually removed and reinstalled. For more information, see [Manually uninstalling Deep Security Agent, Relay, and Notifier from Windows](#)
5. The installed Comodo certificate could be the cause of the issue. To resolve the issue, see ["Anti-Malware Driver offline" status occurs due to Comodo certificate issue](#).
6. All instances and virtual machines deployed from a catalog or vApp template from vCloud Director are given the same BIOS UUID. Deep Security distinguishes different VMs by their BIOS UUID, so a duplicate value in the vCenter causes an Anti-Malware Engine Offline error. To resolve the issue, see [VM BIOS UUIDs are not unique when virtual machines are deployed from vApp templates \(2002506\)](#).

Trend Micro Deep Security On-Premise 11.3

If your agent is Linux:

1. To check that the agent is running, enter the following command in the command line:
 - `service ds_agent status`
2. If you're using a Linux server, your kernel might not be supported. For more information, see ["Error: Module installation failed \(Linux\)" on page 1289](#).

If the problem is still unresolved after following these instructions, create a diagnostic package and contact support. For more information, see ["Create a diagnostic package and logs" on page 1484](#).

Agentless protection

1. In the Deep Security Manager, verify synchronization to vCenter and NSX. Under the **Computers** section, right click on your vCenter and go to **Properties**. Click **Test Connection**. Then click on the NSX tab and test the connection. Click **Add/Update Certificate** in case the certificate has changed.
2. Log into the NSX manager and verify that it is synchronizing to vCenter properly.
3. Log into your vSphere client and go to **Network & Security > Installation > Service Deployments**. Check for errors with Trend Micro Deep Security and Guest Introspection, and resolve any that are found.
4. In vSphere client, go to **Network & Security > Service Composer**. Verify that the security policy is assigned to the appropriate security group.
5. Verify that your vmware tools are compatible with Deep Security. For more information, see [VMware Tools 10.x Interoperability Issues with Deep Security](#).
6. Verify that the File Introspection Driver (vsepflt) is installed and running on the target VM. As an admin, run `sc query vsepflt` at the command prompt.
7. All instances and virtual machines deployed from a catalog or vApp template from vCloud Director are given the same BIOS UUID. Deep Security distinguishes different VMs by there BIOS UUID, so a duplicate value in the vCenter causes an Anti-

Trend Micro Deep Security On-Premise 11.3

Malware Engine Offline error. To resolve the issue, see [VM BIOS UUIDs are not unique when virtual machines are deployed from vApp templates \(2002506\)](#).

8. If the problem is still unresolved, open a case with support with the following information:
 - Diagnostic package from each Deep Security Manager. For more information, see ["Create a diagnostic package and logs" on page 1484](#).
 - Diagnostic package from the Deep Security Virtual Appliance.
 - vCenter support bundle for the effected VMs.

Error: Check Status Failed

You can check the status of the agent / appliance on a computer from the Deep Security Manager console. On the Computers page, right-click the computer and click **Actions > Check Status**.

If you get a "Check Status Failed" error, open the error message to see a more detailed description.

If description indicates a protocol error, it's usually caused by a communication issue. There are a few possible causes:

- Check whether the computer (or the policy assigned to the computer) is configured for agent-initiated communication or bidirectional communication. Unless you are using Deep Security as a Service, the "Check Status" operation will fail if you are using agent-initiated communication.
- Check that the Deep Security Manager can communicate with the agent. The manager should be able to reach the agent. See ["Port numbers, URLs, and IP addresses" on page 111](#).
- Check the resources on the agent computer. Lack of memory, CPU, or disk space can cause this error.

If the description indicates a SQLITE_IOERR_WRITE[778]: disk I/O error, there is likely a problem with the agent computer. The most common problem is that the disk is full or write-protected.

Error: Log Inspection Rules Require Log Files

If a log inspection rule requires you to add the location of the files to be monitored, or if you add an unnecessary log inspection rule and the files do not exist on your machine, the following error will occur in the **Computer**¹ or **Policy editor**²:

To resolve the error:

1. Click on the **Log Inspection Rules Require Log Files** error. A window will open with more information about the error. Under **Description**, the name of the rule causing the error will be listed.
2. In the Deep Security Manager, go to **Policies > Common Objects > Rules > Log Inspection Rules** and locate the rule that is causing the error.
3. Double-click the rule. The rule's properties window will appear.
4. Go to the **Configuration** tab.

If the file's location is required:

1. Enter the location under **Log Files to monitor** and click **Add**.
2. Click **OK**. Once the agent receives the policy, the error will clear.

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

Trend Micro Deep Security On-Premise 11.3

If the files listed do not exist on the protected machine:

1. Go to the **Computer**¹ or **Policy editor**² > Log Inspection.
2. Click **Assign/Unassign**.
3. Locate the unnecessary rule and uncheck the checkbox.
4. Click **OK**. Once the agent receives the policy, the error will clear.

To prevent this error, run a recommendation scan for suggested rules:

1. On the Deep Security Manager, go to **Computers**.
2. Right-click the computer you'd like to scan and click **Actions > Scan for Recommendations**.
3. View the results on the **General** tab of the protection module in the **Computer**³ or **Policy editor**⁴.

Alert: Integrity Monitoring information collection has been delayed

This alert indicates that the rate at which integrity monitoring information is collected has been temporarily delayed. The delay is due to an increase in the volume of integrity monitoring data that is being transmitted from agents to Deep Security Manager. During this time the baseline and integrity monitoring event views may not be current for some computers.

This alert is automatically dismissed when the collection of integrity monitoring data is no longer delayed.

For more information about integrity monitoring, see ["Set up integrity monitoring" on page 824](#).

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

³To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

⁴To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

Alert: The memory warning threshold of Manager Node has been exceeded

The **Memory Warning Threshold Exceeded** or **Memory Critical Threshold Exceeded** alerts appear in Deep Security when the maximum memory that has been allotted for Deep Security Manager has been exceeded.

The following Deep Security Manager message is also logged:

```
The DSM has reached the maximum memory that's been allocated for the application. (default = 4GB) <InformationItem>  
<Name>usedMemory</Name> <Value>3.98 GB (4,269,473,792 bytes)</Value> </InformationItem> <InformationItem>  
<Name>maxMemory</Name> <Value>3.98 GB (4,269,473,792 bytes)</Value>
```

To resolve the issue, increase the RAM available to the Deep Security Manager to a minimum of 8 GB.

Increase the allocated memory on a Windows server

1. Go to the Deep Security Manager folder and create a new file called `Deep Security Manager.vmoptions`.
This is the same folder where `Deep Security Manager.exe` is located. For example: `C:\Program Files\Trend Micro\Deep Security Manager`
2. Add the following line to the file: `-Xmx8g`
3. Save the file and ["Restart the Deep Security Manager" on page 979](#).

Increase the allocated memory on a Linux server

1. Go to `/opt/dsm` and create a new file called `dsm_s.vmoptions`.
2. Add the following line to the file: `-Xmx8g`
3. Save the file and ["Restart the Deep Security Manager" on page 979](#).

Verify the memory allocation change

You can confirm that the memory allocation change has taken effect by going to **Administration > System Information** Deep Security Manager and viewing the memory information under **System Details > Manager Node**.

Alert: Manager Time Out of Sync

The system time on the Deep Security Manager operating system must be synchronized with the time on the database computer. This alert appears in the Alert Status widget of the manager console when the computer times are more than 30 seconds out of sync.

To synchronize the times, apply the following configurations:

- Configure the database and all manager nodes to use the same time zone.
- Ensure that the database and all manager nodes are synchronizing time to the same time source.
- If the manager runs on a Linux operating system, ensure the `ntpd` daemon is running.

Event: Max TCP connections

Deep Security is configured to allow a maximum number of TCP connections to protected computers. When the number of connections exceeds the maximum, network traffic is dropped and Max TCP Connections firewall events occur. To prevent dropped connections, increase the maximum allowed TCP connections on the computer where the Max TCP Connection event occurs.

Note: The intrusion protection module enables the network engine which enforces the allowed number of TCP connections.

Trend Micro Deep Security On-Premise 11.3

1. In Deep Security Manager, click **Policies**.
2. Determine which policy to configure to affect the computer in question. See "[Policies, inheritance, and overrides](#)" on [page 524](#).
3. To open the policy that you want to configure, double-click the policy.
4. In the left-hand pane, click **Settings** and then click the **Advanced** tab.
5. In the **Advanced Network Engine Settings** area, if Inherit is selected clear the checkbox to enable changes.
6. Increase the value of the **Maximum TCP Connections** property to 10000 or more, according to your needs.
7. Click **Save**.

Warning: Census, Good File Reputation, and Predictive Machine Learning Service Disconnected

The Census, Good File Reputation, and Predictive Machine Learning Services are security services hosted by the Trend Micro Smart Protection Network. They are necessary for the full and successful operation of the Deep Security behavior monitoring, predictive machine learning, and process memory scan features.

The following table maps the services to features.

Service name	Required for these features
Global Census Service	behavior monitoring , predictive machine learning
Good File Reputation Service	behavior monitoring , predictive machine learning , process memory scans
Predictive Machine Learning Service	predictive machine learning

If you see the alert...

Census, Good File Reputation, and Predictive Machine Learning Service Disconnected

Trend Micro Deep Security On-Premise 11.3

...there are a few causes:

- ["Cause 1: The agent or relay-enabled agent doesn't have Internet access" below](#)
- ["Cause 2: A proxy was enabled but not configured properly" below](#)

Cause 1: The agent or relay-enabled agent doesn't have Internet access

If your agent or relay-enabled agent doesn't have access to the Internet, then it can't reach these services.

Solutions:

- Check your firewall policies and ensure that the outbound HTTP and HTTPS ports (by default, 80 or 443) are open.
- If you are unable to open those ports, see ["Configure agents that have no Internet access" on page 354](#) for other solutions.

Cause 2: A proxy was enabled but not configured properly

The Census, Good File Reputation and Predictive Machine Learning Services can be accessed using a proxy.

To check whether a proxy was enabled and make sure it was configured properly:

1. Open the **Computer or Policy editor**¹.
2. On the left, click Settings.
3. In the main pane, click the General tab.
4. Find the heading titled, **Network Setting for Census, Good File Reputation Service, and Predictive Machine Learning**.

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

5. If a proxy was specified, click **Edit** and make sure its **Proxy Protocol**, **Address**, **Port** and optional **User Name** and **Password** are accurate.

Warning: Reconnaissance Detected

The reconnaissance scan detection feature serves as an early warning of a potential attack or intelligence gathering effort against a network.

Types of reconnaissance scans

Deep Security can detect several types of reconnaissance scans:

- **Computer OS Fingerprint Probe:** The agent or appliance detects an attempt to discover the computer's OS.
- **Network or Port Scan:** The agent or appliance reports a network or port scan if it detects that a remote IP is visiting an abnormal ratio of IPs to ports. Normally, an agent or appliance computer will only see traffic destined for itself, so a port scan is the most common type of probe that will be detected. The statistical analysis method used in computer or port scan detection is derived from the "TAPS" algorithm proposed in the paper "Connectionless Port Scan Detection on the Backbone" presented at IPCCC in 2006.
- **TCP Null Scan:** The agent or appliance detects packages with no flags set.
- **TCP SYNFIN Scan:** The agent or appliance detects packets with only the SYN and FIN flags set.
- **TCP Xmas Scan:** The agent or appliance detects packets with only the FIN, URG, and PSH flags set or a value of 0xFF (every possible flag set).

Suggested actions

When you receive a Reconnaissance Detected alert, double-click it to display more detailed information, including the IP address that is performing the scan. Then, you can try one of these suggested actions:

Trend Micro Deep Security On-Premise 11.3

- The alert may be caused by a scan that is not malicious. If the IP address listed in the alert is known to you and the traffic is okay, you can add the IP address to the reconnaissance allow list:
 - a. In the **Computer or Policy editor**¹, go to **Firewall > Reconnaissance**.
 - b. The **Do not perform detection on traffic coming from** list should contain a list name. If a list name hasn't already been specified, select one.
 - c. You can edit the list by going to **Policies > Common Objects > Lists > IP Lists**. Double-click the list you want to edit and add the IP address.
- You can instruct the agents and appliances to block traffic from the source IP for a period of time. To set the number of minutes, open the **Computer or Policy editor**², go to **Firewall > Reconnaissance** and change the **Block Traffic** value for the appropriate scan type.
- You can use a firewall or Security Group to block the incoming IP address.

Note: Deep Security Manager does not automatically clear the "Reconnaissance Detected" alerts, but you can manually clear the issue from Deep Security Manager.

For more information on reconnaissance scans, see ["Firewall settings" on page 801](#).

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

²You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Warning: Insufficient disk space

An "Insufficient Disk Space" warning indicates that the computer where the Deep Security Agent or Appliance is running is low on disk space and may not be able to store more events. If you open the warning to display its details, it will show you the location of the agent or appliance, how much free space is left, and how much is required by the agent or appliance.

To fix this issue, check the drive or file system that's affected and clear anything you can.

Note: The agent or appliance will continue to protect your instance even if the drive is out of space; however, it will stop recording events.

Tips

- Even though the warning is generated by the Deep Security Agent or Appliance, another program that shares the same file system could be causing the space issue.
- Deep Security Agent automatically truncates and rotates its log files.
- Deep Security Agent will clean up its own log files, but not those of other applications.
- Deep Security Manager does not automatically clear the "Insufficient Disk Space" warnings, but you can manually clear them from Deep Security Manager.

Create and manage users

Deep Security has users, roles, and contacts that can be created and managed under **Administration > User Management**.

- **Users** are Deep Security account holders who can sign in to the Deep Security Manager with a unique user name and password. You can ["Synchronize with an Active Directory" on the next page](#) or ["Add or edit an individual user" on page 1309](#)

- **Roles** are a collection of permissions to view data and perform operations within Deep Security Manager. Each user is assigned a role. See ["Define roles for users" on page 1313](#).
- **Contacts** do not have a user account and cannot sign in to Deep Security Manager but they can be designated as the recipients of email notifications and scheduled reports. See ["Add users who can only receive reports" on page 1335](#).

Synchronize with an Active Directory

If you use Active Directory to manage users, you can synchronize Deep Security with the Active Directory to populate the user list. Users can then sign into Deep Security Manager using the password stored in the directory.

Note: To successfully import an Active Directory user account into Deep Security as a Deep Security user or contact, the Active Directory user account must have a **userPrincipalName** attribute value. The **userPrincipalName** attribute corresponds to an Active Directory account holder's "User logon name".

Note: If you are using Deep Security in FIPS mode, you must import the Active Directory's SSL certificate before synchronizing with the Directory. See ["Manage trusted certificates" on page 364](#).

1. In Deep Security Manager go to **Administration > User Management > Users**.
2. Click **Synchronize with Directory** to display the **Synchronize with Directory** wizard.
3. Type the address of the directory server and your access credentials and click **Next**. The wizard attempts to connect to the Active Directory.

Note: If you are using Deep Security in FIPS mode, click **Test Connection** in the Trusted Certificate section to check whether the Active Directory's SSL certificate has been imported successfully into Deep Security Manager.

Trend Micro Deep Security On-Premise 11.3

4. You will then be prompted to select which Active Directory group of users to import and whether they will be users or contacts. Once they have been imported, you are given the option to create a scheduled task to periodically synchronize with the directory to keep your list up to date.

The imported list of users are locked out of the Deep Security Manager by default. You will have to modify their properties to allow them to sign in to the Deep Security Manager.

Note: If you delete a user from Deep Security Manager who was added as a result of synchronizing with an Active Directory and then resynchronize with the directory, the user will reappear in your user list if they are still in the Active Directory.

Filtering the Active Directory

The **Synchronize with Directory** wizard has an area called Search Options where you can write filters to specify a subset of users to import into the Deep Security Manager. The filter language follows the Internet Engineering Task Force "Lightweight Directory Access Protocol (LDAP): String Representation of Search Filters RFC 4515".

The default filter (objectClass=group) imports all users.

The RFC 4515 filter syntax can be used to filter for specific users or groups in a directory. For example, the following filter would import only users who are members of an Active Directory group called "DeepSecurityUsers": "(&(objectClass=group)(cn=DeepSecurityUsers))".

The RFC 4515 definition is available at <https://datatracker.ietf.org/doc/rfc4515/>.

Note: The new users, although being in the "locked out" state, are given the Full Access user role.

Add or edit an individual user

1. In Deep Security Manager go to **Administration > User Management > Users**.
2. Click **New** to add a new user or double-click an existing user account to edit its settings.
3. Specify the general properties for the user, including:
 - **Username:** The username that the user will enter on the Deep Security Manager login screen.
 - **Password** and **Confirm Password:** Note the password requirements listed in the dialog box. You can password requirements in the user security settings (see ["Enforce user password rules" on page 1056](#)).
 - **Name:** (Optional) The name of the account holder.
 - **Description:** (Optional) A description of the account.
 - **Role:** Use the list to assign a predefined role to this user. You can also assign a role to a user from the Users list, by right-clicking a user and then clicking **Assign roles**.

Note: The Deep Security Manager comes preconfigured with two roles: Full Access and Auditor. The Full Access role grants users all possible privileges for managing the Deep Security system, such as creating, editing, and deleting computers, computer groups, policies, rules, and so on. The auditor role gives users the ability to view all of the information in the Deep Security system but not the ability to make any modifications except to their personal settings (password, contact information, view preferences, and so on). Roles with various levels of system access rights can be created and modified on the Roles page or by selecting **New** in the **Role** list.

- **Language:** The language that will be used in the interface when this user logs in.
- **Time zone:** Time zone where the user is located. This time zone is used when displaying dates and times in the Deep Security Manager.
- **Time format:** Time format used to display time in the Deep Security Manager. You can use 12-hour or 24-hour format.

- **Password never expires:** When this option is selected, the user's password will never expire. Otherwise, it will expire as specified in the user security settings (see ["Enforce user password rules" on page 1056](#)
4. If you want to enable multi-factor authentication (MFA), click **Enable MFA**. If MFA is already enabled for this user, you can select **Disable MFA** to disable it. For details, see ["Set up multi-factor authentication" on page 1058](#).
 5. Click the **Contact information** tab and enter any contact information that you have for the user and also indicate if they are your primary contact or not. You can also check the **Receive Alert Emails** check box to include this user in the list of users who receive email notifications when alerts are triggered.
 6. You can also edit the settings on the **Settings** tab. However, increasing some of these values will affect Deep Security Manager performance. If you make changes and aren't happy with the results, you can click **Reset to Default Settings** (at the bottom of the tab) to reset all settings on this page to their default values:

Module

- **Hide Unlicensed Modules:** This setting determines whether unlicensed modules will be hidden rather than simply grayed out for this User. This option can be set globally on the **Administration > System Settings > Advanced** tab.

Refresh Rate

- **Status Bar:** This setting determines how often the status bar of the Deep Security Manager refreshes during various operations such as discovering or scanning computers.
- **Alerts List/Summary:** How often to refresh the data on the Alerts page in List view or Summary view.
- **Computers List:** How often to refresh the data on the Computers page.

Note: The **Last Successful Update** column value will not be recalculated unless the page is manually reloaded.

- **Computer Details:** The frequency with which an individual computer's property page refreshes itself with the latest information (if required).

List Views

- **Remember last Tag filter on each page:** Events pages let you filter displayed events by Tag(s). This List Views setting determines if the "Tag" filter setting is retained when you navigate away from and return to an Events page.
- **Remember last Time filter on each page:** Events pages let you filter displayed events by Time period and computer(s). These List Views settings determine if the "Period" and "Computer" filter settings are retained when you navigate away from and return to an Events page.
- **Remember last Computer filter on each page:** Events pages let you filter displayed events by Time period and computer(s). These List Views settings determine if the "Period" and "Computer" filter settings are retained when you navigate away from and return to an Events page.
- **Remember last Advanced Search on each page:** If you have performed an "Advanced Search" on an Events page, this setting will determine if the search results are kept if you navigate away from and return to the page.
- **Number of items to show on a single page:** Screens that display lists of items will display a certain number of items per "Page". To view the next page, you must use the pagination controls. Use this setting to change the number of list-items displayed per page.
- **Maximum number of items to retrieve from database:** This setting limits the number of items that can be retrieved from the database for display. This prevents the possibility of the Deep Security Manager getting bogged down trying to display an excessive number of results from a database query. If a query produces more than this many results, a message will appear at the top of the display informing you that only a portion of the results are being displayed.

Note: Increasing these values will affect Deep Security Manager performance.

Reports

- **Enable PDF Encryption:** When this option is selected, reports exported in PDF format will be password protected with the **Report Password**.

Change a user's password

To change a user's password, click **Administration > User Management > Users**, right-click the user, and click **Set Password**. You will be prompted for the old password as well as the new password.

Lock out a user or reset a lockout

If a user enters the wrong password too many times when trying to sign in, they will be locked out automatically. If you have resolved the situation and want to allow the user the log in, see ["Unlock a locked out user name" on page 1338](#).

View system events associated with a user

To see any system events associated with a user, click **Administration > User Management > Users**, right-click the user, and click **View System Events**.

Delete a user

To remove a user account from Deep Security Manager, click **Administration > User Management > Users**, click the user, and then click **Delete**.

Note: If you delete a user from Deep Security Manager who was added as a result of synchronizing with an Active Directory and then resynchronize with the directory, the user will reappear in your user list if they are still in the Active Directory.

Define roles for users

Deep Security uses role-based access control (RBAC) to restrict user permissions to parts of Deep Security. Access rights and editing privileges are attached to roles and not to users. Once you have installed Deep Security Manager, you should create individual accounts for each user and assign each user a role that will restrict their activities to all but those necessary for the completion of their duties. To change the access rights and editing privileges of an individual user, you must assign a different role to the user or edit the role.

The access that roles have to computers and policies can be restricted to subsets of computers and policies. For example, users can be permitted to view all existing computers, but only permitted to modify those in a particular group.

Deep Security comes preconfigured with two roles:

- **Full Access:** The full access role grants the user all possible privileges in terms of managing the Deep Security system including creating, editing, and deleting computers, computer groups, policies, rules, malware scan configurations, and others.
- **Auditor:** The auditor role gives the user the ability to view all the information in the Deep Security system but without the ability to make any modifications except to their own personal settings, such as password, contact information, dashboard layout preferences, and others.



Note: Depending on the level of access granted, controls in Deep Security Manager will be either visible and changeable, visible but disabled, or hidden. For a list of the rights granted in the preconfigured roles, as well as the default rights settings when creating a new role, see ["Default settings for full access, auditor, and new roles" on page 1326](#).

Trend Micro Deep Security On-Premise 11.3

You can create new roles that can restrict users from editing or even seeing Deep Security objects such as specific computers, the properties of security rules, or the system settings.

Before creating user accounts, identify the roles that your users will take and itemize what Deep Security objects those roles will require access to and what the nature of that access will be (viewing, editing, creating, and so on). Once you have created your roles, you can then begin creating user accounts and assigning them specific roles.

Note: Do not create a new role by duplicating and then modifying the full access role. To ensure that a new role only grants the rights you intend, create the new role by clicking **New** in the toolbar. The rights for a new role are set at the most restrictive settings by default. You can then proceed to grant only the rights that are required. If you duplicate the full access role and then apply restrictions, you risk granting some rights that you did not intend.

Clicking **New** () or **Properties** () displays the **Role properties window** with six tabs (**General**, **Computer Rights**, **Policy Rights**, **User Rights**, **Other Rights**, and **Assigned To**).

Add or edit a role

1. In Deep Security Manager go to **Administration > User Management > Roles**.
2. Click **New** to add a new role or double-click an existing role to edit its settings.
3. Specify the general properties for the role, including:
 - **Name:** The name of the role, which will appear on the Roles page and in the list of available roles when adding a user.
 - **Description:** (Optional) A description of the role.
 - **Access Type:** Select whether users with this role will have access to Deep Security Manager, the Deep Security Manager Web service API, or both.

- **Note:** To enable the Web service API, go to **Administration > System Settings > Advanced > SOAP Web Service API**.
4. Use the **Computer Rights** pane to confer viewing, editing, deleting, alert-dismissal, and event tagging rights to users in a role. These rights can apply to all computers and computer groups or they can be restricted to only certain computers. If you wish to restrict access, select the **Selected Computers** radio button and put a check next to the computer groups and computers that users in this role will have access to.
 5. **Note:** These rights restrictions will affect not only the user's access to computers in Deep Security Manager, but also what information is visible, including events and alerts. As well, email notifications will only be sent if they relate to data that the user has access rights to.

GeneralComputer RightsPolicy RightsUser RightsOther RightsAssigned To

Computer and Group Rights

Allow Users to:

View

Edit

Delete

Dismiss Alerts for

Tag Items for

All Computers

Selected Computers:

Computers

Laptops

Network Appliances

Servers

Allow viewing of non-selected computers and data (e.g. events, reports)

Allow viewing of events and alerts not related to computers

Allow new computers to be created in selected Groups

Allow sub-groups to be added or removed in selected Groups

Advanced Rights

Allow computer file imports

Allow Directories to be added, removed and synchronized

Allow VMware vCenters to be added, removed and synchronized

Allow Cloud Accounts to be added, removed and synchronized

OKCancelApply

Four basic options are available:

1315

Trend Micro Deep Security On-Premise 11.3

- **Allow viewing of non-selected computers and data:** If users in this role have restricted edit, delete, or dismiss-alerts rights, you can still allow them to view but not change information about other computers by checking this box.
- **Allow viewing of events and alerts not related to computers:** Set this option to allow users in this role to view non-computer-related information (for example, system events, like users being locked out, new firewall rules being created, IP Lists being deleted, and so on)

Note: The previous two settings affect the data that users have access to. Although the ability of a user to make changes to computers have been restricted, these two settings control whether they can see information relating to computers they don't otherwise have access to. This includes receiving email notifications related to those computers.


- **Allow new computers to be created in selected Groups:** Set this option to allow users in this role to create new computers in the computer groups they have access to.
- **Allow sub-groups to be added/removed in selected Groups:** Set this option to allow users in this role to create and delete subgroups within the computer groups they have access to.

You can also enable these in the Advanced Rights section:

- **Allow computer file imports:** Allow Users in this Role to import computers using files created using the Deep Security Manager's **Computer Export** option.
- **Allow Directories to be added, removed and synchronized:** Allow Users in this Role to add, remove, and synchronize computers that are being managed using an LDAP-based directory like MS Active Directory.
- **Allow VMware vCenters to be added, removed and synchronized:** Allow Users in this Role to add, remove and synchronize VMware vCenters. (Not available with Deep Security as a Service)
- **Allow Cloud Providers to be added, removed, and synchronized:** Allow Users in this Role to add, remove, and synchronize Cloud Providers. (Not available with Deep Security as a Service)

Trend Micro Deep Security On-Premise 11.3

6. Use the **Policy Rights** tab to confer viewing, editing, and deleting rights to users in a role. These rights can apply to all policies or they can be restricted to only certain policies. If you wish to restrict access, click **Selected Policies** and put a check mark next to the policies that users in this role will have access to.

General	Computer Rights	Policy Rights	User Rights	Other Rights	Assigned To
Policy Rights Allow Users to: <div>  <input checked="" type="checkbox"/> View <input type="checkbox"/> Edit <input type="checkbox"/> Delete </div> <div> <input checked="" type="radio"/> All Policies <input type="radio"/> Selected Policies </div> <div> <input type="checkbox"/> Policies <input checked="" type="checkbox"/> Base Policy <input checked="" type="checkbox"/> Deep Security <input type="checkbox"/> Deep Security Manager <input type="checkbox"/> Deep Security Virtual Appliance <input type="checkbox"/> Linux Server <input type="checkbox"/> Solaris Server <input checked="" type="checkbox"/> Windows <input type="checkbox"/> Windows 10 Desktop <input type="checkbox"/> Windows 7 Desktop <input type="checkbox"/> Windows 8 Desktop <input type="checkbox"/> Windows Anti-Malware Protection <input type="checkbox"/> Windows Mobile Laptop </div> <div> <input checked="" type="checkbox"/> Allow viewing of non-selected Policies <input type="checkbox"/> Allow new Policies to be created </div>					
Advanced Rights <input type="checkbox"/> Allow Policy imports					
<div>OK</div> <div>Cancel</div> <div>Apply</div>					

When you allow rights to a policy that has "child" policies, users automatically get rights to the child policies as well.

Trend Micro Deep Security On-Premise 11.3

Two basic options are available:

- **Allow viewing of non-selected Policies:** If users in this role have restricted edit or delete rights, you can still allow them to view but not change information about other policies by checking this box.
- **Allow new Policies to be created:** Set this option to allow users in this role to create new policies.

You can also enable this in the Advanced Rights section:

- **Allow Policy imports:** Allow users in this role to import policies using files created with the Deep Security Manager **Export** option on the **Policies** tab.

7. The options on the **User Rights** tab allow you to define permissions for administrator accounts.

General	Computer Rights	Policy Rights	User Rights	Other Rights	Assigned To	
---------	-----------------	---------------	-------------	--------------	-------------	--

User Rights

Allow Users to:

- ☒ Change own password and contact information only
- ☐ Create and manage Users with equal or less access
- ☐ Have full control over all Roles and Users
- ☐ Custom

OK

Cancel

Apply















- **Change own password and contact information only:** Users in this role can change their own password and contact information only.
- **Create and manage Users with equal or less access:** Users in this role can create and manage any users who do not have any privileges greater than theirs. If there is even a single privilege that exceeds those of the users with this role, the users with this role will not be able to create or manage them.
- **Have full control over all Roles and Users:** Gives users in this role the ability to create and edit and users or roles without restrictions. Be careful when using this option. If you assign it to a role, you may give a user with otherwise restricted privileges the ability to create and then sign in as a user with full unrestricted access to all aspects of the Deep Security Manager.
- **Custom:** You can further restrict the ability of a user to view, create, edit, or delete users and roles by selecting **Custom** and using the options in the **Custom Rights** section. Some options may be restricted for certain users if the **Can only manipulate Users with equal or lesser rights** option is selected.

The **Can only manipulate Users with equal or lesser rights** option limits the authority of users in this role. They will only be able to effect changes to users that have equal or lesser rights than themselves. Users in this Role will not be able to create, edit, or delete roles. Selecting this option also places restrictions on some of the options in the **Custom Rights** section:

- **Can Create New Users:** Can only create users with equal or lesser rights.
 - **Can Edit User Properties:** Can only edit a user (or set or reset password) with equal or lesser rights.
 - **Can Delete Users:** Can only delete users with equal or lesser rights.
8. The **Other Rights** tab enables you to restrict roles' permissions so that they can only access specific Deep Security features, and sometimes specific actions with those features. This can be useful if, for example, you have a team of administrators, and

Trend Micro Deep Security On-Premise 11.3

you want to make sure that they don't accidentally overwrite each others' work. By default, roles are **View Only** or **Hide** for each feature. To allow to full control or customized access, select **Custom** from the list.

General	Computer Rights	Policy Rights	User Rights	Other Rights	Assigned To	
Other Rights						
	Alerts			View-Only		
	Alert Configuration			View-Only		
	IP Lists			View-Only		
	Port Lists			View-Only		
	Schedules			View-Only		
	System Settings (Global)			Hide		
	System Information			Hide		
	Diagnostics			View-Only		
	Tagging			View-Only		
	Tasks			Hide		
	Multi-Tenant Administration			View-Only		
	Scan Cache Configuration Administration			View-Only		
	Contacts			Hide		
	Licenses			Hide		
				OK	Cancel	Apply

9. The **Assigned To** tab displays a list of the users who have been assigned this role. If you want to test that roles are working correctly, sign in as a newly created user and verify the functionality.

Default settings for full access, auditor, and new roles

The following table identifies the default rights settings for the full access role and the auditor role. Also listed are the rights settings that are in place when creating a new role by clicking New in the toolbar on the Roles page.

RIGHTS	SETTINGS BY ROLE		
General	Full Access Role	Auditor Role	New Role Defaults
Access to DSM User Interface	Allowed	Allowed	Allowed
Access to Web Service API	Allowed	Allowed	Not allowed
Computer Rights	Full Access Role	Auditor Role	New Role Defaults
View	Allowed, All Computers	Allowed, All Computers	Allowed, All Computers
Edit	Allowed, All Computers	Not allowed, All Computers	Not allowed, All Computers

Trend Micro Deep Security On-Premise 11.3

RIGHTS	SETTINGS BY ROLE		
Delete	Allowed, All Computers	Not allowed, All Computers	Not allowed, All Computers
Dismiss Alerts for	Allowed, All Computers	Not allowed, All Computers	Not allowed, All Computers
Tag Items for	Allowed, All Computers	Not allowed, All Computers	Not allowed, All Computers
Allow viewing of non-selected computers and data (e.g. events, reports)	Allowed	Allowed	Allowed, All Computers
Allow viewing of events and alerts not related to computers	Allowed	Allowed	Allowed, All Computers
Allow new computers to be created in selected Groups	Allowed	Not allowed	Not allowed
Allow sub-groups to be added or removed in selected Groups	Allowed	Not allowed	Not allowed
Allow computer file imports	Allowed	Not allowed	Not allowed

Trend Micro Deep Security On-Premise 11.3

RIGHTS	SETTINGS BY ROLE		
Allow Cloud Accounts to be added, removed and synchronized	Allowed	Not allowed	Not allowed
Policy Rights	Full Access Role	Auditor Role	New Role Defaults
View	Allowed, All Policies	Allowed, All Policies	Allowed, All Policies
Edit	Allowed, All Policies	Not allowed, All Policies	Not allowed, All Policies
Delete	Allowed, All Policies	Not allowed, All Policies	Not allowed, All Policies
View non-selected Policies	Allowed	Allowed	Allowed
Create new Policies	Allowed	Not allowed	Not allowed
Import Policies	Allowed	Not allowed	Not allowed
User Rights (See note on User rights below)	Full Access Role	Auditor Role	New Role Defaults
View Users	Allowed	Allowed	Not

Trend Micro Deep Security On-Premise 11.3

RIGHTS	SETTINGS BY ROLE		
			allowed
Create Users	Allowed	Not allowed	Not allowed
Edit User Properties	Allowed	Not allowed	Not allowed
Delete Users	Allowed	Not allowed	Not allowed
View Roles	Allowed	Allowed	Not allowed
Create Roles	Allowed	Not allowed	Not allowed
Edit Role Properties	Allowed	Not allowed	Not allowed
Delete Roles	Allowed	Not allowed	Not allowed
Delegate Authority	Allowed	Not allowed	Not allowed
Other Rights	Full Access Role	Auditor Role	New Role Defaults

Trend Micro Deep Security On-Premise 11.3

RIGHTS	SETTINGS BY ROLE		
Alerts	Full (Can Dismiss Global Alerts)	View-Only	View-Only
Alert Configuration	Full (Can Edit Alert Configurations)	View-Only	View-Only
IP Lists	Full (Can Create, Edit, Delete)	View-Only	View-Only
Port Lists	Full (Can Create, Edit, Delete)	View-Only	View-Only
Schedules	Full (Can Create, Edit, Delete)	View-Only	View-Only
System Settings (Global)	Full (Can View, Edit System Settings (Global))	View-Only	Hide
Diagnostics	Full (Can Create Diagnostic Packages)	View-Only	View-Only
Tagging	Full (Can Tag (Items not belonging to Computers), Can Delete Tags, Can Update Non-Owned Auto-Tag Rules, Can Run Non-Owned Auto-Tag Rules, Can Delete Non-Owned Auto-Tag Rules)	View-Only	View-Only
Tasks	Full (Can View, Add, Edit, Delete Tasks, Execute Tasks)	View-Only	Hide
Multi-Tenant Administration	Full	Hide	View-Only
Scan Cache Configuration Administration	Full	View-Only	View-Only
Contacts	Full (Can View, Create, Edit, Delete Contacts)	View-Only	Hide
Licenses	Full (Can View, Change License)	View-Only	Hide

Trend Micro Deep Security On-Premise 11.3

RIGHTS	SETTINGS BY ROLE		
Updates	Full (Can Add, Edit, Delete Software; Can View Update For Components; Can Download, Import, Apply Update Components; Can Delete Deep Security Rule Updates)	View-Only	Hide
Asset Values	Full (Can Create, Edit, Delete Asset Values)	View-Only	View-Only
Certificates	Full (Can Create, Delete SSL Certificates)	View-Only	View-Only
Relay Groups	Full	View-Only	View-Only
Proxy	Full	View-Only	View-Only
SAML Identity Providers	Full	Hide	Hide
Malware Scan Configuration	Full (Can Create, Edit, Delete Malware Scan Configuration)	View-Only	View-Only
Quarantined File	Full (Can Delete, Download Quarantined File)	View-Only	View-Only
Web Reputation Configuration	Full	View-Only	View-Only
Directory Lists	Full (Can Create, Edit, Delete)	View-Only	View-Only
File Lists	Full (Can Create, Edit, Delete)	View-Only	View-Only
File Extension Lists	Full (Can Create, Edit, Delete)	View-Only	View-Only
Firewall Rules	Full (Can Create, Edit, Delete Firewall Rules)	View-Only	View-Only

Trend Micro Deep Security On-Premise 11.3

RIGHTS	SETTINGS BY ROLE		
Firewall Stateful Configurations	Full (Can Create, Edit, Delete Firewall Stateful Configurations)	View-Only	View-Only
Intrusion Prevention Rules	Full (Can Create, Edit, Delete)	View-Only	View-Only
Application Types	Full (Can Create, Edit, Delete)	View-Only	View-Only
MAC Lists	Full (Can Create, Edit, Delete)	View-Only	View-Only
Contexts	Full (Can Create, Edit, Delete)	View-Only	View-Only
Integrity Monitoring Rules	Full (Can Create, Edit, Delete)	View-Only	View-Only
Log Inspection Rules	Full (Can Create, Edit, Delete)	View-Only	View-Only
Log Inspection Decoders	Full (Can Create, Edit, Delete)	View-Only	View-Only

The custom settings corresponding to the **Change own password and contact information only** option are listed in the following table:

Custom settings corresponding to "Change own password and contact information only" option	
Users	
Can View Users	Not allowed
Can Create New Users	Not allowed
Can Edit User Properties (User can always edit select properties of own account)	Not allowed

Trend Micro Deep Security On-Premise 11.3

Custom settings corresponding to "Change own password and contact information only" option	
Can Delete Users	Not allowed
Roles	
Can View Roles	Not allowed
Can Create New Roles	Not allowed
Can Edit Role Properties (Warning: conferring this right will let Users with this Role edit their own rights)	Not allowed
Can Delete Roles	Not allowed
Delegate Authority	
Can only manipulate Users with equal or lesser rights	Not allowed

The custom settings corresponding to the **Create and manage Users with equal or less access** option are listed in the following table:

Custom settings corresponding to "Create and manage Users with equal or less access" option	
Users	
Can View Users	Allowed

Trend Micro Deep Security On-Premise 11.3

Custom settings corresponding to "Create and manage Users with equal or less access" option	
Can Create New Users	Allowed
Can Edit User Properties (User can always edit select properties of own account)	Allowed
Can Delete Users	Allowed
Roles	
Can View Roles	Not allowed
Can Create New Roles	Not allowed
Can Edit Role Properties (Warning: conferring this right will let Users with this Role edit their own rights)	Not allowed
Can Delete Roles	Not allowed
Delegate Authority	
Can only manipulate Users with equal or lesser rights	Allowed

The custom settings corresponding to the **Have full control over all Roles and Users** option are listed in the following table:

Custom settings corresponding to "Have full control over all Roles and Users" option	
Users	

Trend Micro Deep Security On-Premise 11.3

Custom settings corresponding to "Have full control over all Roles and Users" option	
Can View Users	Allowed
Can Create New Users	Allowed
Can Edit User Properties (User can always edit select properties of own account)	Allowed
Can Delete Users	Allowed
Roles	
Can View Roles	Allowed
Can Create New Roles	Allowed
Can Edit Role Properties (Warning: conferring this right will let Users with this Role edit their own rights)	Allowed
Can Delete Roles	Allowed
Delegate Authority	
Can only manipulate Users with equal or lesser rights	Not applicable

Add users who can only receive reports

"Contacts" are users who cannot sign in to the Deep Security Manager but can periodically be sent reports (using scheduled tasks). Contacts can be assigned a "clearance" level that maps to existing roles. When a contact is sent a report, the report will not contain any information not accessible to a user of the same level. For example, three contacts may each be listed as the

Trend Micro Deep Security On-Premise 11.3

recipients of a weekly summary report but the contents of the three reports could be entirely different for each contact depending on their computer rights.

Add or edit a contact

1. In Deep Security Manager go to **Administration > User Management > Contacts**.
2. Click **New** to add a new contact or double-click an existing contact to edit its settings.
3. In the **General Information** section, specify the name, description, and preferred language of this contact.
4. In the **Contact Information** section, enter the email address to which reports will be sent if this contact is included in a report distribution list. (See the **Reports** page for more information.)
5. In the **Clearance** section, specify the role that determines the information this contact will be allowed to see. For example, if a computer report has been scheduled to be sent to this contact, only information on the computers that his role permits him access to will be included in the report.
6. In the **Password Protected Reports** section, select **Reports generated by this user are password protected** to password-protect exported PDF reports with the **Report Password**.

Delete a contact

To remove a contact from Deep Security Manager, click **Administration > User Management > Contacts**, click the contact, and then click **Delete**.

Create an API key for a user

To use the Deep Security Manager API, you will need an API key.

Trend Micro Deep Security On-Premise 11.3

Note: API keys can only be used with the new ["Use the Deep Security API to automate tasks" on page 417](#) available in Deep Security Manager 11.1 and later.

Note: Trend Micro recommends creating one API key for every user needing API access to the Deep Security Manager.

Tip: You can automate API key creation using the Deep Security API. For examples, see the [Create and Manage API Keys](#) guide in the Deep Security Automation Center.

To create a new API key:

1. Go to **Administration > User Management > API Keys**.
2. Click **New**.
3. In the Properties window, enter a **Name** and **Description** for the API key.
4. Click on the **Role** list and select a role. **Auditor** grants read-only access to the Deep Security Manager through the API, while **Full Access** grants both read and write access. If you need more specific roles for API key users, you can select **New** and define one. See ["Define roles for users" on page 1313](#) for more information on doing so.
5. Select a **Language**.
6. Select a **Time Zone**.
7. Optionally select **Expires on** and select an expiry date for the API key.
8. Click **OK**.
9. Copy the **Secret key value**.

Note: Make sure to copy the secret key value now, this is the only time it will be shown.

Lock out an existing API key

If an existing API key has been compromised you can lock it out:

Trend Micro Deep Security On-Premise 11.3

1. Double click on the API key you want to lock out.
2. Optionally select **Locked Out (Denied permission to authenticate)** to block usage of the API key.
3. Click **OK**.

Unlock a locked out user name

If you have attempted to sign in multiple times to Deep Security Manager with an incorrect password, your user account will be locked out. The number of sign-in attempts allowed before lock out is configured in **Administration > System Settings > Security > Number of incorrect sign-in attempts allowed (before lock out)**.

You can unlock users in different ways, depending on the following situations:

- If an administrator user is available, see ["Unlock users as an administrator" below](#).
- If all the administrative users are locked out, see ["Unlock administrative users from a command line" below](#).

Unlock users as an administrator

1. Log in to Deep Security Manager with a working administrator user name and password.
2. Go to **Administration > User Management > Users**. Select the user you want to unlock, right-click, and click **Properties**.
3. In the wizard, go to **General > Sign-In Credentials**. Deselect the **Locked Out (Denied permission to sign in)** check box.
4. Click **Save**.

Unlock administrative users from a command line

1. Go to your local command line interface.

If your Deep Security Manager is Windows, go to the `..\Program Files\Trend Micro\Deep security Manager` directory.

Trend Micro Deep Security On-Premise 11.3

If your Deep Security Manager is Linux, go to the `/opt/dsm` directory.

2. Enter the following command:

```
dsm_c -action unlockout -username <username>
```

Implement SAML single sign-on

Note: SAML single sign-on is not available when FIPS mode is enabled. See ["FIPS 140-2 support" on page 1381](#).

To implement SAML single sign-on, see ["Getting started with SAML single sign-on" on page 1341](#).

What are SAML and single sign-on?

Security Assertion Markup Language (or **SAML**) is an open authentication standard that allows for the secure exchange of user identity information from one party to another. SAML supports **single sign-on**, a technology that allows for a single user login to work across multiple applications and services. For Deep Security, implementing SAML single sign-on means that users signing in to your organization's portal would be able to seamlessly sign in to Deep Security without an existing Deep Security account.

How SAML single sign-on works in Deep Security

Establishing a trust relationship

In SAML single sign-on, a trust relationship is established between two parties: the **identity provider** and the **service provider**. The identity provider has the user identity information stored on a directory server. The service provider (which in this case is Deep Security) uses the identity provider's user identities for its own authentication and account creation.

The identity provider and the service provider establish trust by exchanging a **SAML metadata document** with one another.

Trend Micro Deep Security On-Premise 11.3

Note: At this time, Deep Security supports **only** the HTTP POST binding of the SAML 2.0 identity provider (IdP)-initiated login flow, and not the service provider (SP)-initiated login flow

Creating Deep Security accounts from user identities


Once Deep Security and the identity provider have exchanged SAML metadata documents and established a trust relationship, Deep Security can access the user identities on the identity provider's directory server. However, before Deep Security can actually create accounts from the user identities, account types need to be defined and instructions for transforming the data format need to be put in place. This is done using **groups**, **roles** and **claims**.

Groups and roles specify the tenant and access permissions that a Deep Security user account will have. Groups are created on the identity provider's directory server. The identity provider assigns user identities to one or more of the groups. Roles are created in the Deep Security Manager. There must be both a group and a role for each Deep Security account type, and their access permissions and tenant assignment must match.

Once there are matching groups and roles for each user type, the group data format needs to be transformed into a format Deep Security can understand. This is done by the identity provider with a claim. The claim contains instructions for transforming the group data format into the matching Deep Security role.

Tip: Learn more about the ["SAML claims structure" on page 1346](#) required by Deep Security.

Below is a representation of this process:



Implement SAML single sign-on in Deep Security

Once trust has been established between Deep Security and an identity provider with a SAML metadata document exchange, matching groups and roles have been created, and a claim put in place to translate the group data into roles, Deep Security can use SAML single sign-on to automatically make Deep Security accounts for users signing in through your organization's portal.

For more information on implementing SAML single sign-on, see ["Getting started with SAML single sign-on" below](#).

Getting started with SAML single sign-on

Note: SAML single sign-on is not available when FIPS mode is enabled. See ["FIPS 140-2 support" on page 1381](#).

When you configure Deep Security to use SAML single sign-on, users signing in to your organization's portal can seamlessly sign in to Deep Security without an existing Deep Security account. SAML single sign-on also makes it possible to implement user authentication access control features such as:

Trend Micro Deep Security On-Premise 11.3

- Password strength or change enforcement.
- One-Time Password (OTP).
- Two-Factor Authentication (2FA) or Multi-Factor Authentication (MFA).

For a more detailed explanation of Deep Security's implementation of the SAML standard, see ["Implement SAML single sign-on" on page 1339](#).

Note: At this time, Deep Security supports **only** the HTTP POST binding of the SAML 2.0 identity provider (IdP)-initiated login flow, and not the service provider (SP)-initiated login flow

To use SAML single sign-on with Deep Security, you will need to do the following:

1. ["Configure pre-set up requirements" below](#)
2. ["Configure Deep Security as a SAML service provider" on the next page](#)
3. ["Configure SAML in Deep Security" on page 1345](#)
4. ["Provide information for your identity provider administrator" on page 1346](#)
5. ["SAML claims structure" on page 1346](#)
6. ["Test SAML single sign-on" on page 1350](#)
7. ["Service and identity provider settings" on page 1350](#)

Configure pre-set up requirements

1. Ensure your Deep Security Manager is functioning properly.
2. Contact the identity provider administrator to:
 - Establish a naming convention for mapping directory server groups to Deep Security roles.
 - Obtain their identity provider SAML metadata document.

Trend Micro Deep Security On-Premise 11.3

- Ask them to add any required user authentication access control features to their policy.

Support is available to assist with the following identity providers that have been tested in Deep Security with SAML single sign-on:

- Active Directory Federation Services (ADFS)
- Okta
- PingOne
- Shibboleth

Configure Deep Security as a SAML service provider

As the first step in the SAML single sign-on configuration, you will need to set up Deep Security as a service provider.

For a more detailed explanation of Deep Security's implementation of the SAML standard, see ["Implement SAML single sign-on" on page 1339](#).

Note: In multi-tenant Deep Security installations, only the primary tenant administrator can configure Deep Security as a SAML service provider.

1. On the **Administration** page, go to **User Management > Identity Providers > SAML**.
2. Click **Get Started**.
3. Enter an **Entity ID** and a **Service Name**, and then click **Next**.

Note: The **Entity ID** is a unique identifier for the SAML service provider. The SAML specification recommends that the entity ID is a URL that contains the domain name of the entity, and industry practices use the SAML metadata URL as the

entity ID. The SAML metadata is served from the `/saml` endpoint on the Deep Security Manager, so an example value might be `https://<DSMServerIP:4119>/saml`.

4. Select a certificate option, and click **Next**. The service provider certificate is not used at this time, but would be used in the future to support service-provider-initiated login or single sign-out features. When creating the service provider, you can import a certificate and private key or create a new self-signed certificate and private key.

Import a Certificate and Private Key

1. Click **Choose File** and open the PKCS #12 keystore file containing your certificate.
2. Enter the password for the keystore.
3. Click **Next**.

You will be shown a summary of your certificate details.

4. Click **Finish**.

Generate a new self-signed server certificate

1. Enter the following details for your certificate:
 - Common Name (CN)
 - Organization (O)
 - Organizational Unit (OU)
 - Email Address (E)
2. Click **Next**.

Trend Micro Deep Security On-Premise 11.3

You will be shown a summary of your certificate details.

3. Click **Finish**.

Keep the current Server Certificate

1. Click **Next**, and then click **Finish**.

Deep Security is now set up as a SAML service provider.

Configure SAML in Deep Security

Import your identity provider's SAML metadata document

Note: Your Deep Security account must have both administrator and "Create SAML identity provider" permissions.

1. On the Administration page, go to **User Management > Identity Providers > SAML**.
2. Click **Get Started**.
3. Click **Choose File**, select the SAML metadata document provided by your identity provider, and click **Next**.
4. Enter a **Name** for the identity provider, and then click **Finish**.

You will be brought to the Roles page.

Create Deep Security roles for SAML users

You need to create a role for each of your expected user types. Each role must have a corresponding group in your identity provider's directory server, and match the group's access permissions and tenant assignment.

Your identity provider's SAML integration will have a mechanism to transform group membership into SAML claims. Consult the documentation that came with your identity provider to learn more about claim rules.

For information on how to create roles, see ["Define roles for users" on page 1313](#).

Trend Micro Deep Security On-Premise 11.3

Provide information for your identity provider administrator

Download the Deep Security Manager service provider SAML metadata document

1. On the Administration page, go to **User Management > Identity Providers > SAML**.
2. Under SAML Service Provider, click **Download**.

Your browser will download the Deep Security service provider SAML metadata document (`ServiceProviderMetadata.xml`).

Send URNs and the Deep Security SAML metadata document to the identity provider administrator

You need to give the identity provider administrator Deep Security's service provider SAML metadata document, the identity provider URN and the URN of each Deep Security role you created.

Tip:

To view role URNs, go to **Administration > User Management > Roles** and look under the URN column.

To view identity provider URNs, go to **Administration > User Management > Identity Providers > SAML > Identity Providers** and look under the URN column.

Once the identity provider administrator confirms they have created groups corresponding to the Deep Security roles and any required rules for transforming group membership into SAML claims, you are done with configuring SAML single sign-on.

Note: If necessary, you can inform the identity provider administrator about the "[SAML claims structure](#)" below required by Deep Security.

SAML claims structure

The following SAML claims are supported by Deep Security :

Trend Micro Deep Security On-Premise 11.3

- "Deep Security user name (required)" below
- "Deep Security user role (required)" below
- "Maximum session duration (optional)" on the next page
- "Preferred language (optional)" on page 1349

Deep Security user name (required)

The claim must have a SAML assertion that contains an `Attribute` element with a `Name` attribute of `https://deepsecurity.trendmicro.com/SAML/Attributes/RoleSessionName` and a single `AttributeValue` element. The Deep Security Manager will use the `AttributeValue` as the Deep Security user name.

Sample SAML data (abbreviated)

```
<samlp:Response xmlns:samlp="urn:oasis:names:tc:SAML:2.0:protocol">
  <Assertion xmlns="urn:oasis:names:tc:SAML:2.0:assertion">
    <AttributeStatement>
      <Attribute Name="https://deepsecurity.trendmicro.com/SAML/Attributes/RoleSessionName">
        <AttributeValue>alice</AttributeValue>
      </Attribute>
    </AttributeStatement>
  </Assertion>
</samlp:Response>
```

Deep Security user role (required)

The claim must have a SAML assertion that contains an `Attribute` element with a `Name` attribute of `https://deepsecurity.trendmicro.com/SAML/Attributes/Role` and between one and ten `AttributeValue` elements. The Deep

Trend Micro Deep Security On-Premise 11.3

Security Manager uses the attribute value(s) to determine the tenant, identity provider, and role of the user. A single assertion may contain roles from multiple tenants.

Sample SAML data (abbreviated)

Note: The line break in the `AttributeValue` element is present for readability; in the claim it must be on a single line.

```
<samlp:Response xmlns:samlp="urn:oasis:names:tc:SAML:2.0:protocol">
  <Assertion xmlns="urn:oasis:names:tc:SAML:2.0:assertion">
    <AttributeStatement>
      <Attribute Name="https://deepsecurity.trendmicro.com/SAML/Attributes/Role">
        <AttributeValue>urn:tmds:identity:[pod ID]:[tenant ID]:saml-provider/[IDP name],
          urn:tmds:identity:[pod ID]:[tenant ID]:role/[role name]</AttributeValue>
      </Attribute>
    </AttributeStatement>
  </Assertion>
</samlp:Response>
```

Maximum session duration (optional)

If the claim has a SAML assertion that contains an `Attribute` element with a `Name` attribute of

`https://deepsecurity.trendmicro.com/SAML/Attributes/SessionDuration` and an integer-valued `AttributeValue` element, the session will automatically terminate when that amount of time (in seconds) has elapsed.

Sample SAML data (abbreviated)

```
<samlp:Response xmlns:samlp="urn:oasis:names:tc:SAML:2.0:protocol">
  <Assertion xmlns="urn:oasis:names:tc:SAML:2.0:assertion">
    <AttributeStatement>
```

Trend Micro Deep Security On-Premise 11.3

```
<Attribute Name="https://deepsecurity.trendmicro.com/SAML/Attributes/SessionDuration">
  <AttributeValue>28800</AttributeValue>
</Attribute>
</AttributeStatement>
</Assertion>
</samlp:Response>
```

Preferred language (optional)

If the claim has a SAML assertion that contains an `Attribute` element with the `Name` attribute of `https://deepsecurity.trendmicro.com/SAML/attributes/PreferredLanguage` and a string-valued `AttributeValue` element that is equal to one of the supported languages, the Deep Security Manager will use the value to set the user's preferred language.

The following languages are supported:

- `en-US` (US English)
- `ja-JP` (Japanese)
- `zh-CN` (Simplified Chinese)

Sample SAML data (abbreviated)

```
<samlp:Response xmlns:samlp="urn:oasis:names:tc:SAML:2.0:protocol">
  <Assertion xmlns="urn:oasis:names:tc:SAML:2.0:assertion">
    <AttributeStatement>
      <Attribute Name="https://deepsecurity.trendmicro.com/SAML/Attributes/PreferredLanguage">
        <AttributeValue>en-US</AttributeValue>
      </Attribute>
    </AttributeStatement>
```


Trend Micro Deep Security On-Premise 11.3

```
</Assertion>  
</samlp:Response>
```

Test SAML single sign-on

Navigate to the single sign-on login page on the identity provider server, and log in to the Deep Security Manager from there. You should be redirected to the Deep Security Manager console. If SAML single sign-on is not functioning, follow the steps below:

Review the set-up

1. Review the ["Configure pre-set up requirements" on page 1342](#) section.
2. Ensure that the user is in the correct directory group.
3. Ensure that the identity provider and role URNs are properly configured in the identity provider federation service.

Create a Diagnostic Package

1. Go to **Administration > System Information** and click **Diagnostic Logging**.
2. Select **SAML integration Issues** and click **Save**.
3. Generate logs. Replicate the issue by logging in to the Deep Security Manager through your identity provider.
4. After the login fails, generate a diagnostic package by navigating to **Administration > System Information** and clicking on **Create Diagnostic Package**.
5. Once the diagnostic package has been created, navigate to <https://success.trendmicro.com> to open a Technical Support Case, and upload the diagnostic package during the case creation.

Service and identity provider settings

You can set how far in advance Deep Security will alert you to the expiry date of the server and identity provider certificates, as well as how much time must pass before inactive user accounts added through SAML single sign-on are automatically deleted.

To change these settings, go to **Administration > System Settings > Security > Identity Providers**.

Navigate and customize Deep Security Manager

You can customize the Deep Security Manager console to suit your needs and to display useful information about your deployment.

- ["Group computers dynamically with smart folders" below](#)
- ["Customize the dashboard" on page 1077](#)
- ["View active Deep Security Manager nodes" on page 1367](#)
- ["Check your license information" on page 975](#)

Group computers dynamically with smart folders

A smart folder is a dynamic group of computers that you define with a saved search query. It finds matching computers each time you click the group. For example, if you want to view your computers grouped by attributes such as operating system or AWS project tags, you can do this using smart folders.

Tip: If you prefer to search for resources programmatically, you can automate resource searches using the Deep Security API. For examples, see the [Search for Resources](#) guide in the Deep Security Automation Center.

You create smart folders by defining:

1. What to search (1 - computer properties)
2. How to determine a match (2 - operator)

3. What to search for (3 - value)

The screenshot displays the 'Add Rule Group' dialog in Trend Micro Deep Security. It shows a rule group configuration with two rules. The first rule is 'Operating System CONTAINS Red Hat' and the second is 'Operating System CONTAINS Linux'. Red circles with numbers 1, 2, and 3 are placed below the first rule's dropdown, operator, and value fields respectively, corresponding to the section header '3. What to search for (3 - value)'.

Create a smart folder

1. Go to **Computers > Smart Folders**.

2. Click **Create a Smart Folder**.

A default, empty search criteria group ("rule group") appears. You must configure this first. If you need to define more or alternative possible matches, you can add more rule groups later.

3. Type a name for your smart folder.

4. In the first dropdown, select a property that all matching computers have, such as **Operating System**. (See "[Searchable Properties](#)" on page 1357.)

If you selected AWS Tag, also type the tag's name.

Trend Micro Deep Security On-Premise 11.3

5. Select the [operator](#): whether to match identical, similar, or opposite computers, such as **CONTAINS**.

Note: Some operators are not available for all properties.

6. Type all or part of the search term.

Note: Wild card characters are not supported.

Tip: If you enter multiple words, it compares the *entire phrase* - not each word separately. No match occurs if the property's value has words in a different order, or only some of the words.

To match *any* of the words, instead click **Add Rule** and **OR**, and then add another value: one word per rule.

7. If computers must match multiple properties, click **Add Rule** and **AND**. Repeat steps 4-6.

For more complex smart folders, you can chain multiple search criteria. Click **Add Group**, then click **AND** or **OR**. Repeat steps 4-7.

For example, you might have Linux computers deployed both on-premises and in clouds such as AWS, Azure, or vCloud. You could create a smart folder that contains all of them by using 3 rule groups based on:

- a. local physical computers' operating system
- b. AWS tag
- c. vCenter or vCloud name

The screenshot displays the Smart Folder configuration interface in Trend Micro Deep Security On-Premise 11.3. The interface is structured as follows:

- Top Level:** A container with a logic selector set to **OR** and a **+ Add Rule Group** button.
- Group 1:**
 - Logic selector: **OR**
 - Buttons: **+ Add Rule** and **✖ Delete Group**
 - Rule 1: Operating System **CONTAINS** Linux
 - Rule 2: Operating System **CONTAINS** Red Hat
- Group 2:**
 - Logic selector: **OR**
 - Buttons: **+ Add Rule** and **✖ Delete Group**
 - Rule 1: AWS Tag, Tag Key: **EQUALS** Operating System, Tag Value: **CONTAINS** Amazon Linux
 - Rule 2: AWS Tag, Tag Key: **EQUALS** Operating System, Tag Value: **CONTAINS** Red Hat
- Group 3:**
 - Logic selector: **OR**
 - Buttons: **+ Add Rule** and **✖ Delete Group**
 - Rule 1: vCenter Name **CONTAINS** Linux
 - Rule 2: vCloud Name **CONTAINS** Red Hat

Tip: To test the results of your query before saving your smart folder, click **Preview**.

8. Click **Save**.
9. To verify, click your new smart folder. Verify that it contains all expected computers.

Trend Micro Deep Security On-Premise 11.3


Tip: For faster smart folders, remove unnecessary AND operations, and reduce sub-folder depths. They increase query complexity, which reduces performance.

Also verify that it omits computers that shouldn't match the query. If you need to edit your smart folder's query, double-click the smart folder.

Note: If your account's role doesn't have the permissions, some computers won't appear, or you won't be able to edit their properties. For more information, see ["Define roles for users" on page 1313](#).

Edit a smart folder

If you need to edit your smart folder's query, double-click the smart folder.

To reorder search criteria rules or rule groups, move your cursor onto a rule or group until it changes to a , then drag it to its destination.

Clone a smart folder

To duplicate and modify an existing smart folder as a template for a new smart folder, right-click the original smart folder, then select **Copy Smart Folder**.

Focus your search using sub-folders


You can use sub-folders to filter a smart folder's search results.

Smart folders can be nested up to 10 levels deep.

Trend Micro Deep Security On-Premise 11.3

- Smart folder 1
 - Sub-folder 2
 - Sub-folder 3 ...

For example, you might have a smart folder for all your Windows computers, but want to focus on computers that are specifically Windows 7, and maybe specifically either 32-bit or 64-bit. To do this, under the "Windows" parent folder, you could create a child smart folder for Windows 7. Then, under the "Windows 7" folder, you would create two child smart folders: 32-bit and 64-bit.



1. Right-click a smart folder and select **Create Child Smart Folder**.
2. Edit your child smart folder's query groups or rules. Click **Save**.
3. Click your new smart folder. Verify that it contains all expected computers. Also verify that it omits computers that shouldn't match the query.

Automatically create sub-folders

Note: Applies to AWS computers only.

Trend Micro Deep Security On-Premise 11.3

Instead of manually creating child folders, if you use Amazon's cloud, you can automatically create sub-folders for each value of an AWS tag. For information on how to apply AWS tags to your computers, see Amazon's guide on [Tagging Your Amazon EC2 Resources](#).

Note: AWS tag-based sub-folders replace any existing manually created child folders under the parent folder.

1. Select the **Automatically create sub-folders for each value of a specific AWS tag key**: check box located below the smart folder groups.
2. Type name of the AWS tag. Sub-folders are automatically created for each of this tag's values.
3. Click **Save**.

Tip: Empty sub-folders can appear if an AWS tag value is not being used anymore. To remove them, right-click the smart folder and select **Synchronize Smart Folder**.

Searchable Properties

Properties are an attribute that some or all computers you want to find have. Smart folders show computers that have the selected property, and its value matches.

Note: Type your search *exactly as that property appears in Deep Security Manager*- not, for example, vCenter/AWS/Azure. Otherwise your smart folder query won't match.

To find the exact matching text, (unless otherwise noted) go to **Computers** and look in the navigation pane on the left.

General

Property	Description	Data type	Examples
Hostname	The computer's host name, as seen on Computers > Details in Hostname.	string	ca-staging-web1

Trend Micro Deep Security On-Premise 11.3

Property	Description	Data type	Examples
Computer Display Name	The computer's display name in Deep Security (if any), as seen on Computers > Details in Display Name.	string	nginxTest
Folder Name	The computer's assigned group.	string	US-East
Operating System	The computer's operating system, as seen on Computers > Details in Platform.	string	Microsoft Windows 7 (64 bit) Service Pack 1 Build 7601
IP Address	<p>The computer's IP address.</p> <p>You can find the IP address in Deep Security Manager. To find the IP of:</p> <ul style="list-style-type: none"> an AWS instance or Azure VM that was added to Deep Security through Add > Add AWS Account or Add > Add Azure Account, go the AWS or Azure computer's details page, and under the General tab, scroll to the Virtual machine Summary section. The AWS IP addresses are listed in these fields: <ul style="list-style-type: none"> Private IP Address Public IP (PIP) Address <p>Note: If you added the AWS or Azure computer through Add</p>	IPv4 or IPv6 address, or an IPv4 range	172.20.1.5- 172.20.1.55 2001:db8:face::5

Property	Description	Data type	Examples
	<p>> Add Computers, its IP is located in the same place as a physical computer's.</p> <ul style="list-style-type: none"> a physical computer (not AWS, Azure, vCenter, or vCloud), go to the computer's details page and on the left, click Interfaces <p>Note: If "DHCP" is displayed instead of a static IP address, it won't match the smart folder query.</p> <ul style="list-style-type: none"> a vCenter or vCloud VM, go to the vCenter computer's details page, and under the General tab, scroll to the Virtual machine Summary section. The vCenter or vCloud IP address is listed in the IP Address field. 		
Policy	The computer's assigned Deep Security policy, as seen on Computers > Details .	string (option in drop-down list)	Base Policy
Activated	Whether or not the computer has been activated with Deep Security Manager, as seen on Computers > Details .	Boolean	Yes
Docker Host	Whether or not Docker is installed on the computer, as seen on	Boolean	No

Trend Micro Deep Security On-Premise 11.3

Property	Description	Data type	Examples
	Computers > Details.		
Computer Type	The type of computer. Options are: Physical Computer, Amazon EC2 Instance, Amazon WorkSpace, vCenter VM, Azure Instance, Azure ARM Instance.	string (option in drop-down list)	Examples: Physical Computer, Amazon EC2 Instance
Last Successful Recommendation Scan	Whether or not the computer has had a successful recommendation scan within a specified time period. The last recommendation scan date and results can be seen on Computers > Details > General > Intrusion Prevention or Integrity Monitoring or Log Inspection > Recommendations .	Date operator drop-down list, String, Date unit drop-down list	OLDER THAN, 7, DAYS

AWS

Property	Description	Data type	Examples
Tag	The computer's AWS tag key:value pair, as seen on Computers > Details > Overview > General under Virtual machine Summary, in Cloud Instance Metadata. Type the tag name, then its value. Case-sensitive.	string	Tag Key: env Tag Value: staging
Security Group Name	The computer's associated AWS security group name, as seen on Computers > Details > Overview > General under Virtual machine Summary, in Security Group(s).	string	SecGrp1

Trend Micro Deep Security On-Premise 11.3

Property	Description	Data type	Examples
Security Group ID	The computer's AWS security group ID, as seen on Computers > Details > Overview > General under Virtual machine Summary, in Security Group(s).	string	sg-12345678
AMI ID	The computer's Amazon Machine AMI ID, as seen on Computers > Details > Overview > General under Virtual machine Summary, in AMI ID.	string	ami-23c44a56
Account ID	The computer's associated 12-digit AWS Account ID , as seen on Computers when you right-click Amazon Account and select Properties . Results include computers in sub-folders.	string	123456789012
Account Name	The computer's associated AWS Account Alias , as seen on Computers when you right-click the AWS Cloud Connector and select Properties . Results include computers in sub-folders.	string	MyAccount-123
Region ID	The computer's AWS region suffix . Results include computers in sub-folders.	string	us-east-1
Region Name	The computer's associated AWS region name. Results include computers in sub-folders.	string	US East (Ohio)

Trend Micro Deep Security On-Premise 11.3

Property	Description	Data type	Examples
VPC ID	<p>The computer's Virtual Private Cloud (VPC) ID.</p> <p>If an alias exists, the folder name is the alias, followed by the VPC ID in parentheses. Otherwise the folder's name is the VPC ID.</p> <p>Results include computers in sub-folders.</p>	string	vpc-3005e48a
Subnet ID	<p>The computer's associated Virtual Private Cloud (VPC) subnet ID.</p> <p>If an alias exists, the folder name is the alias, followed by the VPC subnet ID in parentheses. Otherwise the folder's name is the VPC subnet ID.</p> <p>Results include computers in sub-folders.</p>	string	subnet-b1c2e468
Directory ID	<p>The ID of the AWS directory where the user entry associated with an Amazon WorkSpace resides. The directory ID is seen on the Computers > Details > Virtual machine Summary, in the WorkSpace Directory field. That field takes the format <directory_alias>(<directory_ID>), for example, myworkspacedir(d-9367232d89).</p>	string	d-9367232d89

Azure

Property	Description	Data type	Examples
Subscription Name	The computer's associated Azure subscription account ID, as seen on Computers when you right-click Azure and select Properties . Results include computers in sub-folders.	string	MyAzureAccount
Resource Group	The computer's associated resource group.	string	MyResourceGroup

vCenter

Property	Description	Data type	Examples
Name	The computer's associated vCenter. Results include computers in sub-folders.	string	vCenter - lab13-vc.example.com
Datacenter	The computer's associated vCenter data center. Results include computers in sub-folders.	string	lab13-datacenter
Folder	The computer's vCenter folder. Results include computers in sub-folders.	string	db_dev
Parent ESX Hostname	The hostname of the ESXi hypervisor where the computer's guest VM is running, as seen on Computers .	string	lab13-esx2.example.com

Trend Micro Deep Security On-Premise 11.3

Property	Description	Data type	Examples
Custom Attribute	The computer's assigned vCenter custom attribute, as seen on Computers > Details in Virtual machine Summary.	string (comma-separated attribute name and value)	env, production

vCloud

Property	Description	Data type	Examples
Name	The computer's associated vCloud. Results include computers in sub-folders.	string	vCloud-lab23
Datacenter	The computer's associated vCloud data center. Results include computers in sub-folders.	string	lab13-datacenter
vApp	The computer's associated vCloud data center folder. Results include computers in sub-folders.	string	db_dev

Folder

Property	Description	Data type	Examples
Name	The hostname of the Microsoft Active Directory or LDAP directory. Results include computers in sub-folders.	string	ad01.example.com

Trend Micro Deep Security On-Premise 11.3

Property	Description	Data type	Examples
Folder	The computer's Microsoft Active Directory or LDAP folder name. Results include computers in sub-folders.	string	Computers

Operators

Smart folder operators indicate whether matching computers should have a property value that is identical, similar, or dissimilar to your search term. Not all operators are available for every property.

Operator	Description	Example usage
EQUALS	The search query only finds computers that are an exact match.	A search query for 'Windows' in the Operating System property does not find computers with 'Windows 7' or 'Microsoft Windows'.
DOES NOT EQUAL	The search query finds any computers that are not an exact match.	A search query for 'Amazon Linux (64 bit)' in the Operating System property finds all computers other than Amazon Linux 64-bit machines.
CONTAINS	The search query finds any computers that contain the search term.	A search query for '203.0.113.' in the IP Address property finds any computers on the 203.0.113.xxx subnet.
DOES NOT CONTAIN	The search query finds any computers that do not contain the search term.	A search query for 'Windows' in the Operating System property finds any computers that do not have 'Windows' in their operating system name.
ANY VALUE	The search query finds all computers with the selected property.	A search query in the Group Name property finds all computers in that group.
IN RANGE	The search query finds all computers between the specified start and end range.	A search query in the IP Address property with Start Range 10.0.0.0 and End Range 10.255.255.255 would find all computers with IP addresses between 10.0.0.0 and 10.255.255.255.

Trend Micro Deep Security On-Premise 11.3

Operator	Description	Example usage
NOT IN RANGE	The search query finds all computers that are not between the specified start and end range.	A search query in the IP Address property with Start Range 10.0.0.0 and End Range 10.255.255.255 finds all computers that have IP addresses outside the range of 10.0.0.0 and 10.255.255.255.
Yes	The search query finds all computers with the selected property.	A search query with 'Yes' selected for the Docker property finds any computers with the Docker service running.
No	The search query finds all computers that do not have the selected property.	A search query with 'No' selected for the Docker property would find any computers that do not have the Docker service running.
OLDER THAN	<p>The search query finds all computers prior to the specified date for the property.</p> <p>Used with an accompanying DAYS, WEEKS, HOURS, or MINUTES operator.</p>	A search query with 'OLDER THAN', '7', 'DAYS' for the 'Last Successful Recommendation Scan' property finds computers that have had a successful recommendation scan 8 days or longer ago.
MORE RECENTLY THAN	<p>The search query finds all computers more recent than the specified date for the property.</p> <p>Used with an accompanying DAYS, WEEKS, HOURS, or MINUTES operator.</p>	A search query with 'MORE RECENTLY THAN', '1', 'MONTH' for the 'Last Successful Recommendation Scan' property finds computers that have had a successful recommendation scan earlier than 1 month ago.
NEVER	The search query finds all	A search query with 'NEVER' for the 'Last Successful Recommendation

Operator	Description	Example usage
	computers that do not match the property.	Scan' property finds computers that have never had a successful recommendation scan.

View active Deep Security Manager nodes

To display a list of all active Deep Security Manager nodes, go to **Administration > Manager Nodes** . (See also ["Run Deep Security Manager on multiple nodes" on page 191.](#))

To display details about one of the manager nodes, double-click its row in the list. The Properties window will display:

- **Hostname:** The hostname of the computer where Deep Security Manager is installed.
- **Description:** A description of the manager node.
- **Performance Profile:** Deep Security Manager's performance can be affected by several factors including number of CPUs, available bandwidth, and database responsiveness. The manager's default performance settings are designed to be suited for most installation environments. However, if you experience performance issues your support provider may suggest that you change the performance profile assigned to one or more of your Deep Security Manager nodes. (You should not change these settings without first consulting your support provider.)

Note: The "Simultaneous Endpoint Disk and Network Jobs" referred to in the tables below include anti-malware scans, integrity monitoring scans, reconnaissance scans, sending policy updates to computers, and distributing security updates.

- **Aggressive:** This performance profile is optimized for installations where the Deep Security Manager is installed on a dedicated server. For example, this is how some common concurrent operations could be distributed per manager node using the **Aggressive** performance profile:

Trend Micro Deep Security On-Premise 11.3

Operation	2-core system	8-core system
Activations	10	20
Updates	25	50
Recommendation Scans	5	12
Check Status	100	Same (100)
Agent- or Appliance-Initiated Heartbeats	20 Active 40 Queued	50 Active 40 Queued
Simultaneous Endpoint Disk and Network Jobs	50	50
Simultaneous Endpoint Disk and Network Jobs per ESXi	3	3

- **Standard:** This Performance Profile is optimized for installations where the Deep Security Manager and the database are on the same computer. For example, this is how some common concurrent operations could be distributed per manager node using the **Standard** performance profile:

Operation	2-core system	8-core system
Activations	5	10
Updates	16	46
Recommendation Scans	3	9
Check Status	65	100
Agent- or Appliance-Initiated Heartbeats	20 Active 40 Queued	50 Active 40 Queued
Simultaneous Endpoint Disk and Network Jobs	50	50
Simultaneous Endpoint Disk and Network Jobs per ESXi	3	3

- **Unlimited Agent Disk and Network Usage:** This setting is identical to **Aggressive** but has no limit on computer disk and network usage operations.

Operation	2-core system	8-core system
Activations	10	20
Updates	25	25

Trend Micro Deep Security On-Premise 11.3

Operation	2-core system	8-core system
Recommendation Scans	5	12
Check Status	100	Same (100)
Agent- or Appliance-Initiated Heartbeats	20 Active 40 Queued	50 Active 40 Queued
Simultaneous Endpoint Disk and Network Jobs	Unlimited	Unlimited
Simultaneous Endpoint Disk and Network Jobs per ESXi	Unlimited	Unlimited

Note: All performance profiles limit the number of concurrent component updates to 100 per relay group.

- **Status:** Indicates the node's online and active status from the perspective of the Deep Security Manager node you are currently logged into.
- **Options:** You can choose to decommission a manager node. The node must be offline (uninstalled or service halted) to be decommissioned.

Customize advanced system settings

Several features for advanced users are located on **Administration > System Settings > Advanced**.

Tip: You can automate system setting changes using the Deep Security API. For examples, see the [Configure Policy, Computer, and System Settings](#) guide in the Deep Security Automation Center.

Primary Tenant Access

By default, the primary tenant can access your Deep Security environment.

Trend Micro Deep Security On-Premise 11.3

If the primary tenant enabled the "Primary Tenant Access" settings in your environment, however, you can prevent the primary tenant from accessing your Deep Security environment, or grant access for a limited amount of time.

Load Balancers

Note: The load balancer settings are not available when FIPS mode is enabled. See "[FIPS 140-2 support](#)" on page 1381.

Agents are configured with a list of Deep Security Manager and Deep Security Relays. When multiple managers and relays are deployed *without* a [load balancer](#), agents will automatically contact the managers and relays using a round robin sequence.

To better scale your network, you can put a load balancer in front of the managers or relays. When you configure the load balancer hostname and [port numbers](#), it will override the IP address or hostname and port numbers currently used by the agents.

The script generator uses the address of the Deep Security Manager that you are connected to. This ensures that the scripts continue to function even if one of the Deep Security Manager nodes fails or is down for maintenance or upgrades.

Note: The load balancer must be non-terminating for the SSL or TLS session with the agent's heartbeat port number because it uses mutual authentication. SSL inspection that terminates (for example, if you try to use SSL offloading) will break the session.

Multi-tenant Mode

1. Select **Enable Multi-Tenant Mode**.
2. In the wizard that appears, enter your **Multi-Tenant Activation Code** and click **Next**.
3. Select the license mode, either:
 - **Inherit Licensing from Primary Tenant:** All tenants use the same licenses as the primary tenant.
 - **Per Tenant Licensing:** Tenants themselves enter a license when they log in for the first time.

4. Click **Next**.

Deep Security Manager Plug-ins

Plug-ins are modules, reports and other add-ons for the Deep Security Manager. Trend Micro occasionally produces new or additional versions of these which are distributed as self-installing packages.

SOAP Web Service API

Much of the Deep Security Manager's functionality can be controlled via SOAP-invoked Web services. The WSDL (Web Services Description Language) can be found at the URL displayed in the panel on the page. For assistance with Deep Security Manager's Web services API contact your support provider.

Note: A User's ability to access Web Services in the Deep Security Manager will depend on that User being granted the appropriate privileges. These privileges are associated with the Role the User has been assigned. The setting is found on the **General** tab of the **Role properties window** found at **Administration > User Management > Roles**.

Status Monitoring API

The REST Status Monitoring API lets you query the Deep Security Manager (including individual Manager Nodes) for status information such as CPU and memory usage, number of queued jobs, total and Tenant-specific database size. For assistance with Deep Security Manager's REST Status Monitoring API contact your support provider.

Export

Export file character encoding: The character encoding used when you export data files from the Deep Security Manager. The encoding must support characters in your chosen language.

Exported Diagnostics Package Language: Your support provider may ask you generate and send them a Deep Security diagnostics package. This setting specifies the language the package will be in. The diagnostic package is generated on **Administration > System Information**.

Whois

Whois can be used to look up which domain name is associated with an IP address when you review logged intrusion prevention and firewall events. Enter the search URL using "[IP]" as a placeholder for the IP address to look up.

(For example, "http://reports.internic.net/cgi/whois?whois_nic=[IP]&type=nameserver".)

Licenses

Hide unlicensed Protection Modules for new Users determines whether unlicensed modules are hidden rather than simply grayed out for subsequently created Users. (This setting can be overridden on a per-user basis on **Administration > User Management > Users > Properties**).

Click **View Scan Cache Configurations** to display a list of saved Scan Cache Configurations. Scan Cache Configurations are settings used by the Virtual Appliance to maximize the efficiency of Anti-Malware and Integrity Scans in a virtualized environment. See "[Virtual Appliance Scan Caching](#)" on page 885 for more information.

CPU Usage During Recommendation Scans


This setting controls the amount of CPU resources dedicated to performing Recommendation Scans. If you notice that CPU usage is reaching unreasonably high levels, try changing to a lower setting to remedy the situation. For other performance controls, see **Administration > Manager Nodes > Properties > Performance Profiles**.

NSX

If Deep Security is being used to protect virtual machines in a VMware NSX environment and if it is installed with multiple Deep Security Manager nodes, this setting will determine which Deep Security Manager node communicates with the NSX Manager. (For more information on integrating Deep Security with an NSX environment, see ["Install or upgrade Deep Security" on page 144](#). For more information on multiple Deep Security Manager Nodes, see ["Run Deep Security Manager on multiple nodes" on page 191](#).)

Logo

You can replace the Deep Security logo that appears on the login page, at the top right of the Deep Security Manager GUI, and at the top of reports. Your replacement image must be in PNG format, be 320 px wide and 35 px high, and have a file size smaller than 1 MB. A template is available in the `installfiles` directory of the Deep Security Manager.



Click **Import Logo** to import your own logo, or click **Reset Logo** to reset the logo to its default image.

Manager AWS Identity

You can configure cross-account access. Select either:

- **Use Manager Instance Role:** The more secure option to configure cross-account access. Attach a policy with the sts:AssumeRole permission to the Deep Security Manager's instance role, then select this option. Does not appear if the Deep Security Manager does not have an instance role, or if you're using an Azure Marketplace or on-premise installation of Deep Security Manager.
- **Use AWS Access Keys:** Create the keys and attach a policy with the sts:AssumeRole permission before you select this option, and then type the **Access Key** and **Secret Key**. Does not appear if you're using an Azure Marketplace or on-premise installation of Deep Security Manager.

Application control


Each time you create an [application control](#) ruleset or change it, it must be distributed to all computers that use it. Shared rulesets are bigger than local rulesets. Shared rulesets are also often applied to many servers. If they all downloaded the ruleset directly from the manager at the same time, high load could cause slower performance. Global rulesets have the same considerations.

Using Deep Security Relays can solve this problem. (For information on configuring relays, see ["Distribute security and software updates with relays" on page 380.](#))

Steps vary by whether or not you have a multi-tenant deployment.

Single tenant deployments


Go to **Administration > System Settings > Advanced** and then select **Serve application control rulesets from relays**.



Multi-tenant deployments

The primary tenant (t0) can't access other tenants' (tN) configurations, so t0 relays don't have tN application control rulesets. (Other features like IPS don't have this consideration, because their rules come from Trend Micro, not a tenant.)

Other tenants (Tn) must create their own [relay group](#), then select **Serve application control rulesets from relays**.

**Warning:**

Verify compatibility with your deployment before using relays. If the agent doesn't have any previously downloaded ruleset currently in effect, and if it **doesn't receive new application control rules**, then the computer won't be protected by application control. If application control ruleset download fails, a [ruleset download failure event will be recorded on the manager](#) and on the agent.

Relays might either change performance, break application control ruleset downloads, or be required; it varies by proxy location, multi-tenancy, and global/shared vs. local rulesets.

Trend Micro Deep Security On-Premise 11.3

Required for...	Faster performance for...	Slower performance for...	Don't enable for...
<p>Agent > Proxy > Manager</p> <p>Note: In Deep Security Agent 10.0 GM and earlier, agents didn't have support for connections through a proxy to relays. If a ruleset download fails due to a proxy, and if your agents require a proxy to access the relay or manager</p>	<p>Shared rulesets</p> <p>Global ruleset</p>	<p>Local rulesets</p>	<p>Multi-tenant configurations when non-primary tenants (tN) use the default, primary (t0) relay group:</p> <ul style="list-style-type: none"> • Agent (tN) > DSR (t0) > DSM (tN) • Agent (tN) > Proxy > DSR (t0) > DSM (tN)

Trend Micro Deep Security On-Premise 11.3

Required for...	Faster performance for...	Slower performance for...	Don't enable for...
<div>(including Deep Security as a Service), then you must either:<ul style="list-style-type: none">• update agents' software, then configure the proxy• bypass the proxy• add a relay and then select Serve application control</div>			

Required for...	Faster performance for...	Slower performance for...	Don't enable for...
rulesets from relays			

Accelerate compliance

Trend Micro helps to accelerate compliance by consolidating multiple security controls into one product, while also delivering comprehensive auditing and reporting. For more information, see [Regulatory Compliance](#) on the Trend Micro website.

Depending on your requirements, see:

- ["Meet PCI DSS requirements with Deep Security" on the next page](#)
- ["GDPR" on the next page](#)
- ["FIPS 140-2 support" on page 1381](#)
- [Set up AWS Config Rules](#)
- ["Bypass vulnerability management scan traffic in Deep Security" on page 1394](#)
- ["Use TLS 1.2 with Deep Security" on page 1396](#)

Meet PCI DSS requirements with Deep Security

Coalfire (a PCI auditor) has written a commissioned white paper that examines how Trend Micro Deep Security can be used to help secure Payment Card Industry (PCI) data in accordance with the PCI Data Security Standard (PCI DSS).

For more information, see the white paper [Using Trend Micro's Hybrid Cloud Security Solution to Meet PCI DSS 3.2 Compliance](#).

Tip: For tips on how to:

- accelerate PCI DSS compliance in AWS, see [Accelerating PCI Compliance in AWS using Deep Security](#).
- enable TLS 1.2 for PCI compliance, see "Use TLS 1.2 with Deep Security" on page 1396.

Trend Micro Deep Security as a Service is now a PCI DSS Level 1 Service Provider! This means you can further streamline your PCI DSS certification process and take more items off of your to do list. For more information, see [Trend Micro Deep Security as a Service Achieves PCI DSS Level 1 Certification](#).

GDPR

The European Union's (EU) General Data Protection Regulation (GDPR) mandates that organizations anywhere in the world processing EU citizen data reassess their data processing controls and put a plan in place to better protect it. For information about GDPR and Trend Micro, see the [Trend Micro GDPR Compliance](#) site.

For information about personal data collection in Deep Security, see "Privacy and personal data collection disclosure" on page 66.

FIPS 140-2 support

Federal Information Processing Standard (FIPS) is a set of standards for cryptographic modules. For in-depth information about FIPS, see the [National Institute of Standards and Technology \(NIST\) website](#). Deep Security provides settings that enable cryptographic modules to run in a mode that is compliant with FIPS 140-2 standards. We have obtained certification for our [Java crypto module](#) and [Native crypto module \(OpenSSL\)](#).

There are some differences between a Deep Security deployment running in FIPS mode instead of non-FIPS mode (see ["Differences when operating Deep Security in FIPS mode" on the next page](#)).

Tip: If you intend to replace the Deep Security Manager SSL certificate, do so before enabling FIPS mode. If you need to replace the certificate after enabling FIPS mode, you will need to disable FIPS mode, follow the instructions in ["Replace the Deep Security Manager SSL certificate" on page 1035](#), and then re-enable FIPS mode.

To operate Deep Security in a FIPS 140-2 mode, you will need to:

1. Review ["Differences when operating Deep Security in FIPS mode" on the next page](#) to make sure the Deep Security features you require are available when operating in FIPS 140-2 mode.
2. Ensure that your Deep Security Manager and Deep Security Agents meet the ["System requirements for FIPS mode" on page 1383](#).
3. ["Enable FIPS mode for your Deep Security Manager" on page 1384](#).
4. If your Deep Security Manager needs to connect to an external service (such as an Active Directory, vCenter, or NSX Manager) using SSL, see ["Connect to external services when in FIPS mode" on page 1385](#).
5. ["Enable FIPS mode for the operating system of the computers you are protecting" on page 1386](#).
6. ["Enable FIPS mode for the Deep Security Agent on the computers you are protecting" on page 1386](#)
7. ["Enable FIPS mode for the Deep Security Virtual Appliance" on page 1387](#).

Trend Micro Deep Security On-Premise 11.3

8. With some versions of the Linux kernel, you must enable Secure Boot to enable FIPS mode. See ["Linux Secure Boot support for agents" on page 367](#) for instructions.

Release	Kernel Version	Secure Boot Required
RHEL 7.4	3.10.0-693	No
RHEL 7.3	3.10.0-514	No
RHEL 7.2	3.10.0-327	No
RHEL 7.1	3.10.0-229	No
RHEL 7.0 GA	3.10.0-123	Yes

This section also includes instructions on how to ["Disable FIPS mode" on page 1393](#).

Differences when operating Deep Security in FIPS mode

These Deep Security features are **not available** when operating in FIPS mode:

- Connecting to virtual machines hosted on VMware vCloud, as described in ["Add virtual machines hosted on VMware vCloud" on page 483](#). The **Administration > System Settings > Agents > Agentless vCloud Protection** settings are also unavailable.
- Multi-tenant environment
- Load balancer settings (**Administration > System Settings > Advanced > Load Balancers**)
- Deep Security Scanner (integration with SAP Netweaver)
- The Connected Threat Defense feature

Trend Micro Deep Security On-Premise 11.3

- Identity provider support via SAML 2.0
- When configuring SMTP settings, the STARTTLS option is not available.

System requirements for FIPS mode

Deep Security Manager requirements

The Deep Security Manager requirements with FIPS mode enabled are the same as those described in ["System requirements" on page 76](#), with the following exceptions.

Only these operating systems are supported:

- Red Hat Enterprise Linux 7 (64bit)
- Windows Server 2016 (64-bit)
- Windows Server 2012 or 2012 R2 (64-bit)
- Windows Server 2008 or 2008 R2 (64-bit)

Only these databases are supported:

- PostgreSQL 9.6 (see ["Using FIPS mode with a PostgreSQL database" on page 1387](#))
- Microsoft SQL Server 2016 Enterprise Edition (See ["Using FIPS mode with a Microsoft SQL Server database" on page 1391](#))
- Microsoft SQL Server 2014 Enterprise Edition (See ["Using FIPS mode with a Microsoft SQL Server database" on page 1391](#))
- Microsoft SQL Server 2012 Enterprise Edition (See ["Using FIPS mode with a Microsoft SQL Server database" on page 1391](#))
- Microsoft SQL Server 2008 R2 Enterprise Edition (See ["Using FIPS mode with a Microsoft SQL Server database" on](#)

Trend Micro Deep Security On-Premise 11.3

[page 1391](#))

- Microsoft SQL Server 2008 Enterprise Edition (See ["Using FIPS mode with a Microsoft SQL Server database" on page 1391](#))

Note: Oracle Database is not supported, even if it has enabled FIPS mode for SSL connections.

Note: Microsoft SQL Server named pipes are not supported.

Deep Security Agent requirements

The Deep Security Agent requirements with FIPS mode enabled are the same as those described in ["System requirements" on page 76](#). FIPS mode is not supported with all operating systems. To check which operating systems are supported, see ["Supported features by platform" on page 85](#).

Deep Security Virtual Appliance requirements

Deep Security Manager 11.0 Update 3 and later is required to support FIPS mode on the appliance. For details on the appliance's system requirements, see ["System requirements" on page 76](#).

Enable FIPS mode for your Deep Security Manager

Enable FIPS mode for a Deep Security Manager on Windows

1. Use the Services window of the Microsoft Management Console to stop the "Trend Micro Deep Security Manager" service.
2. In the Windows command line, go to the Deep Security Manager's working folder, for example, `C:\Program Files\Trend Micro\Deep Security Manager`.
3. Enter this command to enable FIPS mode:

Trend Micro Deep Security On-Premise 11.3

```
dsm_c -action enablefipsmode
```

4. Restart the Deep Security Manager service.

Enable FIPS mode for a Deep Security Manager on Linux

1. On the Deep Security Manager computer, open a command line and go to the Deep Security Manager's working folder, for example, `/opt/dsm`.
2. Enter this command to stop the Deep Security Manager service:

```
service dsm_s stop
```

3. Enter this command to enable FIPS mode:

```
dsm_c -action enablefipsmode
```

4. Enter this command to restart the Deep Security Manager service:

```
service dsm_s start
```

Connect to external services when in FIPS mode

When Deep Security Manager is operating in FIPS mode and you want to connect to an external service (such as an Active Directory, vCenter, or NSX Manager) with an SSL connection, you must import the SSL certificate for that external service into the manager before connecting to it. For instructions on how to import the certificate, see ["Manage trusted certificates" on page 364](#).

For instructions on importing computers from an Active Directory, see ["Add computer groups from Microsoft Active Directory" on page 486](#).

For instructions on synchronizing user information with an Active Directory, see ["Create and manage users" on page 1306](#).

Trend Micro Deep Security On-Premise 11.3

For instructions on adding a VMware vCenter to Deep Security Manager, see ["Add a vCenter when Deep Security Manager is in FIPS mode" on page 453](#).

Enable FIPS mode for the operating system of the computers you are protecting

For instructions on enabling FIPS mode on Windows, please refer to the Microsoft Support site: [System cryptography: Use FIPS compliant algorithms for encryption, hashing, and signing" security setting effects in Windows XP and in later versions of Windows](#).

For instructions on enabling FIPS mode on RHEL 7 or CentOS 7, please refer to Red Hat documentation: [Federal Standards and Regulations](#) and [How can I make RHEL 6 or RHEL 7 FIPS 140-2 compliant](#).

Enable FIPS mode for the Deep Security Agent on the computers you are protecting

Note: This step is not required for new Deep Security 11.0 or higher agents that you install after enabling FIPS mode in Deep Security Manager. In that situation, FIPS mode is already enabled for the agent.

Enable FIPS mode for a Windows agent

1. In the Windows system root folder (for example, `C:\Windows`), look for a file named `ds_agent.ini`. Open the file in a text editor or create a new file if you don't have one already.
2. Add this line to the file:

```
FIPSMODE=1
```

3. Restart the Deep Security Agent service.

Enable FIPS mode for an RHEL 7 or CentOS 7 agent

1. In `/etc/`), look for a file named `ds_agent.conf`. Open the file in a text editor or create a new file if you don't have one already.
2. Add this line to the file:

```
FIPSMode=1
```

3. Restart the Deep Security Agent:

```
/etc/init.d/ds_agent restart
```

Enable FIPS mode for the Deep Security Virtual Appliance

1. In `<DSVA_root>/etc/`, look for a file named `ds_agent.conf`. Open the file in a text editor or create a new file if you don't have one already.
2. Add this line to the file:

```
FIPSMode=1
```

3. Restart the appliance from the command line:

```
/etc/init.d/ds_agent restart
```

Using FIPS mode with a PostgreSQL database

If you are using PostgreSQL as your Deep Security Manager database, there are some extra requirements in addition to those outlined in ["Prepare a database for Deep Security Manager" on page 122](#).

In FIPS mode, the keystore must be the BCFKS type. Instead of converting the java default keystore (`C:\Program Files\Trend Micro\Deep Security Manager\jre\lib\security\cacerts` or `/opt/dsm/jre/lib/security/cacerts`) directly, copy the default keystore to another location and use it as the default keystore for SSL connection.

Trend Micro Deep Security On-Premise 11.3

1. Create the PostgreSQL environment
2. Copy the "server.crt" file from the PostgreSQL server and paste them into <Deep Security Manager install folder>.
3. Install Deep Security Manager.
4. ["Enable FIPS mode for your Deep Security Manager" on page 1384.](#)
5. Copy the default Java cacerts file into the Deep Security Manager root installation folder.

On Windows:

```
copy "C:\Program Files\Trend Micro\Deep Security Manager\jre\lib\security\cacerts" "C:\Program Files\Trend Micro\Deep Security Manager\cacerts"
```

On Linux:

```
cp "/opt/dsm/jre/lib/security/cacerts" "/opt/dsm/cacerts"
```

6. Convert the keystore file from JKS to BCFKS. The following command will create a cacerts.bcfks file in the Deep Security Manager installation folder:

On Windows:

```
cd C:\Program Files\Trend Micro\Deep Security Manager\jre\bin

keytool -importkeystore -srckeystore "C:\Program Files\Trend Micro\Deep Security Manager\cacerts" -
srcstoretype JKS -deststoretype BCFKS -destkeystore "C:\Program Files\Trend Micro\Deep Security
Manager\cacerts.bcfks" -srcstorepass <changeit> -deststorepass <changeit> -providerpath "C:\Program
Files\Trend Micro\Deep Security Manager\jre\lib\ext\ccj-3.0.0.jar" -providerclass
com.safelogic.cryptocomply.jcajce.provider.CryptoComplyFipsProvider
```

where <changeit> is replaced with your own values.

On Linux:

Trend Micro Deep Security On-Premise 11.3

```
cd /opt/dsm/jre/bin
```

```
keytool -importkeystore -srckeystore "/opt/dsm/cacerts" -srcstoretype JKS -deststoretype BCFKS -destkeystore  
"/opt/dsm/cacerts.bcfks" -srcstorepass <changeit> -deststorepass <changeit> -providerpath  
"/opt/dsm/jre/lib/ext/ccj-3.0.0.jar" -providerclass  
com.safelogic.cryptocomply.jcajce.provider.CryptoComplyFipsProvider
```

where `<changeit>` is replaced with your own values.

7. Import the certificate ("Deep Security Manager root folder/server.crt"):

On Windows:

```
cd C:\Program Files\Trend Micro\Deep Security Manager\jre\bin
```

```
keytool -import -alias psql -file "C:\Program Files\Trend Micro\Deep Security Manager\server.crt" -keystore  
"C:\Program Files\Trend Micro\Deep Security Manager\cacerts.bcfks" -storepass <changeit> -provider  
com.safelogic.cryptocomply.jcajce.provider.CryptoComplyFipsProvider -providerpath "C:\Program Files\Trend  
Micro\Deep Security Manager\jre\lib\ext\ccj-3.0.0.jar" -storetype BCFKS
```

where `<changeit>` is replaced with your own value.

On Linux:

```
cd /opt/dsm/jre/bin
```

```
keytool -import -alias psql -file "/opt/dsm/server.crt" -keystore "/opt/dsm/cacerts.bcfks" -storepass  
<changeit> -provider com.safelogic.cryptocomply.jcajce.provider.CryptoComplyFipsProvider -providerpath  
"/opt/dsm/jre/lib/ext/ccj-3.0.0.jar" -storetype BCFKS
```

where `<changeit>` is replaced with your own value.

Trend Micro Deep Security On-Premise 11.3

8. The Deep Security installer can use a `.vmoptions` file to assign the JVM parameter:

On Windows, create a file named `Deep Security Manager.vmoptions` in the installation folder and add the following text in the file: `-Djavax.net.ssl.keyStoreProvider=CCJ`

```
-Djavax.net.ssl.trustStore=C:\Program Files\Trend Micro\Deep Security Manager\cacerts.bcfks
```

```
-Djavax.net.ssl.trustStorePassword=<changeit>
```

```
-Djavax.net.ssl.keyStoreType=BCFKS
```

```
-Djavax.net.ssl.trustStoreType=BCFKS
```

where `<changeit>` is replaced with your own value.

On Linux, create a file named `dsm_s.vmoptions` in the installation folder and add the following text in the file:

```
-Djavax.net.ssl.keyStoreProvider=CCJ
```

```
-Djavax.net.ssl.trustStore=/opt/dsm/cacerts.bcfks
```

```
-Djavax.net.ssl.trustStorePassword=<changeit>
```

```
-Djavax.net.ssl.keyStoreType=BCFKS
```

```
-Djavax.net.ssl.trustStoreType=BCFKS
```

where `<changeit>` is replaced with your own value.

9. Open the `<Deep Security Manager directory>\webclient\webapps\ROOT\WEB-INF\dsm.properties` file in a text editor and add:

```
database.PostgreSQL.connectionParameters=ssl=true
```

Trend Micro Deep Security On-Premise 11.3

10. Open the `/opt/postgresql/data/postgresql.conf` file in a text editor and add:

```
ssl= on
```

```
ssl_cert_file= 'server.crt'
```

```
ssl_key_file= 'server.key'
```

11. Restart PostgreSQL and then restart the Deep Security Manager service.

12. Check the connection:

```
cd /opt/postgresql/bin
```

```
./psql -h 127.0.0.1 -Udsm dsm
```

Enter the password when prompted. You should see:

```
dsm=> select a.client_addr, a.application_name, a.username, s.* from pg_stat_ssl s join pg_stat_activity a
using (pid) where a.datname='dsm';
```

Using FIPS mode with a Microsoft SQL Server database

If you are using Microsoft SQL Server as your Deep Security Manager database, you must set up the database SSL encryption using the instructions below **before** enabling FIPS mode.

1. Stop the Deep Security Manager service.
2. Create a BCFKS keystore file with the SQL server certificate. You can use the keytool in `C:\Program Files\Trend Micro\Deep Security Manager\jre\bin`.
3. Use the following command to import the SQL server certificate (`C:\sqlserver_cert.cer`) to a new keystore file (`C:\Program Files\Trend Micro\Deep Security Manager\mssql_keystore.bcfks`):

Note: If the Deep Security Manager package doesn't contain a `ccj-3.0.0.jar` file, get the jar file from the FIPS page.

Trend Micro Deep Security On-Premise 11.3

```
keytool -import -alias mssql -file "C:\sqlserver_cert.cer" -keystore "C:\Program Files\Trend Micro\Deep Security Manager\mssql_keystore.bcfks" -storepass <changeit> -provider com.safelogic.cryptocomply.jcajce.provider.CryptoComplyFipsProvider -providerpath "C:\Program Files\Trend Micro\Deep Security Manager\jre\lib\ext\ccj-3.0.0.jar" -storetype BCFKS
```

where <changeit> is replaced with your own value.

During the import process, answer "YES" to trust this certificate.

4. If the keystore file is created successfully, you will be able to use the following command to list see the certificate listed in the keystore:

```
keytool -list -v -keystore "C:\Program Files\Trend Micro\Deep Security Manager\mssql_keystore.bcfks" -provider com.safelogic.cryptocomply.jcajce.provider.CryptoComplyFipsProvider -providerpath "C:\Program Files\Trend Micro\Deep Security Manager\jre\lib\ext\ccj-3.0.0.jar" -storetype BCFKS -storepass <changeit>
```

where <changeit> is replaced with your own value.

5. Open the C:\Program Files\Trend Micro\Deep Security Manager\webclient\webapps\ROOT\WEB-INF\dsm.properties file in a text editor and add the following lines enable SSL/TLS and FIPS settings:

```
database.SqlServer.encrypt=true
```

```
database.SqlServer.trustServerCertificate=false
```

```
database.SqlServer.fips=true
```

```
database.SqlServer.trustStorePassword=<changeit>
```

```
database.SqlServer.fipsProvider=CCJ
```

```
database.SqlServer.trustStoreType=BCFKS
```

```
database.SqlServer.trustStore=C:\Program Files\Trend Micro\Deep Security Manager\mssql_keystore.bcfks
```

Trend Micro Deep Security On-Premise 11.3

where `<changeit>` is replaced with your own value.

6. Optionally, you can also change the SQL server/client connection protocols from Named Pipes to TCP/IP. This will allow for FIPS support after upgrading to Deep Security 10.2:
 - a. In the SQL Server Configuration Manager, go to **SQL Network Configuration > Protocols for MSSQLSERVER** and enable **TCP/IP**.
 - b. Go to **SQL Native Client 11.0 Configuration > Client Protocols** and enable **TCP/IP**.
 - c. Follow the instruction provided by Microsoft to enable encrypted connections for an instance of the SQL Server database. [See Enable Encrypted Connections to the Database Engine](#).
 - d. Edit the `dsm.properties` file to change `database.sqlserver.driver=MSJDBC` and `database.SqlServer.namedPipe=false`.
7. Restart the Deep Security Manager service.
8. ["Enable FIPS mode for your Deep Security Manager" on page 1384](#).

Disable FIPS mode

1. To disable FIPS mode for the Deep Security Manager, follow the instructions that you used to enable it (see ["Enable FIPS mode for your Deep Security Manager" on page 1384](#)), but use this command in place of step 3:

```
dsm_c -action disablefipsmode
```
2. To disable FIPS mode for the Deep Security Agent, follow the instructions that you used to enable it (see ["Enable FIPS mode for the Deep Security Agent on the computers you are protecting" on page 1386](#)), but instead of `FIPSMODE=1`, use `FIPSMODE=0`.

Bypass vulnerability management scan traffic in Deep Security

If you are using a vulnerability management provider such as Qualys or Nessus (for PCI compliance, for example), you need to set up Deep Security to bypass or allow this provider's scan traffic through untouched.

- ["Create a new IP list from the vulnerability scan provider IP range or addresses" below](#)
- ["Create firewall rules for incoming and outbound scan traffic" on the next page](#)
- ["Assign the new firewall rules to a policy to bypass vulnerability scans" on page 1396](#)

After these firewall rules have been assigned to the new policy, the Deep Security Manager will ignore ANY traffic from the IPs you have added in your IP List.

Deep Security will not scan the vulnerability management provider traffic for stateful issues or vulnerabilities - it will be allowed through untouched.

Create a new IP list from the vulnerability scan provider IP range or addresses

Have handy the IP addresses that the vulnerability scan provider has given you.

1. In the Deep Security Manager, go to **Policies**.
2. In the left pane, expand **Lists > IP Lists**.
3. Click **New > New IP List**.
4. Type a **Name** for the new IP List, for example "Qualys IP list".
5. Paste the IP addresses that the vulnerability management provider has given you into the **IP(s)** box, one per line.
6. Click **OK**.

Create firewall rules for incoming and outbound scan traffic

After you've created the IP list, you need to create two firewall rules: one for incoming and one for outgoing traffic.

Name them as suggested, below:

<name of provider> Vulnerability Traffic - Incoming

<name of provider> Vulnerability Traffic - Outgoing

1. In the main menu, click **Policies**.
2. In the left pane, expand **Rules**.
3. Click **Firewall Rules > New > New Firewall Rule**.
4. Create the first rule to bypass Inbound AND Outbound for TCP and UDP connections that are incoming to and outgoing from vulnerability management provider.

Tip: For settings not specified, you can leave them as the default.

Name: (suggested) <name of provider> Vulnerability Traffic - Incoming

Action: Bypass

Protocol: Any

Packet Source: IP List and then select the new IP list created above.

5. Create a second rule:

Name: <name of provider> Vulnerability Traffic - Outgoing

Action: Bypass

Protocol: Any

Packet Destination: IP List and then select the new IP list created above.

Assign the new firewall rules to a policy to bypass vulnerability scans

Identify which policies are already used by computers that will be scanned by the vulnerability management provider.

Edit the policies individually to assign the rules in the firewall module.

1. Click **Policies** on the main menu.
2. Click **Policies** in the left pane.
3. In the right pane, for each policy, double-click to open the policy details.
4. In the pop-up, in the left pane, click **Firewall**.
5. Under **Assigned Firewall Rules**, click **Assign/Unassign**.
6. Ensure your view at the top-left shows **All** firewall rules in the .
7. Use the search window to find the rules you created and select them.
8. Click **OK**.

Use TLS 1.2 with Deep Security

In Deep Security Manager 11.1 and higher, TLS 1.2 is enforced by default for new installations.

Trend Micro Deep Security On-Premise 11.3

Review the table below to determine whether you need to take action.

If you are doing...	And your deployment includes...	Do this...
A new installation of Deep Security Manager 11.1 or higher	Only 10.0 and higher Deep Security Agents, Relays, and Virtual Appliances	<p>Nothing.</p> <p>By default, TLS 1.2 is used between all components and enforced on the manager and relays.</p>
	Pre-10.0 Deep Security Agents, Relays, or Virtual Appliances	<p>(Recommended.) Upgrade all of your components to 10.0 or higher versions which support TLS 1.2. See "Upgrade components to use TLS 1.2" on page 1404. This is the best option to increase the security of your deployment.</p> <p>Alternatively, you can enable early TLS 1.0 to ensure backward compatibility with older components. See "Enable early TLS (1.0)" on page 1412.</p>
An upgrade to Deep Security Manager 11.1 or higher	Only 10.0 and higher Deep Security Agents, Relays, or Virtual Appliances	<p>(Recommended.) Enable TLS 1.2 enforcement to increase the security of your deployment. See "Enforce TLS 1.2" on page 1406.</p> <p>Alternatively, you can do nothing. Whatever your TLS settings were in your previous deployment are preserved. If you had enforced TLS 1.2 before, then your enforcement settings are preserved after the upgrade. Conversely, if you had disabled enforcement, then those settings are preserved as well.</p>

Trend Micro Deep Security On-Premise 11.3

If you are doing...	And your deployment includes...	Do this...
	Pre-10.0 Deep Security Agents, Relays, or Virtual Appliances	<p>(Recommended.) Although no immediate action is required, you should plan to upgrade older components to 10.0 or higher which support TLS 1.2, and then enforce TLS 1.2. See "Upgrade components to use TLS 1.2" on page 1404 and "Enforce TLS 1.2" on page 1406. This is the best option to increase the security of your deployment.</p> <p>Alternatively, you can do nothing. Whatever your TLS settings were in your previous deployment are preserved. If TLS 1.0 was allowed before, then it will also be allowed after the upgrade.</p>

Topics on this page:

- ["Benefits of TLS 1.2" on the next page](#)
- ["TLS 1.2 architectures" on the next page](#)
- ["Upgrade components to use TLS 1.2" on page 1404](#)
- ["Enforce TLS 1.2" on page 1406](#)
- ["Enable early TLS \(1.0\)" on page 1412](#)
- ["Determine whether TLS 1.2 is enforced" on page 1414](#)
- ["Guidelines for deploying agents, virtual appliances, and relays after TLS 1.2 is enforced" on page 1415](#)

Benefits of TLS 1.2

Transport Layer Security (TLS), and the earlier Secure Sockets Layer (SSL), are encryption protocols that enable secure connections between different endpoints. When Deep Security components need to communicate, they determine the latest mutually-supported version of the encryption protocol and then use that version to secure all communication for the duration of their session. The latest version of TLS is 1.2. SSL has been discontinued due to security issues.

Trend Micro strongly recommends that you use TLS 1.2 communication between all its components. This page describes the benefits of TLS 1.2, and how to use and enforce it in your Deep Security environment.

The main benefits of TLS 1.2 are:

- **additional security.** TLS 1.2 has been enhanced to safeguard against the latest exploits.
- **PCI compliance.** The [Payment Card Industry Data Security Standard](#) (PCI DSS) is an information security standard that promotes the safety of cardholder data. To be PCI-compliant, organizations must disable Secure Sockets Layer (SSL) and early TLS on applicable connections. For more information on PCI compliance, see "[Meet PCI DSS requirements with Deep Security](#)" on page 1380.

TLS 1.2 architectures

The diagrams below show the TLS communication in the Deep Security architecture.

Figure 1 shows the TLS communication when TLS 1.2 *is* enforced (This is the default for new 11.1 or higher Deep Security Manager installations.) You can see that the 9.6 agents can no longer communicate with Deep Security Manager, and neither can older third-party applications.

Trend Micro Deep Security On-Premise 11.3

Figure 2 shows the TLS communication when TLS 1.2 is *not* enforced. You can see that 10.0 or higher agents communicate with Deep Security Manager over TLS 1.2, while 9.6 versions communicate over early TLS. Similarly, newer third-party applications use TLS 1.2, while older ones use early TLS.

Figure 1: TLS 1.2 is enforced





Figure 2: TLS 1.2 is *not* enforced



Upgrade components to use TLS 1.2

If you want your Deep Security components to use TLS 1.2, just make sure that each component supports TLS 1.2.

Follow the instructions below to verify that your Deep Security components support TLS 1.2 and upgrade them if needed.

Note: If you want to *enforce* TLS 1.2 and prevent the use of early TLS, see instead ["Enforce TLS 1.2" on page 1406](#).

Verify and upgrade your Deep Security Manager

- Make sure you're using one of the following versions of Deep Security Manager, and if not, upgrade it:
 - Use Deep Security Manager 10.0 *update 8* or later if you're planning to ["Enforce TLS 1.2" on page 1406](#) on the manager. Only 10.0 update 8 and later managers support TLS 1.2 enforcement.
 - Use Deep Security Manager 10.0 or later if you're *not* planning to ["Enforce TLS 1.2" on page 1406](#) on the manager. Only 10.0 and later managers support TLS 1.2 communication.
- For upgrade instructions see ["Install or upgrade Deep Security" on page 144](#).

Verify your Deep Security Manager database

- If you're using Microsoft SQL Server as your Deep Security Manager database, make sure the database supports TLS 1.2, and if not, upgrade it. See [this Microsoft article](#) for guidance.
- If you're using a PostgreSQL database, it supports TLS 1.2 so no action is necessary.
- If you're using an Oracle database, only Oracle's native encryption is supported for database-manager communication, not TLS, so no action is necessary.
- By default, there is no encryption between the database (SQL Server, PostgreSQL, or Oracle) and Deep Security Manager. You can [enable it manually](#).

Verify your Deep Security Agents

- If you have existing Deep Security Agents, make sure they're at version 10.0 or higher. Only 10.0 or higher agents support TLS 1.2.

Note: If some agents are left un-upgraded (that is, they are pre-10.0), those agents communicate over early TLS, and you may need to enable early TLS. For details, see ["Enable early TLS \(1.0\)" on page 1412](#).

To upgrade your agents:

1. Import the latest Deep Security Agent software into Deep Security Manager, either manually or automatically. See ["Update the Deep Security Agent" on page 984](#) for details.
2. Upgrade your Deep Security Agents:
 - To automatically upgrade an agent, see ["Initiate an agent update" on page 985](#).
 - To manually upgrade an agent, see ["Manually upgrade the agent" on page 986](#).

Verify your Deep Security Relays

- Make sure you're using one of the following versions of Deep Security Relay, and if not, upgrade it:
 - Use Deep Security Relay 10.0 *update 8* or later if you're planning to ["Enforce TLS 1.2" on the next page](#) on the relay. Only 10.0 update 8 and higher relays support TLS 1.2 enforcement.
 - Use Deep Security Relay 10.0 or later if you're *not* planning to ["Enforce TLS 1.2" on the next page](#) on the relay. Only 10.0 and higher relays support TLS 1.2 communication.

To upgrade a relay, follow the same process as upgrading an agent:

Trend Micro Deep Security On-Premise 11.3

1. Import the latest Deep Security Relay software into Deep Security Manager, either manually or automatically. See ["Update the Deep Security Agent" on page 984](#) for details.
2. Upgrade the relay:
 - To automatically upgrade a relay, see ["Initiate an agent update" on page 985](#).
 - To manually upgrade a relay, see ["Manually upgrade the agent" on page 986](#).

Verify your Deep Security Virtual Appliance

Make sure you're using Deep Security Virtual Appliance 10.0 or higher.

To upgrade the appliance:

1. Temporarily [enable early TLS \(1.0\)](#).
2. Upgrade the appliance to 10.0 or higher (see ["Upgrade an existing appliance SVM automatically" on page 988](#)). The new virtual appliance now supports TLS 1.2.
3. Once the upgrade is finished, [re-enable TLS 1.2 enforcement](#).

Note: The minimum VSphere and NSX software versions required for the virtual appliance already support TLS 1.2. See ["System requirements" on page 76](#) for details.

Enforce TLS 1.2

Topics in this section:

Trend Micro Deep Security On-Premise 11.3

- ["Where can TLS 1.2 be enforced?" below](#)
- ["What happens when TLS 1.2 enforced?" below](#)
- ["Is TLS 1.2 enforced by default?" on the next page](#)
- ["Under what circumstances is TLS 1.2 enforcement possible? " on the next page](#)
- ["Enforce TLS 1.2 on Deep Security Manager" on the next page](#)
- ["Enforce TLS 1.2 on the Deep Security Relay" on page 1409](#)
- ["Enforce TLS 1.2 on just the manager's GUI port \(4119\)" on page 1409](#)
- ["Test that TLS 1.2 is enforced" on page 1410](#)

Where can TLS 1.2 be enforced?

There are two enforcement points:

- on the Deep Security Manager
- on the Deep Security Relays

What happens when TLS 1.2 enforced?

When TLS 1.2 is enforced, the manager and relays stop accepting early TLS connections, and any applications that try to use early TLS are denied access and cease to function properly.

If you choose *not* to enforce TLS 1.2, the manager and relays still accept early TLS as well as TLS 1.2 connections. This means that both older and newer applications are able to connect.

Trend Micro Deep Security On-Premise 11.3

Is TLS 1.2 enforced by default?

- If you have a new installation of Deep Security Manager 11.1 or higher (not an upgrade), TLS 1.2 is enforced by default.
- If you are upgrading an existing Deep Security Manager to 11.1 or higher, then your existing TLS settings are preserved, so if TLS was not enforced previously, it will continue to not be enforced after the upgrade. Conversely, if it was enforced, it will continue to be enforced.

Under what circumstances is TLS 1.2 enforcement possible?

You can only enforce TLS 1.2 if *all* Deep Security Agents have been upgraded to 10.0 or higher, which is the version at which TLS 1.2 is supported.

Enforce TLS 1.2 on Deep Security Manager

1. Before you begin:
 - Make sure that Deep Security Manager is at version *10.0 Update 8* or higher. You need this version to enforce TLS 1.2.
 - Make sure that all other components support TLS 1.2. See ["Upgrade components to use TLS 1.2" on page 1404](#).
2. On the Deep Security Manager computer, run this [dsm_c command](#):

```
dsm_c -action settlsprotocol -MinimumTLSProtocol ShowValue
```

A TLS version appears. This is the minimum TLS version that Deep Security Manager currently accepts.

3. Run this `dsm_c` command:

```
dsm_c -action settlsprotocol -MinimumTLSProtocol TLSv1.2
```

This command sets the minimum TLS version to 1.2. Deep Security Manager now accepts TLS 1.2 connections and disallows TLS 1.0 connections.

Trend Micro Deep Security On-Premise 11.3

The Deep Security Manager service is restarted automatically.

Enforce TLS 1.2 on the Deep Security Relay

1. Before you begin:
 - Make sure that Deep Security Relay is at version *10.0 Update 8* or higher. You need this version to enforce TLS 1.2.
 - Make sure that all your components support TLS 1.2. See ["Upgrade components to use TLS 1.2" on page 1404](#).
 - Make sure that you have [enforced TLS 1.2 on Deep Security Manager](#).
2. Resend the policies associated with your relays:
 - a. In Deep Security Manager, click **Computers** and find one of your relays in the list of computers. If you're not sure which ones are your relays, at the top, click **Administration**. On the left, expand **Updates** and then click **Relay Management**. In the main pane, expand a relay group to see your relays.
 - b. Double-click the relay in the list of computers.
 - c. In the main pane, click the **Actions** tab.
 - d. Click **Send Policy** to resend the policy.
 - e. Resend the policy to each of your relays.

Enforce TLS 1.2 on just the manager's GUI port (4119)

Only read this section if you were unable to do a full enforcement on the Deep Security Manager and Relays as described previously in ["Enforce TLS 1.2 on Deep Security Manager" on the previous page](#) and ["Enforce TLS 1.2 on the Deep Security Relay" above](#).

This section describes how to set the minimum TLS version to TLS 1.2 on port 4119. Applications that connect on port 4119 are typically web browsers and REST or SOAP API clients. Older Deep Security components that do not support TLS 1.2 can continue to connect to the manager (on port 4120, by default) using TLS 1.0.

Trend Micro Deep Security On-Premise 11.3

1. On Deep Security Manager, enable TLS 1.0 by running this [dsm_c command](#):

```
dsm_c -action settlsprotocol -MinimumTLSProtocol TLSv1
```

Deep Security Manager now accepts TLS 1.0 connections from older agents and applications.

2. Disable early TLS on the manager's GUI port (4119) (it is possible that it's already disabled):
 - a. Open the `configuration.properties` file in the root of the Deep Security Manager installation directory.
 - b. Under `serviceName=`, look for the `protocols=` setting.

This setting defines the protocols that can be used to connect to Deep Security Manager when it is acting as a server to web browsers and REST or SOAP API clients.

- c. If the `protocols=` setting is present, remove it so that only TLS 1.2 is allowed on port 4119.
 - d. Save the file.
3. Restart the Deep Security Manager service.

Test that TLS 1.2 is enforced

1. On a Deep Security component where early TLS 1.2 is enforced, run the following nmap command:

```
nmap --script ssl-enum-ciphers <ds_host> -p <ds_port> -Pn
```

where:

- `<ds_host>` is replaced with the IP address or hostname of the manager or relay
- `<ds_port>` is replaced with the listening port where TLS is being used (4119 for manager, 4122 for the relay, and 4118 for the agent—if manager-initiated activation is used)

The response should only list TLS 1.2. Example response:

Trend Micro Deep Security On-Premise 11.3

```
PORT STATE SERVICE
```

```
443/tcp open https
```

```
| ssl-enum-ciphers:
```

```
| | TLSv1.2:
```

```
| ciphers:
```

```
| TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384 (secp256r1) - A
```

```
| TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256 (secp256r1) - A
```

```
| TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA384 (secp256r1) - A
```

```
| TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256 (secp256r1) - A
```

```
| TLS_RSA_WITH_AES_256_GCM_SHA384 (rsa 2048) - A
```

```
| TLS_RSA_WITH_AES_128_GCM_SHA256 (rsa 2048) - A
```

```
| TLS_RSA_WITH_AES_256_CBC_SHA256 (rsa 2048) - A
```

```
| TLS_RSA_WITH_AES_128_CBC_SHA256 (rsa 2048) - A
```

```
| TLS_RSA_WITH_AES_256_CBC_SHA (rsa 2048) - A
```

```
| TLS_RSA_WITH_AES_128_CBC_SHA (rsa 2048) - A
```

```
| TLS_RSA_WITH_3DES_EDE_CBC_SHA (rsa 2048) - C
```

```
| compressors:
```

Enable early TLS (1.0)

By default, early TLS (1.0) is disabled. You'll need to enable it if you have a *new* installation of Deep Security Manager 11.1 or higher (not an upgrade) and:

- you are using pre-10.0 agents. These only support early TLS. [Go here](#) to see if a 10.0 or higher agent is available for your OSs.
- you are using third-party components that are older and need to use early TLS to communicate with Deep Security Manager.
- you are using a pre-10.0 version of the Deep Security Virtual Appliance (which is no longer supported).

To enable early TLS (1.0), follow the instructions below.

Enable TLS 1.0 on Deep Security Manager and the Deep Security Relay

1. On the Deep Security Manager computer, run this [dsm_c command](#):

```
dsm_c -action settlsprotocol -MinimumTLSProtocol ShowValue
```

A TLS version appears. This is the minimum TLS version that Deep Security Manager currently accepts.

2. Run this `dsm_c` command:

```
dsm_c -action settlsprotocol -MinimumTLSProtocol TLSv1
```

This command sets the minimum TLS version to 1.0.

TLS 1.0 is now re-enabled on your Deep Security Manager.

The Deep Security Manager service is restarted automatically.

Trend Micro Deep Security On-Premise 11.3

3. Resend the policies associated with your relays:

- a. In Deep Security Manager, click **Computers** and find one of your relays in the list of computers. If you're not sure which ones are your relays, at the top, click **Administration** On the left, expand **Updates** and then click **Relay Management**. In the main pane, expand a relay group to see your relays.
- b. Double-click the relay in the list of computers.
- c. In the main pane, click the **Actions** tab.
- d. Click **Send Policy** to resend the policy.
- e. Resend the policy to each of your relays.

TLS 1.0 is now re-enabled on your relays.

Enable TLS 1.0 on the manager's GUI port (4119)

Read this section if you previously enforced TLS 1.2 only on the manager's GUI port (4119) and now want to re-enable early TLS 1.0 on this port.

1. Follow the instructions in "[Enable TLS 1.0 on Deep Security Manager and the Deep Security Relay](#)" on the previous page. This re-enables TLS 1.0 on the GUI port (4119).

Enable TLS 1.0 in deployment scripts

Deep Security Agents and Deep Security Relays can be deployed using [deployment scripts](#). You may need to modify these scripts as follows:

1. If you are deploying onto Windows XP, 2003, or 2008, remove these lines from the deployment script:

```
#requires -version 4.0
```

```
[Net.ServicePointManager]::SecurityProtocol = [Net.SecurityProtocolType]::Tls12;
```


Trend Micro Deep Security On-Premise 11.3

Windows XP, 2003, and 2008 do not support PowerShell 4.0, which is required for TLS 1.2.

2. If you are deploying onto Red Hat Enterprise Linux 6, remove this tag from the deployment script:

```
--tls1.2
```

Red Hat Enterprise Linux 6 uses curl 7.19 by default which does not support TLS 1.2.

3. If you are deploying onto any other supported operating system, leave the deployment scripts as they are.

Determine whether TLS 1.2 is enforced

If you're not sure whether TLS 1.2 is enforced on Deep Security Manager, follow the instructions below to find out.

1. On the Deep Security Manager computer, open a command prompt and run the following [dsm_c command](#):

```
dsm_c -action settlsprotocol -MinimumTLSProtocol ShowValue
```

The minimum TLS protocol accepted by the manager is displayed. If it shows TLS 1.2, then TLS 1.2 is enforced. If it shows TLS 1.0, then early TLS is allowed and TLS 1.2 is not enforced.

Determining whether TLS 1.2 is enforced on the relay is harder. If you pushed out your TLS settings to the relay through policy according to ["Enforce TLS 1.2 on the Deep Security Relay" on page 1409](#) or ["Enable TLS 1.0 on Deep Security Manager and the Deep Security Relay" on page 1412](#), then those TLS settings apply to the relay. If you did not push out TLS settings through policy, then the relay's default TLS settings apply. The relay's default settings depend on its version: if you're using an 11.1 or higher relay, then TLS 1.2 is enforced by default. For pre-11.1 relays, TLS 1.2 is not enforced by default.

Guidelines for deploying agents, virtual appliances, and relays after TLS 1.2 is enforced

This section discusses special considerations when deploying agents, virtual appliances and relays when TLS 1.2 is enforced. If you [enabled early TLS \(1.0\)](#), then there are no special considerations, and you do not need to read this section.

Topics in this section:

- ["Guidelines for deploying agents, virtual appliances, and relays when TLS 1.2 is enforced" below](#)
- ["Guidelines for using deployment scripts when TLS 1.2 is enforced" below](#)

Guidelines for deploying agents, virtual appliances, and relays when TLS 1.2 is enforced

- You must deploy 10.0 or higher agents, virtual appliances, and relays. Only 10.0 or higher agents and relays support TLS 1.2.
- If you need to deploy a 9.6 or earlier agent or relay you must [enable early TLS \(1.0\)](#).

Guidelines for using deployment scripts when TLS 1.2 is enforced

If TLS 1.2 is enforced, you can install 10.0 or higher agents and relays using [deployment scripts](#). Below are some guidelines to ensure the deployment scripts work:

1. If you are deploying an agent or relay onto Windows computers, use PowerShell 4.0 or higher, which supports TLS 1.2.
2. If you are deploying an agent or relay onto Linux, use curl 7.34.0 or higher, which supports TLS 1.2.
3. If you are deploying onto Windows XP, 2003, or 2008

OR

If you are deploying onto Red Hat Enterprise Linux 6

...these OSs don't support TLS 1.2 and you must ["Enable early TLS \(1.0\)" on page 1412](#) and [modify your deployment scripts](#).

Upgrade the Deep Security cryptographic algorithm

Deep Security 9.6 SP1 and earlier use RSA-1024 and SHA-1 to secure communication between the Deep Security Manager and Deep Security Agents. By default, Deep Security 10.0 or later uses RSA-2048 and DSA-256, which are more secure algorithms.

A new installation of Deep Security 10.0 or later will use RSA-2048 and DSA-256 but if you upgrade from an earlier version to Deep Security 10.0 or later, it will continue to use the earlier cryptographic algorithms unless you upgrade them separately.

This article describes how to upgrade the algorithms after upgrading to Deep Security 10.0 or later. After you change the settings as described in this article, the Deep Security Manager generates new certificates for itself and all managed agents. When agents connect to the Deep Security Manager again, the manager sends new certificates to the agents.

Upgrade the algorithm on Windows

1. Use the Services window of the Microsoft Management Console to stop the "Trend Micro Deep Security Manager" service.
2. In the Windows command line, go to the Deep Security Manager's working folder, for example, `C:\Program Files\Trend Micro\Deep Security Manager`.
3. Use the `dsm_c` command with parameters to change to the new settings. For example:

```
dsm_c -action changesetting -name settings.security.defaultSignatureAlg -value "SHA256withRSA"
```

```
dsm_c -action changesetting -name settings.security.defaultKeyLength -value "2048"
```

```
dsm_c -action changesetting -name settings.security.forceCertificateUpdate -value "true"
```

4. If you don't see any errors, restart the Trend Micro Deep Security Manager service.

Upgrade the algorithm on Linux

1. At the command line, go to the directory where the Deep Security Manager service is running and stop the service by entering:

```
service dsm_s stop
```

2. In the Linux command line, go to the Deep Security Manager's working folder, for example, `/opt/dsm`.
3. Use the `dsm_c` command with parameters to change to the new settings. For example:

```
./dsm_c -action changesetting -name settings.security.defaultSignatureAlg -value "SHA256withRSA"
```

```
./dsm_c -action changesetting -name settings.security.defaultKeyLength -value "2048"
```

```
./dsm_c -action changesetting -name settings.security.forceCertificateUpdate -value "true"
```

4. If you don't see any errors, restart the Trend Micro Deep Security Manager service.

Upgrade the algorithm in a multi-node environment

If you are running Deep Security Manager on multiple nodes, execute the `dsm_c` commands (described above) on one of the nodes, and then manually restart the "Trend Micro Deep Security Manager" service on each of the other nodes to make the changes take effect there.

Upgrade the algorithm in a multi-tenant environment

In Deep Security 10.0, the algorithm settings are independent for each tenant. You will need to update the settings for each tenant by appending the tenant name (using `-tenantname`) or tenant ID (using `-tenantid`) on the `dsm_c` command. For example, to change the settings for a tenant whose ID is 5:

```
dsm_c -action changesetting -name settings.security.defaultSignatureAlg -value "SHA256withRSA" -tenantid 5
```

Trend Micro Deep Security On-Premise 11.3

```
dsm_c -action changesetting -name settings.security.defaultKeyLength -value "2048" -tenantid 5
```

```
dsm_c -action changesetting -name settings.security.forceCertificateUpdate -value "true" -tenantid 5
```

Migrate a Microsoft SQL Server Express database to Enterprise

Microsoft SQL Server Express is supported in very limited deployments (see ["Microsoft SQL Server Express considerations" on page 132](#) for details). If you are using a Microsoft SQL Server Express database but find its limitations too constricting, you can migrate it to a [supported database](#).

1. Stop the Deep Security Manager service so that it stops writing to the database.

Deep Security Agents will continue to apply their current protection policies while the manager is stopped. Events will be kept and transmitted when Deep Security Manager returns online.

2. Back up the database(s).
3. Back up the database connection settings file:

```
[Deep Security install directory]/webclient/webapps/ROOT/WEB-INF/dsm.properties
```

4. Move the database to the new database engine. Restore the backup.
5. Edit dsm.properties to connect to the migrated database:

```
database.SqlServer.user
```

```
database.name
```

```
database.SqlServer.instance
```

```
database.SqlServer.password
```

Trend Micro Deep Security On-Premise 11.3

```
database.type
```

```
database.SqlServer.server
```

If using the default instance, you can delete the `database.SqlServer.instance` setting.

You can enter a plain text password for `database.SqlServer.password`; Deep Security Manager will encrypt it when the service starts, like this:

```
database.SqlServer.password=!CRYPT!20DE3D96312D6803A53C0D1C691FE6DEB7476104C0A
```

6. Restart the Deep Security Manager service.
7. To verify that it has successfully reconnected to the database, log in to Deep Security Manager.

Existing protected computers and event logs should appear. As new events such as administrator logins or policy changes occur, they should be added. If not, verify that you have granted permissions to the database user account on the new database server.

Uninstall Deep Security

When you manually uninstall an activated agent or relay from a computer, the computer doesn't notify Deep Security Manager that the software has been uninstalled. On the Computers page in Deep Security Manager, the computer's status will be "Managed (Offline)" or similar, depending on the context. To avoid this, on Deep Security Manager, either:

- Deactivate the agent or relay *before* you uninstall it, or
- Delete the computer from the list *after* you uninstall

Uninstall Deep Security Relay

A Deep Security Relay is an agent where you have enabled the relay feature, so in order to remove the relay, you must uninstall the agent software.

Uninstall a relay (Windows)

Note: Before updating or uninstalling a Deep Security agent or relay on Windows, you must disable agent self-protection. To do this, on the Deep Security Manager, go to **Computer editor**¹ > **Settings** > **General**. In **Agent Self Protection**, and then either deselect **Prevent local end-users from uninstalling, stopping, or otherwise modifying the Agent** or enter a password for local override.

From the Windows Control Panel, select **Add/Remove Programs**. Double-click **Trend Micro Deep Security Agent**, and click **Remove**.

Alternatively, you can uninstall from the command line:

```
msiexec /x <package name including extension>
```

For a silent uninstall, add `/quiet`.

Uninstall a relay (Linux)

To completely remove the relay and any configuration files it created on a platform that uses the Red Hat package manager (rpm), such as CentOS, Amazon Linux, Oracle Linux, SUSE, or Cloud Linux, enter the command:

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

```
# sudo rpm -ev ds_agent
Stopping ds_agent: [ OK ]
Unloading dsa_filter module [ OK ]
```

If iptables was enabled prior to the installation of the relay-enabled agent, it will be re-enabled when the relay-enabled agent is uninstalled.

Note: Remember to remove the relay-enabled agent from Deep Security Manager's list of managed computers, and to remove it from the relay group.

Uninstall Deep Security Agent

Uninstall an agent (Windows)

Note: Before updating or uninstalling a Deep Security Agent or Relay on Windows, you must disable agent self-protection. To do this, on the Deep Security Manager, go to **Computer editor**¹ > **Settings** > **General**. In **Agent Self Protection**, and then either deselect **Prevent local end-users from uninstalling, stopping, or otherwise modifying the Agent** or enter a password for local override.

1. Deactivate the agent using the Deep Security Manager by going to the **Computers** page, right-clicking the computer and selecting **Actions** > **Deactivate**.

If you are unable to deactivate the agent because the Deep Security Manager is unable to communicate with the agent, you will need to do the following before continuing to the next step:

```
C:\Program Files\Trend Micro\Deep Security Agent>dsa_control --selfprotect 0
```

¹To open the Computer editor, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).

Trend Micro Deep Security On-Premise 11.3

2. Go to the Control Panel and select **Uninstall a program**. Look for the Trend Micro Deep Security Agent and then select **Uninstall**.

Alternatively, you can uninstall from the command line:

```
msiexec /x <package name including extension>
```

For a silent uninstall, add `/quiet`.

Uninstall an agent (Linux)

If your version of Linux provides a graphical package management tool, you can search for the `ds_agent` package and use the tool to remove the package. Otherwise, use the command line instructions below.

To completely remove the agent and any configuration files it created on a platform that uses the Red Hat package manager (rpm), such as CentOS, Amazon Linux, Oracle Linux, SUSE, or Cloud Linux, enter the command:

```
# sudo rpm -ev ds_agent
Stopping ds_agent: [ OK ]
Unloading dsa_filter module [ OK ]
```

If iptables was enabled prior to installing Deep Security Agent, it will be re-enabled when the agent is uninstalled.

If the platform uses Debian package manager (dpkg), such as Debian and Ubuntu, enter the command:

```
$ sudo dpkg -r ds-agent
Removing ds-agent...
Stopping ds_agent: .[OK]
```

Trend Micro Deep Security On-Premise 11.3

Uninstall an agent (Solaris 9 or 10)

Enter the command:

```
pkgrm ds-agent
```

(Note that uninstall may require a reboot.)

Uninstall an agent (Solaris 11)

Enter the command:

```
pkg uninstall ds-agent
```

Uninstall may require a reboot.

Uninstall an agent (AIX)

Enter the command:

```
installp -u ds_agent
```

Uninstall an agent (HP-UX)

Enter the command:

```
swremove ds_agent
```

Uninstall Deep Security Notifier

From the Windows Control Panel, select **Add/Remove Programs**. Double-click **Trend Micro Deep Security Notifier**, and click **Remove**.

To uninstall from the command line:

```
msiexec /x <package name including extension>
```

For a silent uninstall, add `/quiet`.

Uninstall Deep Security Manager

Uninstall the manager (Windows)

From the Windows Start Menu, go to **Trend Micro > Trend Micro Deep Security Manager Uninstaller**, and follow the wizard steps to complete the uninstallation.

To initiate the same Windows GUI uninstall procedure from the command line, go to the installation folder and enter:

```
<installation folder>\Uninstall.exe
```

For a silent uninstall from the command line (without the Windows GUI prompts), add `-q`.

```
<installation folder>\Uninstall.exe -q
```

During a silent uninstall via command line, the configuration files are kept so that if you re-install in future, the installer repairs or upgrades using existing settings, without asking you to input them again.

Uninstall the manager (Linux)

To uninstall via command line, go to the installation folder and enter:

```
sudo ./uninstall
```

For a silent uninstall, add `-q`.

During a silent uninstall via command line, by default, the configuration files are kept so that if you re-install in future, the installer repairs upgrades using existing settings, without asking you to input them again.

If you selected not to keep the configuration files during the uninstallation, and you later want to reinstall Deep Security Manager, you should perform a manual clean-up before reinstalling. To remove the Deep Security Manager installation directory enter the command:

```
sudo rm -rf <installation location>
```

The default installation location is `/opt/dsm`.

Uninstall Deep Security from your NSX environment

Uninstalling Deep Security from your NSX environment removes the Deep Security Virtual Appliance from NSX and all the related history from Deep Security Manager.


Topics on this page:

- ["Uninstall Deep Security from NSX automatically" on the next page](#)
- ["Uninstall Deep Security from NSX manually" on page 1430](#)

Uninstall Deep Security from NSX automatically


1. In Deep Security Manager, go to **Computers**.
2. In the navigation tree on the left, right-click the vCenter and select **Remove VMware vCenter**.
3. Select one of these options:
 - **Remove VMware vCenter and all subordinate computers/groups from DSM:** Removes vCenter and all records of the VMs including the Deep Security policies and rules assigned to them.
 - **Remove VMware vCenter but retain computer data and Group hierarchy:** Removes vCenter but retains its hierarchical structure and the records of the VMs including the Deep Security Policies and Rules assigned to them.
 - **Remove VMware vCenter, retain computer data, but flatten hierarchy:** Removes vCenter but retains the records of the VMs including the Deep Security policies and rules assigned to them. The hierarchical structure of the vCenter is flattened to a single group.

Trend Micro Deep Security On-Premise 11.3



Trend Micro Deep Security On-Premise 11.3

4. After selecting an option, click **Next**.



Trend Micro Deep Security On-Premise 11.3

5. Click **Next** again to proceed with the removal.

Assuming you selected the first option, **Remove VMware vCenter and all subordinate computers/groups from DSM**, all Deep Security Virtual Appliances and NSX policies are removed automatically from your NSX environment.

A success message is displayed indicating `VMware vCenter was removed successfully`.

Note: If Deep Security Manager has lost connectivity with the NSX Manager, you may see an error stating `Unable to remove Deep Security from VMware`. If this error occurs, you must remove Deep Security service from NSX Manager manually. See [the next section](#) for details.

Uninstall Deep Security from NSX manually

If you tried to remove vCenter from Deep Security Manager using the steps in "[Uninstall Deep Security from NSX automatically](#)" on [page 1426](#), and you saw an error stating `Unable to remove Deep Security from VMware`, it may be because Deep Security Manager lost connectivity with NSX Manager. If this error occurs, you must remove Deep Security from NSX Manager manually. The steps are:

- "[Step 1: Remove the NSX Manager from Deep Security Manager](#)" below
- "[Step 2: Remove the Trend Micro service on NSX Manager](#)" on the next page


Step 1: Remove the NSX Manager from Deep Security Manager

1. In Deep Security Manager, go to **Computers**.
2. In the navigation tree on the left, right-click the vCenter and select **Properties**.
3. On the **NSX Manager** tab, click **Remove NSX Manager**.
4. Click **OK**.

Step 2: Remove the Trend Micro service on NSX Manager

1. In the vSphere Web Client, go to **Home > Networking and Security > Service Composer > Security Policies**.


Delete the **Deep Security** security policies.



2. Go to **Home > Networking and Security > Installation > Service Deployments**.


Delete the **Trend Micro Deep Security** service deployment.

Trend Micro Deep Security On-Premise 11.3



3. Go to Home > Networking and Security > Service Definitions > Service Managers.

Select Deep Security Service Manager and click the pencil icon. Deselect Operational State.



Trend Micro Deep Security On-Premise 11.3

Edit Service Manager

Name: * Deep Security Service Manager

Description: Service manager for DS services.

Administration URL:

Base API URL: https://[redacted]/rest

Credentials

Name: T0

Password:

Retype Password:

Thumbprint:

Vendor Details

Vendor ID:


Vendor Name:

☐ Operational State

OK Cancel


4. Go to **Home > Networking and Security > Service Definitions > Services**.

Click **Trend Micro Deep Security** and click the pencil icon.




5. In the left navigation pane, click **Service Instances**, and then click **Trend Micro Deep Security-GlobalInstance**, also on the left.

In the main pane, select **Default (EBT)** and click **Delete** to remove the service profile.





6. In the left navigation pane, click **Service Instances**.

In the main pane, click **Trend Micro Deep Security-GlobalInstance** and click **Delete** to remove the service instance.



7. Select the **Trend Micro Deep Security** service definition and click the delete icon at the very top to remove it.





You have now manually removed Deep Security from your NSX environment.

Automate offline computer removal with inactive agent cleanup

If your Deep Security deployment has a large number of offline computers not communicating with the Deep Security Manager, first try using a connector (see ["Add AWS cloud accounts" on page 455](#) or ["Add a Microsoft Azure account to Deep Security" on page 477](#)). When you use a connector, the complete life cycle of your computers is managed automatically, meaning that computers deleted from your cloud accounts are also automatically removed from Deep Security. If you can't use a connector in your environment, you can automate the removal of inactive computers using **inactive agent cleanup**. Inactive agent cleanup will check hourly for computers that have been offline and inactive for a specified period of time (from 2 weeks to 12 months) and remove them.

Note: Inactive agent cleanup will remove a maximum of 1000 offline computers at each hourly check. If there are more offline computers than this, 1000 will be removed at each consecutive check until all of the offline computers have been removed.

After enabling inactive agent cleanup, you can also

- ["Ensure computers that are offline for extended periods of time remain protected with Deep Security" below](#) (optional but recommended).
- ["Set an override to prevent specific computers from being removed" on the next page](#) (optional).
- ["Check the audit trail for computers removed by an inactive cleanup job" on the next page](#).

Note: Inactive agent cleanup does not remove offline computers that have been added by a cloud connector.

Enable inactive agent cleanup

1. Go to the **Administration** page.
2. Under **System Settings > Agents > Inactive Agent Cleanup**, select **Delete Agents that have been inactive for**.
3. From the list, select the period that a computer must be inactive before being removed.
4. ["Ensure computers that are offline for extended periods of time remain protected with Deep Security" below](#) (optional but recommended).
5. Click **Save**.

Ensure computers that are offline for extended periods of time remain protected with Deep Security

If you have offline computers that are active but communicate irregularly with the Deep Security Manager, inactive agent cleanup will remove them if they don't communicate within the period of inactivity you defined. To ensure that these computers reconnect to Deep Security Manager, we recommend enabling both **Agent-Initiated Activation** and **Reactivate unknown Agents**. To do so, under **System Settings > Agents > Agent Initiated Activation**, first select **Allow Agent-Initiated Activation** and then select **Reactivate Unknown Agents**.

Note: When a removed computer reconnects, it will not have a policy, and will be added as a new computer. Any direct links to the computer will be removed from the Deep Security Manager event data.

Tip: You can automatically assign a policy assigned to a computer upon agent-initiated activation with an [event-based task](#).

Set an override to prevent specific computers from being removed

You can set an override at the computer or policy level to explicitly prevent computers from being removed by inactive agent cleanup.

To set an override

1. Open the **Computer or Policy editor**¹ for the computer or policy you want to set an override on.
2. Go to **Settings > General**.
3. Under **Inactive Agent Cleanup Override**, select **Yes**.
4. Click **Save**.

Check the audit trail for computers removed by an inactive cleanup job

When an inactive agent cleanup job runs, system events will be generated that you can use to track removed computers.

You'll need to check the following system events:

¹You can change these settings for a policy or for a specific computer. To change the settings for a policy, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details). To change the settings for a computer, go to the Computers page and double-click the computer that you want to edit (or select the computer and click Details).


Trend Micro Deep Security On-Premise 11.3

- ["2953 - Inactive Agent Cleanup Completed Successfully" on the next page](#)
- ["251 - Computer Deleted" on the next page](#)
- ["716 - Reactivation Attempted by Unknown Agent" on the next page](#) (if 'Reactivate Unknown Agents' is enabled)

Search system events

To view the system events generated by an inactive agent cleanup job, you need to create a search that filters for them:

1. Go to the **Events and Reports** page.
2. In the top-right corner, click the Search field list and select **Open Advanced Search**.



3. For the **Period**, select **Custom Range** from the list.
4. For **From**, enter the date and time just before the inactive agent cleanup job was first run. For **To**, enter the date and time just after the cleanup job finished.
5. For the **Search**, select **Event ID** and **In**, and then enter **2953, 251**. You can optionally enter **716** and any of the event IDs (**130, 790, 350, 250**) associated with computer reactivation.

This will display all the system events generated by an inactive agent cleanup job. You can sort the events by time, event ID or event name by clicking on the corresponding column. You can then double-click an event to get more information about it, as detailed below.

System event details

2953 - Inactive Agent Cleanup Completed Successfully

This event is generated when the inactive agent cleanup job runs and successfully removes computers. The description for this event will tell you how many computers were removed.

Note: If more than one check is needed to remove all computers, a separate system event will be generated for each check.

251 - Computer Deleted

In addition to the 'Inactive Agent Cleanup Completed Successfully' event, a separate 'Computer Deleted' event is generated for each computer that was removed.

716 - Reactivation Attempted by Unknown Agent

If **Reactivate Unknown Agents** is enabled, this event will be generated for an activated computer that was removed when it attempts to reconnect to the Deep Security Manager. Each reactivated computer will also generate the following system events:

- **130** - Credentials Generated
- **790** - Agent-Initiated Activation Requested
- **350** - Policy Created (if you've enabled an event-based task that assigns a policy)
- **250** - Computer Created
or
252 - Computer Updated

FAQs

Deep Security release strategy and life cycle policy

Trend Micro provides two types of Deep Security releases:

- Major releases: Released annually, major releases provide new features, bug fixes, and feature enhancements, and include long-term support.
- Feature releases: Released between major releases, feature releases provide early access to new features. (For more information, see ["Feature releases" on page 72.](#)) Feature releases include shorter support periods. Feature release functionality is cumulative and is ultimately rolled into the next major release.

You might choose to obtain major releases because they are more compatible with longer adoption cycles, and you value sustainability over early adoption of new features. However, if new features are more critical to your immediate requirements, you can obtain feature releases before the next major release becomes available.

Topics on this page:

- ["Support milestones for major releases" on the next page](#)
- ["Major release support services" on the next page](#)
- ["Agent platform support policy" on page 1445](#)

Support milestones for major releases

The following table lists the life cycle milestones for major releases and indicates their timing relative to the initial availability of the release.

Life cycle milestone	Timing (Global)
General Availability (GA)	GA (Annually)
End of standard support (Only extended support is subsequently available.)	GA + 3 years
End of life (End of extended support.)	GA + 4 years

Trend Micro publishes a [list of end-of-life products](#).

Major release support services

The following table indicates which support items are available during the life cycle of Deep Security major releases.

Support item	Standard support	Extended support
Small enhancements (no change to core functionality)	✓	
Linux kernel updates	✓	On request
General bug fixes	✓	
Critical bug fixes (system crash or hang, or loss of major functionality)	✓	✓

Trend Micro Deep Security On-Premise 11.3

Support item	Standard support	Extended support
Critical and high vulnerability fixes	✓	✓
Medium and low vulnerability fixes	✓	
Anti-Malware pattern updates	✓	✓
Intrusion prevention system, integrity monitoring, and log inspection rules updates	✓	✓
Support for Agents and Deep Security Manager on new versions of supported operating systems	✓	

For a list of support items that are provided for feature releases, see ["Feature releases" on page 72](#).

Agent platform support policy

Deep Security Agent software is released several times a year as described in the release policy [found above](#).

Agent platforms (operating systems) are supported according to the policy below. We recognize that in some cases you must commit to platforms for many years. This policy is designed to provide predictability when you deploy Deep Security in these environments.

Agent platform support policy:

- The agent is supported on a large range of platforms, as shown in the ["Agent platform support table" on page 80](#).
- The support duration of any individual release of agent software is determined by the [Deep Security release life cycle and support policy](#). For example, you'll receive three years of standard support and four years of extended support for major releases of the agent (10.0, 11.0, and so on). In cases where you plan to use an OS platform for an extended period of time,

Trend Micro Deep Security On-Premise 11.3

you must also plan to upgrade the agent software on a regular basis to stay within the support life cycle for any specific Deep Security software release. In cases where an older agent is recommended for a given platform, this agent will be considered a part of the overall solution and takes on the support dates for the release in which it is contained. See the bullet below for details.

- Platforms continue to be supported until at least the OS vendor's end-of-extended-support date. Where interest dictates, Trend Micro extends support significantly beyond this date.
- To ensure that you have the latest performance and security updates from your OS vendor, Trend Micro strongly encourages you to move to the latest version of the OS for which an agent is available.
- We strive to release a new version of the Deep Security Agent for all supported platforms. However, in some cases we recommend the use of a previous release of the agent to provide coverage for older platforms. For example, with Deep Security 11.0, the latest agent for Windows 2000 is Deep Security Agent 9.6. This 9.6 agent becomes part of the overall 11.0 Deep Security solution and takes on the support dates for the release in which it is contained.
- You'll always receive advance warning if we end support for a platform, and we'll never shorten the support life cycle of a software release post-General Availability (GA).*

** Once a platform is no longer supported by the OS vendor, there is a risk that a technical issue arises that cannot be fixed without the support of the OS vendor. If this situation occurs, Trend Micro will communicate the limitation to you immediately. Note that this situation may result in loss of functionality. We will do our best to deal with any technical issues if they arise.*

Why does my Windows machine lose network connectivity when I turn on protection?

A Windows machine will lose connectivity for a brief period of time during the network driver installation while the Deep Security Agent installs a network driver to examine traffic. This only happens the *first* time a policy is applied that includes one of the following:

- Web reputation
- Firewall
- Intrusion prevention


A Windows machine uses the same driver is used for all three protection modules listed above. Turning on web reputation, firewall or intrusion prevention after one of those features already turned on will not cause another network blip. You may see a similar interruption in network connectivity when the agent is upgraded (as the driver may also need to be upgraded).

How do I get news about Deep Security?

Deep Security publishes a news feed to inform you of upcoming events, emerging threat trends, product updates, and tips to improve your Deep Security deployment.

You can access the news feed by clicking **News** at the top of the Deep Security Manager:

Trend Micro Deep Security On-Premise 11.3



You can also access the news feed in an RSS and Atom feed reader by subscribing to:

<https://news.deepsecurity.trendmicro.com/news.atom>

AWS GovCloud (US) support

There are two ways that Deep Security provides [AWS GovCloud \(US\)](#) support:

- You can use the Trend Micro Deep Security AMI (Per Protected Instance Hour or BYOL license type) that is available from the AWS GovCloud Marketplace. The deployment instructions for the AWS GovCloud (US) region are the same as any other region. See [Getting started with Deep Security AMI from AWS Marketplace](#).
- You can install the enterprise version of the Deep Security software on an AWS instance running in the AWS GovCloud (US) region.

Note: Deep Security as a Service does not support GovCloud. Computers on the AWS GovCloud must comply with user and data transmission restrictions as specified by United States of America International Traffic in Arms Regulations (ITAR). Because

Trend Micro Deep Security On-Premise 11.3

the Deep Security as a Service operating model requires the transmission of data outside of the AWS GovCloud, using it to manage computers in the GovCloud would break this compliance.

Protecting GovCloud instances using a manager in a commercial AWS instance

Warning: Be aware that if your Deep Security Manager is outside of the AWS GovCloud, using it to manage computers in the GovCloud would break ITAR compliance.

If your Deep Security Manager is in a commercial AWS instance and you want to use it to protect GovCloud instances, you cannot use the cloud connector provided in the Deep Security Manager console to add the instances. If Deep Security Manager is running in a special region (like GovCloud), it can connect to that region and also connect to instances in commercial AWS regions. But if Deep Security Manager is in a commercial region, it can connect to all commercial AWS regions but not special regions like GovCloud.

If you want to add a special region connector (like GovCloud) into a Deep Security Manager running in commercial AWS, you will need to use the Deep Security API to do so and supply the `seedRegion` argument to tell the Deep Security Manager that it's connecting outside of commercial AWS. For information on using the API, see ["Use the Deep Security API to automate tasks" on page 417](#).

How can I minimize heartbeat alerts for offline environments in an AWS Elastic Beanstalk environment?

AWS Elastic Beanstalk allows you to create multiple environments so that you can run different versions of an application at the same time. These environments usually include a production and development environment and often the development

Trend Micro Deep Security On-Premise 11.3

environment is powered down at night. When the development environment is brought back online in the morning, Deep Security will generate alerts related to communication problems for the period of time that it was offline. Although these alerts are actually false from your perspective, they are legitimate alerts from the perspective of Deep Security because an alert is generated whenever a specified number of heartbeats is missed.

You can minimize these heartbeat-related alerts or even prevent them from being generated for environments that you know will be offline for a period of time every day by creating a policy with specific heartbeat settings and applying that policy to the servers in those partially offline environments.

1. Go to the **Policies** tab in the main Deep Security Manager window.
2. Create a new policy or edit an existing one.
3. Click the **Settings** tab in the **Policy editor**¹ and go to the **Computer** tab.
4. Change one or both of the **Heartbeat Interval** and **Number of Heartbeats that can be missed before an alert is raised** setting to numbers that take into account the number of hours your Elastic Beanstalk environment will be offline.
For example, if you know that a server will be offline for 12 hours a day and the Heartbeat Interval is set at 10 minutes, you could change the Number of Heartbeats that can be missed before an alert is raised setting to unlimited to never get an alert or you could increase the Heartbeat Interval to something greater than 10 to get fewer alerts.
5. Click **Save** and apply the policy to all relevant servers.

For more information on using Deep Security in an AWS Elastic Beanstalk environment, you can watch the Trend Micro webinar [Deploying Scalable and Secure Web Apps with AWS Elastic Beanstalk and Deep Security](#).

¹To open the Policy editor, go to the Policies page and double-click the policy that you want to edit (or select the policy and click Details).

Why can't I add my Azure server using the Azure cloud connector?

If an Azure server loses connectivity to the Azure metadata service, the Deep Security Manager will no longer be able to identify it as an Azure server and you will be unable to add it using the Azure cloud connector.

This situation can happen if the server's public or private IP address is changed outside of the Azure console. The Azure server relies on DHCP to communicate with the metadata service and changing the IP outside of the console disables DHCP.

Microsoft recommends against changing the Azure VM's IP address from within its operating system, unless necessary, such as when assigning multiple IP addresses to a Windows VM. For details, see [this Azure article](#).

To check if your Azure server is able to connect to the Azure metadata service, run the [Detect Windows Azure Virtual Machine](#) PowerShell script from the Microsoft Script Center.

Why can't I view all of the VMs in an Azure subscription in Deep Security?

If not all of the virtual machine resources in an Azure subscription are being displayed on the Computers page of Deep Security Manager, this could be because they were deployed using the Azure deployment model Resource Manager. All resources are deployed using this model unless you select **Classic** from the **Select a deployment model** list.

Not all VMs are displayed because older versions of the Deep Security Manager use the [Service Management API](#) provided by the classic Azure deployment model (the Service Management model) to connect to Azure virtual machines so it can only enumerate VMs deployed with the Classic model.

To see both Classic or Resource Manager VMs, upgrade your cloud connector. For more information, see "[Why should I upgrade to the new Azure Resource Manager connection functionality?](#)" on page 482.

Note: If you are unable to upgrade your Resource Manager servers as per the article above, you can still protect them by using the deployment script on the VM and letting the activation create a new computer object outside of the connector.

Troubleshooting

"Activation Failed" agent status

When activating or re-activating a Deep Security Agent, if you receive an "Activation Failed" error message, see:

- [Deep Security Manager \(DSM\) imported via vCenter shows "Activation Failed \(Duplicate Computer\)".](#)
- [Event ID 705: Activation Failed appears when activating the Deep Security Agent \(DSA\).](#)

"Offline" agent

A computer [status](#) of "Offline" or "Managed (Offline)" means that the Deep Security Manager hasn't communicated with the Deep Security Agent's instance for some time and has exceeded the missed heartbeat threshold. (See ["Configure the heartbeat" on page 344.](#)) The status change can also appear in alerts and events.

Causes

Heartbeat connections can fail because:

Trend Micro Deep Security On-Premise 11.3

- The agent is installed on a workstation or other computer that has been shut down. If you are using Deep Security to protect computers that sometimes get shut down, make sure the policy assigned to those computers does not raise an alert when there is a missed heartbeat. In the policy editor, go to **Settings > General > Number of Heartbeats that can be missed before an alert is raised** and change the setting to "Unlimited".
- Firewall, IPS rules, or security groups block the heartbeat [port number](#)
- Outbound (ephemeral) ports were blocked accidentally. See "[Activation Failed - Blocked port](#)" on page 1280 for troubleshooting tips.
- Bi-directional communication is enabled, but only one direction is allowed or reliable (see "[Configure communication directionality](#)" on page 346)
- Computer is powered off
- Computer has left the [context](#) of the private network
This can occur if roaming endpoints (such as a laptop) cannot connect to the manager at their current location. Guest Wi-Fi, for example, often restricts open ports, and has NAT when traffic goes across the Internet.
- Amazon WorkSpace computer is being powered off, and the heartbeat interval is fast, for example, one minute; in this case, wait until the WorkSpace is fully powered off, and at that point, the status should change from 'Offline' to 'VM Stopped'
- DNS was down, or could not resolve the manager's hostname
- The manager, the agent, or both are under very high system resource load
- The agent process might not be running
- Certificates for [mutual authentication](#) in the SSL or TLS connection have become invalid or revoked (see "[Replace the Deep Security Manager SSL certificate](#)" on page 1035)
- The agent's or manager's system time is incorrect (required by SSL/TLS connections)
- Deep Security [rule update](#) is not yet complete, temporarily interrupting connectivity

Trend Micro Deep Security On-Premise 11.3

- On AWS EC2, ICMP traffic is required, but is blocked

Tip: If you are using manager-initiated or bi-directional communication, and are having communication issues, we strongly recommend that you change to agent-initiated activation (see ["Use agent-initiated communication with cloud accounts" on page 350](#)).

To troubleshoot the error, verify that the agent is running, and then that it can communicate with the manager.

Verify that the agent is running

On the computer with the agent, verify that the Trend Micro Deep Security Agent service is running. Method varies by operating system.

- On Windows, open the Microsoft Windows Services Console (services.msc) or Task Manager. Look for the service named ds_agent.
- On Linux, open a terminal and enter the command for a process listing. Look for the service named ds_agent or ds-agent, such as:

```
sudo ps -aux | grep ds_agent
```

```
sudo service ds_agent status
```

Verify DNS

If agents connect to the manager via its domain name or hostname, not its IP address, test the DNS resolution:

```
nslookup [manager domain name]
```

DNS service must be reliable.

If the test fails, verify that the agent is using the correct DNS proxy or server (internal domain names can't be resolved by a public DNS server such as Google or your ISP). If a name such as dsm.example.com cannot be resolved into its IP address, communication will fail, even though correct routes and firewall policies exist for the IP address.

If the computer uses DHCP, in the computer or policy settings, in the **Advanced Network Engine** area, you might need to enable **Force Allow DHCP DNS**(see "[Network engine settings](#)" on page 549).

Allow outbound ports (agent-initiated heartbeat)

Telnet to [required port numbers](#) on the manager to verify that a route exists, and the port is open:

```
telnet [manager IP]:4120
```

Tip: Telnet success proves most of the same things as a ping: that a route and correct firewall policy exist, and that Ethernet frame sizes are correct. (Ping is disabled on computers that use the default security policy for the manager. Networks sometimes block ICMP ping and traceroute to block attackers' reconnaissance scans. So usually, you can't ping the manager to test.)

If telnet fails, trace the route to discover which point on the network is interrupting connectivity.

- On Linux, enter the command:

```
traceroute [agent IP]
```

- On Windows, enter the command:

```
tracert [agent IP]
```

Trend Micro Deep Security On-Premise 11.3

Adjust firewall policies, routes, NAT port forwarding, or all three to correct the problem. Verify both network and host-based firewalls, such as Windows Firewall and Linux iptables. For an AWS EC2 instance, see Amazon's documentation on [Amazon EC2 Security Groups for Linux Instances](#) or [Amazon EC2 Security Groups for Windows Instances](#). For an Azure VM instance, see Microsoft's Azure documentation on [modifying a Network Security Group](#).

If connectivity tests from the agent to the manager succeed, then next you must test connectivity in the other direction. (Firewalls and routers often require policy-route pairs to allow connectivity. If only 1 of the 2 required policies or routes exist, then packets will be allowed in one direction but not the other.)

Allow inbound ports (manager-initiated heartbeat)

On the manager, ping the agent and telnet to the heartbeat port number to verify that heartbeat and configuration traffic can reach the agent:

```
ping [agent IP]
```

```
telnet [agent IP]:4118
```

If the ping and telnet fail, use:

```
tracert [agent IP]
```

to discover which point on the network is interrupting connectivity. Adjust firewall policies, routes, NAT port forwarding, or all three to correct the problem.

If IPS or firewall rules are blocking the connection between the agent and the manager, then the manager cannot connect in order to unassign the policy that is causing the problem. To solve this, enter the command on the computer to reset policies on the agent:

```
dsa_control -r
```

Note: You must re-activate the agent after running this command.

Allow ICMP on Amazon AWS EC2 instances

In the AWS cloud, routers require ICMP type 3 code 4. If this traffic is blocked, connectivity between agents and the manager may be interrupted.

You can force allow this traffic in Deep Security. Either create a firewall policy with a force allow, or in the computer or policy settings, in the **Advanced Network Engine** area, enable **Force Allow ICMP type3 code4** (see ["Network engine settings" on page 549](#)).

High CPU usage

On a computer protected by Deep Security Agent, you can use these steps to determine and resolve the cause of high CPU usage.

1. Verify that the Trend Micro Deep Security Agent process (ds_agent.exe on Windows) has unusually high CPU usage.
Method varies by operating system.

Windows: Task Manager

Linux: `top`

2. Verify that the agent is updated to the latest version.
3. Apply the best practices on ["Performance tips for anti-malware" on page 683](#) and ["Performance tips for intrusion prevention" on page 768](#).
4. If you have just enabled application control, wait until the initial baseline ruleset is complete. Time required varies by the number of files on the file system. The CPU usage should decrease.

Trend Micro Deep Security On-Premise 11.3

5. If a recommendation scan is being performed, try running scans during a time when the computer is less busy, or (if the computer is a VM) allocating more vCPUs.
6. Temporarily disable each protection feature (anti-malware etc.), one at a time. Check CPU usage each time to determine if a specific module is the cause.
7. If high CPU usage still continues, try temporarily stopping the agent. Verify that the issue stops when the agent is stopped. If it does, [collect diagnostic information](#) and give it to your support provider.

"Anti-Malware Driver Offline" status with VMware

See [Anti-malware driver offline](#).

Anti-Malware Windows platform update failed

Double-click the error message to display more detailed information. The "Message" in the error event may include:

- ["An incompatible Anti-Malware component from another Trend Micro product" below](#)
- ["An incompatible Anti-Malware component from a third-party product" on the next page](#)
- ["Other/unknown Error" on the next page](#)

An incompatible Anti-Malware component from another Trend Micro product

To solve this error:

1. Uninstall the incompatible Trend Micro product (for example, Office Scan or Endpoint Sensor).
2. Reinstall the Deep Security Agent.

An incompatible Anti-Malware component from a third-party product

To solve this error:

1. Uninstall the third-party product.
2. Reinstall the Deep Security Agent.
3. Add Deep Security to the third-party software's exception list. Contact Trend Micro support if you need assistance.

Other/unknown Error

To solve this error:

1. Uninstall and reinstall the Deep Security Agent.
2. If the error is not resolved, call Trend Micro support for assistance.

Performance issues on an agentless virtual machine

Cause: Limited resources

1. Make sure that Deep Security Virtual Agent resource is reserved from settings.
2. Ensure that the deployment has met the requirements specified in the installation instructions.

Cause: Anti-malware

1. On Deep Security Manager, go to **Computers**.
2. Double-click the protected computer.

3. For **Anti-Malware**, select **Off**.

Cause: Network traffic

- Add scan exclusions for locations that are known to reduce performance without improving security. For details, see [Recommended scan exclusion list for Trend Micro Endpoint products in OfficeScan \(OSCE\)](#).

Note: The thin driver exclusion is case-sensitive.

Cause: Policy

- Change the policy setting for the virtual machine to **None**.

Cause: High CPU

1. Identify which Deep Security Virtual Agent has high CPU usage.
 - Go to the vCenter console, click each Deep Security Virtual Agent and select **Performance** to identify the machine with high CPU usage.
2. Run the hop tool to determine which process is consuming most of the CPU usage.
3. Identify the high CPU process memory consumption.
 - a. Execute the following to check the process memory status: `#cat /proc/$PID/status` (Replace `$PID` with your own PID.)
 - b. Verify that the vmsize is reasonable.
 - c. Export the content to a log file using this command:

```
#cat /proc/$PID/status > /tmp/HighCPUProcessMemory.txt
```

```
#sudo lsof -p $PID > /tmp/HighCPUProcessOpenedFile.t
```

Trend Micro Deep Security On-Premise 11.3

4. Check if the Deep Security Virtual Agent has enough free memory.
 - a. Run the command `cat /proc/meminfo` to identify the Deep Security Virtual Agent system free memory.
 - b. Run the command `cat /proc/meminfo > /tmp/DSVAMemory.txt` to export the content to a log file.

Cause: Security Update

1. Check the connection between the relay and its update source or proxy server.
 - a. Verify if you need to use a proxy server or not.
 - b. Log into the Deep Security, go to **Administration > System Settings > Proxy**, and confirm that the configuration settings are correct.
2. Perform a ping test between the agent and the relay-enabled agent.
3. Make sure that the [relay port number](#) is open by using `telnet [relay IP] [port number]`.
4. Test the DNS to determine if the hostname of the relay can be resolved.
5. Check if any firewalls are blocking the communication and disable them if they are.
6. Unassign the current policy and check if the issue still persists.

Security update connectivity

Verify the connectivity between the relay server and its Active Update source or proxy server.

1. To verify that both a route exists and that the [relay port number](#) is open, enter the command:

```
telnet [relay IP] [port number]
```

If the telnet fails, verify that a route exists and that firewall policies (if any) allow the traffic by pinging or using traceroute. Also verify that the port number is open, and doesn't have a port conflict.

Trend Micro Deep Security On-Premise 11.3

2. To verify that the DNS server can resolve the domain name of the relay, enter the command:

```
nslookup [relay domain name]
```

If the test fails, verify that the agent is using the correct DNS proxy or server (internal domain names can't be resolved by a public DNS server such as Google or your ISP).

If you are using Deep Security as a Service, you might not be using your own relays; instead, you will be using the relays that are built into the service: relay.deepsecurity.trendmicro.com.

3. If you use a proxy server, on Deep Security, confirm that the [proxy settings](#) are correct.
4. To determine if your Deep Security settings are blocking connectivity, unassign the current policy.

SQL Server domain authentication problems

If you experience problems connecting to the SQL Server database when installing Deep Security Manager, follow the instructions below to troubleshoot the problem.

Note: This topic's scope is limited to Windows domain authentication issues. If you are using SQL Server Authentication instead, see "[Prepare a database for Deep Security Manager](#)" on page 122 and review the configuration steps listed in that topic to troubleshoot any problems.

Tip: 'Windows domain authentication' goes by many names: Kerberos authentication, domain authentication, Windows authentication, integrated authentication, and a few others. In this topic, the terms 'Kerberos' and 'Windows domain authentication' are used.

["Step 1: Verify the host name and domain" on the next page](#)

["Step 2: Verify the servicePrincipalName \(SPN\)" on page 1464](#)

["Step 3: Verify the krb5.conf file \(Linux only\)" on page 1478](#)

["Step 4: Verify the system clock " on page 1480](#)

["Step 5: Verify the firewall " on page 1480](#)

Step 1: Verify the host name and domain

You must make sure the **Host name** field is in FQDN format and resolvable by the DNS server:

1. When you run the Deep Security Manager installer and reach the database step, make sure you specify the SQL server's FQDN. Don't input an IP address or NetBIOS host name.

Example of a valid host name: `sqlserver.example.com`

2. Make sure the FQDN is registered and resolvable by the DNS server. To check if the correct host name was configured in the DNS entry, use the `nslookup` command-line utility. This utility can be invoked from any computer on the domain. Enter the following command:

```
nslookup <SQL Server FQDN>
```

where `<SQL_Server_FQDN>` is replaced with the FQDN of the SQL server. If the utility can resolve the provided FQDN successfully, then the DNS entry is configured properly. If the FQDN cannot be resolved, then configure a DNS A record and reverse record that includes the FQDN.

3. Still on the installer's database page, click **Advanced** and make sure you specify the SQL server's full domain name in the **Domain** field. The domain must include one or more dots ("."). Don't input a short domain name or NetBIOS name.

Example of a valid domain name: `example.com`

Trend Micro Deep Security On-Premise 11.3

4. Check if the domain name is in FQDN format using the `nslookup` command-line utility. Enter the following command:

```
nslookup <Domain_Name>
```

where `<Domain_Name>` is replaced with the full domain name of the SQL server. If the utility can resolve the provided domain name, then it is the full domain name.

Note: Database authentication using Microsoft workgroups is not supported by Deep Security Manager 10.2 and later. For Windows domain authentication, you'll need to have installed an Active Directory domain controller, configured a domain, and added the SQL server to this domain. If there is no Active Directory domain infrastructure in your environment, you must use SQL Server Authentication instead. (To use SQL Server Authentication instead of Windows domain authentication, enter the Deep Security Manager database owner's user name and password into the **User name** and **Password** fields on the **Database** page of the manager's installer. Do not input a domain. The omission of a domain name causes SQL Server Authentication to be used. For details, see ["Microsoft SQL Server" on page 124.](#))

Step 2: Verify the servicePrincipalName (SPN)

You must make sure the servicePrincipalName (SPN) is configured correctly in Active Directory.

For Microsoft SQL Server, the SPN is in this format:

```
MSSQLSvc/<SQL_Server_Endpoint_FQDN>
```

```
MSSQLSvc/<SQL_Server_Endpoint_FQDN>:<PORT>
```

To verify that the SPN is correct, run through these tasks. At the end are some step-by-step instructions for specific use cases, references to other documentation, and debugging tips.

["Step 2a: Identify the account \(SID\) running the SQL Server service" on the next page](#)

Trend Micro Deep Security On-Premise 11.3

"Step 2b: Find the account in Active Directory" on page 1467

"Step 2c: Identify which FQDN to use in the SPN " on page 1468

"Step 2d: Identify whether you're using a default instance or named instance " on page 1468

"Case 1: Set the SPN under a local virtual account" on page 1469

"Case 2: Set the SPN under a domain account" on page 1471

"Case 3: Set the SPN under a Managed Service account" on page 1473

"Case 4: Set the SPN for a failover cluster" on page 1475


"SPN references" on page 1477

"SPN debugging tips" on page 1477

Step 2a: Identify the account (SID) running the SQL Server service

The SPN is configured inside the account running the SQL Server service.

To identify which account is running the SQL Server service, use the `services.msc` utility. You see the SQL Server service appear, along with the associated account.



Step 2b: Find the account in Active Directory

Once you know the name of the account running the SQL Server service, you must locate it in Active Directory. The account can be in a few possible locations depending on whether it is a local virtual account, a domain account, or a Managed Service account. The table below outlines these possible locations. You can use the ADSI Editor ([adsiedit.msc](#)) on the Active Directory computer to look for the different folders in Active Directory and find the account.

Account type	Name of account	Location of account in Active Directory	Description
Local virtual account	NT SERVICE\MSSQLSERVER (default instance) NT SERVICE\MSSQL\$InstanceName (named instance)	CN=Computer CN=<Computer_Name>	Services that run under virtual accounts access network resources by using the credentials of the computer account. The default standalone SQL Server service uses this account to start up.
Domain account	A domain user name, for example, SQLServerServiceUser	CN=Users CN=<User_Name>	Services started using this account access the network resources using a domain user's credentials. SQL Server failover clusters require a domain account to run the service. The standalone SQL Server service can also be configured to use a domain account to start up.
Managed Service account	A Managed Service account name, for example SQLServerMSA	CN=Managed Service Account CN=<Account_Name>	Introduced in Windows Server 2008 R2, the Managed Service Account resembles the domain account, but can be used to perform interactive logons. Both the standalone SQL Server service and the SQL Server cluster services can be configured to use a Managed Service account to start up.

Step 2c: Identify which FQDN to use in the SPN

For naming consistency, it is recommended that you set the SPN to the FQDN of the endpoint. The endpoint is the target to which the SQL Server client (Deep Security Manager) connects, and may be an individual SQL Server or a cluster. Consult the table below for details on which FQDN to use.

If the SQL Server installation type is...	Set the SPN to...
Standalone SQL Server	The FQDN of the host where the SQL Server is installed
Failover SQL Server cluster	The FQDN of the SQL Server cluster (individual SQL Server nodes are not the endpoint and should not be used in the FQDN)

Step 2d: Identify whether you're using a default instance or named instance

You must know whether the SQL Server was installed as a default instance or a named instance because the port number and instance name (if one was specified) need to go into the SPN.

- The default instance typically uses port 1433.
- A named instance uses a different port. To determine this port, consult [this webpage](#).

Example: If the FQDN endpoint of the SQL Server service is `sqlserver.example.com` and it is the default instance, then the SPN will be in the format:

```
MSSQLSvc/sqlserver.example.com
```

```
MSSQLSvc/sqlserver.example.com:1433
```

Trend Micro Deep Security On-Premise 11.3

Another example: If the FQDN endpoint of SQL Server service is `sqlserver.example.com` and it is a named instance using port 51635 with an instance name of `DEEPSECURITY`, then the SPN will be in the format:

```
MSSQLSvc/sqlserver.example.com:DEEPSECURITY
```

```
MSSQLSvc/sqlserver.example.com:51635
```

Case 1: Set the SPN under a local virtual account

To set the SPN for a standalone SQL Server that runs under a local virtual account:

1. On the Active Directory computer, open `ADSIEdit.msc`. The ADSI Editor opens.
2. Locate the SQL Server host in **CN=Computers**.
3. Right-click the SQL Server host, and select **Properties**.
4. On the **Attribute Editor** tab, scroll to **servicePrincipalNames** and click the **Edit** button.
5. If the attribute values don't exist, add each one individually using the **Add** button. Click **OK**.

ADSI Edit

File Action View Help

ADSI Edit

- Default naming context [Dio-SQL2014.ad.dsl:
 - DC=ad,DC=dsiab
 - CN=Builtin
 - CN=Computers
 - CN=DIOWIN2016
 - CN=MSSQLSRV** SQL Server Host
 - OU=Domain Controllers
 - CN=ForeignSecurityPrincipals
 - CN=LostAndFound
 - CN=Managed Service Accounts
 - CN=NTDS Quotas
 - CN=Program Data
 - CN=System
 - CN=TPM Devices
 - CN=Users

Attributes:

Attribute	Value
sAMAccountName	MSSQLSRV\$
sAMAccountType	805306369 = (MACHINE_ACCOUNT)
scriptPath	<not set>
secretary	<not set>
securityIdentifier	<not set>
seeAlso	<not set>
serialNumber	<not set>
servicePrincipalName	TERMSRV/MSSQLSRV; TERMSRV/MSSG
shadowExpire	<not set>
shadowFlag	<not set>
shadowInactive	<not set>
shadowLastChange	<not set>
shadowMax	<not set>
shadowMin	<not set>

Edit Filter

OK Cancel Apply Help

Case 2: Set the SPN under a domain account

The SPN configuration is similar to the local virtual account configuration except that the SPN is set in domain account (**CN=Users**) running the SQL Server service.

ADSI Edit

File Action View Help

← → ↻ ↺ ↻ ↻ ? ↻

ADSI Edit

- Default naming context [DIO-ADC.dslab.com]
 - DC=dslab,DC=com
 - CN=Builtin
 - CN=Computers
 - OU=Domain Controllers
 - CN=ForeignSecurityPrincipals
 - CN=LostAndFound
 - CN=Managed Service Accounts
 - CN=NTDS Quotas
 - CN=Program Data
 - CN=System
 - CN=TPM Devices
 - CN=Users**
 - CN=ADFS ServiceAccount
 - CN=Administrator
 - CN=Allowed RODC Password Replicat
 - CN=Cert Publishers
 - CN=Cloneable Domain Controllers
 - CN=Denied RODC Password Replicat
 - CN=DnsAdmins
 - CN=DnsUpdateProxy
 - CN=Domain Admins
 - CN=Domain Computers
 - CN=Domain Controllers
 - CN=Domain Guests

ADSI Edit

Name Class Distinguished Name

CN=SQLServerServiceUser Properties

Attribute Editor Security

Attributes:

Attribute	Value
sAMAccountName	sqlserver
sAMAccountType	805306368 = (NORMAL_USER_ACCOUNT
scriptPath	<not set>
secretary	<not set>
securityIdentifier	<not set>
seeAlso	<not set>
serialNumber	<not set>
servicePrincipalName	MSSQLSvc/SQL2012.dslab.com:1433; MSS
shadowExpire	<not set>
shadowFlag	<not set>
shadowInactive	<not set>
shadowLastChange	<not set>
shadowMax	<not set>
shadowMin	<not set>

< ||| >

Edit Filter

OK Cancel Apply Help

Case 3: Set the SPN under a Managed Service account

The SPN is set in the Managed Service account (**CN=Managed Service Account**) running the SQL Server service.

ADSI Edit

File Action View Help

← → ↗ ✖ 🔄 📄 ? 🖨

ADSI Edit

- Default naming context [DIO-ADC.dslab.com]
 - DC=dslab,DC=com
 - CN=Builtin
 - CN=Computers
 - OU=Domain Controllers
 - CN=ForeignSecurityPrincipals
 - CN=LostAndFound
 - CN=Managed Service Accounts**
 - CN=SQLServerMSA**
 - CN=StandaloneSQL StandaloneSC
 - CN=NTDS Quotas
 - CN=Program Data
 - CN=System
 - CN=TPM Devices
 - CN=Users
 - CN=ADFS ServiceAccount
 - CN=Administrator
 - CN=Allowed RODC Password Rep
 - CN=Cert Publishers
 - CN=Cloneable Domain Controller
 - CN=Denied RODC Password Repli
 - CN=DnsAdmins
 - CN=DnsUpdateProxy
 - CN=Domain Admins
 - CN=Domain Computers

Managed Service Account running SQL Server

CN=SQLServerMSA Properties


Attribute Editor Security

Attributes:

Attribute	Value
secretary	<not set>
securityIdentifier	<not set>
seeAlso	<not set>
serialNumber	<not set>
servicePrincipalName	MSSQLSvc/SQLServer.dslab.com; MSSQLS
shadowExpire	<not set>
shadowFlag	<not set>
shadowInactive	<not set>
shadowLastChange	<not set>
shadowMax	<not set>
shadowMin	<not set>
shadowWarning	<not set>
showInAddressBook	<not set>
showInAdvancedVie...	<not set>

Case 4: Set the SPN for a failover cluster

An SQL Server failover cluster can run under a domain account or a Managed Service account. Refer to ["Case 2: Set the SPN under a domain account" on page 1471](#) or ["Case 3: Set the SPN under a Managed Service account" on page 1473](#) for instructions. Make sure to set the SPN to the FQDN of the SQL *cluster* endpoint, not an individual SQL node.



SPN references

Below are links to Microsoft's official documents about SPN configurations:

[Register a Service Principal Name for Kerberos Connections](#)

[How to Configure an SPN for SQL Server Site Database Servers](#)

[How to: Enable Kerberos Authentication on a SQL Server Failover Cluster](#)

SPN debugging tips


To verify that the correct SPN configuration was set, use the command line tool `setspn` to query for registered SPN entries. The command syntax is:

```
setspn -T <Full_Domain_Name> -F -Q MSSQLSvc/<SQL_Server_Endpoint_FQDN>*
```

where:

- `<Full_Domain_Name>` is replaced with the domain name of your environment.
- `<SQL_Server_Endpoint_FQDN>` is replaced with the FQDN of SQL Server.

For example: Assume that a standalone SQL Server resides at `SQL2012.dslab.com`, and runs under a local virtual account in the domain `dslab.com`. You can use command below to query all registered SPNs that have a prefix of `MSSQLSvc/SQL2012.dslab.com` and see if it is correctly configured.



```

Administrator: Command Prompt

C:\Users\Administrator>setspn -T DSLAB.com -F -Q MSSQLSvc/SQL2012.dslab.com*
Checking forest DC=dslab,DC=com
CN= SQL2012, CN=Computers, DC=dslab, DC=com
    MSSQLSvc/SQL2012.dslab.com:1433
    MSSQLSvc/SQL2012.dslab.com
Existing SPN found!
  
```

SPN entry is found in CN of host (computer) providing the service

From the command result, you can then verify that the SPN has been set and registered in correct LDAP path, and in the account that is running the SQL Server service (in this case, it is the computer account).

Step 3: Verify the krb5.conf file (Linux only)

If you're installing the manager on Linux, you must make sure the `/etc/krb5.conf` exists and contains the correct domain and realm information:

1. Open or create the `/etc/krb5.conf` file in a text editor to configure Kerberos.
2. Provide the following information:

```

[libdefaults]

...

default_realm = <DOMAIN>

...

[realms]

<DOMAIN> = {
  
```

Trend Micro Deep Security On-Premise 11.3

```
kdc = <ACTIVE_DIRECTORY_CONTROLLER_FQDN>

admin_server = <ACTIVE_DIRECTORY_CONTROLLER_FQDN>

}

[domain_realm]

.<DOMAIN_FQDN> = <DOMAIN>

<DOMAIN_FQDN> = <DOMAIN>
```

where <DOMAIN>, <ACTIVE_DIRECTORY_CONTROLLER_FQDN> and <DOMAIN_FQDN> are replaced with your own values.

Example file:

```
[libdefaults]

default_realm = EXAMPLE.COM

default_tkt_etypes = des3-hmac-sha1 des-cbc-crc

default_tgs_etypes = des3-hmac-sha1 des-cbc-crc

dns_lookup_kdc = true

dns_lookup_realm = false


[realms]

EXAMPLE.COM = {

    kdc = kerberos.example.com

    kdc = kerberos-1.example.com
```

Trend Micro Deep Security On-Premise 11.3

```
admin_server = kerberos.example.com  
  
}  
  
[domain_realm]  
  
.example.com = EXAMPLE.COM  
example.com = EXAMPLE.COM  
  
[logging]  
  
kdc = SYSLOG:INFO  
  
admin_server = FILE=/var/kadm5.log
```

3. Save and close the file.

Step 4: Verify the system clock

You must make sure the system clocks on the domain controller, SQL Server, and Deep Security Manager computer are synchronized. With Kerberos, the maximum allowable clock skew is five minutes by default.

Step 5: Verify the firewall

You must make sure the firewall is not blocking the SQL connection. A default SQL Server instance allows connections through port 1433, while a named SQL Server instance uses a port that is selected at random. To find out which port to connect to, the SQL client (Deep Security Manager in this case) queries the available named instances and finds the mapping port by issuing a lookup

Trend Micro Deep Security On-Premise 11.3

request to the SQL Server browser service. The SQL Server browser service runs on port 1434 (UDP). Verify that your firewall configuration allows port 1433 (if you're using a default instance), or 1434 (if you're using a named instance).

Purple screen of death

If you encounter a Purple Screen of Death issue, collect the necessary files and submit them to [Trend Micro Technical Support](#) to determine if the issue is coming from the VMware side or Trend Micro side.

1. Capture a screen shot of the Purple Diagnostic Screen via remote KVM or take a picture of the physical console's Purple Diagnostic Screen prior to reboot.
2. Get the core dump from the VMkernel sent to the ESXi Dump Collector Network Service.
 - a. Log in to the vSphere client and navigate to the Home page.
 - b. Click **Hosts and Clusters** and select the ESXi host.
 - c. Click **Export > Export System Logs**.
 - d. Click **Select all** and choose the log store location to complete the process.
3. Extract the log from the dump using the procedure in this VMware article: [Extracting the log file after an ESX or ESXi host fails with a purple screen error \(1006796\)](#).
4. Gather a vm-support log bundle from the ESXi host by typing "vm-support" in the ESXi command line.

Prevent MTU-related agent communication issues across Amazon Virtual Private Clouds (VPC)

Agents in different VPCs might experience problems when trying to communicate with Deep Security Manager. This could be because the network [maximum transmission unit \(MTU\)](#) supported by Amazon Web Services is 1500 and Deep Security Agent

Trend Micro Deep Security On-Premise 11.3

communication traffic can exceed this, which results in fragmented and dropped packets.

You can prevent this MTU-related communication issue from happening by adding a new firewall rule to all firewall policies. The key settings for this new firewall rule are shown in the image below.

GeneralOptionsAssigned To

General Information

Name:

New Firewall Rule

Description:

Action:

Force Allow

Priority:

0 - Lowest

Packet direction:

Incoming

Frame Type:

IP

☐ Not

Protocol:

ICMP

☐ Not

Packet Source

IP:

Any

☐ Not

MAC:

Any

☐ Not

Port:

Any

☐ Not

Packet Destination

IP:

Any

☐ Not

MAC:

Any

☐ Not

Port:

Any

☐ Not

Specific Flags

Create a diagnostic package and logs

To diagnose an issue, your support provider may ask you to send a diagnostic package containing debug information for either or both:

- [Deep Security Manager](#)
- [Deep Security Agent](#)

Deep Security Manager diagnostics

Create a diagnostic package for Deep Security Manager

1. Go to **Administration > System Information**.
2. Click **Create Diagnostic Package**.

The package will take several minutes to create. After the package has been generated, a summary will be displayed and your browser will download a ZIP file containing the diagnostic package.

Enable debug logs for Deep Security Manager

In addition to a diagnostic package, your support provider may ask you to enable diagnostic logging.

Warning: Don't enable diagnostic logging unless recommended by your support provider. Diagnostic logging can consume large amounts of disk space and increase CPU usage.

Trend Micro Deep Security On-Premise 11.3

1. Go to **Administration > System Information**.
2. Click **Diagnostic Logging**.
3. In the wizard that appears, select the options requested by your support provider.

If you have a multi-tenant Deep Security Manager, and the issue that you want to diagnose only occurs with a specific tenant, select that tenant's name in the option that appears. This will focus the debug logs, and minimize performance impacts while debug logging is enabled.

Some features need more time and disk space to collect enough debug logs. For example, you might need to increase **Maximum log file size** to 25 MB and the time period to 24 hours for **Database-related Issues** and **Cloud Account Synchronization - AWS**.

Note: If you decrease **Maximum number of log files**, Deep Security Manager does not automatically delete existing log files that now exceed the maximum. For example, if you reduce from 10 to 5 log files, `server5.log` to `server9.log` would all still exist. To reclaim disk space, manually delete those files from the file system.

While diagnostic logging is running, Deep Security Manager will display the message **Diagnostic Logging enabled** on the status bar. If you changed the default options, the status bar will display the message **Non default logging enabled** upon diagnostic logging completion.

4. To find diagnostic logging files, go to the root directory of the Deep Security Manager, and look for file names with the pattern `server#.log`, such as `server0.log`.

Deep Security Agent diagnostics

For an agent, you can create a diagnostic package either:

Trend Micro Deep Security On-Premise 11.3

- via the Deep Security Manager
- using the CLI on a protected computer (if the Deep Security Manager cannot reach the agent remotely)

For Linux-specific information on increasing or decreasing the anti-malware debug logging for the diagnostic package, see ["Increase debug logging for anti-malware in protected Linux instances" on page 723](#).

Your support provider may also ask you collect:

- a screenshot of Task Manager (Windows) or output from `top` (Linux) or `prstat` (Solaris) or `topas` (AIX)
- [debug logs](#)
- [Perfmon log](#) (Windows) or Syslog
- [memory dumps](#) (Windows) or core dumps ([Linux](#), [Solaris](#), [AIX](#))

Create an agent diagnostic package via Deep Security Manager

Note: Deep Security Manager must be able to connect to an agent remotely to create a diagnostic package for it. If the Deep Security Manager cannot reach the agent remotely, or if the agent is using agent-initiated activation, you must create the diagnostic package directly from the agent.

1. Go to **Computers**.
2. Double-click the name of the computer you want to generate the diagnostic package for.
3. Select the **Actions** tab.
4. Under **Support**, click **Create Diagnostics Package**.
5. Click **Next**.

Trend Micro Deep Security On-Premise 11.3

The package will take several minutes to create. After the package has been generated, a summary will be displayed and your browser will download a ZIP file containing the diagnostic package.

Create an agent diagnostic package via CLI on a protected computer

Linux

1. Connect to the server that you want to generate the diagnostic package for.
2. Enter the command:

```
sudo /opt/ds_agent/dsa_control -d
```

The output shows the name and location of the diagnostic package: `/var/opt/ds_agent/diag`

Windows

1. Connect to the computer that you want to generate the diagnostic package for.
2. Open a command prompt as an administrator, and enter the command.

In PowerShell:

```
& "& "\Program Files\Trend Micro\Deep Security Agent\dsa_control" -d
```

In cmd.exe:

```
cd C:\Program Files\Trend Micro\Deep Security Agent  
dsa_control.cmd -d
```

The output shows the name and location of the diagnostic package: `C:\ProgramData\Trend Micro\Deep Security Agent\diag`

Collect debug logs with DebugView

On Windows computers, you can collect debug logs using DebugView software.

Warning: Only collect debug logs if your support provider asks for them. During debug logging, CPU usage will increase, which will make high CPU usage issues worse.

1. Download the [DebugView utility](#).
2. If self-protection is enabled, disable it.
3. Stop the Trend Micro Deep Security Agent service.
4. In the C:\Windows directory, create a plain text file named ds_agent.ini.
5. In the ds_agent.ini file, add this line:

```
trace=*
```

6. Launch DebugView.exe.
7. Go to **Menu > Capture**.
8. Enable these settings:
 - **Capture Win32**
 - **Capture Kernel**
 - **Capture Events**
9. Start the Trend Micro Deep Security Agent service.
10. Export the information in DebugView to a CSV file.
11. Re-enable self-protection if you disabled it at the beginning of this procedure.

Increase verbose diagnostic package process memory

In environments with a large number of hosts (for example, 10,000 hosts or more,) the verbose diagnostic package process (`dsm_c.exe`) may run out of memory while creating the diagnostic package. To prevent this, you can increase the memory allocated to the verbose diagnostic package JVM process to 2 GB.

1. Go to the Deep Security Manager installation directory.
2. Create a new file with the name "dsm_c.voptions".
3. Open the file and add the line `-Xmx2g`.

Note: If 2 GB of memory is not enough, you can further increase the allocated memory by changing the value in the above line (for example, `-Xmx4g` for 4 GB or `-Xmx6g` for 6 GB).

4. Save the file and run `dsm_c.exe`.