

Trend Micro Incorporated reserves the right to make changes to this document and to the products described herein without notice. Before installing and using the software, please review the readme files, release notes, and the latest version of the applicable user documentation, which are available from the Trend Micro Web site at:

<http://downloadcenter.trendmicro.com/>

Trend Micro, the Trend Micro t-ball logo, Deep Security, and TrendLabs are trademarks or registered trademarks of Trend Micro, Incorporated. All other product or company names may be trademarks or registered trademarks of their owners.

Copyright © 2017 Trend Micro Incorporated. All rights reserved.

Document Part No.: APEM97219_150921

The user documentation for Trend Micro Deep Security introduces the main features of the software and installation instructions for your production environment. Read through it before installing or using the software.

Detailed information about how to use specific features within the software are available in the online help file and the online Knowledge Base at Trend Micro's Web site.

Trend Micro always seeks to improve its documentation. If you have questions, comments, or suggestions about this or any Trend Micro document, please contact us at docs@trendmicro.com.

Please evaluate this documentation on the following site:

<http://www.trendmicro.com/download/documentation/rating.asp>

Contents

- What Is Trend Micro Deep Security?4
- What Are Web Services?.....4
 - Audience4
 - Terminology4
- Getting Started.....6
 - Enabling the Web Service API6
 - Creating a Web Service Administrator Account7
 - Obtaining the Web Service WSDL and SSL Certificate8
 - Developing a Web Service Client Application9
- Web Service API Capabilities 11
 - What Is Possible? 11
 - What is Not Possible? 15
- Reference 18
 - Transport Objects 18
 - Enumeration Objects 68
 - Web Methods 93

What Is Trend Micro Deep Security?

Trend Micro™ Deep Security™ is a server and application protection software that allows systems to become self-defending. Deep Security Agent is deployed on physical servers and virtual machines to provide comprehensive protection, including:

- Firewall Intrusion Detection and Prevention (IDS/IPS)
- Web Application Protection
- Application Control
- Integrity Monitoring
- Log Inspection

All Deep Security Agents are centrally managed by Deep Security Manager.

What Are Web Services?

To assist in deployment and integration into customer and partner environments, Trend Micro has developed a SOAP Web Service API that is exposed by Deep Security Manager. This allows for an easy, language-neutral method to externally access data and programming configurations.

Audience

This document is targeted at customer and partner system integrators, and customization developers. A typical application of the Web Service API would be to integrate Deep Security into existing configuration and control management systems, or collection of events. It is assumed that the reader is familiar with Trend Micro Deep Security, software development in a recommended language, and the concepts and terminology described in the Terminology section.

Terminology

Term	Description
Web Service	Web Services is defined as an application programming interface (API) used to remotely access service-exposed information and functionality that is executed on the remote system hosting the Web service. It is a collection of web methods assembled into a service.
WSDL	Web Service Definition Language (WSDL) is defined by the Web Service as the source for all knowledge of the service-available functionality. Web Service development tools will consume the WSDL and automatically generate the client-side code required to build a Web Service client for that service.
Web Method	A function of the Web Service called from the client that is executed by the service as a remote call.

SOAP	SOAP (Simple Object Access Protocol) is a protocol specification for exchanging structured information in the implementation of Web Services. Its message format is based on XML and relies on other protocols for message communication between client and server.
HTTP	HTTP is a request/response message standard for client/service communication used by Internet browsers and web servers.
HTTPS	HTTPS is a combination of HTTP and the SSL/TLS protocol. This allows for encrypted communication between HTTP client/service partners.
IDE	Integrated Development Environment (IDE) is a development tool used for designing, developing, compiling, and debugging software application.

Getting Started

The basic steps to getting started with the Web Service API are as follows:

- 1) Enable the Web Service API.
- 2) Create an administrator account that an external Web Service client can utilize.
- 3) Obtain the Web Service WSDL and SSL Certificate.
- 4) Develop an external Web Service client to communicate with Deep Security Manager.

Enabling the Web Service API

- 1) Open an Internet browser and connect to the Deep Security Manager:

`https://<hostname/IP>:4119`

- 2) Navigate to **Administration-> System Settings**, and select the **Advanced** tab.
- 3) Select **Enabled** under SOAP Web service API, then click **Save**.

Creating a Web Service Administrator Account

Deep Security Manager allows for powerful role-based access, including settings to control if an administrator account may access the Web Service API or Manager user interface. For security reasons, it is recommended that a new administrator account and a new Web Service-specific role be created.

The Web Service API enforces all other Role access controls, such as Computer Rights, Security Profile Rights, and User Rights. If a Role is created for the Web Service API that only permits Computers of a certain Computer Group to be viewable, then a Web Service client using that administrator will only be able to access the specified Computer Group.

To create a new Role for Web Service only access, complete the following steps:

- 1) Open an Internet browser and connect to the Deep Security Manager:

`https://<hostname/IP>:4119`

- 2) Navigate to **Administration -> User Management -> Roles**, and click **New...**
- 3) Create the Role as normal, but de-select "Allow Access to Deep Security Manager User Interface" and select "Allow Access to Web Service API".
- 4) When all other configuration is complete, click **Save**.
- 5) Navigate to **User Management -> Users**, and click **New**.
- 6) Create a new administrator for use only with the Web Service API. Assign the new Role previously created to this administrator.

Make note of the new administrator account username and password.

Obtaining the Web Service WSDL and SSL Certificate

All Web Service SOAP implementations will require the target Web Service WSDL file. The WSDL is used to automatically generate source code that can be used for developing the Web Service client application. Additionally, the respective SOAP implementation will need to reconcile the fact that HTTPS communication is required between the client application and the Deep Security Manager Web Service. Typically this means that the Deep Security Manager SSL certificate will need to be imported in the trusted X.509 certification used by the SOAP implementation. For example, Microsoft Visual Studio requires that the SSL certificate be imported into the Windows certificate store on each Windows platform that the client application will run on. For Java Axis, the Java Key Store is used and can be easily copied with the client application to each platform that the client application will run on. Alternatively there is the option to develop an alternative certificate validation policy implementation to bypass this default requirement.

To download the Web Service WSDL file, complete the following steps:

- 1) Open an Internet browser and connect to the Deep Security Manager Web Service URI:

`https://<hostname/IP>:4119/webservice/Manager?WSDL`

- 2) Save the document as Manager.wsdl.

There are many ways to retrieve an installed Deep Security Manager's public certificate. The following is one method using Firefox:

- 1) Launch Firefox and connect to the Deep Security Manager web page.
- 2) Double-click on the Lock icon next to the address.
- 3) Click **More Information**.
- 4) Click **View Certificate**.
- 5) Click the **Details** tab.
- 6) Click **Export...**
- 7) Export the certificate as "X.509 Certificate (DER)".
- 8) Save it as Manager.cer.

Developing a Web Service Client Application

Using a programming language that supports the SOAP (<http://en.wikipedia.org/wiki/SOAP>) over HTTP standard, a client application can be developed to make remote calls to Deep Security Manager. The language chosen should be the conclusion of familiarity, suitability for the task at hand, and language compatibility for the intended integration. Apache Axis works well and is the native implementation of the Web Service itself. The Microsoft .Net Framework's support for Web Services through Visual Studio is a very robust choice. Here is a list of potential SOAP Web Service implementations that can be used:

- C#/VB.NET/Managed C++ using .NET Framework
<http://msdn2.microsoft.com/en-us/netframework/default.aspx>
- Java using Apache Axis
<http://ws.apache.org/axis/java/index.html>
- C++ using gSOAP
<http://www.cs.fsu.edu/~engelen/soap.html>
- C++ using Apache Axis
<http://ws.apache.org/axis/cpp/index.html>
- PHP using PEAR
<http://pear.php.net/package/SOAP>
- Ruby using soap4r
<http://dev.ctor.org/soap4r>
- Perl using SOAP:Lite
<http://www.soaplite.com/>
- CORBA using SOAP2CORBA
<http://soap2corba.sourceforge.net/>
- Python using Python Web Services
<http://pywebsvcs.sourceforge.net/>

Once the selected development environment has been configured, the SOAP implementation will require that the Deep Security Manager WSDL be added and source code generated from it before development can begin. For example, with Microsoft Visual Studio a new Project can be created, and the Manager WSDL file can be added as a new Web Reference, with Apache Axis for Java leverage ANT and the wsdl2java task in order to generate Java code from the WSDL file.

Next, the respective SOAP implementation will have support for HTTPS communication, which requires that the Deep Security Manager SSL certificate be imported into a supported key store container. For Microsoft Windows and Visual Studio, this is the Windows Certificate Store. To import the certificate, it can be double-clicked on the Web Service client application machine, and imported as trusted. For Java and Apache Axis, the SSL certificate

will need to be imported into the JDK/JRE “cacerts” key store using the Java keytool command that is included with the JDK/JRE.

For more information on how to import a SSL certificate, or how to use HTTPS support for the respective SOAP implementation, consult the SOAP implementation documentation.

For more examples on how to develop with the Deep Security Manager Web Service API, see the Trend Micro Deep Security Web Service sample package. It can be obtained from a Trend Micro sales or support representative.

Web Service API Capabilities

The Deep Security Manager Web Service API enables customers and partners to:

- Retrieve configuration and event information
- Create, update and delete configuration settings
- Initiate a Manager operation

What Is Possible?

Although the Web Service API endeavors to implement as many Deep Security Manager features as possible, not all functionality that is available in the Deep Security Manager interface is necessarily available through the Web Service API. The following list details the high level functionality, grouped by major category, which is possible with the Web Service API.

Dashboard

- Retrieve counters for dashboard widgets
- Retrieve feature summary for the system
- Retrieve an overall computer and alert status for the system

Computers

- Retrieve Computers
- Add/Update a computer
- Delete a Computer
- Activate a Computer
- Deactivate a Computer
- Lock a Computer
- Unlock a Computer
- Retrieve Computer status
- Initiate Computer "Update Now" operation
- Initiate Computer "Get Events Now" operation
- Initiate Computer Agent software upgrade operation
- Assign Computer to a Security Profile
- Un-assign Computer from a Security Profile
- Get System settings configured at the Computer level
- Set(override) System settings configured at the Computer level
- Clear System settings configured at the Computer level

Groups

- Retrieve Groups
- Add/Update a Group
- Delete a Group
- Move a Computer to a Group

Security Profile

- Retrieve Security Profiles
- Add/Update a Security Profile
- Edit a Security Profile
- Delete a Security Profile
- Set Firewall/DPI/Integrity Monitoring/Log Inspection state at Security Profile level
- Assign Firewall/DPI/Integrity Monitoring/Log Inspection rules at Security Profile level
- Unassign Firewall/DPI/Integrity Monitoring/Log Inspection rules at Security Profile level
- Get System setting configured at the Security Profile level
- Set(override) System settings configured at the Security Profile level
- Clear System settings configured at the Security Profile level

Anti-Malware

- Retrieve Anti-Malware events
- Retrieve Anti-Malware configurations
- Add/Update Anti-Malware configurations
- Delete Anti-Malware configurations
- Add/Update Directory Lists
- Delete Directory Lists
- Add/Update File Lists
- Delete File Lists
- Add/Update File Extension Lists
- Delete File Extension Lists

Web Reputation

- Retrieve Web Reputation events
- Retrieve Web Reputation configurations *
- Add/Update Web Reputation configurations *
- Delete Web Reputation configurations *

These operations are performed with the system setting APIs and not via dedicated APIs.

Firewall

- Retrieve Firewall events
- Retrieve Firewall rules
- Add/Update Firewall rule
- Edit Firewall rule
- Delete Firewall rule
- Retrieve Stateful Configurations
- Add/Update Stateful Configurations
- Edit Stateful Configurations
- Delete Stateful Configurations

Deep Packet Inspection

- Retrieve DPI events
- Retrieve DPI rules
- Add/Update DPI rule
- Edit DPI rule
- Delete DPI rule
- Retrieve Application Types
- Add Application Types
- Edit Application Types
- Delete Application Types
- Retrieve Application Type Overrides
- Add Application Type Overrides
- Edit Application Type Overrides
- Delete Application Type Overrides

Note that only user-created Application Types can be modified or deleted. Application Types issued by Trend Micro are read-only.

Note that Application Type Overrides are only supported at the Security Policy level, not the Computer level.

Integrity Monitoring

- Retrieve Integrity Monitoring events
- Retrieve Integrity Monitoring rules
- Add/Update Integrity Monitoring rules
- Edit Integrity Monitoring rules
- Delete Integrity Monitoring rules
- Initiate Computer "Scan For Integrity Changes" operation
- Initiate Computer "Rebuild Baseline" operation

Log Inspection

- Retrieve Log Inspection events
- Retrieve Log Inspection rules
- Add/Update Log Inspection rules
- Edit Log Inspection rules
- Delete Log Inspection rules
- Retrieve Log Inspection Decoders
- Add/Update Log Inspection Decoder
- Edit Log Inspection Decoder
- Delete Log Inspection Decoder

IP Lists

- Retrieve IP Lists
- Add/Update IP list
- Edit IP lists

- Delete IP lists

MAC Lists

- Retrieve MAC Lists
- Add/Update MAC list
- Edit MAC lists
- Delete MAC lists

Port Lists

- Retrieve Port Lists
- Add/Update Port list
- Edit Port lists
- Delete Port lists

Schedules

- Retrieve Schedules
- Add/Update Schedules
- Edit Schedules
- Delete Schedules

System

- Retrieve System Events
- Get System(global) settings
- Set System(global) settings
- Retrieve System Information

License

- Retrieve License
- Update License

Updates

- Retrieve Security Center customer account
- Set Security Center customer account
- Test Security Center customer account
- Import Security Update from file
- Retrieve stored Security Updates
- Apply stored Security Update
- Export stored Security Update
- Delete stored Security Update
- Retrieve stored Agent/Appliance software
- Export stored software
- Delete stored software

What is Not Possible?

The Deep Security Manager Web Service API is missing capabilities required to provide for the following notable functionality.

Alerts

- Retrieve Alert
- Dismiss Alerts

Reports

- Generate Reports

Computers

- Edit Computer general information
- Initiate "Scan for Recommendations" operation
- Clear Recommendations
- Create Diagnostic Package
- Configure Computer interface settings
- Edit Firewall/DPI/Integrity Monitoring/Log Inspection state at Computer level
- Assign Firewall/DPI/Integrity Monitoring/Log Inspection rules at Computer level
- Override Firewall/DPI/Integrity Monitoring/Log Inspection rule configurations at Computer level
- Override Application Type Properties at Computer level

Groups

- Add vCenter
- Configure Directory/Sync with LDAP

Security Profile

- Select "Real Time" Integrity Monitoring state at Security Profile level
- Override Firewall/DPI/Integrity Monitoring/Log Inspection rule configurations at Security Profile level

Anti-Malware

- Retrieve or operate on quarantined files

Firewall

- Assign Context to a rule

Deep Packet Inspection

- Edit[configuration] of Security Update downloaded DPI rules
- Assign Context to a rule
- Configure SSL certificates
- Modify or delete Application Types issued by Trend Micro.

Integrity Monitoring

- Select "Real Time" Integrity Monitoring state
- Edit [configuration] of downloaded Integrity Monitoring rules
- Assign Context to a Integrity Monitoring rule

Log Inspection

- Edit [configuration] of downloaded Log Inspection rules
- Assign Context to a Log Inspection rule

Contexts

- Retrieve Contexts
- Add/Update/Edit/Delete Context

Tags

- Delete Tags

Scheduled Tasks

- Retrieve Scheduled Tasks
- Add/Edit/Delete Scheduled Tasks

Role

- Retrieve Roles
- Add/Edit/Delete Roles

Users

- Retrieve Users
- Add/Edit/Delete Users

Contacts

- Retrieve Contacts
- Add/Edit/Delete Contacts

Updates

- Download Security Update from Security Center
- Download Software from Security Center

Reference

This section describes all relevant transport and enumeration class objects.

Transport Objects

Transport objects are modeled after Deep Security Manager web interface objects and configuration groups. These transport objects can be constructed as new or retrieved from the Manager by calling the appropriate web method.

A Web Service definition may declare object classes that inherit properties from other base object classes, so only the relevant object classes are covered in this section. If during development, you encounter any WSDL-defined object classes that are not documented, they are likely inherited base object classes or response object classes that are not directly used by any Web Methods and do not have any direct value.

ApplicationTypeTransport

DESCRIPTION Represents an Application Type that reflects some network attributes to which DPI rules are assigned. The DPI engine will determine if a DPI rule should apply to a connection based on the assigned Application Type network attributes.

PROPERTIES

Name	Type	Description
ID	int	ApplicationTypeTransport ID
description	string	ApplicationTypeTransport description
name	string	ApplicationTypeTransport name
TBUID	string	Internal TBUID of a Trend Micro issued Application Type
direction	EnumDirection	<p>The initial direction of the connection which this ApplicationTypeTransport would apply, e.g., INCOMING, OUTGOING</p> <p>Depending on whether the application type is a server or client, the initial direction of the connection to inspect would either be INCOMING for a server, or OUTGOING for a client. E.g. Inspection of “Web Server Common” Application Type for a connection stream on TCP port 80 would be initially an INCOMING direction because incoming Web Server connections should be inspected</p>

ignoreRecommendations	boolean	Whether the Recommendation Engine should ignore this rule
protocolIcmp	ProtocolIcmp	ApplicationTypeTransport protocol ICMP type
protocolPortBased	ProtocolPortBased	ApplicationTypeTransport protocol Port type
protocolType	EnumApplicationTypeProtocolType	ApplicationTypeTransport protocol Application type, e.g., UCMP, TCP, UDP, TCP_UDP
authoritative	boolean	Whether the rule is an internal read only Trend Micro rule

ApplicationTypeOverrideTransport

DESCRIPTION Represents an Override for a specific Application Type and Security Profile. The ports and/or the recommendations flag can be overridden.

PROPERTIES

Name	Type	Description
ID	int	ApplicationTypeOverrideTransport ID
ApplicationTypeID	int	ApplicationTypeTransportID this override applies to
SecurityProfileID	int	SecurityProfileTransportID this override applies to
portType	EnumPortType	Assigned EnumPortType, e.g., ANY, PORTS, DEFINED_LIST
ports	String	Comma delimited list of ports and ranges if portType is PORTS
portListID	Integer	PortListTransport ID assigned if portType is DEFINED_LIST
ignoreRecommendations	boolean	Whether the Recommendation Engine should ignore this rule

ApplierInformationTransport

DESCRIPTION Represents the response information regarding the application of a software update using the securityUpdateApply web method.

PROPERTIES

Name	Type	Description
------	------	-------------

DPIRulesAdded	int	Number of DPI rules added
DPIRulesAddedAndAssigned	int	Number of DPI rules added and assigned
DPIRulesDeleted	int	Number of DPI rules removed
DPIRulesUpdated	int	Number of DPI rules updated
applicationTypesAdded	int	Number of Application Types added
applicationTypesDeleted	int	Number of Application Types removed
applicationTypesUpdated	int	Number of Application Types updated
detailedSummary	string	Detailed string summary of the update operation
integrityMonitoringRulesAdded	int	Number of Integrity Monitoring rules added
integrityMonitoringRulesDeleted	int	Number of Integrity Monitoring rules removed
integrityMonitoringRulesUpdated	int	Number of Integrity Monitoring rules updated
logInspectionDecodersAdded	int	Number of Log Inspection Decoders added
logInspectionDecodersDeleted	int	Number of Log Inspection Decoders deleted
logInspectionDecodersUpdated	int	Number of Log Inspection Decoders updated
logInspectionRulesAdded	int	Number of Log Inspection rules added
logInspectionRulesDeleted	int	Number of Log Inspection rules deleted
logInspectionRulesUpdated	int	Number of Log Inspection rules updated

portListsAdded	int	Number of Port Lists added
portListsUpdated	int	Number of Port Lists updated

AttributeTransport

DESCRIPTION Represents an Integrity Monitoring entity object attribute that the parent rule should be monitoring.

PROPERTIES

Name	Type	Description
friendlyValue	string	Human readable version of the value property
name	string	Attribute name
value	string	Attribute raw value which may be encoded depending on the attribute type

DPIEventListTransport

DESCRIPTION Represents a returned list of DPI events.

PROPERTIES

Name	Type	Description
truncated	boolean	Whether the event list was truncated or not
DPIEvents	ArrayOfDPIEventTransport	ArrayOfDPIEventTransport which contains a list of DPIEventTransport objects

DPIEventTransport

DESCRIPTION Represents a DPI event and contains all properties that belong to the event.

PROPERTIES

Name	Type	Description
DPIEventID	long	DPIEventTransport ID
DPIRuleID	int	DPIRuleTransport ID that triggered this event
action	string	Resulting action of the triggered event, e.g., log or deny
data	base64Binary	Any captured packet data in Base64 encoded format
dataFlags	int	A binary indication of xor'd flags from the network

		engine which are used to indicate conditions of the engine and data capture, e.g., TRUNCATED 0x01, OVERFLOW 0x02, SUPRESSED 0x04, HAVE DATA 0x08, REF DATA 0x10
dataIndex	int	Index of the final character in the data which triggered the event
destinationIP	string	Destination IP Address
destinationMAC	string	Destination MAC Address
destinationPort	string	Destination Port
direction	string	Direction of the event, e.g., incoming, or outgoing
driverTime	long	Epoch time the Agent driver recorded at the time of the event
endTime	dateTime	End time of the event if repeated multiple times, e.g., Internet browsers will resend a request multiple times if the connection is dropped and the exact same event would be repeated multiple times
eventOrigin	EnumEventOrigin	Origin of the event, e.g., AGENT, GUESTAGENT, APPLIANCEAGENT
flags	string	Data packet flags, e.g., ACK FIN
flow	string	Flow of the packet the log was recorded for in relation to the connection direction, e.g., 0 = FORWARD, 1 = BACKWARD
hostID	int	HostTransport ID of the computer where the event was triggered
hostName	string	HostTransport Name of the computer where the event was triggered
iface	string	Name of the physical network interface where the event was triggered
note	string	Internal note property that the engine may set for use by the Manager, e.g., Drop_data
packetSize	int	Size of the packet which triggered the event
protocol	string	Protocol of the connection
rank	int	Calculated Rank value (Computer Asset Value * IPS Filter Ranking)
reason	string	Name of the DPI filter which triggered the event
repeatCount	int	Repeat count of the event if repeated multiple times, e.g., Internet browsers will resend a request multiple times if the connection is dropped and the exact same event would be repeated multiple times

sourceIP	string	Source IP Address
sourceMAC	string	Source MAC Address
sourcePort	string	Source Port
startTime	dateTime	Start time of the event if repeated multiple times, e.g., Internet browsers will resend a request multiple times if the connection is dropped and the exact same event would be repeated multiple times
status	int	Error status code which will be 0 if no abnormal conditions were found
tags	string	Name of any event tags assigned to this event

DPIRuleTransport

DESCRIPTION

Represents a DPI Rule that can be accessed to read, update, or when creating new DPI Rules. Creating and updating DPI Rules is considered advanced and not a routine or repetitive operation. Changing some configuration options, such as includePacketData or raiseAlert are reasonable; however, creating a new DPI rule from scratch programmatically should only be done if full testing of the ruleXML content has been performed prior.

When creating a new rule, if possible it is recommended that an existing base rule is retrieved first, then modified to reflect the new rule, and saved as the new rule.

Once a new rule has been created and saved, the returned transport object from the save rule method should be used for all subsequent configuration operations for the life of the object. The reason for this is that the Manager will populate some fields during the save operation, such as rule ID, and these fields will not be present if you do not use the returned version after saving.

PROPERTIES

Name	Type	Description
ID	int	ID
name	string	Name
description	string	Description
TBUID	string	Internal TBUID of a Trend Micro issued DPI Rule
applicationTypeID	int	ApplicationTypeTransport ID this rule is assigned to
authoritative	boolean	Whether the rule is an internal read only Trend Micro rule

cveNumbers	string	A comma separated listing of the CVE Numbers from the vulnerability information
cvssScore	double	Final calculated CVSS score of the vulnerability information. A rule may resolve multiple vulnerabilities, so this will always be the highest CVSS score.
detectOnly	boolean	Whether the rule is detect only
disableEvent	boolean	Whether the rule is disabled
eventOnPacketDrop	boolean	Whether the rule should trigger an event when the connection is dropped
eventOnPacketModify	boolean	Whether the rule should trigger an event when a packet is modified by a rule (uncommon)
identifier	string	Public identifier of the filter used by Trend Micro to track filters
ignoreRecommendations	boolean	Whether the Recommendation Engine should ignore this rule
includePacketData	boolean	Whether this rule events should include packet data
issued	dateTime	Date this rule was issued
msNumbers	string	A comma separated listing of the Microsoft ID from the vulnerability information
patternAction	EnumDPIRuleAction	Action for START_END_PATTERNS type rule, e.g., DROP_CLOSE, LOG_ONLY
patternCaseSensitive	boolean	Whether a START_END_PATTERNS type rule should consider case sensitivity
patternEnd	string	End pattern
patternIf	EnumDPIRuleIf	Trigger if a START_END_PATTERNS type rule meets the criteria, e.g., ALL_PATTERNS_FOUND, ANY_PATTERNS_FOUND, NO_PATTERNS_FOUND
patternPatterns	string	A newline separated list of strings which will be used by a START_END_PATTERNS type rule
patternStart	string	Start pattern
priority	EnumDPIRulePriority	Rule priority, e.g., HIGHEST, NORMAL, LOWEST
raiseAlert	boolean	Whether an alert should be raised when the rule triggers

ruleXML	string	Rule XML of a CUSTOM_XML type rule. This may not be available for rules that have thirdBrigade set to TRUE
scheduleID	int	ScheduleTransport ID assigned to this rule
severity	EnumDPIRuleSeverity	Severity, e.g., CRITICAL, LOW
signatureAction	EnumDPIRuleAction	Action for SIGNATURE type rule, e.g., DROP_CLOSE, LOG_ONLY
signatureCaseSensitive	boolean	Whether a SIGNATURE type rule should consider case sensitivity
signatureSignature	string	Signature string which will be used by a SIGNATURE type rule
templateType	EnumDPIRuleTemplateType	Rule Type, e.g., CUSTOM_XML, SIGNATURE, START_END PATTERNS

EditableSettingStoredTransport

DESCRIPTION Represents existing Manager settings that can apply to a computer, Security Profile, or System. For example, the DPI engine can be configured to be in Detect at the System scope (top level) and the Security Profile scope can be configured to Prevent.

PROPERTIES

Name	Type	Description
settingKey	EnumEditableSettingKey	Existing setting key, e.g., CONFIGURATION_LOGGINGOVERRIDE
settingUnit	EnumEditableSettingUnit	Setting unit, e.g., MINUTES, EMAIL, IPLIST_ID
settingValue	string	Setting value
settingScope	EnumEditableSettingStoredScope	Scope of the setting, e.g., HOST, PROFILE, SYSTEM

EntityTransport

DESCRIPTION Represents an Integrity Monitoring entity object that references the attributes the parent rule should be monitoring.

PROPERTIES

Name	Type	Description
attributes	ArrayOfAttributeTransport	ArrayOfAttributeTransport array of AttributeTransport objects which reflect the entity attributes being monitored
key	string	Entity key
type	string	Entity type

FirewallEventTransport

DESCRIPTION Represents a Firewall event and contains all properties that belong to the event.

PROPERTIES

Name	Type	Description
firewallEventID	long	FirewallEventTransport ID
action	string	Resulting action of the triggered event, e.g., log or deny
data	base64Binary	Any captured packet data in Base64 encoded format
dataFlags	int	A binary indication of xor'd flags from the network engine which are used to indicate conditions of the engine and data capture, e.g., TRUNCATED 0x01, OVERFLOW 0x02, SUPRESSED 0x04, HAVE DATA 0x08, REF DATA 0x10
dataIndex	int	Index of the final character in the data which triggered the event
destinationIP	string	Destination IP Address
destinationMAC	string	Destination MAC Address
destinationPort	string	Destination Port
direction	string	Direction of the event, e.g., incoming, or outgoing
driverTime	long	Epoch time the Agent driver recorded at the time of the event
endTime	dateTime	End time of the event if repeated multiple times, e.g., Internet browsers will resend a request multiple times if the connection is dropped and the exact same event would be repeated multiple times
eventOrigin	EnumEventOrigin	Origin of the event, e.g., AGENT, GUESTAGENT, APPLIANCEAGENT
flags	string	Data packet flags, e.g., ACK FIN
flow	string	Flow of the packet the log was recorded for in relation to the connection direction, e.g., 0 = FORWARD, 1 = BACKWARD
frameType	string	Connection frame type, e.g., IP, ARP

hostID

int

HostTransport ID of the computer where the event was triggered

hostName	string	HostTransport Name of the computer where the event was triggered
iface	string	Name of the physical network interface where the event was triggered
note	string	Internal note property that the engine may set for use by the Manager, e.g., Drop_data
packetSize	int	Size of the packet which triggered the event
protocol	string	Protocol of the connection
rank	int	Calculated Rank value (Computer Asset Value * IPS Filter Ranking)
reason	string	Name of the Firewall rule which triggered the event
repeatCount	int	Repeat count of the event if repeated multiple times, e.g., Internet browsers will resend a request multiple times if the connection is dropped and the exact same event would be repeated multiple times
sourceIP	string	Source IP Address
sourceMAC	string	Source MAC Address
sourcePort	string	Source Port
startTime	dateTime	Start time of the event if repeated multiple times, e.g., Internet browsers will resend a request multiple times if the connection is dropped and the exact same event would be repeated multiple times
status	int	Error status code which will be 0 if no abnormal conditions were found
tags	string	Name of any event tags assigned to this event

FirewallRuleTransport

DESCRIPTION Represents a Firewall Rule that can be accessed to create, read, or update. Note that some fields are dynamically required. For example, if destinationIPType is set to RANGE, then destinationIPRangeFrom and destinationIPRangeTo are required fields, but destinationIPListID and destinationIPMask are not. The Web Service validation of these transport object properties is the same as what is validated in the Manager web interface itself. For an initial idea on how to configure a new rule transport object, see the Manager interface itself and the configurable fields you would like to attempt programmatically through the Web Service API.

When creating new rule, if possible it is recommended that an existing base rule be retrieved first, then modified to reflect the new rule, and then saved as the new rule.

Once a new rule has been created and saved, the returned transport object from the save rule method should be used for all subsequent configuration operations for the life of the object. The reason for this is the Manager will populate some fields during the save operation, such as rule ID, and these fields will not be present if you do not use the returned version after saving.

Note that there is some complex property validation that is generally implemented by the Manager web interface. For example, if the destinationIPType DEFINED_LIST is set, then the destinationIPListID will be required. If the destinationIPType RANGE is set, then destinationIPRangeFrom and destinationIPRangeTo will be required. This validation will be reported in the form of an exception when trying to save the object.

PROPERTIES

Name	Type	Description
ID	int	ID
name	string	Name
description	string	Description
action	EnumFirewallRuleAction	Resulting action of the triggered event, e.g., log or deny
anyFlags	boolean	Overriding packet flag criteria that includes any packet flags
destinationIP	string	Destination IP Address
destinationIPListID	int	IPListTransport ID of the assigned IP List
destinationIPMask	string	Destination IP Mask
destinationIPNot	boolean	Whether the destination IP criteria should be negative
destinationIPRangeFrom	string	Destination IP range from value
destinationIPRangeTo	string	Destination IP range to value
destinationIPType	EnumFirewallRuleIPType	Assigned EnumFirewallRuleIPType, e.g., ANY, MASKED_IP, RANGE, DEFINED_LIST
destinationMAC	string	Destination MAC
destinationMACListID	int	Assigned MACListTransport ID
destinationMACNot	boolean	Whether the destination MAC criteria should be negative
destinationMACType	EnumMACType	Assigned EnumMACType, e.g., ANY, MAC, DEFINED_LIST
destinationPortListID	int	Assigned PortListTransport ID

destinationPortNot	boolean	Whether the destination Port criteria should be negative
destinationPortType	EnumPortType	Assigned EnumPortType, e.g., ANY, PORTS, DEFINED_LIST
destinationPorts	string	Destination Ports
destinationSingleIP	string	Destination single IP
disabledLog	boolean	Disable logging of events triggered by this rule
frameNot	boolean	Whether the assigned frameType criteria should be negative
frameNumber	string	If frameType is OTHER, then use this value
frameType	EnumFirewallRuleFrameType	Assigned EnumFirewallRuleFrameType, e.g., ANY, IP, ARP, REARP, OTHER
icmpCode	int	If protocolType is ICMP, and anyFlags set to false, then include this ICMP code for the specified icmpType
icmpNot	boolean	Whether the icmpType flags should be negative
icmpType	int	If protocolType is ICMP, and anyFlags set to false, then include this ICMP type code, e.g., 30 = Traceroute, 37 = Domain Name Request
packetDirection	EnumDirection	Direction of the event, e.g., incoming, or outgoing
priority	EnumFirewallRulePriority	Assigned EnumFirewallRulePriority, e.g., HIGHEST, NORMAL, LOW
protocolNot	boolean	Whether the destination Protocol criteria should be negative
protocolNumber	int	If protocolType is set to OTHER, use this value
protocolType	EnumFirewallRuleProtocolType	Assigned EnumFirewallRuleProtocolType, e.g., ANY, ICMP, ICMPV6, TCP, UDP, TCP_UDP, OTHER
raiseAlert	boolean	Whether an alert should be raised when the rule triggers
scheduleID	int	ScheduleTransport ID assigned to this rule
sourceIP	string	Source IP Address
sourceIPListID	int	IPLISTTransport ID of the assigned IP List
sourceIPMask	string	Source IP Mask
sourceIPNot	boolean	Whether the source IP criteria should be

		negative
sourceIPRangeFrom	string	Source IP range from value
sourceIPRangeTo	string	Source IP range to value
sourceIPType	EnumFirewallRuleIPType	Assigned EnumFirewallRuleIPType, e.g., ANY, MASKED_IP, RANGE, DEFINED_LIST
sourceMAC	string	Source MAC
sourceMACListID	int	Assigned MACListTransport ID
sourceMACNot	boolean	Whether the source MAC criteria should be negative
sourceMACType	EnumMACType	Assigned EnumMACType, e.g., ANY, MAC, DEFINED_LIST
sourcePortListID	int	Assigned PortListTransport ID
sourcePortNot	boolean	Whether the source Port criteria should be negative
sourcePortType	EnumPortType	Assigned EnumPortType, e.g., ANY, PORTS, DEFINED_LIST
sourcePorts	string	Source Ports
sourceSingleIP	string	Source single IP
tcpFlagACK	boolean	If protocolType includes TCP, and anyFlags set to false, then include TCP packets with the ACK flag
tcpFlagFIN	boolean	If protocolType includes TCP, and anyFlags set to false, then include TCP packets with the FIN flag
tcpFlagPSH	boolean	If protocolType includes TCP, and anyFlags set to false, then include TCP packets with the PSH flag
tcpFlagRST	boolean	If protocolType includes TCP, and anyFlags set to false, then include TCP packets with the RST flag
tcpFlagSYN	boolean	If protocolType includes TCP, and anyFlags set to false, then include TCP packets with the SYN flag
tcpFlagURG	boolean	If protocolType includes TCP, and anyFlags set to false, then include TCP packets with the URG flag
tcpNot	boolean	Whether the TCP Flag criterion should be negative

HostFilterTransport

DESCRIPTION Used as search criteria to limit the scope of objects returned by computer-related attributes, such as by a Group, a Security Profile, or a specific computer. The event retrieval-related methods will require a HostFilterTransport that is empty to search for all events, or with specific properties populated to limit the scope of the search. For example, setting the HostFilterTransport securityProfileID property to the ID of a Security Profile will limit any event retrieval method calls to events that pertain to computers with the specific Security Profile assigned.

PROPERTIES

Name	Type	Description
hostGroupID	int	HostGroupTransport ID to filter computers by
hostID	int	HostTransport ID to filter computers by
securityProfileID	int	SecurityProfileTransport ID to filter computers by
type	EnumHostFilterType	EnumHostFilterType to filter computers by

HostGroupTransport

DESCRIPTION Represents a computer group folder that computers can be assigned to for organizational purposes.

PROPERTIES

Name	Type	Description
ID	int	ID
name	string	Name
description	string	Description
external	boolean	Administrative external boolean for integration purposes
externalID	string	Administrative external ID for integration purposes
parentGroupID	int	If the group belongs to a parent group, then this ID will be set and used to retrieve the parent group

HostStatusTransport

DESCRIPTION Contains the overall status information of a computer, VMWare ESX server, or Deep Security Virtual Appliance. Physical computers, virtual machines, ESX servers, and Deep Security Virtual Appliances are all represented as HostTransport objects. The requested computer HostStatusTransport object can contain optional information about the ESX a virtual machine belongs to, or information about an ESX server.

PROPERTIES

Name	Type	Description
applianceID	int	The HostTransport ID of any protecting Deep Security Virtual Appliance
applianceName	string	The name of any protecting Deep Security Virtual Appliance
esxServerFastPathDriverVersion	string	The fast path driver version a of virtual machine protected by a Deep Security Virtual Appliance
esxServerID	string	The HostTransport ID of a virtual machine hosting ESX server
esxServerName	string	The name of a virtual machine hosting ESX server
esxServerVersion	string	The version of a virtual machine hosting ESX server
locked	boolean	If the computer is locked
overallAntiMalwareStatus	string	Overall Anti Malware status
overallDpiStatus	string	Overall DPI protection status
overallFirewallStatus	string	Overall Firewall protection status
overallIntegrityMonitoringStatus	string	Overall Integrity Monitoring protection status
overallLastSuccessfulCommunication	DateTime	Overall last successful communication date and time.
overallLastSuccessfulUpdate	DateTime	Overall last successful update date and time.
overallLogInspectionStatus	string	Overall Log Inspection protection status.
overallStatus	string	Overall status.
protectionStatusTransports	ProtectionStatusTransport[]	The specific ProtectionStatusTransport objects assigned to the HostTransport object
overallWebReputationStatus	string	Overall Web Reputation Status.

HostTransport

DESCRIPTION	<p>The primary computer transport object that represents the computer systems Deep Security is aware of. Physical computers, virtual machines, ESX servers, and Deep Security Virtual Appliances are all represented as HostTransport objects.</p> <p>To determine a HostTransport status (e.g., Activated, Offline, Installed, etc.) the computer HostStatusTransport should be retrieved and the assigned ProtectionStatusTransport objects should be inspected. The HostTransportStatus will reflect the overall protection status of a computer. If protection is applied by both an in-guest Agent and Virtual Appliance, then two ProtectionStatusTransport objects will be assigned. Agent and Virtual Appliance protection may have different protection capabilities enabled, so inspection of all</p>
-------------	---

assigned ProtectionStatusTransport objects should be considered. Note that this is only necessary where a Virtual Appliance is deployed. Computers and virtual machines that only use Agent protection may only use the HostTransportStatus.

PROPERTIES

Name	Type	Description
displayName	string	Computer display name
external	boolean	Administrative external boolean for integration purposes.
externalID	string	Administrative external ID for integration purposes.
hostGroupID	int	Assigned HostGroupTransport ID
hostType	EnumHostType	Assigned host type
platform	string	Computer platform
securityProfileID	int	Assigned SecurityProfileTransport ID

IDFilterTransport

DESCRIPTION	Used as a search criteria to limit the scope of objects returned by event transport object ID. Each event transport object, such as IntegrityEventTransport, includes an ID property that is assigned as the primary key of an event when it is generated by a computer agent. Using IDFilterTransport, it is possible to filter event retrieval by this event ID in order to retrieve a specific event by ID, or events that are greater or less than a specified ID. For example, a utility that is designed to retrieve all new events on an interval can use the event ID property to uniquely identify which events have already been retrieved. This way retrieval of duplicate events can be avoided. Note that this structure is limited to 32 bit integers for IDs. IDFilterTransport2 supports 64 bit IDs and should be used with the associated event retrieval method in preference to this structure.
-------------	---

PROPERTIES

Name	Type	Description
Id	int	Event transport objects ID to filter by.
operator	EnumOperator	EnumOperator to be used to apply the id property, e.g., greater than, less than, and equal

IDFilterTransport2

DESCRIPTION	Used as a search criteria to limit the scope of objects returned by event transport object ID. Each event transport object, such as IntegrityEventTransport, includes an ID property that is assigned as the primary key of an event when it is generated by a computer agent. Using IDFilterTransport2, it is possible to filter event retrieval by this event ID in order to retrieve a
-------------	---

specific event by ID, or events that are greater or less than a specified ID. For example, a utility that is designed to retrieve all new events on an interval can use the event ID property to uniquely identify which events have already been retrieved. This way retrieval of duplicate events can be avoided.

PROPERTIES

Name	Type	Description
Id	long	Event transport objects ID to filter b.
operator	EnumOperator	EnumOperator to used to apply the id property, e.g., greater than, less than, and equal

IntegrityEventTransport

DESCRIPTION	Represents an Integrity monitoring event and contains all properties that belong to the event. Depending on the triggering rule and the target entity types and attributes monitoring, key, process, and user may contain information about the changed service, file, or user account. The isEntity and wasEntity properties may be used to inspect the changes made to the attribute that triggered the event; however, the description will contain a verbose explanation of the changes.
-------------	--

PROPERTIES

Name	Type	Description
integrityEventID	long	IntegrityEventTransport ID
integrityRuleID	Int	IntegrityRuleTransport ID which triggered this event
change	String	Change applied to the target key, e.g., Created, Updated, Deleted, Renamed
description	String	Description of the monitored attributes and what changed
hostID	int	HostTransport ID of the computer where the event was triggered
hostName	string	HostTransport Name of the computer where the event was triggered
isEntity	EntityTransport	EntityTransport of the monitored entity after the change which triggered the event
key	string	Name of file or registry key which the Integrity rule triggered on during a scan (if available)
logTime	dateTime	Time the triggered event was logged
process	string	Name of process or service which the Integrity rule triggered on during a scan (if available)

rank	int	Calculated Rank value (Computer Asset Value * IPS Filter Ranking)
reason	string	Name of the Integrity rule which triggered the event
severity	EnumIntegrityRuleSeverity	EnumIntegrityRuleSeverity severity level of the triggered event, e.g., CRITICAL, HIGH, MEDIUM, LOW
tags	string	Name of any event tags assigned to this event
type	string	Key type, e.g., Directory, File, Group, Installed Software, Service, User
user	string	Name of the user which the Integrity rule triggered on during a scan (if available)
wasEntity	EntityTransport	EntityTransport of the monitored entity before the change which triggered the event

IntegrityRuleTransport

DESCRIPTION Represents an Integrity Monitoring Rule that can be accessed to create, read, or update.

When creating new rule, if possible it is recommended that an existing base rule be retrieved first, then modified to reflect the new rule, and then saved as the new rule.

Once a new rule has been created and saved, the returned transport object from the save rule method should be used for all subsequent configuration operations for the life of the object. The reason for this is the Manager will populate some fields during the save operation, such as rule ID, and these fields will not be present if you do not use the returned version after saving.

PROPERTIES

Name	Type	Description
ID	int	ID
name	string	Name
description	string	Description
TBUID	string	Internal TBUID of a Trend Micro issued Integrity Monitoring rule
allowOnChange	boolean	Whether on change detection is enabled

authoritative	boolean	Whether the rule is an internal read only Trend Micro rule
content	string	XML content of the rule
identifier	string	Public identifier of the filter used by Trend Micro to track rules
ignoreRecommendations	boolean	Whether the Recommendation Engine should ignore this rule
issued	dateTime	Date this rule was issued
minAgentVersion	string	Minimum Agent version which can support this rule
minManagerVersion	string	Minimum Manager version which can support this rule
raiseAlert	boolean	Whether an alert should be raised when the rule triggers
severity	EnumIntegrityRuleSeverity	EnumDPIRuleSeverity Severity, e.g., CRITICAL, LOW

IPLISTTransport

DESCRIPTION Represents an IP Address List which can be assigned to other objects, such as Firewall rules.

PROPERTIES

Name	Type	Description
ID	int	IPLISTTransport ID
description	string	IPLISTTransport description
name	string	IPLISTTransport name
items	string	A newline separated list of IP Addresses

LogInspectionDecoderTransport

DESCRIPTION Represents a Log Inspection log file decoder. Log Inspection rules are applied after a log file has been first decoded. Some log files require special decoding because of the format the log data is contained in.

PROPERTIES

Name	Type	Description
ID	int	IPLISTTransport ID

description	string	IPLISTTransport description
name	string	IPLISTTransport name
TBUID	string	Internal TBUID of a Trend Micro issued Integrity Monitoring rule
authoritative	boolean	Whether the rule is an internal read only Trend Micro rule
content	string	XML content of the decoder
identifier	string	Public identifier of the filter used by Trend Micro to track rules
issued	dateTime	Date this rule was issued
minAgentVersion	string	Minimum Agent version which can support this rule
minManagerVersion	string	Minimum Manager version which can support this rule

LogInspectionEventTransport

DESCRIPTION Represents a Log Inspection event and contains all properties that belong to the event. Due to the dynamic nature of monitoring many different kinds of application log file, few or many of the properties may be populated. For example, some inspected log files can contain information about a remote computer and so the sourceIP and sourceUser may be populated, while other log files may only contain application related entries like programName. Do not rely on a descriptive property to be always present. Instead perform proper null value checking before utilizing the property.

PROPERTIES

Name	Type	Description
logInspectionEventID	long	LogInspectionEventTransport ID
logInspectionRuleID	string	LogInspectionRuleTransport ID
action	string	Resulting action of the triggered event
command	string	
data	string	Source log file data type, e.g., Windows Events = Crypt32, Security, Application
description	string	Name of the triggered LogInspectionRuleTransport sub-rule
destinationIP	string	Destination IP Address if available

destinationUser	string	Destination User if available
destinationPort	string	Destination Port if available
fullEvent	string	Copy of the triggered full log entry
groups	string	Groups of the LogInspectionRuleTransport triggered sub-rule
hostID	int	HostTransport ID of the computer where the event was triggered
hostName	string	HostTransport Name of the computer where the event was triggered
location	string	Location of the inspected log file
logTime	dateTime	Time of the triggered event
message	string	
programName	string	Name of the monitored log file application
rank	string	Calculated Rank value (Computer Asset Value * IPS Filter Ranking)
reason	string	Name of the Log Inspection rule that triggered the event
ruleID	int	LogInspectionRuleTransport sub-rule ID as defined in the rule syntax
severity	string	Severity of the triggered sub-rule, e.g., Lowest = 1, Critical = 15
sourceHostName	string	Source hostname if available
sourceID	string	Source ID if available
sourceIP	string	Source IP Address if available
sourcePort	string	Source Port if available
sourceUser	string	Source User if available
status	string	
systemName	string	System name of the computer the event triggered on
tags	string	Name of any event tags assigned to this event
url	string	URL attribute of the log event if available

LogInspectionRuleTransport

DESCRIPTION	Represents a Log Inspection Rule that can be accessed to create, read, or update.
	When creating new rule, if possible it is recommended that an existing base rule is retrieved first, and then modified to reflect the new rule, then saved as the new rule.

Once a new rule has been created and saved, the returned transport object from the save rule method should be used for all subsequent configuration operations for the life of the object. The reason for this is the Manager will populate some fields during the save operation, such as rule ID, and these fields will not be present if you do not use the returned version after saving.

PROPERTIES

Name	Type	Description
ID	int	ID
name	string	Name
description	string	Description
TBUID	string	Internal TBUID of a Trend Micro issued Log Inspection rule
alertMinSeverity	int	Minimum severity at which a sub-rule event will trigger a rule Alert
authoritative	boolean	Whether the rule is an internal read only Trend Micro rule
content	string	XML content of the rule

files

string

XML content that reflects the log file and format to inspect

This should contain one or more <localfile> node elements that require <location> and <log_format> elements where location is a path to the log file and format is one of the following pre-defined log handlers:

- single-line-text-log
- syslog
- snort-full
- snort-fast
- apache
- iis
- squid
- nmapg
- mysql_log
- postgresql_log
- djb-multilog
- eventlog

Windows Event Log example:

```
<localfile>
  <location>Application</location>
  <log_format>eventlog</log_format>
</localfile>
```

Multiple single line log files example:

```
<localfile>
  <location>c:\application\error.log</location>
  <log_format>single-line-text-log</log_format>
</localfile>
<localfile>
  <location>c:\application\debug.log</location>
  <log_format>single-line-text-log</log_format>
</localfile>
```

NOTE: LogInspectionRuleTransport objects with the thirdBrigade property set to TRUE will return JIT (Just-In-Time) output logic from the Log Inspection engine and can include internal engine logic fragments. Do not attempt to reuse this internal logic when updating or creating custom Log Inspection rules

Please consult the Deep Security User Guide for more information on supported log file formats

identifier	string	Public identifier of the filter used by Trend Micro to track filters
ignoreRecommendations	boolean	Whether the Recommendation Engine should ignore this rule
issued	dateTime	Date this rule was issued
minAgentVersion	string	Minimum Agent version that can support this rule
minManagerVersion	string	Minimum Manager version that can support this rule
raiseAlert	boolean	Whether an alert should be raised when the rule triggers

MACListTransport

DESCRIPTION Represents a MAC Address List that can be assigned to other objects, such as Firewall rules.

PROPERTIES

Name	Type	Description
ID	int	MACListTransport ID
description	string	MACListTransport description
name	string	MACListTransport name
items	string	A newline separated list of MAC Addresses

PortListTransport

DESCRIPTION Represents a Port List that can be assigned to other objects, such as Firewall rules.

PROPERTIES

Name	Type	Description
ID	int	PortListTransport ID
description	string	PortListTransport description
name	string	PortListTransport name
items	string	A newline separated list of Ports
TBUID	string	Internal TBUID

ProtectionStatusTransport

DESCRIPTION Represents the protection status of a host that is provided by and Agent or Virtual Appliance. A HostTransport object may have up to two ProtectionStatusTransport objects assigned if the computer is a Virtual Machine protected by an in-guest Agent.

PROPERTIES

Name	Type	Description
dpiStatus	string	DPI protection status
fingerprint	string	Fingerprint of the certificate issued to the protection type applied. This will be different between Agent and Appliance protection types, but may be used to determine if the Agent issued certificate has been changed due to legitimate re-activation or illegal tampering
firewallStatus	string	Firewall protection status
integrityMonitoringStatus	string	Integrity Monitoring protection status
lastSuccessfulCommunication	dateTime	Last successful communication
lastSuccessfulUpdate	dateTime	Last successful update
logInspectionStatus	string	Log Inspection protection status
protectionType	EnumProtectionType	Protection type provided, e.g., AGENT, APPLIANCE, NONE
state	EnumState	State of the protection type being applied, e.g., VM_STOPPED, VM_PAUSED, STANDBY, ACTIVATED, OFFLINE, INSTALLED, etc...
stateDescription	string	Description of the protection type state. Use this property when attempting to communicate to the user the state property assigned
status	string	Status of the protection type applied
version	string	Version of the protection type being applied, e.g., Agent or Virtual Appliance version
componentInfoTransports	ArrayOfComponentInfoTransport	Component Info Transports
webReputationStatus	string	Web reputation protection status

ProtocolIcmp

DESCRIPTION Represents a basic ICMP protocol type container.

PROPERTIES

Name	Type	Description
type	EnumProtocolIcmpType	Assigned EnumProtocolIcmpType, e.g., ICMP_ECHO, ICMP_ADDRESS_MASK

ProtocolPortBased

DESCRIPTION Represents an Application Type port protocol container.

PROPERTIES

Name	Type	Description
portListID	int	PortListTransport ID assigned if portType is DEFINED_LIST
portType	EnumPortType	Port type, e.g., ANY, PORTS, DEFINED_LIST
ports	string	Comma delimited list of ports and ranges if portType is PORTS

ScheduleTransport

DESCRIPTION Represents a Schedule container.

PROPERTIES

Name	Type	Description
ID	int	ScheduleTransport ID
description	string	ScheduleTransport description
name	string	ScheduleTransport name
hourOfWeek	String	A custom format that represents each hour of a week. The format is a single line sequence of 168 one and zero characters where a one represents an hour of the week that the assigned schedule should execute beginning Sunday morning. For example,

000000000000000000000000000000001000000...

DESCRIPTION	Represents a Security Profile container that can be assigned to other Computers by ID using their HostTransport object.
-------------	---

Name	Type	Description
ID	int	SecurityProfileTransport ID
description	string	SecurityProfileTransport description
name	string	SecurityProfileTransport name
DPIRuleIDs	int[]	Array of assigned DPIRuleTransport IDs
DPIState	EnumSecurityProfileDPIState	Assigned EnumSecurityProfileDPIState, e.g., ON, OFF, PASSIVE, INHERITED
antiMalwareManualID	int	Anti Malware Manual ID
antiMalwareManualInherit	boolean	Anti Malware Manual Inherit
antiMalwareRealTimeID	int	Anti Malware Real Time ID
antiMalwareRealTimeInherit	boolean	Anti Malware Real Time Inherit
antiMalwareRealTimeScheduleID	int	Anti Malware Real Time Schedule ID
antiMalwareScheduledID	int	Anti Malware Scheduled ID
antiMalwareScheduledInherit	boolean	Anti Malware Scheduled Inherit
antiMalwareState	EnumSecurityProfileAntiMalwareState	Assigned EnumSecurityProfileAntiMalwareState, e.g., ON, OFF, INHERITED
applicationTypeIDs	int[]	Array of assigned ApplicationTypeTransport IDs
firewallRuleIDs	int[]	Array of assigned FirewallRuleTransport IDs
firewallState	EnumSecurityProfileFirewallState	Assigned EnumSecurityProfileFirewallState, e.g., ON, OFF, INHERITED
integrityRuleIDs	int[]	Array of assigned IntegrityMonitoringRuleTransport IDs

integrityState	EnumSecurityProfileIntegrityState	Assigned EnumSecurityProfileIntegrityState, e.g., ON, OFF, INHERITED
logInspectionRuleIDs	int[]	Array of assigned LogInspectionRuleTransport IDs
logInspectionState	EnumSecurityProfileLogInspectionState	Assigned EnumSecurityProfileLogInspectionState, e.g., ON, OFF, INHERITED
parentSecurityProfileID	int	Assigned Security Profile ID
recommendationState	EnumSecurityProfileRecommendationState	Assigned EnumSecurityProfileRecommendationState, e.g., OFF, ONGOING
scheduleID	int	Assigned ScheduleTransport ID
statefulConfigurationID	int	Assigned StatefulConfigurationTransport ID

SecurityUpdateTransport

DESCRIPTION	Represents a downloaded Security Update that can be applied. Once applied, all updates to rules and recommendations in the Security Update will be available to Deep Security. Deep Security Manager can download and keep multiple Security Updates, but only one can be applied at a time. The currently applied Security Update is indicated by the appliedState property EnumSecurityUpdateAppliedState APPLIED_CURRENT value.	
-------------	--	--

PROPERTIES

Name	Type	Description
ID	int	SecurityUpdateTransport ID
appliedState	EnumSecurityUpdateAppliedState	Applied state, e.g., APPLIED, APPLIED_CURRENT, NOT_APPLIED
contentSummary	string	Summary of the Security Update
detectOnly	boolean	Used to indicate whether new Security Update rules should be applied as Detect Only. This can be used to limit risk associated with automatic assignment of untested new rules in a new Security Update This property should be set before calling the securityUpdateApply() method for it to be effective
downloaded	dateTime	Download date
name	string	Simple friendly name
released	dateTime	Trend Micro release date

SoftwareTransport

DESCRIPTION Represents a downloaded Software update that can be applied to the target type. Generally Software updates are Agent software updates. However Deep Security Virtual Appliances can also be considered a Software package.

PROPERTIES

Name	Type	Description
ID	int	SecurityUpdateTransport ID
fingerprint	string	Hashed fingerprint of the software file
imported	dateTime	Download or import date
name	string	Simple friendly name
notes	string	Release notes
platform	string	Target platform
released	dateTime	Trend Micro release date
version	string	Software version

StatefulConfigurationTransport

DESCRIPTION Represents a Stateful Inspection configuration container.

PROPERTIES

Name	Type	Description
ID	int	StatefulConfigurationTransport ID
description	string	StatefulConfigurationTransport description
name	string	StatefulConfigurationTransport name
ackStormDropConnection	boolean	Enable ACK Storm protection connection drops when detected
ackStormProtection	boolean	Enable ACK Storm protection
ackStormProtectionThreshold	int	The number of acknowledged packets before enforcing ACK Storm protection
allowIncomingActiveFTP	boolean	Allow Active FTP when assigned computer acts as a server
allowIncomingPassiveFTP	boolean	Allow Passive FTP when assigned computer acts as a server

allowOutgoingActiveFTP

boolean

Allow Active FTP when assigned computer acts as a client

allowOutgoingPassiveFTP	boolean	Allow Passive FTP when assigned computer acts as a client
denyFragmentedPackets	boolean	Deny incoming fragmented packets
denyTcpCwrEceFlags	boolean	Deny TCP packets containing CWR, EXE flags when there is network congestion (See RFC 3168 for ECN field definitions)
enableICMPStatefulInspection	boolean	Enable stateful inspection of packets at the ICMP level
enableICMPStatefulLogging	boolean	Enable logging of ICMP stateful inspection
enableTCPStatefulInspection	boolean	Enable stateful inspection of packets at the TCP level
enableTCPStatefulLogging	boolean	Enable logging of TCP stateful inspection
enableUDPStatefulInspection	boolean	Enable stateful inspection of packets at the UDP level
enableUDPStatefulLogging	boolean	Enable logging of UDP stateful inspection
limitHalfOpenConnections	boolean	Enable limiting of the number of half open TCP connections
limitHalfOpenConnectionsTo	int	The number of limited half open TCP connections
limitIncomingConnections	boolean	Enable limiting of incoming connections from a single computer
limitIncomingConnectionsTo	int	The number of limited incoming connection from a single computer
limitOutgoingConnections	boolean	Enable limiting of outgoing connections from a single computer
limitOutgoingConnectionsTo	int	The number of limited outgoing connection from a single computer
synFloodProtection	boolean	Enable SYN flood protection
synFloodProtectionThreshold	int	The number of half open TCP connections allowed before SYN flood protection is enforced

SystemEventTransport

DESCRIPTION Represents a Deep Security Manager System event. A System event can target many different aspects of Deep Security, such as a configuration change to a Security Profile or Computer setting, or applying a Security Update to a Computer.

PROPERTIES

Name	Type	Description
actionPerformedBy	string	Name of the administrator who performed the action that generated the event
description	string	SystemEventTransport Description
event	string	SystemEventTransport Summary
eventID	int	Common Event ID that can be used uniquely identify the event cause (see Deep Security Manager for a list of Event IDs and the action type)
eventOrigin	EnumEventOrigin	Originating source of the event, e.g., UNKNOWN, AGENT, MANAGER
managerHostname	string	Hostname of the Manager
systemEventID	long	SystemEventTransport ID
tags	string	Name of any event tags assigned to this event
target	string	Summary name of the target of the event action
targetID	int	Transport object ID of the target
targetType	string	Type of the target such as an administrator, computer or schedule.
time	dateTime	Time of the event
type	string	Event level type, e.g., Error, Info, Warning

SystemInformationTransport

DESCRIPTION Represents a Deep Security Manager system information container.

PROPERTIES

Name	Type	Description
key	string	System information key
name	string	System information name
value	string	System information value

TimeFilterTransport

DESCRIPTION Used as search criteria limit the scope of objects returned by time related attributes, such as from, to, or a specific time. If the type is set to EnumTimeFilterType CUSTOM_RANGE, then the rangeFrom and rangeTo property will be required. If the EnumTimeFilterType SPECIFIC_TIME type is set, then the specificTime property will be required.

PROPERTIES

Name	Type	Description
rangeFrom	dateTime	HostGroupTransport ID to filter computers by.
rangeTo	dateTime	HostTransport ID to filter computers by.
specificTime	dateTime	SecurityProfileTransport ID to filter computers by.
type	EnumTimeFilterType	EnumTimeFilterType to filter computers by.

UserTransport

DESCRIPTION Represents User Transport.

PROPERTIES

Name	Type	Description
ID	int	
country	string	
description	string	
emailAddress	string	
fullName	string	
language	string	
lockedOut	boolean	
mobileNumber	string	
pageNumber	string	
password	string	
passwordNeverExpires	boolean	
phoneNumber	string	
receiveNotifications	boolean	

TagFilterTransport

DESCRIPTION Used as a search criteria to specify the criteria of tags for the search

PROPERTIES

Name	Type	Description
tags	string	The requested tags, depending on the type field
type	EnumTagFilterType	ALL returns an unbounded set, UNTAGGED returns only events that have no tags. Otherwise the tags field is a freeform field that takes comma delimited tag names (with the not '!' character indicated where not tagged).

CounterTransport

DESCRIPTION This object represents an abstraction of data that is represented on the dashboard.

PROPERTIES

Name	Type	Description
description	string	Blank, for future use
percentOfTotal	float	Percentage of the data in this counter in relation to all data for the given time period.
percentOfTotalString	string	Same as percentOfTotal, but as a string
text	string	Counter dependant
value	long	The actual number of events that triggered that match this counter
valueString	string	Same as value, but as a string
previousValue	long	The previous value of the same counter, but in the previous time period. Useful for trend calculation.

CounterHostTransport

DESCRIPTION A counter object specific from a host. This extends from CounterTransport, so all fields of that class apply here.

PROPERTIES

Name	Type	Description
hostID	Int	The hostID this counter applies to
icon	string	The icon URL that should be used for this host.

CounterWithIDTransport

DESCRIPTION A counter object specific for a specific item, typically a rule. This extends from CounterTransport, so all fields of that class apply here.

PROPERTIES

Name	Type	Description
itemID	Int	The ID of the item this counter corresponds to.

CounterAlertTypeTransport

DESCRIPTION A counter object that aggregates alert information. This extends from CounterTransport, so all fields of that class apply here.

PROPERTIES

Name	Type	Description
severity	int	The severity of the alert.
percentOpen	string	
averageTimeOpen	string	

FeatureSummaryDetailTransport

DESCRIPTION An object that represents the status summary of a protection module.

PROPERTIES

Name	Type	Description
featureName	string	The name of the module
protectedComputerNum	long	Number of computers that currently have this module activated.

totalEventNum	long	Total number of events
preventedEventNum	long	Number of events that were prevented
detectedEventNum	long	Number of events that were detected
previousTotalEventNum	long	Total event count for the previous time period
previousPreventedEventNum	long	Prevent count for the previous time period
previousDetectedEventNum	long	Detect count for the previous time period

HostStatusSummaryTransport

DESCRIPTION An object that represents the high level computer summary for the system.

PROPERTIES

Name	Type	Description
criticalHosts	Int	Number of hosts in critical state
lockedHosts	int	Number of hosts in locked state
onlineHosts	int	Number of managed, online hosts
unmanageHosts	int	Number of unmanaged hosts
warningHosts	int	Number of hosts in warning state

StatusSummaryTransport

DESCRIPTION An collection of objects that represent the high level status for the system

PROPERTIES

Name	Type	Description
alertErrorNum	int	Number of current error alerts
alertWarningNum	int	Number of current warning alerts
hostStatusSummary	HostStatusSummaryTransport	Computer status summary

ComponentInfoTransport

DESCRIPTION Represents the information for an individual component in the system. Components are patterns, rule updates, manifests, etc., typically items that are visible on the System->Updates page.

PROPERTIES

Name	Type	Description
type	int	An internal type of the component
id	int	An ID representing the component
name	string	The friendly name of the component
shortName	string	The short name for the component
currentVersion	string	The current version of the component
lastUpdate	dateTime	The last time this component was updated
nameKey	string	An internal key for the component
deployed	int	Number of endpoints on which this component is deployed
needDeployed	int	Number of endpoints on which this component is out of date

JobProgressTransport

DESCRIPTION Collects the progress for a given system job, i.e., " Update Security Configuration on N computers"

PROPERTIES

Name	Type	Description
complete	Int	Number jobs that have completed in the time period
error	int	Number that have failed in error
pending	int	Number that are still outstanding
unable	int	Number of jobs that were unable to start

ConfigurationTransport

DESCRIPTION The superclass for many configuration transport objects.

PROPERTIES

Name	Type	Description
ID	int	The ID of the transport object
description	string	Description of the object
name	string	Name of the object

ProtectionStatusTransport

DESCRIPTION An object representing the current module protection status for a given computer.

PROPERTIES

Name	Type	Description
dpiStatus	string	The status of the DPI module for the computer
fingerprint	string	The certificate fingerprint
firewallStatus	string	The status of the Firewall module for the computer
integrityMonitoringStatus	string	The status of the Integrity Monitoring module for the computer
lastSuccessfulCommunication	dateTime	Last successful communication time
lastSuccessfulUpdate	dateTime	Last configuration update time
logInspectionStatus	string	The status of the Log Inspection module for the computer
protectionType	EnumProtectionType	Type of protection this object represents (i.e., Agent, Appliance)
state	EnumState	Computer state
stateDescription	string	Description of the state
status	string	Overall status of the computer
version	string	Version of agent/appliance software
componentInfoTransports	ArrayOfComponentInfoTransport	Component information for this computer
webReputationStatus	string	The status of the Web Reputation module for the computer

SystemEventListTransport

DESCRIPTION A collection of system events

PROPERTIES

Name	Type	Description
systemEvents	ArrayOfSystemEventTransport	The collection of system events

IntegrityEventListTransport

DESCRIPTION A collection of integrity events

PROPERTIES

Name	Type	Description
integrityEvents	ArrayOfIntegrityEventTransport	The collection of integrity events

LogInspectionEventListTransport

DESCRIPTION A collection of log inspection events

PROPERTIES

Name	Type	Description
logInspectionEvents	ArrayOfLogInspectionEventTransport	The collection of log inspection events

ScanFileListTransport

DESCRIPTION Extends ItemsTransport, this is a collection of File Lists.

PROPERTIES

Name	Type	Description
------	------	-------------

ScanFileExtListTransport

DESCRIPTION Extends ItemsTransport, this is a collection of File Extension Lists.

PROPERTIES

Name	Type	Description
------	------	-------------

ScanDirectoryListTransport

DESCRIPTION Extends ItemsTransport, this is a collection of Directory Lists.

PROPERTIES

Name	Type	Description
------	------	-------------

AntiMalwareTransport

DESCRIPTION An object that represents an anti malware configuration object.

PROPERTIES

Name	Type	Description
alert	boolean	Indicates if alerts should be created when events get triggered based on this configuration object
excludeScanDirectoryListID	int	The directory list ID to exclude from scans
excludeScanFileExtListID	int	The File Extension List ID to exclude from scans
excludeScanFileListID	int	The File List ID to exclude from scans
fileToScan	EnumAntiMalwareFilesToScan	What types of files to scan
firstScanAction	EnumAntiMalwareScanCustomAction	The specific custom action to perform
folderToScan	EnumAntiMalwareFoldersToScan	The enum that specifies how to scan folders
scanAction	EnumAntiMalwareScanAction	The default action to perform
intelliTrapEnabled	boolean	Is intellitraps enabled

scanCompressed	boolean	Should compressed files be scanned
scanCompressedLayer	int	Maximum Compressed Layers scannable
scanCompressedSmaller	int	Used by Scan Compressed. The size is in MB
scanCompressedNumberOfFiles	int	The maximum number of files to scan in a compressed file
scanDirList	int	The ID of the Directory list to scan, if folderToScan is setup to point at a specific list
scanFilesActivity	EnumAntiMalwareScanFilesActivity	During real time scan, whether to scan files opened for read, write, or read and write
secondScanAction	EnumAntiMalwareScanCustomAction	The second specific customer action to perform
toScanFileExtListID	int	The File Extension list ID to scan
spywareEnabled	boolean	Is spyware enabled
scanCustomActionForGeneric	EnumAntiMalwareScanCustomAction	A specific custom action to perform for malware classified as generic
unScannableFileAction	EnumAntiMalwareScanCustomAction	A specific custom action to perform for malware the is unscannable
configurationType	EnumAntiMalwareConfigType	Type of config, either for Real-Time scan or Manual/Scheduled
scanNetworkFolder	boolean	If network folders should be scanned
cpuUsage	EnumAntiMalwareCpuUsage	Controls CPU Usage Level
scanOLE	boolean	Scan embedded Microsoft Office objects
scanOLEExploit	boolean	Option to detect exploit code in OLE files
scanOLELayer	int	OLE layers to scan
scanActionForVirus	EnumAntiMalwareScanCustomAction	Scan action for Malware of type Virus
scanActionForTrojans	EnumAntiMalwareScanCustomAction	Scan action for Malware of type Trojans
scanActionForPacker	EnumAntiMalwareScanCustomAction	Scan action for Malware of type Packer

scanActionForSpyware	EnumAntiMalwareScanCustomAction	Scan action for Malware of type Spyware
scanActionForOtherThreats	EnumAntiMalwareScanCustomAction	Scan action for Malware of type other threats
scanActionForCookie	EnumAntiMalwareScanCustomAction	Scan action for Malware of type cookie
excludeScanProcessFileListID	int	File list ID of excluded processes

AntiMalwareSpywareItemTransport

DESCRIPTION Represents an Anti-Malware spyware event and contains all properties that belong to the event.

PROPERTIES

Name	Type	Description
antiMalwareQuarantinedFileID	int	If a file was quarantined as a result of the event, this will contain the ID of the quarantined file
antiMalwareSpywareItemID	int	If a this event was the result of spyware, this will point at the ID of the spyware item
hostID	int	The host ID this event corresponds to
objectInfo	string	File-path, registry key, process name...etc
objectType	int	Type identifier for Process, Cookies, File System, System Registry, Shortcut Link, Host File, Other
riskLevel	int	Risk level gauge Very Low (0), Low (25), Medium(50), High(75), Very High(100)
scanAction	int	Scan Action: The action taken upon each spyware items: Pass (1), Delete (2), Quarantined (3), Clean (4), Deny Access (5)
scanResultAction	int	Represent whether the action is successful (0) or failed (Error Code)
spywareType	int	Type identifier for Adware, Cookie, Dialer, Keylogger, Trojan, Worm, Downloader, etc

AntiMalwareEventTransport

DESCRIPTION Represents an Anti-Malware event

PROPERTIES

Name	Type	Description
antiMalwareConfigID	int	The ID of the Anti-Malware configuration this event corresponds to
antiMalwareEventID	long	The ID of the event
endTime	dateTime	Endtime of this event if it was repeated multiple times (not currently used)
errorCode	int	The VSAPI error code indicates the reason of the actions of failure
hostID	int	The host ID this event corresponds to
infectedFilePath	string	The infected file full path
infectionSource	string	The source computer of the infection
logDate	dateTime	The time this event occurred
malwareName	string	The name of the malware
malwareType	EnumMalwareType	The type of the malware
protocol	int	The protocols: Local Files(0), Network shared folder(1), etc. However, currently Agent only support local files.
quarantineRecordID	int	The ID of the quarantined file, if a file was quarantined as a result of this event
scanResultAction1	int	The result of the first scan action: represent whether the action is successful (0) or failed (Error Code)
scanResultAction2	int	The result of the second scan action: represent whether the action is successful (0) or failed (Error Code)
scanAction1	int	The actual first scan action being taken: e.g. Pass (1), Delete (2), Quarantined (3), Clean (4), Deny Access (5)
scanAction2	int	The actual second scan action being taken: e.g. Pass (1), Delete (2), Quarantined (3), Clean (4), Deny Access (5)

scanType	EnumAntiMalwareScanType	Type of scan this event was captured under
----------	-------------------------	--

spywareItems	ArrayOfAntiMalwareSpywareItemTransport	An array of spyware items associated with this event
startTime	dateTime	Starttime of this event if it was repeated multiple times (not currently used)
tags	string	Any tags associated with this event
summaryScanResult	string	Summary field for the Scan Result: e.g. passed, deleted, quarantined, cleaned, deny access.

AntiMalwareEventListTransport

DESCRIPTION A list of Anti-Malware events

PROPERTIES

Name	Type	Description
antiMalwareEvents	ArrayOfAntiMalwareEventTransport	The events

AlertStatusTransport

DESCRIPTION An object representing summary information for one individual alert

PROPERTIES

Name	Type	Description
alertDate	dateTime	The time of the alert
alertType	string	The type of the alert
severity	int	The severity of the alert as an integer
severityText	string	The severity of the alert as a string

HostDetailTransport

DESCRIPTION An object that holds detailed information about one computer object. All the "overall" fields are fields created by merging states of potentially multiple endpoints (i.e., Agent + Appliance).

PROPERTIES

Name	Type	Description
antiMalwareClassicPatternVersion	string	Current version of the classic Anti-Malware pattern
antiMalwareEngineVersion	string	<i>obsolete – this string will return "N/A"</i>

antiMalwareIntelliTrapExceptionVersion	string	Current version of the IntelliTrap exception pattern
antiMalwareIntelliTrapVersion	string	Current version of the IntelliTrap pattern
antiMalwareSmartScanPatternVersion	string	Current version of the Smart Scan pattern
antiMalwareSpywarePatternVersion	string	Current version of the Spyware pattern
hostGroupName	string	Name of Group this computer belongs to
cloudObjectImageId	string	Cloud Object Image Id
cloudObjectInstanceId	string	Cloud Object Instance Id
cloudObjectInternalUniqueId	string	Cloud Object Internal Unique Id
cloudObjectSecurityGroupIds	string	Cloud Object Security Group Ids
cloudObjectType	EnumCloudObjectType	Cloud Object Type
hostLight	EnumHostLight	Current color that represents the computers status
lastAntiMalwareScheduledScan	dateTime	Last time an Anti-Malware scheduled scan was performed
lastAntiMalwareEvent	dateTime	The time of the most recent Anti-Malware event for this computer
lastAntiMalwareManualScan	dateTime	Last time an Anti-Malware manual scan was performed
lastDpiEvent	dateTime	The time of the most recent DPI Event for this computer
lastFirewallEvent	dateTime	The time of the most recent Firewall Event for this computer
lastIPUsed	string	The last IP that was used for this computer during communication with the manager
lastIntegrityMonitoringEvent	dateTime	The time of the most recent Integrity Monitoring Event for this computer
lastLogInspectionEvent	dateTime	The time of the most recent Log Inspection Event for this computer
light	int	An integer representing the computers status light
locked	boolean	The locked state of the computer
overallAntiMalwareStatus	string	Overall Anti-Malware status of the computer
overallDpiStatus	string	Overall DPI status of the computer
overallFirewallStatus	string	Overall Firewall status of the computer
overallIntegrityMonitoringStatus	string	Overall Integrity Monitoring status of the computer
overallLastRecommendationScan	dateTime	The time of the last recommendation scan

overallLastSuccessfulCommunication	dateTime	The time of the last communication with the Manager
overallLastSuccessfulUpdate	dateTime	The time of the last successful Configuration Update
overallLastUpdateRequired	dateTime	The time the last configuration update was required at the manager
overallLogInspectionStatus	string	Overall Log Inspection status of the computer
overallStatus	string	Overall status of the computer
overallVersion	string	Overall version of the computer
securityProfileName	string	Name of the security profile assigned to the computer
virtualName	string	Internal virtual name (only populated if this is a computer provisioned through vCenter)
virtualUuid	string	Internal virtual UUID (only populated if this is a computer provisioned through vCenter)
componentClasses	ArrayOf_xsd_int	Array of class ids for components
componentNames	ArrayOf_xsd_string	Array of component names
componentTypes	ArrayOf_xsd_int	Array of component types
componentVersions	ArrayOf_xsd_string	Array of component versions
overallWebReputationStatus	string	Overall Web Reputation status of the computer
lastWebReputationEvent	dateTime	The time of the most recent Web Reputation event for this computer

HostInterfaceTransport

DESCRIPTION The Host's Interface Transport Object.

PROPERTIES

Name	Type	Description
dhcp	boolean	DHCP On or Off
hostBridgeId	int	The ID of the Host Bridge
interfaceTypeId	int	The ID of the Interface Type
mac	string	Mac Address
notAvailable	boolean	True is the HostInterface isn't available
virtualDeviceKey	int	The Virtual Device Key

ExternalFilterTransport

DESCRIPTION A filter that can be used to filter by the ExternalID field of a host or host group

PROPERTIES

Name	Type	Description
hostExternalID	string	The ID to filter the host by
hostGroupExternalID	string	The ID to filter the host group by
type	EnumExternalFilterType	The type of filter

WebReputationEventTransport

DESCRIPTION An object representing a web reputation event

PROPERTIES

Name	Type	Description
hostID	long	The ID of the host this event corresponds to
hostName	string	The name of the host this event corresponds to
logTime	dateTime	The time this event occurs
rank	int	The rank of the event
risk	EnumWebReputationEventRisk	The risk level of this event
tags	string	Any tags associated with this event
url	string	The URL that triggered this event
webReputationEventID	int	The ID of the event

WebReputationEventListTransport

DESCRIPTION A list of web reputation event objects.

PROPERTIES

Name	Type	Description
webReputationEvents	ArrayOfWebReputationEventTransport	The web reputation events.

Enumeration Objects

EnumApplicationTypeProtocolType

DESCRIPTION Application Type Protocol enumeration.

Values	ICMP
	TCP
	UDP
	TCP_UDP

EnumAntiMalwareFilesToScan

DESCRIPTION Anti Malware Files to Scan enumeration.

Values	ALLFILES
	INTELLISCAN
	EXTLISTSCAN

EnumAntiMalwareScanCustomAction

DESCRIPTION Anti Malware Scan Custom Action enumeration.

Values	UNSPECIFIED
	PASS
	DELETE
	QUARANTINE
	CLEAN
	DENY_ACCESS

EnumAntiMalwareFoldersToScan

DESCRIPTION Anti Malware Folders to Scan enumeration.

Values	ALLFOLDERS
	SPECIFIEDFOLDERS

EnumAntiMalwareScanAction

DESCRIPTION Value comparison result enumeration.

Values	INTELLIACTION
	CUSTOMACTION

EnumAntiMalwareScanFilesActivity

DESCRIPTION Anti Malware Scan Files Activity enumeration.

Values	READ_ONLY
	WRITE_ONLY
	READ_WRITE

EnumAntiMalwareConfigType

DESCRIPTION Anti Malware Configuration Type enumeration.

Values	CONFIGURATIONTYPE_RTS
	CONFIGURATIONTYPE_ODS

EnumAntiMalwareCpuUsage

DESCRIPTION Anti Malware CPU Usage enumeration.

Values	CPUUSAGE_LOW
	CPUUSAGE_MEDIUM
	CPUUSAGE_HIGH

EnumAntiMalwareScanType

DESCRIPTION Malware scan type enumeration.

Values	REALTIME
	MANUAL
	SCHEDULED
	QUICK

EnumCompareResults

DESCRIPTION Value comparison result enumeration.

Values	LESS_THAN
	EQUAL_TO
	GREATER_THAN
	INCOMPATIBLE

EnumCounterFilter

DESCRIPTION Counter Filter enumeration.

Values	ANTI_MALWARE_COMPUTER_ACTIVITY
	INTEGRITY_COMPUTER_ACTIVITY
	LOG_INSPECTION_COMPUTER_ACTIVITY
	FIREWALL_DETECT_COMPUTER_ACTIVITY
	FIREWALL_PREVENT_COMPUTER_ACTIVITY
	FIREWALL_ALL_COMPUTER_ACTIVITY
	DPI_DETECT_COMPUTER_ACTIVITY
	DPI_PREVENT_COMPUTER_ACTIVITY
	DPI_ALL_COMPUTER_ACTIVITY
	ANTI_MALWARE_ACTIVITY
	ANTI_MALWARE_INCOMPLETE_SCAN
	FIREWALL_PREVENT_RULES
	FIREWALL_DETECT_RULES
	FIREWALL_PREVENT_COMMON_EVENTS
	FIREWALL_DETECT_COMMON_EVENTS
	FIREWALL_PREVENT_ACTIVITY
	FIREWALL_DETECT_ACTIVITY
	FIREWALL_ALL_ACTIVITY
	FIREWALL_PREVENT_IP_ACTIVITY
	FIREWALL_DETECT_IP_ACTIVITY
FIREWALL_PREVENT_PORT_ACTIVITY	
FIREWALL_DETECT_PORT_ACTIVITY	

DPI_PREVENT_RULES
DPI_DETECT_RULES
DPI_ALL_RULES
DPI_PREVENT_COMMON_EVENTS
DPI_DETECT_COMMON_EVENTS
DPI_ALL_COMMON_EVENTS
DPI_PREVENT_ACTIVITY
DPI_DETECT_ACTIVITY
DPI_PREVENT_IP_ACTIVITY
DPI_DETECT_IP_ACTIVITY
DPI_PREVENT_APP_TYPE_ACTIVITY
DPI_DETECT_APP_TYPE_ACTIVITY
INTEGRITY_ACTIVITY
INTEGRITY_KEY_ACTIVITY
LOG_INSPECTION_ACTIVITY
LOG_INSPECTION_DESCRIPTION_ACTIVITY
ALERT_TYPE
RECONNAISSANCE_SCAN_ACTIVITY
SYSTEM_EVENT_SUMMARY
WEB_REPUTATION_COMPUTER_ACTIVITY
WEB_REPUTATION_URL_ACTIVITY

EnumCounterSumFilter

DESCRIPTION	Counter Sum Filter enumeration.
-------------	---------------------------------

Values

FIREWALL_PREVENT_ACTIVITY
FIREWALL_DETECT_ACTIVITY
FIREWALL_PREVENT_RULES

FIREWALL_DETECT_RULES
FIREWALL_PREVENT_COMMON_EVENTS
FIREWALL_DETECT_COMMON_EVENTS
DPI_PREVENT_ACTIVITY
DPI_DETECT_ACTIVITY
DPI_PREVENT_RULES
DPI_DETECT_RULES
DPI_PREVENT_COMMON_EVENTS
DPI_DETECT_COMMON_EVENTS
INTEGRITY_ACTIVITY
ANTI_MALWARE_ACTIVITY
LOG_INSPECTION_ACTIVITY
LOG_INSPECTION_SEVERITY_LOW
LOG_INSPECTION_SEVERITY_MEDIUM
LOG_INSPECTION_SEVERITY_HIGH
LOG_INSPECTION_SEVERITY_CRITICAL
INTEGRITY_SEVERITY_LOW
INTEGRITY_SEVERITY_MEDIUM
INTEGRITY_SEVERITY_HIGH
INTEGRITY_SEVERITY_CRITICAL
ANTI_MALWARE_SCANACTION_PASS
ANTI_MALWARE_SCANACTION_DELETE
ANTI_MALWARE_SCANACTION_QUARANTINE
ANTI_MALWARE_SCANACTION_CLEAN
ANTI_MALWARE_SCANACTION_DENY_ACCESS
ANTI_MALWARE_SCANACTION_FAILED
WEB_REPUTATION_ACTIVITY
WEB_REPUTATION_RISK_UNTESTED
WEB_REPUTATION_RISK_BLOCKED
WEB_REPUTATION_RISK_SAFE
WEB_REPUTATION_RISK_SUSPICIOUS
WEB_REPUTATION_RISK_HIGHLY_SUSPICIOUS
WEB_REPUTATION_RISK_DANGEROUS

EnumCloudObjectType

DESCRIPTION Cloud Object Types.

Values	AMAZON_VM
	VCLLOUD_VM

EnumDirection

DESCRIPTION Connection direction enumeration.

Values	INCOMING
	OUTGOING

EnumDPIRuleAction

DESCRIPTION DPI rule action enumeration.

Values	DROP_CLOSE
	LOG_ONLY

EnumDPIRuleIf

DESCRIPTION DPI rule start/end pattern conditional enumeration.

Values	ALL_PATTERNS_FOUND
	ANY_PATTERNS_FOUND
	NO_PATTERNS_FOUND

EnumDPIRulePriority

DESCRIPTION DPI rule priority enumeration.

Values	HIGHEST
	HIGH
	NORMAL
	LOW
	LOWEST

EnumDPIRuleSeverity

DESCRIPTION DPI rule severity enumeration.

Values	CRITICAL
	HIGH
	MEDIUM
	LOW

EnumDPIRuleTemplateType

DESCRIPTION DPI rule template type enumeration.

Values	CUSTOM_XML
	SIGNATURE
	START_END_PATTERNS

EnumEditableSettingKey

DESCRIPTION Editable system settings enumeration.

Values	CONFIGURATION_MOTD_TEXT
	CONFIGURATION_SPNFB_BANDWIDTHLIMITATION
	CONFIGURATION_SPNFB_ENABLEFEEDBACK
	CONFIGURATION_SPNFB_ENABLESUSPICIOUSFILEFEEDBACK
	CONFIGURATION_SPNFB_FEEDBACKINTERVALBYMINUTES
	CONFIGURATION_SPNFB_FEEDBACKINTERVALBYTHREATS
	CONFIGURATION_SPNFB_INDUSTRYTYPE
	CONFIGURATION_AGENTCOMMUNICATIONS
	CONFIGURATION_AGENTHARDENING
	CONFIGURATION_AGENTHARDENINGPASSWORDFLAG
	CONFIGURATION_AGENTHARDENINGPASSWORDVALUE
	CONFIGURATION_AGENTINITIATEDACTIVATION
	CONFIGURATION_AGENTINITIATEDACTIVATIONACTIVEHOST
	CONFIGURATION_AGENTINITIATEDACTIVATIONALLOWHOSTNAME
	CONFIGURATION_AGENTINITIATEDACTIVATIONIPLIST
	CONFIGURATION_AGENTINITIATEDACTIVATIONSECURITYPROFILE
	CONFIGURATION_AGENTLOGFLUSHINTERVAL
	CONFIGURATION_ANTIMALWAREGLOBALMANUALSCANCONFIG

CONFIGURATION_ANTIMALWAREGLOBALREALTIMESCANCONFIG
CONFIGURATION_ANTIMALWAREGLOBALREALTIMESCANSCHEDULECONFIG
CONFIGURATION_ANTIMALWAREGLOBALSCHEDULEDSCANCONFIG
CONFIGURATION_ANTIMALWARESTATE
CONFIGURATION_AUTOREQUIRESUPDATE
CONFIGURATION_AUTOUPDATEAPPLIANCECOMPONENTAFTERACTIVATION
CONFIGURATION_AUTOMATICALLYDELETEANTIMALWAREEVENTSOLDERTHANMINUTES
CONFIGURATION_AUTOMATICALLYDELETETIMERSOLDERTHANMINUTES
CONFIGURATION_AUTOMATICALLYDELETEDPIEVENTSOLDERTHANMINUTES
CONFIGURATION_AUTOMATICALLYDELETEEVENTSOLDERTHANMINUTES
CONFIGURATION_AUTOMATICALLYDELETEFIREWALLEVENTSOLDERTHANMINUTES
CONFIGURATION_AUTOMATICALLYDELETEINTEGRITYEVENTSOLDERTHANMINUTES
CONFIGURATION_AUTOMATICALLYDELETELOGINSPECTIONEVENTSOLDERTHANMINUTES
CONFIGURATION_AUTOMATICALLYDELETEWEBREPUTATIONEVENTSOLDERTHANMINUTES
CONFIGURATION_AUTOMATICALLYUPDATEIPS
CONFIGURATION_CANHOSTCONTACTGLOBALIAU
CONFIGURATION_CANROAMINGAGENTUPDATECOMPONENT
CONFIGURATION_COLLECTFULLANTIMALWAREEVENTS
CONFIGURATION_COLLECTFULLINTEGRITYEVENTS
CONFIGURATION_COLLECTFULLLOGINSPECTIONEVENTS
CONFIGURATION_CONTEXTS_EXPECTEDCONTENTREGEX
CONFIGURATION_CONTEXTS_TESTINTERVAL
CONFIGURATION_CONTEXTS_TESTURI
CONFIGURATION_DEFAULTALERTEMAIL
CONFIGURATION_DEFAULTFORNEWADMINISTRATORSHIDEUNLICENSEDMODULES
CONFIGURATION_DEFAULTHEARTBEATPERIOD
CONFIGURATION_DETECTIONENGINESTATE
CONFIGURATION_DETECTIONENGINESTATEAUTOAPPLYDPIRULES
CONFIGURATION_DETECTIONENGINESTATEAUTOAPPLYINTEGRITYRULES
CONFIGURATION_DETECTIONENGINESTATEAUTOAPPLYLOGINSPECTIONRULES
CONFIGURATION_DSMGUID

CONFIGURATION_DSRAUTOAPPLYNEWDSRUS
CONFIGURATION_ENABLEEXCLUSIVEINTERFACES
CONFIGURATION_ENVIRONMENTVARIABLEOVERRIDES
CONFIGURATION_EXCLUSIVEINTERFACEPATTERNS
CONFIGURATION_EXPORTEDFILECHARACTERENCODING
CONFIGURATION_FORWARDLOGS_ANTIMALWARE
CONFIGURATION_FORWARDLOGS_ANTIMALWARE_DIRECT
CONFIGURATION_FORWARDLOGS_INTEGRITY
CONFIGURATION_FORWARDLOGS_INTEGRITY_DIRECT
CONFIGURATION_FORWARDLOGS_LOGINSPECTION
CONFIGURATION_FORWARDLOGS_LOGINSPECTION_DIRECT
CONFIGURATION_FORWARDLOGS_PNP
CONFIGURATION_FORWARDLOGS_PNP_DIRECT
CONFIGURATION_FORWARDLOGS_WRS
CONFIGURATION_FORWARDLOGS_WRS_DIRECT
CONFIGURATION_GENERATEDEVENTSPERMINUTE_ANTIMALWARE
CONFIGURATION_GENERATEDEVENTSPERMINUTE_INTEGRITY
CONFIGURATION_GENERATEDEVENTSPERMINUTE_LOGINSPECTION
CONFIGURATION_GENERATEDEVENTSPERMINUTE_PNP
CONFIGURATION_GENERATEDEVENTSPERMINUTE_WRS
CONFIGURATION_GLOBALSTATEFULCONFIG
CONFIGURATION_INTEGRITYCRITICALRANK
CONFIGURATION_INTEGRITYHIGHRANK
CONFIGURATION_INTEGRITYLOWRANK
CONFIGURATION_INTEGRITYMEDIUMRANK
CONFIGURATION_LOGINSPECTIONAPPLYTAGSTOGROUPS
CONFIGURATION_LOGINSPECTIONCRITICALRANK
CONFIGURATION_LOGINSPECTIONHIGHRANK
CONFIGURATION_LOGINSPECTIONLOWRANK
CONFIGURATION_LOGINSPECTIONMEDIUMRANK
CONFIGURATION_LOGINSPECTIONSTATE
CONFIGURATION_LOGINSPECTIONSTORAGECLIP
CONFIGURATION_LOGINSPECTIONSYSLOGCLIP

CONFIGURATION_LOGGINGOVERRIDE
CONFIGURATION_MAXHOSTCLOCKSHIFT
CONFIGURATION_MAXMISSEDHEARTBEATS
CONFIGURATION_MAXIMUMAGENTINSTALLERSARCHIVED
CONFIGURATION_MAXIMUMSECURITYUPDATESARCHIVED
CONFIGURATION_NETWORKCONTROLSTATE
CONFIGURATION_NETWORKDRIVERMODE
CONFIGURATION_NEWVMSACTIVATIONSECURITYPROFILE
CONFIGURATION_NONNOTIFYINGSYSTEMEVENTS
CONFIGURATION_NONRECORDINGSYSTEMEVENTS
CONFIGURATION_NOTIFICATIONMSGFORAM
CONFIGURATION_NOTIFICATIONMSGFORWP
CONFIGURATION_PACKET_DRIVER_BLOCKIPV6
CONFIGURATION_PACKET_DRIVER_BLOCKIPV6FOR8PLUS
CONFIGURATION_PACKET_DRIVER_BLOCKSAMESRCDSTIP
CONFIGURATION_PACKET_DRIVER_BYPASSWAASCONNECTIONS
CONFIGURATION_PACKET_DRIVER_CONNECTIONEVENTSICMP
CONFIGURATION_PACKET_DRIVER_CONNECTIONEVENTSTCP
CONFIGURATION_PACKET_DRIVER_CONNECTIONEVENTSUDP
CONFIGURATION_PACKET_DRIVER_DEBUGMODE
CONFIGURATION_PACKET_DRIVER_DEBUGPACKETMAX
CONFIGURATION_PACKET_DRIVER_DROP6TO4BOGONS
CONFIGURATION_PACKET_DRIVER_DROPEVASIVERETRANSMIT
CONFIGURATION_PACKET_DRIVER_DROPZEROPAYLOAD
CONFIGURATION_PACKET_DRIVER_DROP6TO4BOGONS
CONFIGURATION_PACKET_DRIVER_DROP6TO4MINMTU
CONFIGURATION_PACKET_DRIVER_DROP6TO4RESERVED
CONFIGURATION_PACKET_DRIVER_DROP6TO4SITELOCAL
CONFIGURATION_PACKET_DRIVER_DROP6TO4TYPE0
CONFIGURATION_PACKET_DRIVER_DROP6TO4ANOMALIES
CONFIGURATION_PACKET_DRIVER_DROP6TO4DEPTHCEXCEEDED
CONFIGURATION_PACKET_DRIVER_FILTERIPV4TUNNELS
CONFIGURATION_PACKET_DRIVER_FILTERIPV6TUNNELS

CONFIGURATION_PACKET_DRIVER_FRAGMINOFFSET
CONFIGURATION_PACKET_DRIVER_FRAGMINSIZE
CONFIGURATION_PACKET_DRIVER_IGNORESTATUS0
CONFIGURATION_PACKET_DRIVER_IGNORESTATUS1
CONFIGURATION_PACKET_DRIVER_IGNORESTATUS2
CONFIGURATION_PACKET_DRIVER_LOGRULES
CONFIGURATION_PACKET_DRIVER_LOGSPERSEC
CONFIGURATION_PACKET_DRIVER_MAXCONNECTIONSICMP
CONFIGURATION_PACKET_DRIVER_MAXCONNECTIONSPERIODICCLEANUP
CONFIGURATION_PACKET_DRIVER_MAXCONNECTIONSTCP
CONFIGURATION_PACKET_DRIVER_MAXCONNECTIONSUDP
CONFIGURATION_PACKET_DRIVER_MAXTUNNELDEPTH
CONFIGURATION_PACKET_DRIVER_NODEMAX
CONFIGURATION_PACKET_DRIVER_PASSNULLIP
CONFIGURATION_PACKET_DRIVER_PDUSNAPLENGTH
CONFIGURATION_PACKET_DRIVER_PDUSTATEFUL
CONFIGURATION_PACKET_DRIVER_PDUSTATEFULFIRST
CONFIGURATION_PACKET_DRIVER_PDUSTATEFULPERIOD
CONFIGURATION_PACKET_DRIVER_SETTINGSENABLED
CONFIGURATION_PACKET_DRIVER_SSLSESSIONSIZE
CONFIGURATION_PACKET_DRIVER_SSLSESSIONTIME
CONFIGURATION_PACKET_DRIVER_STRICTTEREDOPORTCHECK
CONFIGURATION_PACKET_DRIVER_TCPMSSLIMIT
CONFIGURATION_PACKET_DRIVER_TCPSILENTRST
CONFIGURATION_PACKET_DRIVER_TIMEOUTACKSTORM
CONFIGURATION_PACKET_DRIVER_TIMEOUTBOOTSTART
CONFIGURATION_PACKET_DRIVER_TIMEOUTCLOSEWAIT
CONFIGURATION_PACKET_DRIVER_TIMEOUTCLOSED
CONFIGURATION_PACKET_DRIVER_TIMEOUTCLOSING
CONFIGURATION_PACKET_DRIVER_TIMEOUTCOLDSTART
CONFIGURATION_PACKET_DRIVER_TIMEOUTCONNCLEANUP
CONFIGURATION_PACKET_DRIVER_TIMEOUTDISCONNECT
CONFIGURATION_PACKET_DRIVER_TIMEOUTERROR

CONFIGURATION_PACKET_DRIVER_TIMEOUTESTAB
CONFIGURATION_PACKET_DRIVER_TIMEOUTFINWAIT
CONFIGURATION_PACKET_DRIVER_TIMEOUTICMP
CONFIGURATION_PACKET_DRIVER_TIMEOUTLASTACK
CONFIGURATION_PACKET_DRIVER_TIMEOUTSYNRCVD
CONFIGURATION_PACKET_DRIVER_TIMEOUTSYNSENT
CONFIGURATION_PACKET_DRIVER_TIMEOUTUDP
CONFIGURATION_PACKET_DRIVER_VERIFYTCPCHECKSUM
CONFIGURATION_PACKETFILTERDENYRANK
CONFIGURATION_PACKETFILTERLOGONLYRANK
CONFIGURATION_PACKETFILTERREJECTIONRANK
CONFIGURATION_PACKETLOG_CACHELIFETIME
CONFIGURATION_PACKETLOG_CACHESIZE
CONFIGURATION_PACKETLOG_CACHESTALETIME
CONFIGURATION_PACKETLOG_IGNORE
CONFIGURATION_PACKETLOG_KEEP
CONFIGURATION_PACKETLOG_LOGOUTOFAALLOWEDPOLICY
CONFIGURATION_PACKETLOG_MAXSIZE
CONFIGURATION_PAYLOAD_DRIVER_IPFRAGSENDTIMEEXCEEDED
CONFIGURATION_PAYLOAD_DRIVER_MAXIPFRAG
CONFIGURATION_PAYLOAD_DRIVER_SETTINGSENABLED
CONFIGURATION_PAYLOAD_DRIVER_TIMEOUTFRAGMENT
CONFIGURATION_PAYLOADFILTERCRITICALRANK
CONFIGURATION_PAYLOADFILTERERRORRANK
CONFIGURATION_PAYLOADFILTERHIGHRANK
CONFIGURATION_PAYLOADFILTERLOWRANK
CONFIGURATION_PAYLOADFILTERMEDIUMRANK
CONFIGURATION_PAYLOADLOGFIRSTPDU
CONFIGURATION_PENDINGAGENTUPDATEALERTLIMIT
CONFIGURATION_PORTSTOSCAN
CONFIGURATION_QUARANTINE_MAXFILESIZE
CONFIGURATION_QUARANTINE_MAXGUESTSPACE
CONFIGURATION_QUARANTINE_MAXQUARANTINEDSPACE

CONFIGURATION_RAISEAGENTOFFLINEERRORSFORINACTIVEVMS
CONFIGURATION_RECOMMENDATIONMONITORINTERVAL
CONFIGURATION_RELAYUPDATESOURCE
CONFIGURATION_RELAYUPDATESOURCE_OTHERAU_URL
CONFIGURATION_SCANLIMITATION_MAXFILESCANSIZE
CONFIGURATION_SINGLEEXCLUSIVEINTERFACEENABLED
CONFIGURATION_SMARTPROTECTIONSERVER_PROXYIDFORGLOBALSERVER
CONFIGURATION_SMARTPROTECTIONSERVER_SMARTSCANALLOWFALLBACK
CONFIGURATION_SMARTPROTECTIONSERVER_SMARTSCANLOCALSERVERS
CONFIGURATION_SMARTPROTECTIONSERVER_SMARTSCANUSEGLOBALSERVER
CONFIGURATION_SMARTPROTECTIONSERVER_SMARTSCANUSEPROXYFORGLOBALSERVER
CONFIGURATION_SMARTPROTECTIONSERVER_WEBREPUTATIONALLOWGLOBAL
CONFIGURATION_SMARTPROTECTIONSERVER_WEBREPUTATIONLOCALRATINGSERVER
CONFIGURATION_SMARTPROTECTIONSERVER_WEBREPUTATIONRATINGSERVERPROXYID
CONFIGURATION_SMARTPROTECTIONSERVER_WEBREPUTATIONUSELOCALRATINGSERVER
CONFIGURATION_SMARTPROTECTIONSERVER_WEBREPUTATIONUSEPROXYFORGLOBALSERVER
CONFIGURATION_SMARTSCANSTATE
CONFIGURATION_SPYWAREAPPROVEDLIST
CONFIGURATION_SYSLOGFACILITY_ANTIMALWARE
CONFIGURATION_SYSLOGFACILITY_INTEGRITY
CONFIGURATION_SYSLOGFACILITY_LOGINSPECTION
CONFIGURATION_SYSLOGFACILITY_PNP
CONFIGURATION_SYSLOGFACILITY_WRS
CONFIGURATION_SYSLOGFORMAT_ANTIMALWARE
CONFIGURATION_SYSLOGFORMAT_INTEGRITY
CONFIGURATION_SYSLOGFORMAT_LOGINSPECTION
CONFIGURATION_SYSLOGFORMAT_PNP
CONFIGURATION_SYSLOGFORMAT_WRS
CONFIGURATION_SYSLOGHOST_ANTIMALWARE
CONFIGURATION_SYSLOGHOST_INTEGRITY

CONFIGURATION_SYSLOGHOST_LOGINSPECTION
CONFIGURATION_SYSLOGHOST_PNP
CONFIGURATION_SYSLOGHOST_WRS
CONFIGURATION_SYSLOGOVERRIDE_ANTIMALWARE
CONFIGURATION_SYSLOGOVERRIDE_INTEGRITY
CONFIGURATION_SYSLOGOVERRIDE_LOGINSPECTION
CONFIGURATION_SYSLOGOVERRIDE_PNP
CONFIGURATION_SYSLOGOVERRIDE_WRS
CONFIGURATION_SYSLOGPORT_ANTIMALWARE
CONFIGURATION_SYSLOGPORT_INTEGRITY
CONFIGURATION_SYSLOGPORT_LOGINSPECTION
CONFIGURATION_SYSLOGPORT_PNP
CONFIGURATION_SYSLOGPORT_WRS
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSCRIPTS
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSEXTENDEDDESCRIPTORS
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSNMPADDRESS
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSNMPCOMMUNITY
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSNMPENABLED
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSNMPPORT
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSNMPPRETRIES
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSNMPTIMEOUT
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSYSLOGADDRESS
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSYSLOGENABLED
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSYSLOGFACILITY
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSYSLOGFORMAT
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSYSLOGIDENTIFICATION
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSYSLOGPORT
CONFIGURATION_SYSTEMEVENTNOTIFICATIONSSYSLOGPREPENDTIMESTAMP
CONFIGURATION_SYSTEMINTEGRITYHASH
CONFIGURATION_SYSTEMINTEGRITYSTATE
CONFIGURATION_TRAFFICANALYSIS_FINGERPRINT_BLOCK
CONFIGURATION_TRAFFICANALYSIS_FINGERPRINT_ENABLED
CONFIGURATION_TRAFFICANALYSIS_FINGERPRINT_NOTIFY

CONFIGURATION_TRAFFICANALYSIS_GLOBAL_ANALYZE
CONFIGURATION_TRAFFICANALYSIS_GLOBAL_ENABLED
CONFIGURATION_TRAFFICANALYSIS_GLOBAL_IGNORE
CONFIGURATION_TRAFFICANALYSIS_NULL_BLOCK
CONFIGURATION_TRAFFICANALYSIS_NULL_ENABLED
CONFIGURATION_TRAFFICANALYSIS_NULL_NOTIFY
CONFIGURATION_TRAFFICANALYSIS_SCAN_BLOCK
CONFIGURATION_TRAFFICANALYSIS_SCAN_ENABLED
CONFIGURATION_TRAFFICANALYSIS_SCAN_NOTIFY
CONFIGURATION_TRAFFICANALYSIS_SYNFIN_BLOCK
CONFIGURATION_TRAFFICANALYSIS_SYNFIN_ENABLED
CONFIGURATION_TRAFFICANALYSIS_SYNFIN_NOTIFY
CONFIGURATION_TRAFFICANALYSIS_XMAS_BLOCK
CONFIGURATION_TRAFFICANALYSIS_XMAS_ENABLED
CONFIGURATION_TRAFFICANALYSIS_XMAS_NOTIFY
CONFIGURATION_UPDATEPROXYAUTH
CONFIGURATION_UPDATEPROXYFLAG
CONFIGURATION_UPDATEPROXYHOST
CONFIGURATION_UPDATEPROXYID
CONFIGURATION_UPDATEPROXYPASS
CONFIGURATION_UPDATEPROXYPORT
CONFIGURATION_UPDATEPROXYTYPE
CONFIGURATION_UPDATEPROXYUSER
CONFIGURATION_UPDATESOURCE
CONFIGURATION_UPDATESOURCE_INTRANET_UNC
CONFIGURATION_UPDATESOURCE_INTRANET_PASSWORD
CONFIGURATION_UPDATESOURCE_INTRANET_USER
CONFIGURATION_UPDATESOURCE_OTHERAU_URL
CONFIGURATION_VSUAUTOASSIGN
CONFIGURATION_VULNERABILITYSHIELDSTATE
CONFIGURATION_WEBREPUTATIONALERTINGON
CONFIGURATION_WEBREPUTATIONALLOWEDDOMAINURLS
CONFIGURATION_WEBREPUTATIONALLOWEDPAGEURLS

CONFIGURATION_WEBREPUTATIONBLOCKUNTESTEDPAGES
CONFIGURATION_WEBREPUTATIONBLOCKEDBYADMINISTRATORRANK
CONFIGURATION_WEBREPUTATIONBLOCKEDDOMAINURLS
CONFIGURATION_WEBREPUTATIONBLOCKEDKEYWORDS
CONFIGURATION_WEBREPUTATIONBLOCKEDPAGELINK
CONFIGURATION_WEBREPUTATIONBLOCKEDPAGEURLS
CONFIGURATION_WEBREPUTATIONDANGEROUSRANK
CONFIGURATION_WEBREPUTATIONENABLED
CONFIGURATION_WEBREPUTATIONHIGHLYSUSPICIOUSRANK
CONFIGURATION_WEBREPUTATIONPORTS
CONFIGURATION_WEBREPUTATIONSECURITYLEVEL
CONFIGURATION_WEBREPUTATIONSUSPICIOUSRANK
CONFIGURATION_WEBREPUTATIONUNTESTEDRANK
CONFIGURATION_WEBSERVICEAPIENABLED
LICENSES_HISTORIC
SECURITY_ACTIVESESSIONSALLOWED
SECURITY_ADMINISTRATORPASSWORDEXPIRY
SECURITY_ADMINISTRATORPASSWORDMINIMUMLENGTH
SECURITY_ADMINISTRATORPASSWORDREQUIRECASE
SECURITY_ADMINISTRATORPASSWORDREQUIREMIX
SECURITY_ADMINISTRATORPASSWORDREQUIRESPECIAL
SECURITY_MINUTESTOTIMEOUT
SECURITY_SIGNINATTEMPTSALLOWED
SMTP_BOUNCEEMAIL
SMTP_FROMEMAIL
SMTP_PASSWORD
SMTP_REQUIRESAUTHENTICATION
SMTP_URL
SMTP_USERNAME
WHOIS_IP

EnumEditableSettingStoredScope

DESCRIPTION	Editable setting scope enumeration. This enumeration indicates which level to assign the setting to, such as configuring the Syslog target settings at the Computer/Host level, or at the Security Profile level.
Values	HOST PROFILE SYSTEM

EnumEditableSettingUnit

DESCRIPTION	Editable setting unit enumeration. This enumeration indicates a system settings unit or type.
Values	IPLIST_ID PORTLIST_ID NONE SECONDS MINUTES HOURS DAYS WEEKS MONTHS YEARS KBYTES PERCENT PORT HOST EMAIL

EnumEventOrigin

DESCRIPTION The origin of an event enumeration.

Values	UNKNOWN AGENT GUESTAGENT APPLIANCEAGENT MANAGER
---------------	---

EnumExternalFilterType

DESCRIPTION The action a Firewall rule should result in once applied enumeration.

Values	ALL_EXT_HOSTS HOSTS_IN_EXT_GROUP HOSTS_IN_EXT_GROUP_AND_ALL_SUBGROUPS SPECIFIC_EXT_HOST
---------------	--

EnumFirewallRuleAction

DESCRIPTION The action a Firewall rule should result in once applied enumeration.

Values	LOG_ONLY ALLOW DENY FORCE_ALLOW BYPASS
---------------	--

EnumFirewallRuleFrameType

DESCRIPTION A Firewall rule frame type enumeration.

Values	ANY IP ARP REVARP OTHER
---------------	-------------------------------------

EnumFirewallRuleIPType

DESCRIPTION A Firewall rule IP type enumeration.

Values

ANY
MASKED_IP
RANGE
DEFINED_LIST
SINGLE_IP

EnumFirewallRulePriority

DESCRIPTION A Firewall rule Priority enumeration.

Values

HIGHEST
HIGH
NORMAL
LOW
LOWEST

EnumFirewallRuleProtocolType

DESCRIPTION A Firewall rule Protocol type enumeration.

Values

ANY
ICMP
ICMPV6
IGMP
GGP
TCP
PUP
UDP
IDP
ND
RAW
TCP_UDP
OTHER

EnumHostDetailLevel

DESCRIPTION Host/Computer detail level enumeration.

Values	LOW
	MEDIUM
	HIGH

EnumHostFilterType

DESCRIPTION Host/Computer filter type used when filtering retrieved events by Host, Group, Security Profile or specific Hosts.

Values	ALL_HOSTS
	HOSTS_IN_GROUP
	HOSTS_USING_SECURITY_PROFILE
	HOSTS_IN_GROUP_AND_ALL_SUBGROUPS
	SPECIFIC_HOST
	MY_HOSTS

EnumHostLight

DESCRIPTION Host/Computer Light color enumeration.

Values	GREEN
	YELLOW
	RED
	GREY
	BLUE

EnumHostType

DESCRIPTION Host/Computer type enumeration. Used to determine if the retrieve HostTransport object is a VM, standard physical computer, ESX server, or Virtual Appliance.

Values	STANDARD
	ESX
	APPLIANCE
	VM

EnumIntegrityRuleSeverity

DESCRIPTION Integrity Monitoring rule severity enumeration.

Values	CRITICAL
	HIGH
	MEDIUM
	LOW

EnumJobType

DESCRIPTION Job Type enumeration.

Values	UPDATE
---------------	--------

EnumMalwareType

DESCRIPTION Malware type enumeration.

Values	GENERAL
	SPYWARE

EnumMACType

DESCRIPTION MAC List type enumeration.

Values	ANY
	MAC
	DEFINED_LIST

EnumOperator

DESCRIPTION General filter operator enumeration. Used when filtering retrieved events by event ID that are greater than, less than, or equal to.

Values	GREATER_THAN
	LESS_THAN
	EQUAL

EnumPortType

DESCRIPTION Port List type enumeration.

Values	ANY
	MAC
	DEFINED_LIST

EnumProtectionType

DESCRIPTION Computer protection type enumeration. Protection for a computer can be applied by an installed Agent or by the Deep Security Virtual Appliance.

Values	NONE
	AGENT
	APPLIANCE

EnumProtocolIcmpType

DESCRIPTION ICMP protocol type enumeration.

Values	ICMP_ECHO
	ICMP_TIMESTAMP
	ICMP_INFORMATION
	ICMP_ADDRESS_MASK
	ICMP_MOBILE_REGISTRATION

EnumSecurityProfileDPIState

DESCRIPTION Security Profile DPI configured state enumeration.

Values	ON
	OFF
	PASSIVE
	INHERITED

EnumSecurityProfileFirewallState

DESCRIPTION Security Profile Firewall configured state enumeration.

Values	ON
	OFF
	INHERITED

EnumSecurityProfileAntiMalwareState

DESCRIPTION Security Profile Anti Malware configured state enumeration.

Values	ON
	OFF
	INHERITED

EnumSecurityProfileIntegrityState

DESCRIPTION Security Profile Integrity Monitoring configured state enumeration.

Values	ON
	OFF
	INHERITED

EnumSecurityProfileLogInspectionState

DESCRIPTION Security Profile Log Inspection configured state enumeration.

Values	ON
	OFF
	INHERITED

EnumSecurityProfileRecommendationState

DESCRIPTION Security Profile Recommendation Engine configured state enumeration.

Values	OFF
	ONGOING

EnumWebReputationEventRisk

DESCRIPTION Web Reputation Event Risk enumeration.

Values	SAFE SUSPICIOUS HIGHLYSUSPICIOUS DANGEROUS UNTESTED BLOCKEDBYADMINISTRATOR
--------	---

EnumSecurityUpdateAppliedState

DESCRIPTION Security Update applied state. Can be used to determine if a retrieved or applied Security Update has been applied and is currently active.

Values	APPLIED APPLIED_CURRENT NOT_APPLIED
--------	---

EnumState

DESCRIPTION Computer HostTransport state enumeration that can be used to determine what state a computer is currently in.

Values	NEUTRAL VM_STOPPED VM_PAUSED STANDBY UNKNOWN NONE INSTALLED HAS_DSM_CERT ACTIVATED OTHER_DSM_AGENT OFFLINE
--------	--

EnumTagFilterType

DESCRIPTION Tag Filters Type enumeration.

Values	ALL
	UNTAGGED
	TAGS

EnumTimeFilterType

DESCRIPTION Time based filter enumeration. Used when filtering retrieved events by event time.

Values	LAST_HOUR
	LAST_24_HOURS
	LAST_7_DAYS
	CUSTOM_RANGE
	SPECIFIC_TIME

EnumRuleType

DESCRIPTION Rule Type enumeration.

Values	APPLICATIONTYPE
	PAYLOADFILTER
	FIREWALLRULE
	INTEGRITYRULE
	LOGINSPECTIONRULE

Web Methods

softwareRetrieveForHost()

DESCRIPTION Retrieves the software for a provided host id.

SYNTAX

```
SoftwareTransport[] softwareRetrieveForHost(int hostID, String sID)
```

PARAMETERS

hostID Identifying Host ID.

sID Authentication session token ID.

RETURNS SoftwareTransport object array.

softwareVersionStringsCompare()

DESCRIPTION Compares two software version strings.

SYNTAX

```
EnumCompareResults softwareVersionStringsCompare(String version1, String version2, String sID)
```

PARAMETERS

version1 First version to compare.

version2 Second version to compare.

sID Authentication session token ID.

RETURNS -1 if version1 < version2
0 if version1 = version2
1 if version1 > version2
2 if version1 and version2 are incompatible version types.

systemInformationRetrieve()

DESCRIPTION Retrieves system information.

SYNTAX

SystemInformationTransport[] systemInformationRetrieve(String sID)

PARAMETERS

sID Authentication session token ID.

RETURNS SystemInformationTransport object array.

hostGroupRetrieve()

DESCRIPTION Retrieves a Host Group by ID.

SYNTAX

HostGroupTransport hostGroupRetrieve(int ID, String sID)

PARAMETERS

ID Identifying Host Group ID.

sID Authentication session identifier ID.

RETURNS HostGroupTransport object.

hostGroupRetrieveByName()

DESCRIPTION Retrieves a Host Group by name.

SYNTAX

HostGroupTransport hostGroupRetrieveByName(String Name, String sID)

PARAMETERS

Name Identifying Host Group name.

sID Authentication session identifier ID.

RETURNS HostGroupTransport object.

hostGroupRetrieveAll()

DESCRIPTION Retrieves all Host Groups.

SYNTAX

```
HostGroupTransport[] hostGroupRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS HostGroupTransport object array.

hostGroupDelete()

DESCRIPTION Deletes a Host Group by ID.

SYNTAX

```
void hostGroupDelete(int ID, String sID)
```

PARAMETERS

ID Identifying Host Group ID.

sID Authentication session identifier ID.

hostGroupCreate()

DESCRIPTION Creates a new Host Group.

SYNTAX

```
HostGroupTransport hostGroupCreate(HostGroupTransport hostGroup, String sID)
```

PARAMETERS

hostGroup HostGroupTransport object to create.

sID Authentication session identifier ID.

RETURNS Newly created HostGroupTransport object.

softwareApplyToHosts()

DESCRIPTION Apply an Agent software install to hosts by IDs.

SYNTAX

```
void softwareApplyToHosts(int[] hostIDs, String installerVersion, String sID)
```

PARAMETERS

hostIDs Array of host IDs to apply software to.

installerVersion The version of the software install to apply.

sID Authentication session identifier ID.

RETURNS Security Center customer account username.

softwareStore()

DESCRIPTION Uploads and stores an Agent software installer on the Manager.

SYNTAX

```
SoftwareTransport softwareStore(byte[] software, String fileName, String notes, String sID)
```

PARAMETERS

software Byte array representation of the software to upload and store.

fileName The filename of the software.

notes Any notes to associate with the software file.

sID Authentication session identifier ID.

RETURNS The resulting uploaded SoftwareTransport object.

softwareRetrieve()

DESCRIPTION Retrieves Agent install file SoftwareTransport object by ID.

SYNTAX

SoftwareTransport softwareRetrieve(int ID, String sID)

PARAMETERS

ID SoftwareTransport ID.

sID Authentication session identifier ID.

RETURNS The resulting uploaded SoftwareTransport object.

softwareRetrieveAll()

DESCRIPTION Retrieves all Agent install file SoftwareTransport objects.

SYNTAX

SoftwareTransport[] softwareRetrieveAll(String sID)

PARAMETERS

sID Authentication session identifier ID.

RETURNS SoftwareTransport object array.

softwareExport()

DESCRIPTION Retrieves byte array representation of Agent install file object by ID.

SYNTAX

byte[] softwareExport(int id, String sID)

PARAMETERS

ID SoftwareTransport ID.

sID Authentication session identifier ID.

RETURNS Byte array representation of the retrieved software file.

softwareDelete()

DESCRIPTION Deletes Agent install file by ID.

SYNTAX

```
void softwareDelete(int[] ids, String sID)
```

PARAMETERS

ids	The list of agent installers to delete
sID	Authentication session identifier ID.

securityUpdateStore()

DESCRIPTION Stores the provided Security Update on the Manager.

SYNTAX

```
SecurityUpdateTransport securityUpdateStore(byte[] securityUpdate, String fileName, String sID)
```

PARAMETERS

securityUpdate	The raw Security Update as provided by Security Center
fileName	The name of the Security Update
sID	Authentication session identifier ID.

RETURNS SecurityUpdateTransport object

securityUpdateGetApplierInformation()

DESCRIPTION Retrieves Security Update information on what would be applied.

SYNTAX

```
ApplierInformationTransport securityUpdateGetApplierInformation(int ID, String sID)
```

PARAMETERS

ID	Security Update ID.
sID	Authentication session identifier ID.

RETURNS ApplierInformationTransport object.

securityUpdateApply()

DESCRIPTION Applies a Security Update.

SYNTAX

ApplierInformationTransport securityUpdateApply(int ID, boolean detectOnly, String sID)

PARAMETERS

ID Security Update ID.

detectOnly Apply in detect only mode.

sID Authentication session identifier ID.

RETURNS ApplierInformationTransport object of the applied Security Update.

securityUpdateRetrieve()

DESCRIPTION Retrieves Security Update.

SYNTAX

SecurityUpdateTransport securityUpdateRetrieve(int ID, String sID)

PARAMETERS

ID Security Update ID.

sID Authentication session identifier ID.

RETURNS SecurityUpdateTransport object.

securityUpdateRetrieveAll()

DESCRIPTION Retrieves all Security Updates.

SYNTAX

SecurityUpdateTransport[] securityUpdateRetrieveAll(String sID)

PARAMETERS

sID Authentication session identifier ID.

RETURNS SecurityUpdateTransport object array.

securityUpdateExport()

DESCRIPTION Retrieves byte array representation of a Security Update.

SYNTAX

```
byte[] securityUpdateExport(int ID, String sID)
```

PARAMETERS

ID Security Update ID.

sID Authentication session identifier ID.

RETURNS Byte array representation of the exported Security Update file.

securityUpdateDelete()

DESCRIPTION Deletes a Security Update.

SYNTAX

```
void securityUpdateDelete(int[] ids, String sID)
```

PARAMETERS

ids Array of Security Update IDs to delete.

sID Authentication session identifier ID.

getApiVersion()

DESCRIPTION Retrieves the Manager Web Service API version. Not the same as the Manager version.

SYNTAX

```
int getApiVersion()
```

PARAMETERS

RETURNS The Web Service API version.

getManagerTime()

DESCRIPTION Retrieve the Manager Web Service API version. Not the same as the Manager version.

SYNTAX

Date getManagerTime()

PARAMETERS

RETURNS Manager time as a language localized object. For example, a Java client would return a Calendar object, and a C# client would return a DateTime object.

authenticate()

DESCRIPTION Authenticates a user for and returns a session ID for use when calling other Web Service methods.

SYNTAX

String authenticate(String username, String password)

PARAMETERS

username Account username.

password Account password.

RETURNS Authenticated user session ID.

authenticateTenant ()

DESCRIPTION Authenticates a user within the given tenant, and returns a session ID for use when calling other methods of Manager. When no longer required, the session should be terminated by calling endSession.

SYNTAX

String authenticateTenant(String tenantName, String username, String password)

PARAMETERS

tenantName Tenant Name.

username Account username.

password Account password.

RETURNS Authenticated user session ID.

endSession()

DESCRIPTION Ends an authenticated user session. The Web Service client should end the authentication session in all exit cases.

SYNTAX

```
void endSession(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS

portListDelete()

DESCRIPTION Deletes Port Lists by ID.

SYNTAX

```
void portListDelete(int[] ids, String sID)
```

PARAMETERS

ids Port List IDs to delete.

sID Authentication session identifier ID.

RETURNS

portListSave()

DESCRIPTION Saves a new or existing Port List.

SYNTAX

```
PortListTransport portListSave(PortListTransport pl, String sID)
```

PARAMETERS

pl PortListTransport object to create.

sID Authentication session identifier ID.

RETURNS Newly created PortListTransport object.

portListRetrieve()

DESCRIPTION Retrieves a Port List by ID.

SYNTAX

```
PortListTransport portListRetrieve(int ID, String sID)
```

PARAMETERS

ID Port List ID.

sID Authentication session identifier ID.

RETURNS PortListTransport object.

portListRetrieveByName()

DESCRIPTION Retrieves a Port List by name.

SYNTAX

```
PortListTransport portListRetrieveByName(String name, String sID)
```

PARAMETERS

name Port List name.

sID Authentication session identifier ID.

RETURNS PortListTransport object.

portListRetrieveAll()

DESCRIPTION Retrieves all Port Lists.

SYNTAX

```
PortListTransport[] portListRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS PortListTransport object array.

MACListDelete()

DESCRIPTION Deletes MAC Lists by ID.

SYNTAX

```
void MACListDelete(int[] IDs, String sID)
```

PARAMETERS

IDs	MAC List IDs to delete.
sID	Authentication session identifier ID.

MACListSave()

DESCRIPTION Saves a new or existing MAC List.

SYNTAX

```
MACListTransport MACListSave(MACListTransport ml, String sID)
```

PARAMETERS

ml	MACListTransport object to create.
sID	Authentication session identifier ID.

RETURNS Newly created MACListTransport object.

MACListRetrieve()

DESCRIPTION Retrieves a MAC List by ID.

SYNTAX

```
MACListTransport MACListRetrieve(int ID, String sID)
```

PARAMETERS

ID	MAC List ID.
sID	Authentication session identifier ID.

RETURNS MACListTransport object.

MACListRetrieveByName()

DESCRIPTION Retrieves a MAC List by name.

SYNTAX

MACListTransport MACListRetrieveByName(String name, String sID)

PARAMETERS

name MAC List name.

sID Authentication session identifier ID.

RETURNS MACListTransport object.

MACListRetrieveAll()

DESCRIPTION Retrieves all MAC Lists.

SYNTAX

MACListTransport[] MACListRetrieveAll(String sID)

PARAMETERS

sID Authentication session identifier ID.

RETURNS MACListTransport object array.

IPListDelete()

DESCRIPTION Deletes IP Lists by ID.

SYNTAX

void IPListDelete(int[] ids, String sID)

PARAMETERS

ids IP List IDs to delete.

sID Authentication session identifier ID.

IPListSave()

DESCRIPTION Saves a new or existing IP List.

SYNTAX

IPLISTTransport IPLISTSave(MACLISTTransport ipl, String sID)

PARAMETERS

ipl IPLISTTransport object to create.

sID Authentication session identifier ID.

RETURNS Newly created IPLISTTransport object.

IPLISTRetrieve()

DESCRIPTION Retrieves an IP List by ID.

SYNTAX

IPLISTTransport IPLISTRetrieve(int ID, String sID)

PARAMETERS

ID IP List ID.

sID Authentication session identifier ID.

RETURNS IPLISTTransport object.

IPLISTRetrieveByName()

DESCRIPTION Retrieves an IP List by name.

SYNTAX

IPLISTTransport IPLISTRetrieveByName(String name, String sID)

PARAMETERS

name IP List name.

sID Authentication session identifier ID.

RETURNS IPLISTTransport object.

IPListRetrieveAll()

DESCRIPTION Retrieves all IP Lists.

SYNTAX

```
IPListTransport[] IPListRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS IPListTransport object array.

applicationTypeDelete()

DESCRIPTION Deletes Application Type by ID. Note that Application Types issued by Trend Micro cannot be deleted.

SYNTAX

```
void applicationTypeDelete(int[] ids, String sID)
```

PARAMETERS

ids Application Type IDs to delete.

sID Authentication session identifier ID.

RETURNS

applicationTypeSave()

DESCRIPTION Saves a new or existing Application Type. Note that Application Types issued by Trend Micro cannot be saved.

SYNTAX

```
ApplicationTypeTransport applicationTypeSave(ApplicationTypeTransport at, String sID)
```

PARAMETERS

at ApplicationTypeTransport object to create.

sID Authentication session identifier ID.

RETURNS Newly created ApplicationTypeTransport object.

applicationTypeRetrieve()

DESCRIPTION Retrieves an Application Type by ID.

SYNTAX

ApplicationTypeTransport applicationTypeRetrieve (int ID, String sID)

PARAMETERS

ID Application Type ID.

sID Authentication session identifier ID.

RETURNS ApplicationTypeTransport object.

applicationTypeRetrieveByName()

DESCRIPTION Retrieves an Application Type by name.

SYNTAX

ApplicationTypeTransport applicationTypeRetrieveByName(String name, String sID)

PARAMETERS

name Application Type name.

sID Authentication session identifier ID.

RETURNS ApplicationTypeTransport object.

applicationTypeRetrieveAll()

DESCRIPTION Retrieves all Application Types.

SYNTAX

ApplicationTypeTransport[] applicationTypeRetrieveAll(String sID)

PARAMETERS

sID Authentication session identifier ID.

RETURNS ApplicationTypeTransport object array.

applicationTypeOverrideDelete()

DESCRIPTION Deletes Application Type Override by ID.

SYNTAX

```
void applicationTypeOverrideDelete(int[] ids, String sID)
```

PARAMETERS

ids Application Type Override IDs to delete.

sID Authentication session identifier ID.

RETURNS

applicationTypeOverrideSave()

DESCRIPTION Saves a new or existing Application Type Override.

SYNTAX

```
ApplicationTypeOverrideTransport applicationTypeOverrideSave(ApplicationTypeOverrideTransport at,  
String sID)
```

PARAMETERS

at ApplicationTypeOverrideTransport object to save.

sID Authentication session identifier ID.

RETURNS Newly created or updated ApplicationTypeOverrideTransport object.

applicationTypeOverrideRetrieve()

DESCRIPTION Retrieves an Application Type Override by ID.

SYNTAX

```
ApplicationTypeOverrideTransport applicationTypeOverrideRetrieve (int ID, String sID)
```

PARAMETERS

ID Application Type Override ID.

sID Authentication session identifier ID.

RETURNS ApplicationTypeOverrideTransport object.

applicationTypeOverrideRetrieveAll()

DESCRIPTION Retrieves all Application Type Overrides.

SYNTAX

ApplicationTypeOverrideTransport[] applicationTypeOverrideRetrieveAll(String sID)

PARAMETERS

sID Authentication session identifier ID.

RETURNS ApplicationTypeOverrideTransport object array.

firewallRuleDelete()

DESCRIPTION Deletes Firewall Rules by ID.

SYNTAX

void firewallRuleDelete(int[] ids, String sID)

PARAMETERS

ids Firewall Rule IDs to delete.

sID Authentication session identifier ID.

firewallRuleSave()

DESCRIPTION Saves a new or existing Firewall Rule.

SYNTAX

FirewallRuleTransport firewallRuleSave(FirewallRuleTransport fr, String sID)

PARAMETERS

fr FirewallRuleTransport object to create.

sID Authentication session identifier ID.

RETURNS Newly created FirewallRuleTransport object.

firewallRuleRetrieve()

DESCRIPTION Retrieves a Firewall Rule by ID.

SYNTAX

```
FirewallRuleTransport firewallRuleRetrieve(int ID, String sID)
```

PARAMETERS

ID	Firewall Rule ID.
sID	Authentication session identifier ID.

RETURNS FirewallRuleTransport object.

firewallRuleRetrieveByName()

DESCRIPTION Retrieves a Firewall Rule by name.

SYNTAX

```
FirewallRuleTransport firewallRuleRetrieveByName(String name, String sID)
```

PARAMETERS

name	Firewall Rule name.
sID	Authentication session identifier ID.

RETURNS FirewallRuleTransport object.

firewallRuleRetrieveAll()

DESCRIPTION Retrieves all Firewall Rule.

SYNTAX

```
FirewallRuleTransport[] firewallRuleRetrieveAll(String sID)
```

PARAMETERS

sID	Authentication session identifier ID.
-----	---------------------------------------

RETURNS FirewallRuleTransport object array.

DPIRuleDelete()

DESCRIPTION Deletes DPI Rules by ID.

SYNTAX

```
void DPIRuleDelete(int[] ids, String sID)
```

PARAMETERS

ids	DPI Rule IDs to delete.
sID	Authentication session identifier ID.

DPIRuleSave()

DESCRIPTION Saves a new or existing DPI Rule.

SYNTAX

```
DPIRuleTransport DPIRuleSave(DPIRuleTransport ipsf, String sID)
```

PARAMETERS

ipsf	The DPIRuleTransport to save.
sID	Authentication session identifier ID.

RETURNS Newly created DPIRuleTransport object.

DPIRuleRetrieve()

DESCRIPTION Retrieves a DPI Rule by ID.

SYNTAX

```
DPIRuleTransport DPIRuleRetrieve(int ID, String sID)
```

PARAMETERS

ID	DPI Rule ID.
sID	Authentication session identifier ID.

RETURNS DPIRuleTransport object.

DPIRuleRetrieveByName()

DESCRIPTION Retrieves a DPI Rule by name.

SYNTAX

```
DPIRuleTransport DPIRuleRetrieveByName(String name, String sID)
```

PARAMETERS

name	DPI Rule name.
sID	Authentication session identifier ID.

RETURNS DPIRuleTransport object.

DPIRuleRetrieveAll()

DESCRIPTION Retrieves all DPI Rule.

SYNTAX

```
DPIRuleTransport[] DPIRuleRetrieveAll(String sID)
```

PARAMETERS

sID	Authentication session identifier ID.
-----	---------------------------------------

RETURNS DPIRuleTransport object array.

logInspectionRuleDelete()

DESCRIPTION Deletes Log Inspection Rules by ID.

SYNTAX

```
void logInspectionRuleDelete(int[] ids, String sID)
```

PARAMETERS

ids	Log Inspection Rule IDs to delete.
sID	Authentication session identifier ID.

logInspectionRuleSave()

DESCRIPTION Saves a new or existing Log Inspection Rule.

SYNTAX

```
LogInspectionRuleTransport logInspectionRuleSave(LogInspectionRuleTransport irt, String sID)
```

PARAMETERS

irt LogInspectionRuleTransport object to create.

sID Authentication session identifier ID.

RETURNS Newly created LogInspectionRuleTransport object.

logInspectionRuleRetrieve()

DESCRIPTION Retrieves a Log Inspection Rule by ID.

SYNTAX

```
LogInspectionRuleTransport logInspectionRuleRetrieve(int id, String sID)
```

PARAMETERS

id Log Inspection Rule ID.

sID Authentication session identifier ID.

RETURNS LogInspectionRuleTransport object.

logInspectionRuleRetrieveByName()

DESCRIPTION Retrieves a Log Inspection Rule by name.

SYNTAX

```
LogInspectionRuleTransport logInspectionRuleRetrieveByName(String name, String sID)
```

PARAMETERS

name Log Inspection Rule name.

sID Authentication session identifier ID.

RETURNS LogInspectionRuleTransport object.

logInspectionRuleRetrieveAll()

DESCRIPTION Retrieves all Log Inspection Rule.

SYNTAX

```
LogInspectionRuleTransport[] logInspectionRuleRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS LogInspectionRuleTransport object array.

logInspectionDecoderDelete()

DESCRIPTION Deletes Log Inspection Decoder by ID.

SYNTAX

```
void logInspectionDecoderDelete(int[] ids, String sID)
```

PARAMETERS

ids Log Inspection Decoder IDs to delete.

sID Authentication session identifier ID.

logInspectionDecoderSave()

DESCRIPTION Saves a new or existing Log Inspection Decoder.

SYNTAX

```
LogInspectionDecoderTransport logInspectionDecoderSave(LogInspectionDecoderTransport irt, String sID)
```

PARAMETERS

irt LogInspectionDecoderTransport object to create.

sID Authentication session identifier ID.

RETURNS Newly created LogInspectionDecoderTransport object.

logInspectionDecoderRetrieve()

DESCRIPTION Retrieves a Log Inspection Decoder by ID.

SYNTAX

```
LogInspectionDecoderTransport logInspectionDecoderRetrieve(int ID, String sID)
```

PARAMETERS

ID	Log Inspection Decoder ID.
sID	Authentication session identifier ID.

RETURNS LogInspectionDecoderTransport object.

logInspectionDecoderRetrieveByName()

DESCRIPTION Retrieves a Log Inspection Decoder by name.

SYNTAX

```
LogInspectionDecoderTransport logInspectionDecoderRetrieveByName(String Name, String sID)
```

PARAMETERS

Name	Log Inspection Decoder name.
sID	Authentication session identifier ID.

RETURNS LogInspectionDecoderTransport object.

logInspectionDecoderRetrieveAll()

DESCRIPTION Retrieves all Log Inspection Decoder.

SYNTAX

```
LogInspectionDecoderTransport[] logInspectionDecoderRetrieveAll(String sID)
```

PARAMETERS

sID	Authentication session identifier ID.
-----	---------------------------------------

RETURNS LogInspectionDecoderTransport object array.

integrityRuleDelete()

DESCRIPTION Deletes Integrity Rules by ID.

SYNTAX

```
void integrityRuleDelete(int[] ids, String sID)
```

PARAMETERS

ids	Integrity Rule IDs to delete.
sID	Authentication session identifier ID.

integrityRuleSave()

DESCRIPTION Saves a new or existing Integrity Rule.

SYNTAX

```
IntegrityRuleTransport integrityRuleSave(IntegrityRuleTransport irt, String sID)
```

PARAMETERS

irt	IntegrityRuleTransport object to create.
sID	Authentication session identifier ID.

RETURNS Newly created IntegrityRuleTransport object.

integrityRuleRetrieve()

DESCRIPTION Retrieves an Integrity Rule by ID.

SYNTAX

```
IntegrityRuleTransport integrityRuleRetrieve(int ID, String sID)
```

PARAMETERS

ID	Integrity Rule ID.
sID	Authentication session identifier ID.

RETURNS IntegrityRuleTransport object.

integrityRuleRetrieveByName()

DESCRIPTION Retrieves an Integrity Rule by name.

SYNTAX

```
IntegrityRuleTransport integrityRuleRetrieveByName(String name, String sID)
```

PARAMETERS

name Integrity Rule name.

sID Authentication session identifier ID.

RETURNS IntegrityRuleTransport object.

integrityRuleRetrieveAll()

DESCRIPTION Retrieves all Integrity Rules.

SYNTAX

```
IntegrityRuleTransport[] integrityRuleRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS IntegrityRuleTransport object array.

scheduleDelete()

DESCRIPTION Deletes Schedule by ID.

SYNTAX

```
void scheduleDelete (int[] IDs, String sID)
```

PARAMETERS

ids Schedule IDs to delete.

sID Authentication session identifier ID.

scheduleSave()

DESCRIPTION Saves a new or existing Schedule.

SYNTAX

```
ScheduleTransport scheduleSave(ScheduleTransport s, String sID)
```

PARAMETERS

s ScheduleTransport object to create.

sID Authentication session identifier ID.

RETURNS Newly created ScheduleTransport object.

scheduleRetrieve()

DESCRIPTION Retrieves a Schedule by ID.

SYNTAX

```
ScheduleTransport scheduleRetrieve(int id, String sID)
```

PARAMETERS

id Schedule ID.

sID Authentication session identifier ID.

RETURNS ScheduleTransport object.

scheduleRetrieveByName()

DESCRIPTION Retrieves a Schedule by name.

SYNTAX

```
ScheduleTransport scheduleRetrieveByName(String name, String sID)
```

PARAMETERS

name Schedule name.

sID Authentication session identifier ID.

RETURNS ScheduleTransport object.

scheduleRetrieveAll()

DESCRIPTION Retrieves all Schedules.

SYNTAX

```
ScheduleTransport[] scheduleRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS ScheduleTransport object array.

statefulConfigurationDelete()

DESCRIPTION Deletes Stateful Configuration by ID.

SYNTAX

```
void statefulConfigurationDelete(int[] ids, String sID)
```

PARAMETERS

ids Stateful Configuration IDs to delete.

sID Authentication session identifier ID.

statefulConfigurationSave()

DESCRIPTION Saves a new or existing Stateful Configuration.

SYNTAX

```
StatefulConfigurationTransport statefulConfigurationSave(StatefulConfigurationTransport s, String sID)
```

PARAMETERS

s StatefulConfigurationTransport object to create.

sID Authentication session identifier ID.

RETURNS Newly created StatefulConfigurationTransport object.

statefulConfigurationRetrieve()

DESCRIPTION Retrieves a Stateful Configuration by ID.

SYNTAX

StatefulConfigurationTransport statefulConfigurationRetrieve(int id, String sID)

PARAMETERS

id Stateful Configuration ID.
sID Authentication session identifier ID.

RETURNS StatefulConfigurationTransport object.

statefulConfigurationRetrieveByName()

DESCRIPTION Retrieves a Stateful Configuration by name.

SYNTAX

StatefulConfigurationTransport statefulConfigurationRetrieveByName(String Name, String sID)

PARAMETERS

name Stateful Configuration name.
sID Authentication session identifier ID.

RETURNS StatefulConfigurationTransport object.

statefulConfigurationRetrieveAll()

DESCRIPTION Retrieves all Stateful Configuration.

SYNTAX

StatefulConfigurationTransport[] statefulConfigurationRetrieveAll(String sID)

PARAMETERS

sID Authentication session identifier ID.

RETURNS StatefulConfigurationTransport object array.

securityProfileDelete()

DESCRIPTION Deletes Security Profile by ID.

SYNTAX

```
void securityProfileDelete(int[] IDs, String sID)
```

PARAMETERS

ids Security Profile IDs to delete.

sID Authentication session identifier ID.

RETURNS

securityProfileSave()

DESCRIPTION Saves a new or existing Security Profile.

SYNTAX

```
SecurityProfileTransport securityProfileSave(SecurityProfileTransport sp, String sID)
```

PARAMETERS

sp SecurityProfileTransport object to create.

sID Authentication session identifier ID.

RETURNS Newly created SecurityProfileTransport object.

securityProfileAssignToHost()

DESCRIPTION Assigns a Security Profile to a Host.

SYNTAX

```
void securityProfileAssignToHost(int securityProfileID, int[] hostIDs, String sID)
```

PARAMETERS

securityProfileID Security Profile ID to assign.

hostIDs Host IDs to assign to Security Profile.

sID Authentication session identifier ID.

RETURNS

hostSecurityProfileClear()

DESCRIPTION Un-assigns a Host from a Security Profile.

SYNTAX

```
void hostSecurityProfileClear(int[] hostIDs, String sID)
```

PARAMETERS

hostIDs	Host IDs to assign to Security Profile.
sID	Authentication session identifier ID.

hostMoveToHostGroup()

DESCRIPTION Assigns a Host Group to a Host.

SYNTAX

```
void hostMoveToHostGroup(int[] hostIDs, int hostGroupID, String sID)
```

PARAMETERS

hostIDs	Host IDs to assign to Host Group.
hostGroupID	Host Group ID.
sID	Authentication session identifier ID.

RETURNS

hostCreate()

DESCRIPTION Creates a new Host object.

SYNTAX

```
HostTransport hostCreate(HostTransport host, String sID)
```

PARAMETERS

host	HostTransport object to create.
sID	Authentication session identifier ID.

RETURNS Newly created HostTransport object.

hostDelete()

DESCRIPTION Deletes Hosts from the Manager.

SYNTAX

```
void hostDelete(int[] IDs, String sID)
```

PARAMETERS

ids	Host IDs to delete.
sID	Authentication session identifier ID.

hostRetrieve()

DESCRIPTION Retrieves a Host by ID.

SYNTAX

```
HostTransport hostRetrieve(int ID, String sID)
```

PARAMETERS

ID	Host ID.
sID	Authentication session identifier ID.

RETURNS HostTransport object.

hostRetrieveByName()

DESCRIPTION Retrieves a Host by name.

SYNTAX

```
HostTransport hostRetrieveByName(String hostname, String sID)
```

PARAMETERS

hostname	Host name.
sID	Authentication session identifier ID.

RETURNS HostTransport object.

hostRetrieveByHostGroup()

DESCRIPTION Retrieves Hosts by Host Group.

SYNTAX

```
HostTransport[] hostRetrieveByHostGroup(int hostGroupID, String sID)
```

PARAMETERS

hostGroupID Host Group ID.

sID Authentication session identifier ID.

RETURNS HostTransport object array.

hostGetStatus()

DESCRIPTION Retrieves a Host status.

SYNTAX

```
HostStatusTransport hostGetStatus(int id, String sID)
```

PARAMETERS

id Host ID to retrieve.

sID Authentication session identifier ID.

RETURNS HostStatusTransport object.

hostAgentActivate()

DESCRIPTION Activates the agents on the set of hosts identified by IDs.

SYNTAX

```
public void hostAgentActivate(int[] hostIDs , String sID)
```

PARAMETERS

hostIDs Array of host IDs to activate.

sID Authentication session identifier ID.

hostAgentDeactivate()

DESCRIPTION Deactivates the agents on the set of hosts identified by IDs.

SYNTAX

```
public void hostAgentDeactivate(int[] hostIDs, String sID)
```

PARAMETERS

hostIDs	Array of host IDs to deactivate.
sID	Authentication session identifier ID.

hostUpdateNow()

DESCRIPTION Immediately initiates the update of hosts identified by IDs.

SYNTAX

```
public void hostUpdateNow(int[] hostIDs, String sID)
```

PARAMETERS

hostIDs	Array of host IDs to update.
sID	Authentication session identifier ID.

hostIntegrityScan()

DESCRIPTION Immediately initiates an integrity scan update of hosts identified by IDs.

SYNTAX

```
public void hostIntegrityScan(int[] hostIDs, String sID)
```

PARAMETERS

hostIDs	Array of host IDs to update.
sID	Authentication session identifier ID.

hostRebuildBaseline()

DESCRIPTION Immediately initiates an integrity scan baseline rebuild of hosts identified by IDs.

SYNTAX

```
public void hostRebuildBaseline(int[] hostIDs, String sID)
```

PARAMETERS

hostIDs	Array of host IDs to update.
sID	Authentication session identifier ID.

hostGetEventsNow()

DESCRIPTION Immediately initiates the fetch of events from hosts identified by IDs. The completion of this method is not synchronized with the event retrieval.

SYNTAX

```
public void hostGetEventsNow(int[] IDs, String sID)
```

PARAMETERS

IDs	Array of host IDs to update.
sID	Authentication session identifier ID.

hostGetEventsNowSync()

DESCRIPTION Immediately initiates the fetch of events from hosts identified by IDs and will block until the events are successfully retrieved or the Manager fails to communicate with the computers requested. There is a maximum timeout of 60 seconds.

SYNTAX

```
void hostGetEventsNowSync(int hostID, String sID)
```

PARAMETERS

hostID	The host on which to perform the action.
sID	Authentication session identifier ID.

securityProfileRetrieve()

DESCRIPTION Retrieves a Security Profile by ID.

SYNTAX

```
public SecurityProfileTransport securityProfileRetrieve(int ID, String sID)
```

PARAMETERS

ID Identifying Security Profile ID.

sID Authentication session identifier ID.

RETURNS SecurityProfileTransport object.

securityProfileRetrieveByName()

DESCRIPTION Retrieves a Security Profile by name.

SYNTAX

```
public SecurityProfileTransport securityProfileRetrieveByName(String name, String sID)
```

PARAMETERS

name Identifying Security Profile name.

sID Authentication session identifier ID.

RETURNS SecurityProfileTransport object.

securityProfileRetrieveAll()

DESCRIPTION Retrieves all Security Profiles.

SYNTAX

```
public SecurityProfileTransport[] securityProfileRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS SecurityProfileTransport object array.

systemSettingSet()

DESCRIPTION Sets the set of system setting key value pairs identified in the EditableSettingTransport array.

SYNTAX

```
public void systemSettingSet(EditableSettingTransport[] EditableSettings, String sID)
```

PARAMETERS

EditableSettings Array of EditableSettingTransport to set.

sID Authentication session identifier ID.

securityProfileSettingGet()

DESCRIPTION Retrieves the set of setting identified by the EnumEditableSettingKey array.

SYNTAX

```
EditableSettingStoredTransport[] securityProfileSettingGet(int securityProfileID, EnumEditableSettingKey[] keys, String sID)
```

PARAMETERS

securityProfileID Identifying Security Profile ID.

keys Array of EnumEditableSettingKey to get.

sID Authentication session identifier ID.

RETURNS EditableSettingStoredTransport object array.

securityProfileSettingSet()

DESCRIPTION Sets a set of Security Profile setting key value pairs identified in the EditableSettingTransport array.

SYNTAX

```
void securityProfileSettingSet(int securityProfileID, EditableSettingTransport[] editableSettings, String sID)
```

PARAMETERS

securityProfileID Identifying Security Profile ID.

editableSettings Array of EditableSettingTransport to set.

sID Authentication session identifier ID.

securityProfileSettingClear()

DESCRIPTION Clears a set of Security Profile setting key value pairs identified in the EnumEditableSettingKey array.

SYNTAX

```
public void securityProfileSettingClear(int ID, EnumEditableSettingKey[] EditableSettings, String sID)
```

PARAMETERS

ID Identifying Security Profile ID.

EditableSettings Array of EditableSettingTransport to clear.

sID Authentication session identifier ID.

hostSettingGet()

DESCRIPTION Retrieves the set of host settings identified by the EnumEditableSettingKey array.

SYNTAX

```
public EditableSettingStoredTransport[] hostSettingGet(int hostID, EnumEditableSettingKey[] keys, String sID)
```

PARAMETERS

hostID	Identifying host ID.
keys	Array of EnumEditableSettingKey to get.
sID	Authentication session identifier ID.

RETURNS EditableSettingStoredTransport object array.

hostSettingSet()

DESCRIPTION Sets a set of host setting key value pairs identified in the EditableSettingTransport array.

SYNTAX

```
public void hostSettingSet(int hostID, EditableSettingTransport[] editableSettings, String sID)
```

PARAMETERS

hostID	Identifying host ID.
editableSettings	Array of EditableSettingTransport to set.
sID	Authentication session identifier ID.

hostSettingClear()

DESCRIPTION Clears host overrides for the setting key value pairs identified in the EnumEditableSettingKey array. The host Security Profile or System inherited setting will then apply.

SYNTAX

```
public void hostSettingClear(int hostID, EnumEditableSettingKey[] keys, String sID)
```

PARAMETERS

hostID	Identifying host ID.
keys	Array of EditableSettingTransport to clear.
sID	Authentication session identifier ID.

systemEventRetrieve()

DESCRIPTION Retrieves the system events specified by the time, host and event ID filters. System events that do not pertain to hosts can be included or excluded. This version supports eventIdFilter filtering on event ID values of type “int” so it is recommended to invoke systemEventRetrieve2 instead.

SYNTAX

```
public SystemEventListTransport systemEventRetrieve(TimeFilterTransport timeFilter, HostFilterTransport hostFilter, IDFilterTransport eventIdFilter, boolean includeNonHostEvents, String sID)
```

PARAMETERS

timeFilter	TimeFilterTransport to filter by.
hostFilter	HostFilterTransport to filter by.
eventIdFilter	IDFilterTransport to filter by.
includeNonHostEvents	Boolean to specify if non-host events should be retrieved as well.
sID	Authentication session identifier ID.

RETURNS SystemEventListTransport object array.

systemEventRetrieve2()

DESCRIPTION Retrieves the system events specified by the time, host and event ID filters. System events that do not pertain to hosts can be included or excluded.

SYNTAX

```
public SystemEventListTransport systemEventRetrieve2e(TimeFilterTransport timeFilter, HostFilterTransport hostFilter, IDFilterTransport2 eventIdFilter, boolean includeNonHostEvents, String sID)
```

PARAMETERS

timeFilter	TimeFilterTransport to filter by.
hostFilter	HostFilterTransport to filter by.
eventIdFilter	IDFilterTransport2 to filter by.
includeNonHostEvents	Boolean to specify if non-host events should be retrieved as well.
sID	Authentication session identifier ID.

RETURNS SystemEventListTransport object array.

DPIEventRetrieve()

DESCRIPTION Retrieves the DPI events specified by the time, host and event ID filters. This version supports eventIdFilter filtering on event ID values of type “int” so it is recommended to invoke DPIEventRetrieve2 instead.

SYNTAX

```
public DPIEventListTransport DPIEventRetrieve2(TimeFilterTransport timeFilter, HostFilterTransport hostFilter, IDFilterTransport2 eventIdFilter, String sID)
```

PARAMETERS

timeFilter	TimeFilterTransport to filter by.
hostFilter	HostFilterTransport to filter by.
eventIdFilter	IDFilterTransport to filter by.
sID	Authentication session identifier ID.

RETURNS DPIEventListTransport object array.

DPIEventRetrieve2()

DESCRIPTION Retrieves the DPI events specified by the time, host and event ID filters.

SYNTAX

```
public DPIEventListTransport DPIEventRetrieve2(TimeFilterTransport timeFilter, HostFilterTransport hostFilter, IDFilterTransport2 eventIdFilter, String sID)
```

PARAMETERS

timeFilter	TimeFilterTransport to filter by.
hostFilter	HostFilterTransport to filter by.
eventIdFilter	IDFilterTransport2 to filter by.
sID	Authentication session identifier ID.

RETURNS DPIEventListTransport object array.

integrityEventRetrieve()

DESCRIPTION Retrieves the integrity events specified by the time, host and event ID filters. This version supports eventIdFilter filtering on event ID values of type “int” so it is recommended to invoke integrityEventRetrieve2 instead.

SYNTAX

```
public IntegrityEventListTransport integrityEventRetrieve(TimeFilterTransport timeFilter, HostFilterTransport hostFilter, IDFilterTransport eventIdFilter, String sID)
```

PARAMETERS

timeFilter	TimeFilterTransport to filter by.
hostFilter	HostFilterTransport to filter by.
eventIdFilter	IDFilterTransport to filter by.
sID	Authentication session identifier ID.

RETURNS DPIEventListTransport object array.

IntegrityEventRetrieve2()

DESCRIPTION Retrieves the integrity events specified by the time, host and event ID filters.

SYNTAX

```
public IntegrityEventListTransport integrityEventRetrieve2(TimeFilterTransport timeFilter, HostFilterTransport hostFilter, IDFilterTransport2 eventIdFilter, String sID)
```

PARAMETERS

timeFilter	TimeFilterTransport to filter by.
hostFilter	HostFilterTransport to filter by.

eventIdFilter IDFilterTransport2 to filter by.

sID Authentication session identifier ID.

RETURNS DPIEventListTransport object array.

logInspectionEventRetrieve()

DESCRIPTION	Retrieves the Log Inspection events specified by the time, host and event ID filters. This version supports eventIdFilter filtering on event ID values of type “int” so it is recommended to invoke logInspectionEventRetrieve2 instead.
-------------	--

SYNTAX

```
public LogInspectionEventListTransport logInspectionEventRetrieve(TimeFilterTransport timeFilter,
    HostFilterTransport hostFilter, IDFilterTransport eventIdFilter, String sID)
```

PARAMETERS

timeFilter	TimeFilterTransport to filter by.
hostFilter	HostFilterTransport to filter by.
eventIdFilter	IDFilterTransport to filter by.
sID	Authentication session identifier ID.

RETURNS	LogInspectionEventListTransport object array.
---------	---

logInspectionEventRetrieve2()

DESCRIPTION	Retrieves the Log Inspection events specified by the time, host and event ID filters.
-------------	---

SYNTAX

```
public LogInspectionEventListTransport logInspectionEventRetrieve2(TimeFilterTransport timeFilter,
    HostFilterTransport hostFilter, IDFilterTransport2 eventIdFilter, String sID)
```

PARAMETERS

timeFilter	TimeFilterTransport to filter by.
hostFilter	HostFilterTransport to filter by.
eventIdFilter	IDFilterTransport2 to filter by.
sID	Authentication session identifier ID.

RETURNS	LogInspectionEventListTransport object array.
---------	---

firewallEventRetrieve()

DESCRIPTION	Retrieves the firewall events specified by the time, host and event ID filters. This version supports eventIdFilter filtering on event ID values of type “int” so it is recommended to invoke logInspectionEventRetrieve2 instead.
-------------	--

SYNTAX

```
public FirewallEventListTransport firewallEventRetrieve(TimeFilterTransport timeFilter, HostFilterTransport hostFilter, IDFilterTransport eventIdFilter, String sID)
```

PARAMETERS

timeFilter	TimeFilterTransport to filter by.
hostFilter	HostFilterTransport to filter by.
eventIdFilter	IDFilterTransport to filter by.
sID	Authentication session identifier ID.

RETURNS FirewallEventListTransport object array.

firewallEventRetrieve2()

DESCRIPTION Retrieves the firewall events specified by the time, host and event ID filters.

SYNTAX

```
public FirewallEventListTransport firewallEventRetrieve2(TimeFilterTransport timeFilter, HostFilterTransport hostFilter, IDFilterTransport2 eventIdFilter, String sID)
```

PARAMETERS

timeFilter	TimeFilterTransport to filter by.
hostFilter	HostFilterTransport to filter by.
eventIdFilter	IDFilterTransport2 to filter by.
sID	Authentication session identifier ID.

RETURNS FirewallEventListTransport object array.

userDelete ()

DESCRIPTION Deletes the set of users defined identified by the provided ids. The user must have rights to delete user.

SYNTAX

```
public void userDelete(int[] ids, String sID)
```

PARAMETERS

ids The list of user ids to delete.

sID Authentication session identifier ID.

userSave ()

DESCRIPTION Saves the supplied user.

SYNTAX

```
UserTransport userSave(UserTransport ipl, String sID)
```

PARAMETERS

ipl The UserTransport to save

sID Authentication session identifier ID.

RETURNS UserTransport object.

userRetrieve ()

DESCRIPTION Retrieves the user with the provided ID (password is always blank)

SYNTAX

```
UserTransport userRetrieve(int id, String sID)
```

PARAMETERS

id The id of the user to retrieve

sID Authentication session identifier ID.

RETURNS UserTransport containing the user with the provided ID

userRetrieveAll ()

DESCRIPTION Retrieves all users (password is always blank).

SYNTAX

```
UserTransport[] userRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS UserTransport object array.

roleGetDefaultID ()

DESCRIPTION Get the full access (read-only) role. This can be used for creating users, especially for 'service users' (user accounts used for API integration).

SYNTAX

```
int roleGetDefaultID(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS the role ID.

pluginRequest ()

DESCRIPTION Dispatches a generic message to a plugin. Can be used to 'push' data or events to a plug-in via the WSAPI.

SYNTAX

```
String pluginRequest(String pluginID, String input, String sID)
```

PARAMETERS

pluginID Plug-in identifier.

input Input (can be string, XML, Base64, etc).

sID Authentication session identifier ID.

RETURNS Output (can be string, XML, Base64, etc), blank if PLM shutdown.

counterRetrieve ()

DESCRIPTION Load a list of counters per host, based on the counter filter type.
This method access the underlying counters that power the dashboard and reports efficiently. The text field of the CounterTransport object is varied by different counters. The description is blank.
Value is the count for the event type (including duplicate rolled events).

SYNTAX

```
CounterTransport[] counterRetrieve(EnumCounterFilter counterFilter, TimeFilterTransport timeFilter, HostFilterTransport hostFilter, TagFilterTransport tagFilter, String sID)
```

PARAMETERS

counterFilter	Type of counter filter to access. Please refer to EnumCounterFilter for officially supported values.
timeFilter	The time range to pull.
hostFilter	The host filter to constrain the query to. Not all hosts will be listed if they have a value of 0.
tagFilter	The tag filter or all tags. All returns an unbounded set, untagged returns only the untagged events, otherwise the freeform field takes comma delimited tag names (with the not '!' character indicating where not tagged).
sID	Authentication session identifier ID.

RETURNS CounterTransport object array.

counterHostRetrieve ()

DESCRIPTION Load a list of counters per host, based on the counter filter type.

SYNTAX

```
public CounterHostTransport[] counterHostRetrieve(EnumCounterFilter counterFilter, TimeFilterTransport timeFilter, HostFilterTransport hostFilter, TagFilterTransport tagFilter, String sID)
```

PARAMETERS

counterFilter	Type of counter filter to access.
timeFilter	Type of counter filter to access.
hostFilter	The host filter to constrain the query to.
tagFilter	The tag filter or all tags.

sID Authentication session identifier ID.

RETURNS CounterHostTransport object array for the hosts that have a value > 0.

counterWithIDRetrieve ()

DESCRIPTION Load a list of counters per host, based on the counter filter type.

SYNTAX

```
public CounterWithIDTransport[] counterWithIDRetrieve(EnumCounterFilter counterFilter,  
TimeFilterTransport timeFilter, HostFilterTransport hostFilter, TagFilterTransport tagFilter, String sID)
```

PARAMETERS

counterFilter Type of counter filter to access. Please refer to EnumCounterFilter for officially supported values

timeFilter The time range to pull.

hostFilter The host filter to constrain the query to. Not all hosts will be listed if they have a value of 0.

tagFilter The tag filter or all tags.

sID Authentication session identifier ID.

RETURNS CounterWithIDTransport object array.

counterAlertTypeRetrieve ()

DESCRIPTION Retrieves the firewall events specified by the time, host and event ID filters.

SYNTAX

```
public CounterAlertTypeTransport[] counterAlertTypeRetrieve(EnumCounterFilter counterFilter,  
TimeFilterTransport timeFilter, HostFilterTransport hostFilter, TagFilterTransport tagFilter, String sID)
```

PARAMETERS

counterFilter Type of counter filter to access. Please refer to EnumCounterFilter for officially supported values

timeFilter The time range to pull.

hostFilter The host filter to constrain the query to. Not all hosts will be listed if they have a value of 0.

tagFilter IDFilterTransport to filter by.

sID	Authentication session identifier ID.
RETURNS	CounterAlertTypeTransport object array.

counterSumRetrieve ()

DESCRIPTION Load a list of counters per host, based on the counter filter type.

SYNTAX

```
public CounterAlertTypeTransport[] counterAlertTypeRetrieve(EnumCounterFilter counterFilter,
TimeFilterTransport timeFilter, HostFilterTransport hostFilter, TagFilterTransport tagFilter, String sID)
```

PARAMETERS

counterFilter	Type of counter filter to access.
timeFilter	The time range to pull.
hostFilter	The host filter to constrain the query to.
tagFilter	The tag filter or all tags.
sID	Authentication session identifier ID.
RETURNS	CounterAlertTypeTransport object array.

featureSummaryRetrieve ()

DESCRIPTION Get status summary of each protection feature.

SYNTAX

```
public FeatureSummaryTransport featureSummaryRetrieve(TimeFilterTransport timeFilter,
TimeFilterTransport previousTimeFilter, String sID)
```

PARAMETERS

timeFilter	the lookup time range
previousTimeFilter	the comparison baseline time range.
sID	Authentication session identifier ID.
RETURNS	FeatureSummary including summaries of each protection feature.

statusSummaryRetrieve ()

DESCRIPTION Return the status summary of the system.

SYNTAX

```
public StatusSummaryTransport statusSummaryRetrieve(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS Status summary including host status summary and alert numbers

componentSummaryRetrieve ()

DESCRIPTION Return component info for each component

SYNTAX

```
public ComponentInfoTransport[] componentSummaryRetrieve(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS ComponentInfoTransport object array.

hostStatusSummaryRetrieve ()

DESCRIPTION Retrieves the summary of the hosts status (error, warning, online, locked, unmanaged) as integers for the given hostFilter.

SYNTAX

```
public HostStatusSummaryTransport hostStatusSummaryRetrieve(HostFilterTransport hostFilter, String sID)
```

PARAMETERS

hostFilter HostFilterTransport to filter by.

sID Authentication session identifier ID.

RETURNS HostStatusSummaryTransport object.

hostJobProgress ()

DESCRIPTION Gets the progress of a given job type since the invocation time.

SYNTAX

```
public JobProgressTransport hostJobProgress(EnumJobType type, java.util.Calendar sinceManagerTime, int[] hostIDs, String sID)
```

PARAMETERS

type	Type of operation (UPDATE, etc)
sinceManagerTime	use getManagerTime before invoking the operation
hostIDs	list of hostIDs to check
sID	Authentication session identifier ID.

RETURNS JobProgressTransport object.

hostClearWarningsErrors ()

DESCRIPTION Clear warnings and errors

SYNTAX

```
public void hostClearWarningsErrors(int[] hostIDs, String sID)
```

PARAMETERS

hostIDs	The ids of the hosts to clear the warnings and errors
sID	Authentication session identifier ID.

systemSettingGet ()

DESCRIPTION Retrieves the set of setting identified by the EnumEditableSettingKey[].

SYNTAX

```
public EditableSettingStoredTransport[] systemSettingGet(EnumEditableSettingKey[] keys, String sID)
```

PARAMETERS

keys	The keys of the settings to return
sID	Authentication session identifier ID.

RETURNS EditableSettingStoredTransport object array.

securityProfileSettingClear ()

DESCRIPTION Removes the provided Security Profile's overrides for the settings in keys, returning the values to those inherited from system.

SYNTAX

```
public void securityProfileSettingClear(int securityProfileID, EnumEditableSettingKey[] keys, String sID)
```

PARAMETERS

securityProfileID	The ID of the security profile that the settings are for.
keys	Transport object containing the required information to store a setting.
sID	Authentication session identifier ID.

hostGetEventsNowSync ()

DESCRIPTION Immediately initiates the fetch of events from the host.

SYNTAX

```
public void hostGetEventsNowSync(int hostID, String sID)
```

PARAMETERS

hostID	The host on which to perform the action
sID	Authentication session identifier ID.

retrieveActivationCode ()

DESCRIPTION Retrieves the current activation code for the specified module

SYNTAX

```
public String retrieveActivationCode(int moduleNumber, String sID)
```

PARAMETERS

moduleNumber The module number on which to perform the action.

sID Authentication session identifier ID.

RETURNS The current activation code for the specified module.

retrieveLicenseProfile ()

DESCRIPTION Retrieves the current license profile code for the specified module

SYNTAX

```
public String retrieveLicenseProfile(int moduleNumber, String sID)
```

PARAMETERS

moduleNumber The module number on which to perform the action.

sID Authentication session identifier ID.

RETURNS The current license profile for the specified module in a String.

addActivationCode ()

DESCRIPTION Adds the activation code for the specified module

SYNTAX

```
public void addActivationCode(int moduleNumber, String activationCode, String sID)
```

PARAMETERS

moduleNumber The module number on which to perform the action. -1 for all modules, 0 for AV, 1 for NET, 2 for IM, 3 for LI

activationCode The activation code to add.

sID Authentication session identifier ID.

logInspectionRuleRetrieveAll ()

DESCRIPTION Retrieves all of the LogInspectionRules

SYNTAX

```
public LogInspectionRuleTransport[] logInspectionRuleRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS LogInspectionRuleTransport object array.

logInspectionDecoderRetrieveByName()

DESCRIPTION Retrieves the logInspectionDecoder with the provided name (Case Sensitive)

SYNTAX

```
public LogInspectionDecoderTransport logInspectionDecoderRetrieveByName(String name, String sID)
```

PARAMETERS

name The name of the logInspectionDecoder to retrieve

sID Authentication session identifier ID.

RETURNS LogInspectionDecoderTransport object.

scanFileListDelete()

DESCRIPTION Deletes the set of Scan File lists identified by the provided ids.

SYNTAX

```
public void scanFileListDelete(int[] ids, String sID)
```

PARAMETERS

ids The list of Scan File list ids to delete.

sID Authentication session identifier ID.

scanFileListSave()

DESCRIPTION Saves the supplied Scan File list.

SYNTAX

```
public ScanFileListTransport scanFileListSave(ScanFileListTransport scanFileListTransport, String sID)
```

PARAMETERS

scanFileListTransport The ScanFileListTransport to save

sID Authentication session identifier ID.

RETURNS ScanFileListTransport object.

scanFileListRetrieve()

DESCRIPTION Retrieves the Scan File list with the provided ID

SYNTAX

```
public ScanFileListTransport scanFileListRetrieve(int id, String sID)
```

PARAMETERS

id The id of the Scan File list to retrieve

sID Authentication session identifier ID.

RETURNS ScanFileListTransport object with the IP list with the provided ID

scanFileListRetrieveByName()

DESCRIPTION Retrieves the Scan File list with the provided name (Case sensitive)

SYNTAX

```
public ScanFileListTransport scanFileListRetrieveByName(String name, String sID)
```

PARAMETERS

name The name id of the Scan File list to retrieve

sID Authentication session identifier ID.

RETURNS ScanFileListTransport object with the IP list with the provided name.

scanFileListRetrieveAll ()

DESCRIPTION Retrieves all of the Scan File lists

SYNTAX

```
public ScanFileListTransport[] scanFileListRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS ScanFileListTransport object array.

scanFileExtListDelete()

DESCRIPTION Deletes the set of Scan File Extension lists identified by the provided ids

SYNTAX

```
public void scanFileExtListDelete(int[] ids, String sID)
```

PARAMETERS

ids public void scanFileExtListDelete(int[] ids, String sID)

sID Authentication session identifier ID.

scanFileExtListSave ()

DESCRIPTION Deletes the set of Scan File Extension lists identified by the provided ids.

SYNTAX

```
public void scanFileExtListDelete(int[] ids, String sID)
```

PARAMETERS

ids The list of Scan File Extension list ids to delete

sID Authentication session identifier ID.

scanFileExtListRetrieve ()

DESCRIPTION Retrieves the Scan File Extension list with the provided ID

SYNTAX

```
public ScanFileExtListTransport scanFileExtListRetrieve(int id, String sID)
```

PARAMETERS

id The id of the Scan File Extension list to retrieve.

sID Authentication session identifier ID.

RETURNS ScanFileExtListTransport object with the IP list with the provided ID.

scanFileExtListRetrieveByName ()

DESCRIPTION Retrieves the Scan File Extension list with the provided name (Case sensitive)

SYNTAX

```
public ScanFileExtListTransport scanFileExtListRetrieveByName(String name, String sID)
```

PARAMETERS

name The name of the Scan File Extension list to retrieve.

sID Authentication session identifier ID.

RETURNS ScanFileExtListTransport object with the IP list with the provided ID

scanFileExtListRetrieveAll()

DESCRIPTION Retrieves all of the Scan File Extension lists

SYNTAX

```
public ScanFileExtListTransport[] scanFileExtListRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS ScanFileExtListTransport object array.

scanDirectoryListDelete ()

DESCRIPTION Retrieves all of the Scan File Extension lists

SYNTAX

```
public void scanDirectoryListDelete(int[] ids, String sID)
```

PARAMETERS

ids	The list of Scan Directory list ids to delete
sID	Authentication session identifier ID.

scanDirectoryListSave()

DESCRIPTION Saves the supplied Scan File Extension list

SYNTAX

```
public ScanDirectoryListTransport scanDirectoryListSave(ScanDirectoryListTransport  
scanDirectoryListTransport, String sID)
```

PARAMETERS

scanDirectoryListTransport	The ScanFileExtListTransport to save
sID	Authentication session identifier ID.

RETURNS ScanDirectoryListTransport object.

scanDirectoryListRetrieve()

DESCRIPTION Retrieves the Scan Directory list with the provided ID

SYNTAX

```
public ScanDirectoryListTransport scanDirectoryListRetrieve(int id, String sID)
```

PARAMETERS

id	The id of the Scan Directory list to retrieve
sID	Authentication session identifier ID.

RETURNS ScanDirectoryListTransport object with the IP list with the provided ID.

scanDirectoryListRetrieveByName()

DESCRIPTION Retrieves the Scan Directory list with the provided name (Case sensitive)

SYNTAX

```
public ScanDirectoryListTransport scanDirectoryListRetrieveByName(String name, String sID)
```

PARAMETERS

name The name of the Scan Directory list to retrieve

sID Authentication session identifier ID.

RETURNS ScanDirectoryListTransport object.

scanDirectoryListRetrieveAll()

DESCRIPTION Retrieves all of the Scan Directory lists.

SYNTAX

```
public ScanDirectoryListTransport[] scanDirectoryListRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS ScanDirectoryListTransport object array.

antiMalwareDelete()

DESCRIPTION Deletes the set of AntiMalware identified by the provided ids

SYNTAX

```
public void antiMalwareDelete(int[] ids, String sID)
```

PARAMETERS

ids The list of AntiMalware ids to delete

sID Authentication session identifier ID.

antiMalwareSave()

DESCRIPTION Saves the supplied AntiMalware

SYNTAX

```
public AntiMalwareTransport antiMalwareSave(AntiMalwareTransport antiMalwareTransport, String sID)
```

PARAMETERS

antiMalwareTransport The AntiMalwareTransport to save

sID Authentication session identifier ID.

RETURNS AntiMalwareTransport object.

antiMalwareRetrieve()

DESCRIPTION Retrieves the AntiMalware with the provided ID

SYNTAX

```
public AntiMalwareTransport antiMalwareRetrieve(int id, String sID)
```

PARAMETERS

id The id of the AntiMalware to retrieve

sID Authentication session identifier ID.

RETURNS The AntiMalwareTransport object.

antiMalwareRetrieveByName()

DESCRIPTION Retrieves the AntiMalware with the provided name (Case sensitive)

SYNTAX

```
public AntiMalwareTransport antiMalwareRetrieveByName(String name, String sID)
```

PARAMETERS

name The name of the AntiMalware to retrieve

sID Authentication session identifier ID.

RETURNS AntiMalwareTransport object.

antiMalwareRetrieveAll()

DESCRIPTION Retrieves all of the AntiMalware

SYNTAX

```
public AntiMalwareTransport[] antiMalwareRetrieveAll(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS AntiMalwareTransport object array.

antiMalwareEventRetrieve()

DESCRIPTION Retrieves the AntiMalware events specified by the time and host filter. This version supports eventIdFilter filtering on event ID values of type "int" so it is recommended to invoke antiMalwareEventRetrieve2 instead.

SYNTAX

```
public AntiMalwareEventListTransport antiMalwareEventRetrieve(TimeFilterTransport timeFilter  
HostFilterTransport hostFilter, IDFilterTransport eventIdFilter, String sID)
```

PARAMETERS

timeFilter Restricts the retrieved events by time.

hostFilter Restricts the retrieved events by host, group, or security profile.

eventIdFilter Restricts the retrieved events by event id.

sID Authentication session identifier ID.

RETURNS AntiMalwareEventListTransport object.

antiMalwareEventRetrieve2()

DESCRIPTION Retrieves the AntiMalware events specified by the time and host filter.

SYNTAX

```
public AntiMalwareEventListTransport antiMalwareEventRetrieve2(TimeFilterTransport timeFilter  
HostFilterTransport hostFilter, IDFilterTransport2 eventIdFilter, String sID)
```

PARAMETERS

timeFilter Restricts the retrieved events by time.

hostFilter Restricts the retrieved events by host, group, or security profile.

eventIdFilter Restricts the retrieved events by event id.

sID Authentication session identifier ID.

RETURNS AntiMalwareEventListTransport object.

updateComponents()

DESCRIPTION Performs a global component update of the system. This will do a full update of all relays, and then the corresponding agent updates

SYNTAX

```
public boolean updateComponents(String sID)
```

PARAMETERS

 sID Authentication session identifier ID.

RETURNS AntiMalwareEventListTransport object.

updateComponentFromAU()

DESCRIPTION Performs a global component update of the system. This will do a full update of all relays, and then the corresponding agent updates, and also for legacy purposes, if 7.5 Appliances are in use, we will utilize some of the parameters and attempt to perform specific updates for those legacy Appliances.

SYNTAX

```
public boolean updateComponentFromAU(int type, int id, boolean applyDSRU, String sID)
```

PARAMETERS

 type If in legacy mode, specifies the specific type of component to update

 Id If in legacy mode, specifies the ID of the component to update

 applyDSRU If in legacy mode, indicates if the DSRU should be applied or not

 sID Authentication session identifier ID.

RETURNS True if the update was successful.

hostAntiMalwareScan()

DESCRIPTION Trigger Anti-Malware Manual Scan on specified host.

SYNTAX

```
public void hostAntiMalwareScan(int[] hostIDs, String sID)
```

PARAMETERS

hostIDs	Array of host IDs to apply software to.
sID	Authentication session identifier ID.

hostUpdateComponent()

DESCRIPTION	Update Component
-------------	------------------

SYNTAX

```
public void hostUpdateComponent(int[] hostIDs, int type, int id, String sID)
```

PARAMETERS

hostIDs	Host IDs to update.
type	Component type (ignored)
id	Component id (ignored)
sID	Authentication session identifier ID.

hostRollbackComponent()

DESCRIPTION	Rollback Component on DSVAs to the previous version
-------------	---

SYNTAX

```
public void hostRollbackComponent(int[] hostIDs, int type, int id, String sID)
```

PARAMETERS

hostIDs	All the DSVAs to update.
type	Component type (ignored)
id	Component id (ignored)
sID	Authentication session identifier ID.

alertStatusRetrieve()

DESCRIPTION	Retrieves the alerts.
-------------	-----------------------

SYNTAX

```
public AlertStatusTransport[] alertStatusRetrieve(int count, String sID)
```

PARAMETERS

count	Restricts the retrieved alerts amount
sID	Authentication session identifier ID.

RETURNS The alert list

userRetrieveByName()

DESCRIPTION Retrieves the user with the provided username (Case Sensitive) (password is always blank)

SYNTAX

```
public UserTransport userRetrieveByName(String name, String sID)
```

PARAMETERS

name	The username of the user to retrieve
sID	Authentication session identifier ID.

RETURNS The user with the provided username

counterRetrieve()

DESCRIPTION Load a list of counters per host, based on the counter filter type.

SYNTAX

```
public CounterTransport[] counterRetrieve(EnumCounterFilter counterFilter, TimeFilterTransport timeFilter, HostFilterTransport hostFilter, TagFilterTransport tagFilter, String sID)
```

PARAMETERS

counterFilter	Type of counter filter to access. Please refer to EnumCounterFilter for officially supported values.
timeFilter	The time range to pull.
hostFilter	The host filter to constrain the query to. Not all hosts will be listed if they have a value of 0.
tagFilter	The tag filter or all tags. All returns an unbounded
sID	Authentication session identifier ID.

RETURNS CounterTransport object array.

hostDetailRetrieve()

DESCRIPTION Retrieves the detail information of hosts.

SYNTAX

```
public HostDetailTransport[] hostDetailRetrieve(HostFilterTransport hostFilter, EnumHostDetailLevel hostDetailLevel, String sID)
```

PARAMETERS

hostFilter	Restricts the retrieved hosts by host, group, or security profile
hostDetailLevel	The detail level
sID	Authentication session identifier ID.

RETURNS HostDetailTransport object array.

hostDetailRetrieveByName()

DESCRIPTION Retrieves the detail information of host.

SYNTAX

```
public HostDetailTransport[] hostDetailRetrieveByName(String hostname, EnumHostDetailLevel hostDetailLevel, String sID)
```

PARAMETERS

hostname	The name of host
hostDetailLevel	The detail level
sID	Authentication session identifier ID.
RETURNS	HostDetailTransport object array.

hostDetailRetrieveByExternal()

DESCRIPTION Retrieves the detail information of hosts by External ID (Host/HostGroup).

SYNTAX

```
public HostDetailTransport[] hostDetailRetrieveByExternal(ExternalFilterTransport externalFilter,
EnumHostDetailLevel hostDetailLevel, String sID)
```

PARAMETERS

externalFilter	Restricts the retrieved hosts by hostExternalID, or hostGroupExternalID
hostDetailLevel	The detail level
sID	Authentication session identifier ID.
RETURNS	HostDetailTransport object array.

hostDetailRetrieveByNameStartsWith()

DESCRIPTION Retrieves the detail information of host by starting with startsWithHostname.

SYNTAX

```
public HostDetailTransport[] hostDetailRetrieveByNameStartsWith(String startsWithHostname,
EnumHostDetailLevel hostDetailLevel, String sID)
```

PARAMETERS

startsWithHostname	The name of host
hostDetailLevel	The detail level
sID	Authentication session identifier ID.
RETURNS	HostDetailTransport object array.

webReputationEventRetrieve()

DESCRIPTION Retrieves the Web Reputation events specified by the time and host filter. This version supports eventIdFilter filtering on event ID values of type “int” so it is recommended to invoke webReputationEventRetrieve2 instead.

SYNTAX

```
public WebReputationEventListTransport webReputationEventRetrieve(TimeFilterTransport timeFilter,
HostFilterTransport hostFilter, IDFilterTransport eventIdFilter, String sID)
```

PARAMETERS

timeFilter	Restricts the retrieved events by time
hostFilter	Restricts the retrieved events by host, group, or security profile
eventIdFilter	Restricts the retrieved events by event ID.
sID	Authentication session identifier ID.
RETURNS	WebReputationEventListTransport object.

webReputationEventRetrieve2()

DESCRIPTION Retrieves the Web Reputation events specified by the time and host filter.

SYNTAX

```
public WebReputationEventListTransport webReputationEventRetrieve2(TimeFilterTransport timeFilter,
HostFilterTransport hostFilter, IDFilterTransport2 eventIdFilter, String sID)
```

PARAMETERS

timeFilter	Restricts the retrieved events by time
hostFilter	Restricts the retrieved events by host, group, or security profile
eventIdFilter	Restricts the retrieved events by event ID.
sID	Authentication session identifier ID.

RETURNS WebReputationEventListTransport object.

hostRecommendationScan()

DESCRIPTION Initiate a host recommendation scan.

SYNTAX

```
void hostRecommendationScan(int[] hostIDs, String sID)
```

PARAMETERS

hostIDs	Array of host IDs to scan
sID	Authentication session identifier ID.

hostRecommendationsClear()

DESCRIPTION Clear the existing host recommendation.

SYNTAX

```
public void hostRecommendationsClear(int[] hostIDs, String sID)
```

PARAMETERS

hostIDs	Array of host IDs to clear
sID	Authentication session identifier ID.

hostRecommendationsResolve()

DESCRIPTION Manually resolve recommendations on unresolved hosts by type and rules.

SYNTAX

```
void hostRecommendationsResolve(int hostID, int type, int[] ruleIDs, String sID)
```

PARAMETERS

hostID	The host on which to perform the resolution
type	The type of rule (1 = Intrusion Prevention application type rule, 2 = Intrusion Prevention inspection rule, 4 = Integrity Monitoring rule, 5 = Log Inspection rule)
ruleIDs	An array of rule IDs
sID	Authentication session identifier ID.

hostRecommendationRuleIDsRetrieve()

DESCRIPTION Retrieve host recommendation rule IDs.

SYNTAX

```
public int[] hostRecommendationRuleIDsRetrieve(int hostID, int type, boolean onlyunassigned, String sID)
```

PARAMETERS

hostID	The host for which to retrieve the recommendations
type	The type of rule
onlyunassigned	Boolean to specify if the function should only return rules that are recommended, and not assigned at the host.
sID	Authentication session identifier ID.

RETURNS An array of recommended rule IDs.

securityProfileRecommendationRuleIDsRetrieve()

DESCRIPTION Retrieve security profile recommendation rule IDs.

SYNTAX

```
public int[] securityProfileRecommendationRuleIDsRetrieve(int securityProfileID, int type, String sID)
```

PARAMETERS

securityProfileID	The security profile ID for which to retrieve the recommendations
type	The type of rule
sID	Authentication session identifier ID.

RETURNS An array of recommended rule IDs.

hostRecommendationUnresolvedRetrieve()

DESCRIPTION Retrieve hosts with unresolved recommendation rule IDs.

SYNTAX

```
public int[] hostRecommendationUnresolvedRetrieve(String sID)
```

PARAMETERS

sID Authentication session identifier ID.

RETURNS An array of hosts IDs that have unresolved recommendations.